WALKTHROUGH for Director:

User and User Roles

Draft 1.01 By Colin Crook

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information about the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service. IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send licenseinquiries, in writing, to:

IBM Director of Licensing, IBM Corporation, North Castle Drive, Armonk, NY 10504-1785 U.S.A.

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk. IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products.

All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

User and User Roles

Environment

- JS22 running AIX 6.1 and Director Server 6.2.
- o JS20 & JS21 running AIX 6.1.
- LS22 running Windows Server 2003
- Discovery and Inventory have been completed.
- All systems have full access.

Purpose

Demonstrate creating a user with specific roles. In this case it will be a user that can create Event Automation Plans. The steps can readily be adapted to suit your own requirements.

Steps

1. I assume you are logged in. Director has predefined groups that you can make a user a member of, thus inheriting the roles that are assigned to said group. To me you want to create a group so that you have a blank sheet to start assigning only the roles you want.

First we need to create that group. For this we drop to the command line in AIX. Enter **smit groups** and select **Add a Group**.



2. The following screen is displayed. Give it a group name. Mine is **eventpl**. Press **Enter** and you will get Command OK. Return to the command line.

🚰 192.168.70.227 - F	PuTTY			_ 🗆 🗵
	Ac	dd a Group		<u> </u>
Type or select Press Enter AFT	values in entry field ER making all desired	ls. 1 changes.		
* Group NAME ADMINISTRATIV Group ID USER list ADMINISTRATOR Projects Initial Keyst Keystore Encr Keystore Acce	E group? . list ore Mode yption Algorithm ss		<pre>[Entry Fields] [eventp1] False [] [] [] [] [] [] [] [] [] [] [] []</pre>	+ # + + + + + +
F1=Help F5=Reset F9=Shell	F2=Refresh F6=Command F10=Exit	F3=Cancel F7=Edit Enter=Do	F4=List F8=Image	•

3. You need to authorise the group with Director by issuing:

smcli authusergp eventpl

You should receive:

DNZCLI1033I : The group eventpl was successfully authorized.

4. We now need to create our user. Enter **smit user**. Hit **Enter** for the top option **Add a User**.

On the following menu enter a name for the user and input the primary group and group set. I used **borris** for the user, **staff** for the primary group and **staff**, **eventpl** for the group set.

🛃 192.168.70.227 - PuTTY				
		Add a User		<u> </u>
Type or select valu	es in entry fie	elds.		
Press Enter AFTER m	aking all desin	red changes.		
(TOD)			[Entry Field	1-1
LIOPJ			LEUCLA LIEL	usj
" USER NAME			[DOLLIS]	#
ADMINISTDATIVE HS	F D0		LJ folgo	
ADMINISTRATIVE US	LR?			Ť
Chown CET			[Starr]	, †
ADMINISTRATUE CD	ound		l <mark>s</mark> carr,evencpi	· · ·
ADMINISTRATIVE GR	OUPS			Ť
ROLES	au mo uarpo			+
Another user can	SU IU USER?		true	+
SU GROUPS			[#止止]	+
HOME directory				
Initial PROGRAM				
User INFORMATION			[]	
EXPIRATION date (MMDDhhmmyy)		[0]	
[MORE52]				
F1=Help	F2=Refresh	F3=Cancel	F4=List	
F5=Reset	F6=Command	F7=Edit	F8=Image	e
F9=Shell	F10=Exit	Enter=Do		•

 If you are logged into Director as root you will need to relog in order to see the effect of adding the group eventpl and giving borris membership. Once you are back in, click on **Security** followed by **Users**. You can see the group and user displayed in the right pane.

IBM* Systems Director			We	lcome root		Probl	ems	0	۵û	Com
View: All tasks	Users X									
My Startup Pages										
 Find a Task 	Users									
Find a Resource										
Automation	Manage	authorized users and g	roups, and	their access to	o systems	and tasks.				
H Availability	You can	authorize existing unau	thorized u	ser groups to a	access the	IBM Systems	Director	Server, o	r remov	e autho
	Users									
+ Inventory	Edit	Assign Role	Copy Ro	le to User	Authori	ze Groups	Remo	ove Group	Authoria	zation
H Release Management	Select	Name	2	Domain	٥	State	0	Type		1
	ि	& borris				🔳 Offline	•	Individu	al	
Roles	0	a root				Active		Individu	al	
Credentials	6	& eventpl						Group		
Server Auditing	0	a smadmin						Group		
	0	& smmgr						Group		
System Status and Health	0	A smmon						Group		
⊞ Task Management	0	& smuser						Group		
🗄 Settings										
			A Tot	alu 7						

6. We now need to define what the user can access. Click on **Roles** in the **Security** section. Now click on **Create** in the right pane.

View: All tasks	Us	ers × R	oles ×	
 Welcome My Startup Pages Find a Task Find a Resource Navigate Resources 	Ro	les Manago t	he release that says he assigned to	
Automation		manage c	ne roles that can be assigned to	users.
		Cres	ata Grasta Lika Edit	Delete View Actions
Inventory Invento		O-last		Description
Release Management			Name ⊽_	This permission grants a user the abilit
E Security			& SMAdministrator	The Administrator role has full authorit
Users			& SMManager	The Manager role can perform a subse
Credentials			a SMMonitor	The Monitor role can access those adm
Server Auditing			👗 SMUser	The User role includes any authenticate
E System Status and Health				
Task Management				

7. This brings us into the wizard. On the first screen we enter a name and description. Click **Next**.

/ Welcome	Name
🖓 Name	Specify a name and description for the role.
Permissions	36 N
Summary	
	Description:
	Gives rights to create Event Action Pla

8. There are a lot of individual options under each heading in Available permissions. Some of these can be seen in Selected permissions. The reason for mentioning this is that there maybe something in there that you may want to remove. In my example I just added everything for Automation and Systems Status and Health by selecting them on the left and pressing Add.

The operations I would like this user perform need access to these two areas. The first, **Automation**, is where you define an **Event Action** and where you link the **Monitor/Threshold** to it via an **Event Automation Plan**.

The second **Systems Status and Health** are where we can define our thresholds.

V Welcome	Permissions	
🗸 Name	Select the permissions for the role.	
Name Permissions Summary	C All permissions C All permissions Available permissions:	Add > Selected permissions: Add > I Remove Remove Automation Manager Remove Command Automations Name Command Automations Remove
		특히 Copy an Event Filter Wizard Marc Copy an Event Filter Wizard Marc Create Marc Create Like Marc Edit Marc Edit an Automation Plan Wi Marc Edit an Event Filter Wizard
	tean secting Ere System Configuration Ere System z Management Ere Task Management	배습 Event Actions 환급 Event Automation Plans 환급 Event Filter Wizard 환급 Event Filters 환급 Resume Event Actions

Click Next and then Finish. Your role is now defined.

Roles						
Crea	ate Create Like	Edit	Dele			
Select	Name	\$	Descript			
	🕹 eventplanning		Gives ri			
	🚨 GroupRead	This pe				
	SMAdministrator	The Adr				
	🚨 SMManager	🕹 SMManager				
	🚨 SMMonitor	The Mo				
	💩 SMUser	The Use				

9. Navigate back to **Users** under **Security**. Highlight the radial next to Borris and Press **Assign Role**.

Automation		You can a	authorize existing unau	thorized u:	ser groups to a	access the	IBM Systems	Director	Server, or rem	ove autho
		Usors								
Inventory		Edit	Assign Role	Copy Ro	le to User	Authori	ze Groups	Remo	ve Group Autho	rization
🛨 Release Management						. [1 [
E Security	n	Select	Name	2 _	Domain	\$	State	\$	Туре	÷ 1
		•	& borris				🔲 Offline		Individual	
 Users Roles 	\mathcal{V}	0	& root				📒 Active		Individual	
Credentials		0	& eventpl						Group	
Server Auditing		0	& smadmin						Group	
System Configuration System Confi		0	&' mmar						Group	

Here we select our role, click Next.

✓ Welcome	Roles				
🖒 Roles	Roles				
Groups Summary	Select an	existing role from the ta	ble to as	ssign.	
	Select	Name	, \$	Description \$	
		🚨 eventplanning		Gives rights to create Event Action Plans	1
		🚨 GroupRead		This permission grants a user the ability to view o.	. :
		🚨 SMAdministrator		The Administrator role has full authority to all tas	\$
		🚨 SMManager		The Manager role can perform a subset of the ta	\$
		🚨 SMMonitor		The Monitor role can access those administrative	
		2 CMULTON			

In my example I want only AIX systems accessed by this user so I toggled down though **Groups by System Type** and **Operating Systems**. I then selected **AIX Systems** and pressed **Add**.

🗸 Welcome	Groups	
🗸 Roles	Select the groups to which the role applies.	
🖒 Groups		
Summary	0	
	○ All Resources	
	Available groups:	Selected groups:
	H Groups by Access	AIX Systems
	T Si Groups by Agent	
	T 9 Groups by Status	
	E Groups by System Type	
	T SladeCenter Systems	
	R Consisting Systems	
	ATV Suctores	
	TPM i Systems	
	- Ibm Poysterns	
	Cindx@ Systems	
	The Device Systems	
	E Power Systems	
	I Storage Systems	
	E System x	
	E System z	
	🛄 Generic Systems 💌	

Click Next and Finish.

10. To now log in with the user borris you need to set a password. The thing that caught me out was you have to log in with the user to your AIX image and change the password you have just set. Once you have performed this step when you log in access is limited to the areas we previously defined.

IBM [*] Systems Director				We	lcome borris
View: All tasks	F	Event Autom	×		
Welcome My Startup Pages	ſ				
Automation Event Automation Plans Event Actions Event Filters Compand Automation	E	Use even Event Autor	nation Plans t automation plans to a tomation Plans ate Create Like	utomate f	tasks based on receiv
System Status and Health		Select	Name	- +	Targets
E Settings			Log All Events		All Systems
			tmp		Director