

PERFORCE

C/C++ API User's Guide

2015.1

March 2015

C/C++ API User's Guide

2015.1

March 2015

Copyright © 1999-2015 Perforce Software.

All rights reserved.

Perforce software and documentation is available from <http://www.perforce.com/>. You can download and use Perforce programs, but you can not sell or redistribute them. You can download, print, copy, edit, and redistribute the documentation, but you can not sell it, or sell any documentation derived from it. You can not modify or attempt to reverse engineer the programs.

This product is subject to U.S. export control laws and regulations including, but not limited to, the U.S. Export Administration Regulations, the International Traffic in Arms Regulation requirements, and all applicable end-use, end-user and destination restrictions. Licensee shall not permit, directly or indirectly, use of any Perforce technology in or by any U.S. embargoed country or otherwise in violation of any U.S. export control laws and regulations.

Perforce programs and documents are available from our Web site as is. No warranty or support is provided. Warranties and support, along with higher capacity servers, are sold by Perforce Software.

Perforce Software assumes no responsibility or liability for any errors or inaccuracies that might appear in this book. By downloading and using our programs and documents you agree to these terms.

Perforce and Inter-File Branching are trademarks of Perforce Software.

All other brands or product names are trademarks or registered trademarks of their respective companies or organizations.

Any additional software included within Perforce software is listed in [License Statements on page 271](#).

Table of Contents

About This Manual	xi
Please give us feedback	xix
Chapter 1 Overview	1
Release compatibility of the API	1
Purpose of the API	1
Architecture of the API	1
API files	1
Chapter 2 Application Programming	3
Compiling and linking Perforce applications	3
Link order	3
SSL support	3
OpenSSL Library Version	3
Link order for SSL support	4
Compiler support	4
UNIX	4
Linux	4
Windows	4
Macintosh	5
VMS	5
Sample Jamfile	5
Sample Makefile	6
Building with Jam	6
Building the sample application	7
Sending commands to the versioning service	8
Perforce settings on the user's machine	9
Connecting to the server	9
Displaying Perforce forms	10
Sending commands	10
Processing data from the server	11
Tagged data	11
Untagged Data	12
Disconnecting from the server	12
Performing file I/O	12
Handling errors	15
Connection errors	16
Server errors	16
Class overviews	16
ClientApi - Perforce server connections and commands	16
ClientProgress - progress indicators for Perforce commands	17

ClientUser - I/O for Perforce commands	17
Error - collect and report layered errors	17
ErrorLog - output error messages	18
FileSys - Perforce file I/O	18
Ignore - support for rejecting files	18
KeepAlive - support for client-side disconnection	18
MapApi - logic for view mappings	18
Options - parse and store command line options	19
Signaler - interrupt handling	19
StrBuf - string manipulation	19
StrDict - field/value manipulation	19
StrNum - small numeric strings	20
StrOps - string operations	20
StrPtr - text operations	20
StrRef - refer to existing strings	20
Chapter 3 Public Methods Reference	21
ClientApi methods	21
ClientApi::DefineClient(const char *, Error *)	21
Notes	21
Example	21
ClientApi::DefineHost(const char *, Error *)	22
Notes	22
Example	22
ClientApi::DefineIgnoreFile(const char *, Error *)	23
Notes	23
See also	23
Example	23
ClientApi::DefinePassword(const char *, Error *)	24
Notes	24
Example	24
ClientApi::DefinePort(const char *, Error *)	25
Notes	25
Example	25
ClientApi::DefineUser(const char *, Error *)	26
Notes	26
Example	26
ClientApi::Dropped()	27
Notes	27
Example	27
ClientApi::Final(Error *)	28
Notes	28
Example	28
ClientApi::GetClient()	29
Notes	29
Example	29
ClientApi::GetConfig()	30
Notes	30

Example	30
ClientApi::GetCwd()	31
Notes	31
Example	31
ClientApi::GetHost()	32
Notes	32
Example	32
ClientApi::GetIgnore()	33
Notes	33
See also	33
Example	33
ClientApi::GetIgnoreFile()	34
Notes	34
See also	34
Example	34
ClientApi::GetOs()	35
Notes	35
Example	35
ClientApi::GetPassword()	36
Notes	36
Example	36
ClientApi::GetPort()	37
Notes	37
Example	37
ClientApi::GetProtocol(const char *)	38
Notes	38
Example	38
ClientApi:: GetUser()	39
Notes	39
Example	39
ClientApi::Init(Error *)	40
Notes	40
Example	40
ClientApi::Run(const char *, ClientUser *)	41
Notes	41
Example	41
ClientApi::SetBreak(KeepAlive *breakCallback)	42
Notes	42
See also	42
Example	42
ClientApi::SetClient(const StrPtr *)	44
Notes	44
Example	44
ClientApi::SetClient(const char *)	45
Notes	45
Example	45
ClientApi::SetCwd(const StrPtr *)	46
Notes	46
Example	46
ClientApi::SetCwd(const char *)	47
Notes	47

Example	47
ClientApi::SetCwdNoReload(const StrPtr *)	48
Notes	48
Example	48
ClientApi::SetCwdNoReload(const char *)	49
Notes	49
Example	49
ClientApi::SetHost(const StrPtr *)	50
Notes	50
Example	50
ClientApi::SetHost(const char *)	51
Notes	51
Example	51
ClientApi::SetIgnoreFile(const StrPtr *)	52
Notes	52
See also	52
Example	52
ClientApi::SetIgnoreFile(const char *)	53
Notes	53
See also	53
Example	53
ClientApi::SetPassword(const StrPtr *)	54
Notes	54
Example	54
ClientApi::SetPassword(const char *)	55
Notes	55
Example	55
ClientApi::SetPort(const StrPtr *)	56
Notes	56
Example	56
ClientApi::SetPort(const char *)	57
Notes	57
Example	57
ClientApi::SetProg(const StrPtr *)	58
Notes	58
See also	58
Example	58
ClientApi::SetProg(const char *)	59
Notes	59
See also	59
Example	59
ClientApi::SetProtocol(char *, char *)	60
Notes	60
Example	61
ClientApi::SetProtocolV(char *)	63
Notes	63
Example	63
ClientApi::SetTicketFile(const StrPtr *)	64
Notes	64
Example	64
ClientApi::SetTicketFile(const char *)	65

Notes	65
Example	65
ClientApi::SetUi(ClientUser *)	66
Notes	66
Example	66
ClientApi::SetUser(const StrPtr *)	67
Notes	67
Example	67
ClientApi::SetUser(const char *)	68
Notes	68
Example	68
ClientApi::SetVersion(const StrPtr *)	69
Notes	69
See also	69
Example	69
ClientApi::SetVersion(const char *)	70
Notes	70
See also	70
Example	70
ClientProgress methods	71
ClientProgress::Description(const StrPtr *, int)	71
Notes	71
See also	71
Example	71
ClientProgress::Done(int)	73
Notes	73
See also	73
Example	73
ClientProgress::Total(long)	74
Notes	74
See also	74
Example	74
ClientProgress::Update(long)	75
Notes	75
See also	75
Example	75
ClientUser methods	76
ClientUser::CreateProgress(int)	76
Notes	76
See also	76
ClientUser::Diff(FileSys *, FileSys *, int, char *, Error *)	77
Notes	77
See also	77
Example	77
ClientUser::Diff(FileSys *, FileSys *, FileSys *, int, char *, Error *)	79
Notes	79
ClientUser::Edit(FileSys *, Error *)	80
Notes	80
Example	80
ClientUser::ErrorPause(char *, Error *)	81
Notes	81

Example	81
ClientUser::File(FileSysType)	82
Notes	82
Example	82
ClientUser::Finished()	83
Notes	83
Example	83
ClientUser::HandleError(Error *)	84
Notes	84
Example	84
ClientUser::Help(const char *const *)	85
Notes	85
Example	85
ClientUser::InputData(StrBuf *, Error *)	86
Notes	86
Example	86
ClientUser::Merge(FileSys *, FileSys *, FileSys *, FileSys *, Error *)	87
Notes	87
See also	87
Example	87
ClientUser::Message(Error *)	89
Notes	89
Example	89
ClientUser::OutputBinary(const char *, int)	90
Notes	90
Example	90
ClientUser::OutputError(const char *)	91
Notes	91
Example	91
ClientUser::OutputInfo(char, const char *)	92
Notes	92
Example	92
ClientUser::OutputStat(StrDict *)	94
Notes	94
Example	94
ClientUser::OutputText(const char *, int)	96
Notes	96
Example	96
ClientUser::ProgressIndicator()	97
Notes	97
See also	97
Example	97
ClientUser::Prompt(const StrPtr &, StrBuf &, int, Error *)	98
Notes	98
Example	98
ClientUser::RunCmd(const char *, const char *, [...], Error *)	99
Notes	99
Example	99
Error methods	101
Error::Clear()	101
Notes	101

Example	101
Error::Dump(const char *)	102
Notes	102
Example	102
Error::Fmt(StrBuf *)	103
Notes	103
Example	103
Error::Fmt(StrBuf *, int)	104
Notes	104
Example	104
Error::GetGeneric()	106
Notes	106
Example	106
Error::GetSeverity()	107
Notes	107
Example	107
Error::IsFatal()	108
Notes	108
Example	108
Error::IsWarning()	109
Notes	109
Example	109
Error::Net(const char *, const char *)	110
Notes	110
Example	110
Error::operator << (int)	111
Notes	111
Example	111
Error::operator << (char *)	112
Notes	112
Example	112
Error::operator << (const StrPtr &)	113
Notes	113
Error::operator = (Error &)	114
Notes	114
Example	114
Error::Set(enum ErrorSeverity, const char *)	115
Notes	115
Example	115
Error::Set(ErrId &)	116
Notes	116
Error::Sys(const char *, const char *)	117
Notes	117
Example	117
Error::Test()	118
Notes	118
Example	118
ErrorLog methods	119
ErrorLog::Abort()	119
Notes	119
Example	119

ErrorLog::Report()	120
Notes	120
Example	120
ErrorLog::SetLog(const char *)	121
Notes	121
Example	121
ErrorLog::SetSyslog()	122
Notes	122
Example	122
ErrorLog::SetTag(const char *)	123
Notes	123
Example	123
ErrorLog::UnsetSyslog()	124
Notes	124
Example	124
FileSys methods	125
FileSys::Chmod(FilePerm, Error *)	125
Notes	125
Example	125
FileSys::Close(Error *)	127
Notes	127
Example	127
FileSys::Create(FileSysType)	128
Notes	128
Example	128
FileSys::Open(FileOpenMode, Error *)	129
Notes	129
Example	129
FileSys::Read(const char *, int, Error *)	131
Notes	131
Example	131
FileSys::Rename(FileSys *, Error *)	133
Notes	133
Example	133
FileSys::Set(const StrPtr *)	134
Notes	134
Example	134
FileSys::Stat()	135
Notes	135
Example	135
FileSys::StatModTime()	137
Notes	137
Example	137
FileSys::Truncate()	138
Notes	138
FileSys::Unlink(Error *)	139
Notes	139
Example	139
FileSys::Write(const char *, int, Error *)	140
Notes	140
Example	140

Ignore methods	141
Ignore::Reject(const StrPtr &, const StrPtr &)	141
Notes	141
Example	141
Ignore::RejectCheck(const StrPtr &)	142
Notes	142
Example	142
KeepAlive methods	143
KeepAlive::IsAlive()	143
Notes	143
See also	143
Example	143
MapApi methods	145
MapApi::Clear()	145
Notes	145
MapApi::Count()	146
Notes	146
Example	146
MapApi::GetLeft(int)	148
Notes	148
See also	148
Example	148
MapApi::GetRight(int)	149
Notes	149
See also	149
Example	149
MapApi::GetType(int)	150
Notes	150
See also	150
Example	150
MapApi::Insert(const StrPtr &, MapType)	151
Notes	151
Example	151
MapApi::Insert(const StrPtr &, const StrPtr &, MapType)	152
Notes	152
Example	152
MapApi::Join(MapApi *, MapApi *) [static]	153
Notes	153
Example	153
MapApi::Join(MapApi *, MapDir, MapApi *, MapDir) [static]	155
Notes	155
Example	155
MapApi::Translate(const StrPtr &, StrBuf&, MapDir)	157
Notes	157
Examples	157
Options methods	158
Options::GetValue(char opt, int subopt)	158
Notes	158
See also	158
Example	158
Options::operator[](char opt)	160

Notes	160
See also	160
Example	160
Options::Parse(int &, char ** &, const char *, int, const ErrorId &, Error *)	162
Notes	162
See also	163
Example	163
Options::Parse(int &, StrPtr * &, const char *, int, const ErrorId &, Error *)	168
Notes	168
See also	168
Signaler methods	169
Signaler::Block()	169
Notes	169
See also	169
Example	169
Signaler::Catch()	170
Notes	170
See also	170
Example	170
Signaler::DeleteOnIntr(void *)	171
See also	171
Example	172
Signaler::Intr()	173
Notes	173
Caveat	173
See also	173
Example	173
Signaler::OnIntr(SignalFunc, void *)	176
Notes	176
See also	176
Example	177
Signaler::Signaler() (constructor)	178
Notes	178
See also	178
StrBuf methods	179
StrBuf::Alloc(int)	179
Notes	179
Example	180
StrBuf::Append(const char *)	181
Notes	181
Example	181
StrBuf::Append(const char *, int)	182
Notes	182
Example	182
StrBuf::Append(const StrPtr *)	184
Notes	184
Example	185
StrBuf::Clear()	187
Notes	187
See also	187
Example	187

StrBuf::StrBuf() (Constructor)	189
Notes	189
Example	189
StrBuf::StrBuf(const StrBuf &) (Copy Constructor)	190
Notes	190
Example	190
StrBuf::~StrBuf() (Destructor)	191
Notes	191
Example	191
StrBuf::Extend(char)	192
Notes	192
See also	192
Example	193
StrBuf::Extend(const char *, int)	194
Notes	194
See also	194
Example	195
StrBuf::operator =(const char *)	196
Notes	196
Example	196
StrBuf::operator =(const StrBuf &)	197
Notes	197
Example	197
StrBuf::operator =(const StrPtr &)	198
Notes	198
Example	198
StrBuf::operator =(const StrRef &)	199
Notes	199
Example	199
StrBuf::operator <<(const char *)	200
Notes	200
Example	200
StrBuf::operator <<(int)	202
Notes	202
Example	202
StrBuf::operator <<(const StrPtr *)	204
Notes	204
Example	204
StrBuf::operator <<(const StrRef &)	206
Notes	206
Example	207
StrBuf::Set(const char *)	208
Notes	208
Example	208
StrBuf::Set(const char *, int)	209
Notes	209
Example	209
StrBuf::Set(const StrPtr *)	210
Notes	210
Example	210
StrBuf::Set(const StrPtr &)	211

Notes	211
Example	211
StrBuf::StringInit()	213
Notes	213
See also	213
Example	214
StrBuf::Terminate()	216
Notes	216
Example	216
See also	216
Example	217
StrDict methods	218
StrDict::GetVar(const StrPtr &)	218
Notes	218
Example	218
StrDict::GetVar(const char *)	220
Notes	220
StrDict::GetVar(const char *, Error *)	221
Notes	221
StrDict::GetVar(const StrPtr &, int)	222
Notes	222
StrDict::GetVar(const StrPtr &, int, int)	223
Notes	223
StrDict::GetVar(int, StrPtr &, StrPtr &)	224
Notes	224
StrDict::Load(FILE *)	225
Notes	225
Example	225
StrDict::Save(FILE *)	226
Notes	226
Example	226
StrDict::SetArgv(int, char *const *)	227
Notes	227
Example	227
StrNum methods	228
StrNum::StrNum(int) (constructor)	228
Notes	228
Example	228
StrNum::Set(int)	229
Notes	229
Example	229
StrOps methods	230
StrOps::Caps(StrBuf &)	230
Example	230
StrOps::Dump(const StrPtr &)	231
Notes	231
Example	231
StrOps::Expand(StrBuf &, StrPtr &, StrDict &)	232
Notes	232
Example	232
StrOps::Expand2(StrBuf &, StrPtr &, StrDict &)	233

Notes	233
Example	233
StrOps::Indent(StrBuf &, const StrPtr &)	235
Notes	235
Example	235
StrOps::Lines(StrBuf &, char *[], int)	236
Notes	236
Example	236
StrOps::Lower(StrBuf &)	237
Notes	237
Example	237
StrOps::OtoX(const unsigned char *, int, StrBuf &)	238
Notes	238
Example	238
StrOps::Replace(StrBuf &, const StrPtr &, const StrPtr &, const StrPtr &)	239
Notes	239
Example	239
StrOps::Sub(StrPtr &, char, char)	240
Notes	240
Example	240
StrOps::Upper(StrBuf &)	241
Notes	241
Example	241
StrOps::Words(StrBuf &, const char *[], char *[], int)	242
Notes	242
Example	242
StrOps::XtoO(char *, unsigned char *, int)	243
Notes	243
Example	243
StrPtr methods	244
StrPtr::Atoi()	244
Notes	244
Example	244
StrPtr::CCompare(const StrPtr &)	245
Notes	245
See also	245
Example	245
StrPtr::Compare(const StrPtr &)	247
Notes	247
See also	247
Example	247
StrPtr::Contains(const StrPtr &)	249
Notes	249
Example	249
StrPtr::Length()	250
Example	250
StrPtr::operator [](int)	251
Notes	251
Example	251
StrPtr::operators ==, !=, >, <, <=, >= (const char *)	252
Notes	252

Example	252
StrPtr::operators ==, !=, >, <, <=, >= (const StrPtr &)	253
Notes	253
Example	253
StrPtr::Text()	254
Notes	254
Example	254
StrPtr::Value()	255
Notes	255
Example	255
StrPtr::XCompare(const StrPtr &)	256
Notes	256
See also	256
Example	256
StrRef methods	258
StrRef::StrRef() (constructor)	258
Notes	258
StrRef::StrRef(const StrPtr &) (constructor)	259
Notes	259
Example	259
StrRef::StrRef(const char *) (constructor)	260
Notes	260
Example	260
StrRef::StrRef(const char * , int) (constructor)	261
Notes	261
Example	261
StrRef::Null()	262
Notes	262
Example	262
StrRef::operator =(StrPtr &)	263
Notes	263
Example	263
StrRef::operator =(char *)	264
Notes	264
Example	264
StrRef::operator +=(int)	265
Notes	265
Example	265
StrRef::Set(char *)	266
Notes	266
Example	266
StrRef::Set(char * , int)	267
Notes	267
Example	267
StrRef::Set(const StrPtr *)	268
Notes	268
Example	268
StrRef::Set(const StrPtr &)	269
Notes	269
Example	269

License Statements	271
--------------------------	-----

About This Manual

This guide contains details about using the Perforce C/C++ API to create applications that interact correctly with the Perforce server. Be sure to read the code in the API's header and C++ files in conjunction with this guide.

Interfaces for C/C++, Java, Perl, Ruby, Python, PHP, and other languages are available from our website:

<http://www.perforce.com/product/components/apis>

Please give us feedback

If you have any feedback for us, or detect any errors in this guide, please email details to [<manual@perforce.com>](mailto:manual@perforce.com).

Release compatibility of the API

The Perforce C/C++ API is subject to change from release to release, and is not guaranteed to be source-code compatible from one release to the next. However, applications that you create using the API can run against previous releases of Perforce and will probably run against later releases of Perforce.

Support for specific features depends on the version of Perforce and the API that you use.

Purpose of the API

The Perforce C/C++ API enables you to create applications that interact with end users, send commands to the Perforce server and process data returned from the versioning service. The API is a programmatic interface, and does not send commands directly to the server.

Architecture of the API

The basic client session is managed by a C++ class called `ClientApi`. All user interaction is channeled through the `ClientUser` C++ class. The default methods of `ClientUser` implement the `p4` command line interface. To create custom client applications, create subclasses based on `ClientUser`.

API files

The Perforce C/C++ API consists of header files, link libraries, and the reference implementation of the `ClientUser` class. Only the libraries are platform-specific.

The API is packaged as an archive or zip file. The source code for the libraries is proprietary and is not included. To download the API, go to the Perforce FTP site and download the file for your platform. For example, to obtain the Macintosh version using a Web browser, use the following URL:

<ftp://ftp.perforce.com/perforce/r13.2/bin.macosx105x86/>

and download `p4api.tgz`.

(Specific API files can vary from release to release, and so are not individually described here.)

Compiling and linking Perforce applications

The following sections tell you how to build your application on the target platform.

To build `p4api.cc`, include `clientapi.h`, which includes all the necessary header files for the sample client application.

Link order

The link libraries distributed with P4API must be linked explicitly in the following order.

- `libclient.a`
- `librpc.a`
- `libsupp.a`
- `libp4sslstub.a`

In the Windows distribution, these files are named `libclient.lib`, `librpc.lib`, `libsupp.lib`, and `libp4sslstub.lib` respectively.

SSL support

The Perforce C/C++ API can be configured to support encrypted connections to the Perforce servers. To enable this support you must replace the bundled `libp4sslstub.a` (on Windows, `libp4sslstub.lib`) with copies of the OpenSSL libraries. (If you do not intend to use your application with a Perforce Server that supports encryption then you may simply compile the application with the supplied stub library.)

OpenSSL libraries are available from many sources; the most up-to-date is from <http://www.openssl.org/>.

OpenSSL Library Version

We recommend keeping current with the latest minor version matching the version referenced in the Perforce C/C++ API file `librpc.a` (or `librpc.lib` on Windows). To see which version is referenced by the library, run the following command on UNIX variants or Macintosh:

```
strings librpc.a | grep ^OpenSSL
```

On Windows:

```
strings librpc.lib | findstr /B OpenSSL
```

This command will produce an output similar to the following:

```
OpenSSL 1.0.1g 7 Apr 2014
```

In this example, you would use the latest minor version of OpenSSL that matches version 1.0.1.

Link order for SSL support

To enable SSL support, replace the stub with the ssl and crypto libraries from OpenSSL, resulting in the following link order:

- `libclient.a`
- `librpc.a`
- `libsupp.a`
- `libssl.a`
- `libcrypto.a`

On Windows, the ssl and crypto OpenSSL libraries are named `ssleay32.lib` and `libeay32.lib` respectively.

Compiler support

UNIX

For all UNIX platforms, you can use the `gcc` compiler to compile client applications with the Perforce C/C++ API. On Solaris, you can also use the Forte compiler.

Note that `clientapi.h` includes `stdhdrs.h`, which might attempt to set platform-specific defines. To ensure these defines are set properly, compile with the `-DOS_XXX` flag, where `XXX` is the platform name as specified by Perforce. (Use `p4 -V` to display the platform name; for example, for `LINUX52X86`, specify `-DOS_LINUX`.)

Some platforms require extra link libraries for sockets. Solaris requires the following compiler flags:

`-lsocket -lnsl`

Linux

Some platforms require extra link libraries for runtime support. Linux requires the following compiler flag:

`-lrt`

Windows

Using Microsoft Visual Studio (VC++), compile your client application with the following flags:

`/DOS_NT /MT /DCASE_INSENSITIVE`

For debugging, compile with the `/MTd` flag for multithreading. Do not compile with `/MD` or `/MDd`, because these flags can cause undefined behavior.

Link with the following libraries:

- `libcmt.lib`
- `oldnames.lib`
- `kernel32.lib`
- `ws2_32.lib`
- `advapi32.lib`

Macintosh

To create an MPW tool, link with the following libraries:

- `Interfacelib`
- `PPCToolLibs.o`
- `PLStringFuncsPPC.lib`
- `MSL-MPWCRuntime.lib`
- `MSL-C.PPC-MPW(NL).Lib`
- `MSL-C++.PPC.Lib`
- `ThreadsLib`
- `Mathlib`
- `InternetConfigLib`
- `OpenTransportLib`
- `OpenTptInternetLib`
- `OpenTransportAppPPC.o`

The compiler option `Enums Always Int` must be on.

VMS

Link with `sys$library:libcxxstd.olb/lib`.

Sample Jamfile

The following example shows a Jamfile that can be used to build `p4api.cc`, a Perforce application. (The example that the API is installed in the `api` subdirectory.)

```
C++FLAGS = -g -D_GNU_SOURCE ;
LINK = c++ ;OPTIM = ;
Main p4api : p4api.cc ;
ObjectHdrs p4api : api ;
LinkLibraries p4api : api/libclient.a api/librpc.a api/libsupp.a
                    api/libp4sslstub.a;
```

For more about `jam`, see [“Building with Jam” on page 6](#).

Sample Makefile

The following is a `gnumake` file for building `p4api.cc`, a Perforce application. (The example assumes the API is installed in the `api` subdirectory.)

```
SOURCES = p4api.cc
INCLUDES = -Iapi
OBJECTS = ${SOURCES:.cc=.o}
LIBRARIES = api/libclient.a api/librpc.a api/libsupp.a
            api/libp4sslstub.a
BINARY = p4api
RM = /bin/rm -f

C++ = c++
C++FLAGS = -c -g -D_GNU_SOURCE
LINK = c++
LINKFLAGS =

.cc.o :
    ${C++} ${C++FLAGS} $< ${INCLUDES}

${BINARY} : ${OBJECTS}
    ${LINK} -o ${BINARY} ${OBJECTS} ${LIBRARIES}

clean :
    - ${RM} ${OBJECTS} ${BINARY}
```

Building with Jam

Jam is a build tool, similar in its role to the more familiar `make`. Jamfiles are to `jam` as makefiles are to `make`.

Jam is an Open Source project sponsored by Perforce Software. Jam documentation, source code, and links to precompiled binaries are available from the Jam product information page at:

<http://www.perforce.com/documentation/jam>

The P4API distribution contains the necessary header files (`*.h`) and libraries (`libclient.a`, `librpc.a`, `libsupp.a`, `libp4sslstub.a`) required to compile and link a client application. The distribution also includes a sample application in C++, `p4api.cc`.

In general, the process is similar to most APIs: compile your application sources, then link them with the API libraries. The precise steps needed vary somewhat from platform to platform.

The sample application **p4api.cc** is a portable, minimal Perforce application, which we can use as an example. For purposes of this example, assume a Linux system.

Compile and link **p4api.cc** as follows:

```
$ cc -c -o p4api.o -D_GNU_SOURCE -O2 -DOS_LINUX -DOS_LINUX24 \
> -DOS_LINUXX86 -DOS_LINUX24X86 -I. -Imsg -Isupport -Isys p4api.cc

$ gcc -o p4api p4api.o libclient.a librpc.a libsupp.a libp4sslstub.a
```

The preprocessor definitions (*-Ddefinition*) vary from platform to platform.

In order to build the example across a wide variety of platforms, the API distribution also contains two "Jamfiles" (**Jamrules** and **Jamfile**), that describe how to build the sample application on each platform.

Building the sample application

Once you have Jam on your system, you can use it to build the **p4api** application. On some platforms, **jam** needs an extra hint about the operating system version. For instance, on RedHat Linux 7.1, with a 2.4 linux kernel, use **OSVER=24**:

```
$ jam
Set OSVER to 42/52 [RedHat M.n], or 22/24 [uname -r M.n]

$ uname -r
2.4.2-2

$ jam -s OSVER=24
...found 121 target(s)...
...updating 2 target(s)...
C++ p4api.o
Link p4api
Chmod1 p4api
...updated 2 target(s)...

$ p4api info
User name: you
Client name: you:home:sunflower
Client host: sunflower
Client root: /home/you
Current directory: /home/you/tmp/p4api
Client address: 207.46.230.220:35012
Server address: sunflower:1674
Server root: /home/p4/root
Server date: 2009/09/24 12:15:39 PDT
Server version: P4D/LINUX22X86/2009.1/192489 (2009/04/12)
Server license: Your Company 10 users (expires 2010/02/10)
Server license-ip: 10.0.0.2
```

As shown in the example above, `jam` does not, by default, show the actual commands used in the build (unless one of them fails). To see the exact commands `jam` generates, use the `-o file` option. This causes `jam` to write the updating actions to `file`, suitable for execution by a shell.

To illustrate; first, invoke `jam clean` to undo the build:

```
$ jam -s OSVER=42 clean
...found 1 target(s)...
...updating 1 target(s)...
Clean clean
...updated 1 target(s)...
```

Then use `jam -o build_sample` to create the build file:

```
$ jam -s OSVER=42 -o build_sample
...found 121 target(s)...
...updating 2 target(s)...
C++ p4api.o
Link p4api
Chmod1 p4api
...updated 2 target(s)...

$ cat build_sample
cc -c -o p4api.o -O2 -DOS_LINUX -DOS_LINUX42 -DOS_LINUXX86 \
-DOS_LINUX42X86 -I. -Imsg -Isupport -Isys p4api.cc
gcc -o p4api p4api.o libclient.a librpc.a libsupp.a libp4sslstub.a
chmod 711 p4api
```

The generated `build_sample` can then be executed by a shell:

```
/bin/sh build_sample
```

to produce the executable, which you can test by running `p4api info` or most other Perforce commands:

```
$ p4api changes -m 1
Change 372 on 2002/09/23 by you@you:home:sunflower 'Building API'
```

As you can see, `p4api` is a usable full-featured command line Perforce client (very similar to the `p4` command). The example's functionality comes from the default implementation of the `ClientUser` class, linked from the `libclient.a` library and the rest of the library code, for which source code is not included. The source for the default implementation is provided in the P4API distribution as `clientuser.cc`.

Sending commands to the versioning service

Perforce applications interact with the versioning service by:

1. Initializing a connection.
2. Sending commands.
3. Closing the connection.

The Perforce server does not maintain any kind of session identifier. The server identifies the sender of commands by its combination of Perforce user name and client workspace. Different processes that use the same combination of user and workspace are not distinguished by the Perforce server. To prevent processes from interfering with each other when submitting changelists, be sure to use separate client specifications for each process. If you need to create large numbers of processes, consider creating a cache of client specifications and serving them to processes as required.

Perforce settings on the user's machine

To determine which server and depot are accessed and how files are mapped, the standard classes in the API observe the Perforce settings on the user's machine. Assuming the workstation is configured correctly, your application does not need to provide logic that specifies server, port, workspace, or user.

To override the user's settings, your application can call **Set** methods.

Settings take precedence as follows, highest to lowest:

1. Values set within a Perforce application
2. Values in configuration files (**P4CONFIG**)
3. Values set as environment variables at the operating system prompt
4. Variables residing in the registry (set using the **p4 set** or **p4 set -s** commands on Windows client machines)
5. Default values defined by Perforce software or gathered from the system

Connecting to the server

To connect to the Perforce server for which the client computer is configured, your client application must call the [**client.Init\(\)**](#) method; for example:

```
client.Init( &e );
if ( e.Test() )
{
    printf("Failed to connect:\n" );
    ErrorLog::Abort(); // Displays the error and exits
}
printf( "Connected OK\n" );
```

Your program only needs to connect once. After connecting, the application can issue as many Perforce commands as required. If you intend to use tagged output, your program must call

[client.SetProtocol\(\)](#) before calling [client.Init\(\)](#). For details about using tagged output, refer to “[Tagged data](#)” on page 11.

Displaying Perforce forms

Perforce client commands that collect a large amount of input from the user (such as `p4 branch`, `p4 change`, `p4 label`) use ASCII forms. To interact with your end user, your client application program can display Perforce ASCII forms such as changelists, client specification, and so on. To display a form and collect user input, call [ClientUser::Edit\(\)](#), which puts the form into a temporary file and invokes the text editor that is configured for the client machine.

All form-related commands accept the batch mode flags `-o` and `-i`:

- `-o` causes the form to be passed to [ClientUser::OutputInfo\(\)](#).
- `-i` causes the form to be read with [ClientUser::InputData\(\)](#).

These flags allow changes to the form to occur between separate invocations of the `p4` application, rather than during a single invocation. (For details about the `-o` and `-i` global options, see the [P4 Command Reference](#).)

All form-related commands can return a form descriptor. Your application can use this descriptor to parse forms into constituent variables and to format them from their constituent variables. The `specstring` protocol variable enables this support in the server. Form descriptors are best used with the `tag` protocol variable, which causes the form data to appear using [ClientUser::OutputStat\(\)](#) rather than [OutputInfo\(\)](#).

Select the protocol with [ClientApi::SetProtocol\(\)](#) as follows:

```
client.SetProtocol( "specstring", "" );
client.SetProtocol( "tag", "" );
```

To obtain the descriptor containing the results of the method call, your application must pass a `StrDict` object to [ClientUser::OutputStat\(\)](#). Your application can override the [OutputStat\(\)](#) method in a class derived from `ClientUser`. The Perforce C/C++ API calls this derived method, passing it the output from the command.

Sending commands

The following example illustrates how you set up arguments and execute the `p4 fstat` command on a file named `Jam.html`.

```
char file[] = "Jam.html";
char *filep = &file[0];
client.SetArgv( 1, &filep );
client.Run( "fstat", &ui );
```

For commands with more arguments, use an approach like the following:

```

char    *argv[] = { "-C", "-l", 0, 0 };
int     argc   = 2;
char    *file   = "Jam.html";
argv[ argc++ ] = file;
client.SetArgv( argc, argv );
client.Run( "fstat", &ui );

```

Processing data from the server

The Perforce server (release 99.2 and higher) can return tagged data (name-value pairs) for some commands. The following sections tell you how to handle tagged and untagged data.

Tagged data

The following example shows data returned in tagged format by `p4 -Ztag clients` command. (The `-Z` flag specifies that tagged data is to be returned; this flag is unsupported and intended for debugging use.)

```

...client xyzzy
...Update 972354556
...Access 970066832
...Owner gerry
...Host xyzzy
...Description Created by gerry

```

To enable the Perforce server to return tagged data, your application must call [SetProtocol\("tag", ""\)](#) before connecting to the server. To extract values from tagged data, use the `GetVars` method.

The following Perforce commands can return tagged output. A release number, when present, indicates the first Perforce server release that supports tagged output for the command.

<code>p4 add (2005.2)</code>	<code>p4 fixes (2000.1)</code>	<code>p4 protect -o</code>
<code>p4 branch -o</code>	<code>p4 group -o</code>	<code>p4 reviews (2005.2)</code>
<code>p4 branches</code>	<code>p4 groups (2004.2)</code>	<code>p4 reopen (2005.2)</code>
<code>p4 change -o (2005.2)</code>	<code>p4 have (2005.2)</code>	<code>p4 resolve (2005.2)</code>
<code>p4 changes</code>	<code>p4 info (2003.2)</code>	<code>p4 revert (2005.2)</code>
<code>p4 client -o</code>	<code>p4 integrate (2005.2)</code>	<code>p4 review (2005.2)</code>
<code>p4 clients</code>	<code>p4 job -o</code>	<code>p4 submit (2005.2)</code>
<code>p4 counter (2005.2)</code>	<code>p4 jobs</code>	<code>p4 sync (2005.2)</code>
<code>p4 counters (2000.2)</code>	<code>p4 jobspec -o</code>	<code>p4 trigger -o</code>

<code>p4 delete (2005.2)</code>	<code>p4 label -o</code>	<code>p4 typemap -o (2000.1)</code>
<code>p4 describe</code>	<code>p4 labels</code>	<code>p4 unlock (2005.2)</code>
<code>p4 depots (2005.2)</code>	<code>p4 labelsync (2005.2)</code>	<code>p4 user -o</code>
<code>p4 diff (2005.2)</code>	<code>p4 lock (2005.2)</code>	<code>p4 users</code>
<code>p4 diff2 (2004.2)</code>	<code>p4 logger (2000.2)</code>	<code>p4 verify (2005.2)</code>
<code>p4 edit (2005.2)</code>	<code>p4 monitor (2005.2)</code>	<code>p4 where (2004.2)</code>
<code>p4 filelog</code>	<code>p4 obliterate (2005.2)</code>	
<code>p4 fix (2005.2)</code>	<code>p4 opened</code>	

The tagged output of some commands may have changed since the command's first appearance in this table. The output of `p4 resolve` and `p4 diff` are not fully tagged. For complete details, see the release notes:

<http://www.perforce.com/perforce/r15.1/user/p4apinotes.txt>

To obtain output in the form used by earlier revisions of Perforce, set the `api` variable according to the notes for [SetProtocol\(\)](#).

Untagged Data

To handle untagged data, create a subclass of `ClientUser` for every type of data required and provide alternate implementations of [ClientUser::OutputInfo\(\)](#), [OutputBinary\(\)](#), [OutputText\(\)](#), and [OutputStat\(\)](#).

Disconnecting from the server

After your application has finished interacting with the Perforce server, it must disconnect as illustrated below:

```
client.Final( &e );
e.Abort();
```

To ensure the application can exit successfully, make sure to call [ClientApi::Final\(\)](#) before calling the destructor.

Performing file I/O

The default client file I/O implementation returns a `FileSys` object, which is described in `filesys.h`. To intercept client workspace file I/O, replace the `FileSys *ClientUser::File()` method by subclassing `ClientUser`.

The following example illustrates how you can override **FileSys**.

```
#include "p4/clientapi.h"
class MyFileSys : public FileSys {
public:

    MyFileSys();
    ~MyFileSys();

    virtual void Open( FileMode mode, Error *e );
    virtual void Write( const char *buf, int len, Error *e );
    virtual int Read( char *buf, int len, Error *e );
    virtual int ReadLine( StrBuf *buf, Error *e );
    virtual void Close( Error *e );
    virtual int Stat();
    virtual int StatModTime();
    virtual void Truncate( Error *e );
    virtual void Unlink( Error *e = 0 );
    virtual void Rename( FileSys *target, Error *e );
    virtual void Chmod( FilePerm perms, Error *e );

protected:
    int nchars;
} ;

MyFileSys::MyFileSys()
{
    nchars = 0;
}

MyFileSys::~MyFileSys()
{
    printf( "Number of characters transferred = %d\n", nchars );
}

void MyFileSys::Open( FileMode mode, Error *e )
{
    printf( "In MyFileSys::Open()\n" );
}

void MyFileSys::Write( const char *buf, int len, Error *e )
{
    printf( "In MyFileSys::Write()\n" );
    printf( "%s", buf );
    nchars = nchars + len;
}

int MyFileSys::Read( char *buf, int len, Error *e )
{
    printf( "In MyFileSys::Read()\n" );
    return 0;
}

int MyFileSys::ReadLine( StrBuf *buf, Error *e )
{
```

```
    printf( "In MyFileSys::ReadLine()\n" );
    return 0;
}

void MyFileSys::Close( Error *e )
{
    printf( "In MyFileSys::Close()\n" );
}

int MyFileSys::Stat()
{
    printf( "In MyFileSys::Stat()\n" );
    return 0;
}

int MyFileSys::StatModTime()
{
    printf( "In MyFileSys::StatModTime()\n" );
    return 0;
}

void MyFileSys::Truncate( Error *e )
{
    printf( "In MyFileSys::Truncate()\n" );
}

void MyFileSys::Unlink( Error *e = 0 )
{
    printf( "In MyFileSys::Unlink()\n" );
}

void MyFileSys::Rename( FileSys *target, Error *e )
{
    printf( "In MyFileSys::Rename()\n" );
}

void MyFileSys::Chmod( FilePerm perms, Error *e )
{
    printf( "In MyFileSys::Chmod()\n" );
}

class ClientUserSubclass : public ClientUser {
public:
    virtual FileSys *File( FileSysType type );
};

FileSys *ClientUserSubclass::File( FileSysType type )
{
    return new MyFileSys;
}

int main( int argc, char **argv )
{
    ClientUserSubclass ui;
    ClientApi client;
    Error e;
```

```
char force[] = "-f";
char file[] = "hello.c";
char *args[2] = { &force[0], &file[0] };

// Connect to server

client.Init( &e );
e.Abort();

// Run the command "sync -f hello.c"

client.SetArgv( 2, &args[0] );
client.Run( "sync", &ui );

// Close connection

client.Final( &e );
e.Abort();
return 0;
}
```

The preceding program produces the following output when you run it.

```
% ls -l hello.c
-r--r--r-- 1 member  team          41 Jul 30 16:57 hello.c
% cat hello.c
main()
{
    printf( "Hello World!\n" );
}
% samplefilesys
//depot/main/hello.c#1 - refreshing /work/main/hello.c
In MyFileSys::Stat()
In MyFileSys::Open()
In MyFileSys::Write()
main()
{
    printf( "Hello World!\n" );
}
In MyFileSys::Close()
Number of characters transferred = 41
```

Handling errors

To encapsulate error handling in a maintainable way, subclass `ClientUser` at least once for every command you want to run and handle errors in the [HandleError\(\)](#) method of the derived class.

To best handle the formatting of error text, parse the error text, looking for substrings of anticipated errors, and display the rest. For example:

```

void P4CmdFstat::HandleError(Error *e)
{
    StrBuf m;
    e->Fmt( &m );
    if ( strstr( m.Text(), "file(s) not in client view." ) )
        e->Clear();
    else if ( strstr( m.Text(), "no such file(s)" ) )
        e->Clear();
    else if ( strstr( m.Text(), "access denied" ) )
        e->Clear();
    else
        this->e = *e;
}

```

Connection errors

If any error occurs when attempting to connect with the Perforce server, the [ClientApi::Init\(\)](#) method returns an error code in its `Error` parameter.

Server errors

The [ClientApi::Final\(\)](#) method returns any I/O errors that occurred during [ClientApi::Run\(\)](#) in its `Error` parameter. [ClientApi::Final\(\)](#) returns a non-zero value if any I/O errors occurred or if [ClientUser::OutputError\(\)](#) was called (reporting server errors) during the command run.

To report errors generated by the server during an operation, your application can call the [ClientUser::HandleError\(\)](#) method. The default implementation of [HandleError\(\)](#) is to format the error message and call [ClientUser::OutputError\(\)](#), which, by default, writes the message to standard output. [HandleError\(\)](#) has access to the raw `Error` object, which can be examined with the methods defined in `error.h`. Prior to release 99.1, Perforce servers invoked [OutputError\(\)](#) directly with formatted error text.

Class overviews

The following classes comprise the Perforce API. Public methods for these classes are documented in [Chapter 3, “Public Methods Reference” on page 21](#).

ClientApi - Perforce server connections and commands

The `ClientApi` class represents a connection with the Perforce server.

Member functions in this class are used to establish and terminate the connection with the server, establish the settings and protocols to use while running commands, and run Perforce commands over the connection.

I/O is handled by a `ClientUser` object, and errors are captured in an `Error` object. A `ClientApi` object maintains information about client-side settings (`P4PORT`, etc.) and protocol information, such as the server version, and whether “tagged” output is enabled.

`ClientApi` does not include any virtual functions, and typically does not need to be subclassed.

Any Perforce command that is executed must be invoked through `ClientApi::Run()` after first opening a connection using `ClientApi::Init()`. A single connection can be used to invoke multiple commands by calling `Run()` multiple times after a single `Init()`; this approach provides faster performance than using multiple connections.

ClientProgress - progress indicators for Perforce commands

The `ClientProgress` class introduced in 2012.2 provides a means to report on the progress of running commands; you can customize this behavior by subclassing `ClientUser` and `ClientProgress`.

In `ClientUser`, implement `ClientUser::CreateProgress()` and `ClientUser::ProgressIndicator()`. In `ClientProgress`, implement `ClientProgress::Description()`, `ClientProgress::Total()`, `ClientProgress::Update()`, and `ClientProgress::Done()`.

The methods of your `ClientProgress` object will be called during the life of a server command. Usually, `Description()` is called first with a `description` and a `units` from the server; the units of measure apply to the `Total()` and `Update()` methods. `Total()` is called if there is a known upper bound to the number of units, while `Update()` is called from time to time as progress is made. If your `Update()` implementation returns non-zero, the API assumes the user has also attempted to cancel the operation. `Done()` is called last, with the `fail` argument being non-zero in case of failure. When the command is complete, the API destroys the object by calling the destructor.

Default implementations are used in the `p4` command-line client, and report on the progress of `p4 -I submit` and `p4 -I sync -q`.

ClientUser - I/O for Perforce commands

The `ClientUser` class is used for all client-side input and output. This class implements methods that return output from the server to the user after a command is invoked, and gather input from the user when needed.

Member functions in this class are used to format and display server output, invoke external programs (such as text editors, diff tools, and merge tools), gather input for processing by the server, and to handle errors.

Customized functionality in a Perforce application is most typically implemented by subclassing `ClientUser`. In order to enable such customization, nearly all of `ClientUser`'s methods are virtual. The default implementations are used in the `p4` command-line client.

Error - collect and report layered errors

Member functions in this class are used to store error messages, along with information about generic type and severity, format error messages into a form suitable for display to an end user, or marshal them into a form suitable for transferring over a network.

`Error` objects are used to collect information about errors that occur while running a Perforce command.

When a connection is opened with [ClientApi::Init\(\)](#), a reference to an **Error** object is passed as an argument to [Init\(\)](#). This **Error** object then accumulates any errors that occur; a single **Error** object can hold information about multiple errors. The **Error** can then be checked, and its contents reported if necessary.

Although **Error** itself does not provide any virtual methods that can be re-implemented, the manner in which errors are handled can be changed by re-implementing [ClientUser::HandleError\(\)](#). The default behavior for handling errors typically consists of simply formatting and displaying the messages, but **Error** objects maintain additional information, such as severity levels, which can be used to handle errors more intelligently.

ErrorLog - output error messages

The **ErrorLog** class is used to report layered errors, either by displaying error messages to **stderr**, or by redirecting them to logfiles. On UNIX systems, error messages can also be directed to the **syslog** daemon.

FileSys - Perform file I/O

The **FileSys** class provides a platform-independent set of methods used to create, read and write files to disk.

You can intercept the file I/O and implement your own client workspace file access routines by replacing **FileSys** [*ClientUser::File\(\)](#) in a **ClientUser** subclass.

Note

Replacing the existing I/O routines is non-trivial. Your replacement routines must handle all special cases, including cross-platform file issues.

Unless your application has highly specialized requirements, (for instance, performing all file I/O in memory rather than on disk), this approach is not recommended.

If you intend to replace [File\(\)](#), all of the virtual methods documented are required. The non virtual methods are not required and not documented.

Ignore - support for rejecting files

The **Ignore** class has two methods, [Ignore::Reject\(\)](#) and [Ignore::RejectCheck\(\)](#). Both methods are used by applications to determine whether files destined to be opened for add will be rejected due to matching an entry in an ignore files.

KeepAlive - support for client-side disconnection

The **KeepAlive** class has only one method, [KeepAlive::IsAlive\(\)](#). The method is used by applications to support client-side command termination.

MapApi - logic for view mappings

The **MapApi** class allows a client application to duplicate the logic used by the server when interpreting and combining view mappings such as branch views, client views, and protections.

Each **MapApi** object represents a single mapping that is built by calling [**MapApi::Insert\(\)**](#) to add new lines. A file can be translated through the mapping or tested for inclusion by calling [**MapApi::Translate\(\)**](#). Two **MapApi** objects may be combined into a single new **MapApi** object (for example, a client view and a protection table may be joined into a single mapping that represents all files in the client view that are included in the protection table) by calling [**MapApi::Join\(\)**](#).

Options - parse and store command line options

The **Options** class encapsulates functions useful for parsing command line flags, and also provides a means of storing flag values.

Sample code is provided to illustrate how [**Options::GetValue\(\)**](#) and [**Options::Parse\(\)**](#) work together to parse command line options.

Signaler - interrupt handling

The **Signaler** class enables the API programmer to register functions that are to be called when the client application receives an interrupt signal. The **Signaler** class maintains a list of registered functions and calls each one in turn.

By default, after all of the registered functions have been executed, the process exits, returning -1 to the operating system.

StrBuf - string manipulation

The **StrBuf** class is the preferred general string manipulation class. This class manages the memory associated with a string, including allocating new memory or freeing old memory as required.

The **StrBuf** class is derived from the **StrPtr** class, and makes heavy use of the **buffer** and **length** members inherited from the **StrPtr** class. The **buffer** member of a **StrBuf** instance is a pointer to the first byte in the string. The **length** member of a **StrBuf** instance is the length of the string.

Most member functions maintain the string pointed to by the **buffer** member of a **StrBuf** as a null-terminated string. However, the **Clear** member function does not set the first byte of the string to a null byte, nor does the **Extend** member function append a null byte to an extended string. If you need to maintain a string as null-terminated when using the [**Clear\(\)**](#) and [**Extend\(\)**](#) member functions, follow the calls to [**Clear\(\)**](#) and [**Extend\(\)**](#) with calls to [**Terminate\(\)**](#).

A number of member functions move the string pointed to by a **StrBuf**'s **buffer**, and change the **buffer** member to point to the new location. For this reason, do not cache the pointer. Use [**StrPtr::Text\(\)**](#) whenever the pointer a **StrBuf**'s **buffer** is required.

StrDict - field/value manipulation

The **StrDict** class provides a dictionary object of **StrPtr**'s with a simple Get/Put interface. This class contains abstract methods and therefore cannot be instantiated, but its subclasses adhere to the basic interface documented here.

ClientApi is a descendant of **StrDict**; most notably, the [**StrDict::SetArgv\(\)**](#) method is used to set the arguments to a Perforce command before executing it with [**ClientApi::Run\(\)**](#).

The [ClientUser::OutputStat\(\)](#) method takes a **StrDict** as an argument; the **StrDict** methods are therefore necessary to process data with [OutputStat\(\)](#). Note that pulling information from a **StrDict** is typically easier than trying to parse the text given to [OutputInfo\(\)](#).

StrNum - small numeric strings

The **StrNum** class, derived from **StrPtr**, is designed to hold a small string representing a number. Like a **StrBuf**, it handles its own memory. Unlike a **StrBuf**, it does not dynamically resize itself, and is limited to 24 characters, meaning that the largest number that can be represented by a **StrNum** is 999999999999999999999999.

StrOps - string operations

StrOps is a memberless class containing static methods for performing operations on strings.

StrPtr - text operations

The **StrPtr** class is a very basic pointer/length pair used to represent text.

This class provides a number of methods for comparison and reporting, but it is not in itself very useful for storing data; the **StrBuf** child class is a more practical means of storing data, as it manages its own memory.

StrRef - refer to existing strings

The **StrRef** class is a simple pointer/length pair representing a string. The **StrRef** class is derived from **StrPtr** and does not add a great deal of new functionality to that class, with the exception of methods that make the pointer mutable (and therefore usable), whereas a base **StrPtr** is read-only.

As its name suggests, a **StrRef** serves as a reference to existing data, as the class does not perform its own memory allocation. The **StrBuf** class is most useful when storing and manipulating existing strings.

ClientApi methods

ClientApi::DefineClient(const char *, Error *)

Sets P4CLIENT in the Windows registry and applies the setting immediately.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new P4CLIENT setting
	<code>Error *e</code> an <code>Error</code> object
Returns	<code>void</code>

Notes

To make the new P4CLIENT setting apply to the next command executed with [Run\(\)](#), [DefineClient\(\)](#) sets the value in the registry and then calls [SetClient\(\)](#).

Example

The following code illustrates how this method might be used to make a Windows client application start up with a default P4CLIENT setting.

```
client.Init( &e );
client.DefineClient( "default_workspace", &e );
```

ClientApi::DefineHost(const char *, Error *)

Sets P4HOST in the Windows registry and applies the setting immediately.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new P4HOST setting
	<code>Error *e</code> an Error object
Returns	<code>void</code>

Notes

To make the new P4HOST setting apply to the next command executed with [Run\(\)](#), [DefineHost\(\)](#) sets the value in the registry and then calls [SetHost\(\)](#).

Example

The following code illustrates how this method might be used to make a Windows client application start up with a default P4HOST setting.

```
client.Init( &e );
client.DefineHost( "default_host", &e );
```

ClientApi::DefineIgnoreFile(const char *, Error *)

Sets P4IGNORE in the Windows registry and applies the setting immediately.

Virtual?	No				
Class	ClientApi				
Arguments	<table> <tr> <td>const char *c</td> <td>the new P4IGNORE setting</td> </tr> <tr> <td>Error *e</td> <td>an Error object</td> </tr> </table>	const char *c	the new P4IGNORE setting	Error *e	an Error object
const char *c	the new P4IGNORE setting				
Error *e	an Error object				
Returns	void				

Notes

To make the new P4IGNORE setting apply to the next command executed with [Run\(\)](#), [DefineIgnoreFile\(\)](#) sets the value in the registry and then calls [SetIgnoreFile\(\)](#).

See also

[ClientApi::GetIgnore\(\)](#)
[ClientApi::GetIgnoreFile\(\)](#)
[ClientApi::SetIgnoreFile\(\)](#)

Example

The following code illustrates how this method might be used to make a Windows client application start up with a default P4IGNORE setting.

```
# include "clientapi.h"

int main()
{
    ClientApi client;
    Error e;

    client.Init( &e );
    client.DefineIgnoreFile( ".p4ignore", &e );
}
```

ClientApi::DefinePassword(const char *, Error *)

Sets P4PASSWD in the Windows registry and applies the setting immediately.

Virtual?	No	
Class	ClientApi	
Arguments	<code>const char *c</code>	the new P4PASSWD setting
	<code>Error *e</code>	an Error object
Returns	<code>void</code>	

Notes

To make the new P4PASSWD setting apply to the next command executed with [Run\(\)](#), [DefinePassword\(\)](#) sets the value in the registry and then calls [SetPassword\(\)](#).

[DefinePassword\(\)](#) does *not* define a new server-side password for the user.

Call [DefinePassword\(\)](#) with either the plaintext password, or its MD5 hash

Example

The following code illustrates how this method might be used to make a Windows client application start up with a default P4PASSWD setting.

```
client.Init( &e );
client.DefinePassword( "default_pass", &e );
```

ClientApi::DefinePort(const char *, Error *)

Sets P4PORT in the Windows registry and applies the setting immediately.

Virtual?	No				
Class	ClientApi				
Arguments	<table> <tr> <td>const char *c</td><td>the new P4PORT setting</td></tr> <tr> <td>Error *e</td><td>an Error object</td></tr> </table>	const char *c	the new P4PORT setting	Error *e	an Error object
const char *c	the new P4PORT setting				
Error *e	an Error object				
Returns	void				
Notes					

In order to make the new P4PORT setting apply to the next client connection opened with [Init\(\)](#), [DefinePort\(\)](#) sets the value in the registry and then calls [SetPort\(\)](#).

Example

The following code illustrates how this method might be used to make a Windows client application automatically set itself to access a backup server if the primary server fails to respond. (This example assumes the existence of a backup server that perfectly mirrors the primary server.)

```
client.Init( &e );

if ( e.IsFatal() )
{
    e.Clear();
    ui.OutputError( "No response from server - switching to backup!\n" );
    client.DefinePort( "backup:1666", &e );
    client.Init( &e );
}
```

The first command to which the primary server fails to respond results in the error message and the program reinitializing the client to point to the server at **backup:1666**. Subsequent commands do not display the warning because the new P4PORT value has been set in the registry.

ClientApi::DefineUser(const char *, Error *)

Sets P4USER in the Windows registry and applies the setting immediately.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new P4USER setting
	<code>Error *e</code> an Error object
Returns	<code>void</code>

Notes

To make the new P4USER setting apply to the next command executed with [Run\(\)](#), [DefineUser\(\)](#) sets the value in the registry and then calls [SetUser\(\)](#).

Example

The following code illustrates how this method might be used to make a Windows client application start up with a default P4USER setting.

```
client.Init( &e );
client.DefineUser( "default_user", &e );
```

ClientApi::Dropped()

Check if connection is no longer usable.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	int nonzero if the connection has dropped

Notes

[Dropped\(\)](#) is usually called after [Run\(\)](#); it then checks whether the command completed successfully. If the [Init\(\)](#) is only followed by one [Run\(\)](#), as in [p4api.cc](#), calling [Final\(\)](#) and then checking the [Error](#) is sufficient to see whether the connection was dropped. However, if you plan to make many calls to [Run\(\)](#) after one call to [Init\(\)](#), [Dropped\(\)](#) provides a way to check that the commands are completing without actually cleaning up the connection with [Final\(\)](#).

Example

The [Dropped\(\)](#) method is useful if you want to reuse a client connection multiple times, and need to make sure that the connection is still alive.

For example, an application for stress-testing a Perforce server might run "p4 have" 10,000 times or until the connection dies:

```
ClientApi client;
MyClientUser ui; //this ClientUser subclass doesn't output anything.
Error e;

client.Init( &e );
int count = 0;
while ( !( client.Dropped() ) && count < 10000 )
{
    count++;
    client.Run( "have", &ui );
}
printf( "Checked have list %d times.\n", count );
client.Final( &e ); // Clean up connection.
```

If the [Dropped\(\)](#) result is true, the [while](#) loop ends. The actual error message remains inaccessible until after the call to [client.Final\(\)](#) to close the connection and store the error.

ClientApi::Final(Error *)

Close connection and return error count.

Virtual?	No	
Class	ClientApi	
Arguments	<code>Error *e</code>	an <code>Error</code> object
Returns	<code>int</code>	final number of errors

Notes

Call this method after you are finished using the `ClientApi` object in order to clean up the connection. Every call to [Init\(\)](#) must eventually be followed by exactly one call to [Final\(\)](#).

Example

The following example is a slight modification of `p4api.cc`, and reports the number of errors before the program exits:

```
client.Init( &e );

client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );

printf( "There were %d errors.\n", client.Final( &e ) );
```

ClientApi::GetClient()

Get current client setting.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the client setting

Notes

The return value of [GetClient\(\)](#) is a fixed reference to this `ClientApi` object's setting.

Assigning the return value to a `StrPtr` results in a `StrPtr` containing a `Text()` value that changes if the `ClientApi` object's client setting changes.

Assigning the return value to a `StrBuf` copies the text in its entirety for future access, rather than simply storing a reference to data that might change later.

Under some circumstances, [GetClient\(\)](#) calls [GetHost\(\)](#) and returns that value - specifically, if no suitable P4CLIENT value is available in the environment, or previously set with [SetClient\(\)](#). (This is why, under the Perforce client, client name defaults to the host name if not explicitly set.)

In some instances, [GetHost\(\)](#) does not return valid results until after a call to [Init\(\)](#) - see the [GetHost\(\)](#) documentation for details.

Example

This example demonstrates the use of [GetClient\(\)](#) and the difference between `StrPtrs` and `StrBufs`.

```
ClientApi client;
StrPtr p;
StrBuf b;

client.Init();
client.SetClient( "one" );
p = client.GetClient();
b = client.GetClient();
client.SetClient( "two" );

printf( "Current client %s = %s\n", client.GetClient().Text(), p.Text() );
printf( "Previous client setting was %s\n", b.Text() );
```

Executing the preceding code produces the following output:

```
Current client two = two
Previous client setting was one
```

ClientApi::GetConfig()

Get current configuration file.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the config file setting

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the `P4CONFIG` has not been set, [GetConfig\(\)](#) returns "noconfig".

Example

The following example demonstrates the usage of [GetConfig\(\)](#).

```
ClientApi client;  
  
printf( "Current P4CONFIG is %s\n", client.GetConfig().Text() );
```

Executing the preceding code without having specified a configuration file produces the following output:

```
C:\perforce> a.out  
Current P4CONFIG is noconfig
```

ClientApi::GetCwd()

Get current working directory.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the name of the current directory

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the working directory has been set by a call to [SetCwd\(\)](#) or [SetCwdNoReload\(\)](#), subsequent calls to [GetCwd\(\)](#) return that setting regardless of the actual working directory.

Example

The following example demonstrates the usage of [GetCwd\(\)](#).

```
ClientApi client;
printf( "Current directory is %s\n", client.GetCwd().Text() );
```

Executing the preceding code produces the following output:

```
C:\perforce> a.out
Current directory is c:\perforce
```

ClientApi::GetHost()

Get client hostname.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the hostname

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

In some instances, [GetHost\(\)](#) is not valid until after the network connection has been established with [Init\(\)](#). [GetHost\(\)](#) attempts to pull its value from earlier [SetHost\(\)](#) calls, then from `P4HOST` in the environment, and then from the value of "hostname" returned by the client OS. If none of these is applicable, a reverse DNS lookup is performed, but the lookup will not work unless the connection has been established with [Init\(\)](#).

To guarantee valid results, call [GetHost\(\)](#) only after [Init\(\)](#) or [SetHost\(\)](#). As [GetHost\(\)](#) may sometimes be called during the execution of [GetClient\(\)](#), this warning applies to both methods.

As noted above, [GetHost\(\)](#) does not necessarily return the actual hostname of the machine if it has been overridden by `P4HOST` or an earlier call to [SetHost\(\)](#).

Example

The following example demonstrates the usage of [GetHost\(\)](#).

```
ClientApi client;
client.Init();

printf( "Client hostname is %s\n", client.GetHost().Text() );
```

Executing the preceding code produces the following output:

```
shire% a.out
Client hostname is shire
```

ClientApi::GetIgnore()

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>Ignore *i</code> an Ignore object, which can be used to determine if a path is ignored.

Notes

If P4IGNORE is not set, no paths are ignored.

See also

[ClientApi::DefineIgnoreFile\(\)](#)
[ClientApi::GetIgnoreFile\(\)](#)
[ClientApi::SetIgnoreFile\(\)](#)

Example

This example demonstrates the use of [GetIgnore\(\)](#).

```
if ( client->GetIgnore()->Reject( *clientPath,
                                    client->GetIgnoreFile() ) )
{
    /* handling for ignored file */
}
```

ClientApi::GetIgnoreFile()

Get the full path name of the ignore file used for the current connection.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the path of the ignore file.

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the `P4IGNORE` is unset, [GetIgnoreFile\(\)](#) returns an uninitialized `StrPtr`.

See also

[ClientApi::DefineIgnoreFile\(\)](#)
[ClientApi::GetIgnore\(\)](#)
[ClientApi::SetIgnoreFile\(\)](#)

Example

This example demonstrates the use of [GetIgnoreFile\(\)](#).

```
# include "clientapi.h"

int main()
{
    ClientApi client;
    printf( "The current ignore file is '%s'\n",
           client.GetIgnoreFile().Text() );
}
```

Executing the preceding code produces output similar to the following:

```
The current ignore file is .p4ignore
```

ClientApi::GetOs()

Get name of client operating system.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the OS string

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

[GetOs\(\)](#) returns one of "UNIX", "vms", "NT", "Mac", or null.

Example

The following example demonstrates the usage of [GetOs\(\)](#).

```
ClientApi client;  
  
printf( "Client OS is %s\n", client.GetOs().Text() );
```

Executing the preceding code under Windows produces the following output:

```
C:\perforce> a.out  
Client OS is NT
```

Executing the preceding code on a UNIX machine produces the following output:

```
shire$ a.out  
Client OS is UNIX
```

ClientApi::GetPassword()

Get password setting.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the password

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

This method returns the password currently set on the client, which may or may not be the one set on the server for this user. The command "p4 passwd" sets `P4PASSWD` on the client machine to an MD5 hash of the actual password, in which case [GetPassword\(\)](#) returns this MD5 hash rather than the plaintext version.

However, if the user sets `P4PASSWD` directly with the plaintext version, [GetPassword\(\)](#) returns that plaintext version. In both instances, the result is the same as that displayed by "p4 set" or an equivalent command that displays the value of the `P4PASSWD` environment variable.

[SetPassword\(\)](#) overrides the `P4PASSWD` value, and subsequent [GetPassword\(\)](#) calls return the new value set by [SetPassword\(\)](#) rather than the one in the environment.

Example

The following example demonstrates the usage of [GetPassword\(\)](#).

```
ClientApi client;
printf( "Your password is %s\n", client.GetPassword().Text() );
```

The following session illustrates the effect of password settings on [GetPassword\(\)](#):

```
> p4 set P4PASSWD=p455w04d
> a.out
Your password is p455w04d

> p4 passwd
Enter new password:
Re-enter new password:
Password updated.

> a.out
Your password is 6F577E10961C8F7B519501097131787C
```

ClientApi::GetPort()

Get current port setting.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the port setting

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

If the environment variable `P4PORT` is unset, [GetPort\(\)](#) sets the port to the default value of `perforce:1666`.

Example

The following example demonstrates the usage of [GetPort\(\)](#).

```
ClientApi client;  
  
printf( "You're looking for a server at %s\n", \  
       client.GetPort().Text() );
```

Executing the preceding code produces the following output:

```
You're looking for a server at perforce:1666
```

ClientApi::GetProtocol(const char *)

Get protocol information for this connection.

Virtual?	No	
Class	ClientApi	
Arguments	<code>const char *v</code>	the name of the protocol variable being checked
Returns	<code>StrPtr *</code>	a pointer to the variable's value

Notes

If the variable is unset, the return value is null. If there is a value, it will be a number in most cases, but in the form of a `StrPtr` rather than an `int`.

Call [GetProtocol\(\)](#) only after a call to [Run\(\)](#), because protocol information is not available until after a call to [Run\(\)](#). Calling [GetProtocol\(\)](#) before [Run\(\)](#) results in a return value of `null`, which looks misleadingly like an indication that the variable is unset.

[GetProtocol\(\)](#) reports only on variables set by the server, not variables set by the client with calls to [SetProtocol\(\)](#).

Example

The following example code checks whether the server is case-sensitive.

```

...
client.Init( &e );
...
client.Run();

if ( client.Dropped() )
{
    client.Final( &e );
}

if ( client.GetProtocol( "nocase" ) )
    printf( "Server case-insensitive.\n" );
else
    printf( "Server is case-sensitive.\n" );

```

ClientApi:: GetUser()

Get current user setting.

Virtual?	No
Class	ClientApi
Arguments	None
Returns	<code>const StrPtr &</code> a reference to the user setting

Notes

See [GetClient\(\)](#) for more about the `StrPtr` return value.

Example

The following example demonstrates the usage of [GetUser\(\)](#).

```
ClientApi client;  
printf( "Your username is %s\n", client.GetUser().Text() );
```

Executing the preceding code as `testuser` produces the following output:

```
Your username is testuser
```

ClientApi::Init(Error *)

Establish a connection and prepare to run commands.

Virtual?	No	
Class	ClientApi	
Arguments	Error *e	an Error object
Returns	void	

Notes

[Init\(\)](#) must be called to establish a connection before any commands can be sent to the server. Each call to [Init\(\)](#) must be followed by exactly one call to [Final\(\)](#).

If an error occurs during [Init\(\)](#), it is most likely a connection error, with a severity of E_FATAL.

Example

The following code from `p4api.cc` opens a connection with [Init\(\)](#), sets arguments, runs a command, and closes the connection with [Final\(\)](#).

```
ClientUser ui;
ClientApi client;
Error e;

client.Init( &e );

client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );
client.Final( &e );
return 0;
```

ClientApi::Run(const char *, ClientUser *)

Run a Perforce command and return when it completes.

Virtual?	No
Class	ClientApi
Arguments	const char *func the name of the command to run
	ClientUser *ui a pointer to a ClientUser object.
Returns	void

Notes

The **func** argument to [Run\(\)](#) is the Perforce command to run, (for instance, **info** or **files**). Command arguments are not included and must be set separately with [StrDict::SetArgv\(\)](#).

Initialize the connection with [Init\(\)](#) before calling [Run\(\)](#), because without a connection, no commands can be sent to the server. Attempting to call [Run\(\)](#) before [Init\(\)](#) will probably result in a fatal runtime error.

[Run\(\)](#) returns only after the command completes. Note that all necessary calls to **ClientUser** methods are made during the execution of [Run\(\)](#), as dictated by the server.

Example

The code below runs **p4 info**, using [ClientUser::OutputInfo\(\)](#) to display the results to the user. If a subclass of **ClientUser** is used here as the **ui** argument, that subclass's implementation of [OutputInfo\(\)](#) is used to display the results of the command.

```

ClientApi client;
ClientUser ui;
Error e;

client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );

```

ClientApi::SetBreak(KeepAlive *breakCallback)

Establish a callback that is called every 0.5 seconds during command execution.

Virtual?	No
Class	ClientApi
Arguments	<code>KeepAlive *breakCallback</code> keepalive callback for user interrupt
Returns	<code>void</code>

Notes

To establish the callback routine, you must call [SetBreak\(\)](#) after [ClientApi::Init\(\)](#).

See also

[KeepAlive::IsAlive\(\)](#)

Example

The following example implements a custom [IsAlive\(\)](#) that can be called three times before returning 0 and terminating the connection. If the call to run the `changes` command takes less than 1.5 seconds to complete on the server side, the program outputs the list of changes. If the call to run the `changes` command takes more than 1.5 seconds, the connection is interrupted.

```
#include <clientapi.h>

// subclass KeepAlive to implement a customized IsAlive function.
class MyKeepAlive : public KeepAlive
{
public:
    int IsAlive();
};

// Set up the interrupt callback. After being called 3 times,
// interrupt 3 times, interrupt the current server operation.
int MyKeepAlive::IsAlive()
{
    static int counter = 0;
    if ( ++counter > 3 )
    {
        counter = 0;
        return( 0 );
    }
    return( 1 );
}

// Now test the callback
ClientUser ui;
ClientApi client;
MyKeepAlive cb;
Error e;

client.Init( &e );
client.SetBreak( &cb ); // SetBreak must happen after the Init
client.Run( "changes", &ui );
client.Final( &e );
```

ClientApi::SetClient(const StrPtr *)

Sets the client setting to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new client setting
Returns	<code>void</code>

Notes

[SetClient\(\)](#) does not permanently set the P4CLIENT value in the environment or registry. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following example displays two client specifications by calling [SetClient\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "client_one";
sb2 = "client_two";
args[0] = "-o";

client.SetClient( &sb1 );
client.SetArgv( 1, args );
client.Run( "client", &ui );

client.SetClient( &sb2 );
client.SetArgv( 1, args );
client.Run( "client", &ui );
```

ClientApi::SetClient(const char *)

Sets the client setting to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new client setting
Returns	<code>void</code>

Notes

[SetClient\(\)](#) does not permanently set the P4CLIENT value in the environment or registry. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following example displays two client specifications by calling [SetClient\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
ClientUser ui;

char *args[1];
args[0] = "-o";

client.SetClient( "client_one" );
client.SetArgv( 1, args );
client.Run( "client", &ui );

client.SetClient( "client_two" );
client.SetArgv( 1, args );
client.Run( "client", &ui );
```

ClientApi::SetCwd(const StrPtr *)

Sets the working directory to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new directory path
Returns	<code>void</code>

Notes

[SetCwd\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

Example

The following code sets different working directories and displays them with `p4 info`.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "C:\one";
sb2 = "C:\two";

client.SetCwd( &sb1 );
client.Run( "info", &ui );

client.SetCwd( &sb2 );
client.Run( "info", &ui );
```

ClientApi::SetCwd(const char *)

Sets the working directory to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new directory path
Returns	<code>void</code>

Notes

[SetCwd\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

Example

The following code sets different working directories and displays them with `p4 info`.

```
ClientApi client;
ClientUser ui;

client.SetCwd( "C:\one" );
client.Run( "info", &ui );

client.SetCwd( "C:\two" );
client.Run( "info", &ui );
```

ClientApi::SetCwdNoReload(const StrPtr *)

Sets the working directory to be used for this connection without checking P4CONFIG.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new directory path
Returns	<code>void</code>

Notes

[SetCwd\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Unlike [SetCwd\(\)](#), [SetCwdNoReload\(\)](#) ignores any P4CONFIG files found in the new directory hierarchy.

Example

The following code sets different working directories and displays them with p4 info.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "C:\one";
sb2 = "C:\two";
client.SetCwdNoReload( &sb1 );
client.Run( "info", &ui );

client.SetCwdNoReload( &sb2 );
client.Run( "info", &ui );
```

ClientApi::SetCwdNoReload(const char *)

Sets the working directory to be used for this connection without checking P4CONFIG.

Virtual?	No
Class	ClientApi
Arguments	const char *c the new directory path
Returns	void

Notes

[SetCwd\(\)](#) does not permanently set a new working directory in the client environment. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Unlike [SetCwd\(\)](#), [SetCwdNoReload\(\)](#) ignores any P4CONFIG files found in the new directory hierarchy.

Example

The following code sets different working directories and displays them with p4 info.

```
ClientApi client;
ClientUser ui;

client.SetCwdNoReload( "C:\one" );
client.Run( "info", &ui );

client.SetCwdNoReload( "C:\two" );
client.Run( "info", &ui );
```

ClientApi::SetHost(const StrPtr *)

Sets the hostname to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new hostname value
Returns	<code>void</code>

Notes

[SetHost\(\)](#) does not permanently change the host name of the client or set P4HOST in the environment. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following example sets different hostnames and displays them with p4 info.

```
ClientApi client;
ClientUser ui;
StrBuf sb1;
StrBuf sb2;

sb1 = "magic";
sb2 = "shire";

client.SetHost( &sb1 );
client.Run( "info", &ui );

client.SetHost( &sb2 );
client.Run( "info", &ui );
```

ClientApi::SetHost(const char *)

Sets the hostname to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new hostname value
Returns	<code>void</code>

Notes

[SetHost\(\)](#) does not permanently change the host name of the client or set P4HOST in the environment. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following example sets different hostnames and displays them with p4 info.

```
ClientApi client;
ClientUser ui;

client.SetHost( "magic" );
client.Run( "info", &ui );

client.SetHost( "shire" );
client.Run( "info", &ui );
```

ClientApi::SetIgnoreFile(const StrPtr *)

Sets the full path name of the ignore file to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the full path name of the new ignore file
Returns	<code>void</code>

Notes

[SetIgnoreFile\(\)](#) does not permanently set the P4IGNORE value in the environment or registry. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

See also

[ClientApi::DefineIgnoreFile\(\)](#)
[ClientApi::GetIgnore\(\)](#)
[ClientApi::GetIgnoreFile\(\)](#)

Example

The following example sets an ignore file location by calling [SetIgnoreFile\(\)](#).

```
# include "clientapi.h"

int main()
{
    ClientApi client;
    StrBuf sb;

    sb = ".p4ignore";
    client.SetIgnoreFile( &sb );
}
```

ClientApi::SetIgnoreFile(const char *)

Sets the full path name of the ignore file to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the full path name of the new ignore file
Returns	<code>void</code>

Notes

[SetIgnoreFile\(\)](#) does not permanently set the P4IGNORE value in the environment or registry. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

See also

[ClientApi::DefineIgnoreFile\(\)](#)
[ClientApi::GetIgnore\(\)](#)
[ClientApi::GetIgnoreFile\(\)](#)

Example

The following example sets a ticket file location by calling [SetIgnoreFile\(\)](#).

```
# include "clientapi.h"

int main()
{
    ClientApi client;

    client.SetIgnoreFile( ".p4ignore" );
}
```

ClientApi::SetPassword(const StrPtr *)

Sets the password to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new password value
Returns	<code>void</code>

Notes

[SetPassword\(\)](#) does not permanently change the P4PASSWD value in the environment, nor does it in any way change the password that has been set on the server. The new setting applies only to authentication attempts for commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following trivial example demonstrates how to hard-code a password into an application without making it (immediately) user-visible.

```
ClientApi client;
ClientUser ui;
StrBuf sb;

sb = "p455w04d";

client.SetPassword( &sb );
client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );
```

ClientApi::SetPassword(const char *)

Sets the password to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new password value
Returns	<code>void</code>

Notes

[SetPassword\(\)](#) does not permanently change the P4PASSWD value in the environment, nor does it in any way change the password that has been set on the server. The new setting applies only to authentication attempts for commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following trivial example demonstrates how to hard-code a password into an application without making it (immediately) user-visible.

```
ClientApi client;
ClientUser ui;

client.SetPassword( "p455w04d" );
client.SetArgv( argc - 2, argv + 2 );
client.Run( argv[1], &ui );
```

ClientApi::SetPort(const StrPtr *)

Sets the port to be used to open this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new port value
Returns	<code>void</code>

Notes

[SetPort\(\)](#) does not permanently change the P4PORT value in the environment. The new setting applies only to new connections established by calling this ClientApi object's [Init\(\)](#) method.

Example

The following example demonstrates setting a new port value before initializing the connection.

```
ClientApi client;
Error e;
StrBuf sb;

sb = "ssl:magic:1666";

client.SetPort( &sb );
client.Init( &e );
```

ClientApi::SetPort(const char *)

Sets the port to be used to open this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new port value
Returns	<code>void</code>

Notes

[SetPort\(\)](#) does not permanently change the P4PORT value in the environment. The new setting applies only to new connections established by calling this ClientApi object's [Init\(\)](#) method.

Example

The following example demonstrates setting a new port value before initializing the connection.

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );
```

ClientApi::SetProg(const StrPtr *)

Sets the application or script name for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new program name
Returns	<code>void</code>

Notes

[SetProg\(\)](#) sets the identity of a client application as reported by the `p4 monitor` command, or as recorded by server logging.

Call [SetProg\(\)](#) before calling [Init\(\)](#).

See also

[ClientApi::SetVersion\(\)](#)

Example

The following example appears as `MyApp` in the output of `p4 monitor show`.

```
ClientApi client;
ClientUser ui;
StrBuf sb;
Error e;

sb.Set( "MyApp" );

client.Init( &e );
client.SetProg( &sb );
client.Run( "info", &ui );
```

ClientApi::SetProg(const char *)

Sets the application or script name for this connection.

Virtual?	No
Class	ClientApi
Arguments	const char *c the new program name
Returns	void

Notes

[SetProg\(\)](#) sets the identity of a client application as reported by the p4 monitor command, or as recorded by server logging.

Call [SetProg\(\)](#) before calling [Init\(\)](#).

See also

[ClientApi::SetVersion\(\)](#)

Example

The following example appears as MyApp in the output of p4 monitor show.

```
ClientApi client;
ClientUser ui;
Error e;

client.Init( &e );
client.SetProg( "MyApp" );
client.Run( "info", &ui );
```

ClientApi::SetProtocol(char *, char *)

Sets special protocols for the server to use.

Virtual?	No	
Class	ClientApi	
Arguments	char *p char *v	the name of the variable to set the new value for that variable
Returns	void	

Notes

[SetProtocol\(\)](#) must be called before the connection is established with [Init\(\)](#).

The following variables are supported by [SetProtocol\(\)](#):

Variable	Meaning
tag	To enable tagged output (if tagged output for the command is supported by the server), set the tag variable to any value.
specstring	To enable specially formatted application forms, set the specstring to any value.
api	Set the api variable to the value corresponding to the level of server behavior your application supports.

By default, the value of the **api** protocol variable matches the version of the API with which you built your application; under most circumstances, you do not need to set the protocol version from within your application. If you are concerned about changes in server behavior, you can manually set the **api** variable in order to protect your code against such changes.

For instance, the "p4 info" command supports tagged output as of server release 2003.2, and changes to this format were made in 2004.2. Code requesting tagged output from "p4 info" that was compiled against the 2003.1 API library may break (that is, start producing tagged output) when running against a 2003.2 or newer server. To prevent this from happening, set **api** to the value corresponding to the desired server release.

Command	Set api to	Tagged output supported?
info	unset	Only if both server and API are at 2004.2 or greater
	<=55	Output is not tagged; behaves like 2003.1 or earlier, even if server supports tagged output.
	=56	Output is tagged; behaves like 2003.2.

Command	Set api to	Tagged output supported?
	=57	Output is tagged; behaves like 2004.1, 2004.2, or 2005.1.
	=58	Output is tagged; behaves like 2005.2 or greater

Example

The following example demonstrates the use of [SetProtocol\(\)](#) to enable tagged output. The result of this call is that the `ClientUser` object uses [OutputStat\(\)](#) to handle the output, rather than [OutputInfo\(\)](#).

```
ClientApi client;
Error e;

client.SetProtocol( "tag", "" );
client.Init( &e );
client.Run( "branches", &ui );
client.Final( &e );
```

The following code illustrates how to ensure forward compatibility when compiling against newer versions of the Perforce API or connecting to newer Perforce servers.

```
ClientApi client;
Error e;

printf( "Output is tagged depending on API or server level.\n" );
client.SetProtocol( "tag", "" ); // request tagged output
client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );

printf( "Force 2003.1 behavior regardless of API or server level.\n" );
client.SetProtocol( "tag", "" ); //request tagged output
client.SetProtocol( "api", "55" ); // but force 2003.1 mode (untagged)
client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );

printf( "Request 2003.2 output if API and server support it.\n" );
client.SetProtocol( "tag", "" ); // request tagged output
client.SetProtocol( "api", "56" ); // force 2003.2 mode (tagged)
client.Init( &e );
client.Run( "info", &ui );
client.Final( &e );
```

The "p4 info" command supports tagged output only as of server release 2003.2. In the example, the first [Run\(\)](#) leaves `api` unset; if both the client API and Perforce server support tagged output for `p4 info` (that is, if you link this code with the 2003.2 or later API *and* run it against a 2003.2 or later server), the output is tagged. If you link the same code with the libraries from the 2003.1 release of the API,

however, the first [Run\(\)](#) returns untagged output *even if connected to a 2003.2 server*. By setting `api` to `55`, the second [Run\(\)](#) ensures 2003.1 behavior regardless of API or server level. The third call to [Run\(\)](#) supports 2003.2 behavior against a 2003.2 server and protects against future changes.

ClientApi::SetProtocolV(char*)

Sets special protocols for the server to use.

Virtual?	No
Class	ClientApi
Arguments	<code>char *nv</code> the name and value of the variable to set in <code>var=val</code> form
Returns	<code>void</code>

Notes

[SetProtocolV\(\)](#) functions identically to [SetProtocol\(\)](#), except that its argument is a single string of the format *variable=value*.

Example

The following example demonstrates the use of [SetProtocolV\(\)](#) to enable tagged output. The result is that the `ClientUser` object uses [OutputStat\(\)](#) to handle the output, rather than [OutputInfo\(\)](#).

```
ClientApi client;
Error e;

client.SetProtocolV( "tag=" );
client.Init( &e );
client.Run( "branches", &ui );
client.Final( &e );
```

ClientApi::SetTicketFile(const StrPtr *)

Sets the full path name of the ticket file to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the full path name of the new ticket file
Returns	<code>void</code>

Notes

[SetTicketFile\(\)](#) does not permanently set the P4TICKETS value in the environment or registry. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following example sets a ticket file location by calling [SetTicketFile\(\)](#).

```
ClientApi client;
StrBuf sb;

sb = "/tmp/ticketfile.txt";
client.SetTicketFile( &sb );
```

ClientApi::SetTicketFile(const char *)

Sets the full path name of the ticket file to be used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the full path name of the new ticket file
Returns	<code>void</code>

Notes

[SetTicketFile\(\)](#) does not permanently set the P4TICKETS value in the environment or registry. The new setting applies only to commands executed by calling this ClientApi object's [Run\(\)](#) method.

Example

The following example sets a ticket file location by calling [SetTicketFile\(\)](#).

```
ClientApi client;  
  
client.SetTicketFile( "/tmp/ticketfile.txt" );
```

ClientApi::SetUi(ClientUser *)

Reset the `ClientUser` object used for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>ClientUser *ui</code> a pointer to a <code>ClientUser</code> object.
Returns	<code>void</code>

Notes

Unless you pass the `ClientUser` object to the [Run\(\)](#) method, you must first call [SetUi\(\)](#). The new setting applies to commands executed by calling this `ClientApi` object's [Run\(\)](#) method.

Example

The following example illustrates two ways to run `p4 info`:

```
ClientApi client;
ClientUser ui;

client.Run( "info", &ui );

client.SetUi( &ui );
client.Run( "info" );
```

ClientApi::SetUser(const StrPtr *)

Sets the user for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new user name setting
Returns	<code>void</code>

Notes

[SetUser\(\)](#) does not permanently set the P4USER value in the environment or registry. Calling this method is equivalent to using the "-u" global option from the command line to set the user value for a single command, with the exception that a single `ClientApi` object can be used to invoke multiple commands in a row.

If the user setting is to be in effect for the command when it is executed, you must call [SetUser\(\)](#) before calling [Run\(\)](#).

Example

The following example displays two user specifications by calling [SetUser\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
Error e;
StrBuf sb1;
StrBuf sb2;

sb1 = "user1";
sb2 = "user2";

char *args[1];
args[0] = "-o";

client.SetUser( &sb1 );
client.SetArgv( 1, args );
client.Run( "user", &ui );

client.SetUser( &sb2 );
client.SetArgv( 1, args );
client.Run( "user", &ui );
```

ClientApi::SetUser(const char *)

Sets the user for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new user name setting
Returns	<code>void</code>

Notes

[SetUser\(\)](#) does not permanently set the P4USER value in the environment or registry. Calling this method is equivalent to using the "-u" global option from the command line to set the user value for a single command, with the exception that a single ClientApi object can be used to invoke multiple commands in a row.

If the user setting is to be in effect for the command when it is executed, you must call [SetUser\(\)](#) before calling [Run\(\)](#).

Example

The following example displays two user specifications by calling [SetUser\(\)](#) between [Run\(\)](#) commands.

```
ClientApi client;
Error e;

char *args[1];
args[0] = "-o";

client.SetUser( "user1" );
client.SetArgv( 1, args );
client.Run( "user", &ui );

client.SetUser( "user2" );
client.SetArgv( 1, args );
client.Run( "user", &ui );
```

ClientApi::SetVersion(const StrPtr *)

Sets the application or script version for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const StrPtr *c</code> the new version number
Returns	<code>void</code>

Notes

[SetVersion\(\)](#) sets the version number of a client application as reported by the `p4 monitor -e` command, or as recorded by server logging.

If a client application compiled with version 2005.2 or later of the API does not call [SetVersion\(\)](#), then the version string reported by `p4 monitor -e` (and recorded in the server log) defaults to the `api` value appropriate for the server level as per [SetProtocol\(\)](#).

Call [SetVersion\(\)](#) after calling [Init\(\)](#) and before each call to [Run\(\)](#).

See also

[ClientApi::SetProtocol\(\)](#)
[ClientApi::SetProg\(\)](#)

Example

The following example appears as `2005.2` in the output of `p4 monitor show -e`.

```

ClientApi client;
ClientUser ui;
StrBuf sb;
Error e;

sb.Set( "2005.2" );

client.Init( &e );
client.SetVersion( &sb );
client.Run( "info", &ui );

```

ClientApi::SetVersion(const char *)

Sets the application or script version for this connection.

Virtual?	No
Class	ClientApi
Arguments	<code>const char *c</code> the new version number
Returns	<code>void</code>

Notes

[SetVersion\(\)](#) sets the version number of a client application as reported by the `p4 monitor -e` command, or as recorded by server logging.

If a client application compiled with version 2005.2 or later of the API does not call [SetVersion\(\)](#), then the version string reported by `p4 monitor -e` (and recorded in the server log) defaults to the `api` value appropriate for the server level as per [SetProtocol\(\)](#).

Call [SetVersion\(\)](#) after calling [Init\(\)](#) and before each call to [Run\(\)](#).

See also

[ClientApi::SetProtocol\(\)](#)
[ClientApi::SetProg\(\)](#)

Example

The following example appears as `2005.2` in the output of `p4 monitor show -e`.

```
ClientApi client;
ClientUser ui;
Error e;

client.Init( &e );
client.SetVersion( "2005.2" );
client.Run( "info", &ui );
```

ClientProgress methods

ClientProgress::Description(const StrPtr *, int)

Sets up a description and defines the units by which command progress is measured.

Virtual?	Yes	
Class	ClientProgress	
Arguments	<code>const StrPtr *desc</code>	description from the server
	<code>int units</code>	the units in which progress is to be measured
Returns	<code>void</code>	

Notes

The API calls this method on command startup, supplying your implementation with a description and a client progress unit type. The `units` in which client progress is measured are defined in `clientprog.h` as follows:

Client Progress Unit	Value	Meaning
CPU_UNSPECIFIED	0	No units specified
CPU_PERCENT	1	Value is a percentage
CPU_FILES	2	Value is a count of files
CPU_KBYTES	3	Value is in kilobytes
CPU_MBYTES	4	Value is in megabytes

See also

[ClientUser::CreateProgress\(\)](#)
[ClientUser::ProgressIndicator\(\)](#)
[ClientProgress::Done\(\)](#)
[ClientProgress::Total\(\)](#)
[ClientProgress::Update\(\)](#)

Example

Create a subclass of `ClientProgress` and define an implementation of [Description\(\)](#), even if it is a trivial implementation:

```
void MyProgress::Description( const StrPtr *desc, int units )
{
    printf( "Starting command:\n" );
}
```

ClientProgress::Done(int)

Called when an operation completes.

Virtual?	Yes
Class	ClientProgress
Arguments	int fail operation status: 1 if failed, 0 if successful
Returns	void

Notes

The API calls [Done\(\)](#) on command completion with 0 for success, or 1 for failure.

See also

[ClientUser::CreateProgress\(\)](#)
[ClientUser::ProgressIndicator\(\)](#)
[ClientProgress::Description\(\)](#)
[ClientProgress::Total\(\)](#)
[ClientProgress::Update\(\)](#)

Example

To change the way completed actions are reported, create a subclass of [ClientProgress](#) and define an alternate implementation of [Done\(\)](#). For example, to output "Command failed" or "Command completed" upon success or failure, implement [Done\(\)](#) as follows:

```
void MyProgress::Done( int fail )
{
    printf( fail ? "Command failed\n" : "Command completed\n");
}
```

ClientProgress::Total(long)

Defines the number of units requested during the operation, if known.

Virtual?	Yes	
Class	ClientProgress	
Arguments	long units	Total number of client progress units expected, if known
Returns	void	

Notes

The API calls this method if and when it has determined the number of client progress units, as defined by [Description\(\)](#), are to be processed during the command.

If the total number of expected units changes during the lifetime of a command, the API may call this method more than once. (The total number of expected units is *not* the same as the number of *remaining* units; certain commands may result in multiple calls to this method as the server determines more about the amount of data to be retrieved.)

See also

[ClientUser::CreateProgress\(\)](#)
[ClientUser::ProgressIndicator\(\)](#)
[ClientProgress::Description\(\)](#)
[ClientProgress::Done\(\)](#)
[ClientProgress::Update\(\)](#)

Example

To report how many progress units are expected, create a subclass of `ClientProgress` and define an alternate implementation of [Total\(\)](#).

For example, the following method outputs the number of units expected and is called when, if, and as the total number of expected units changes over the lifetime of the command:

```
void MyProgress::Total( long units )
{
    printf( "Now expecting %l units\n" );
}
```

ClientProgress::Update(long)

Reports on command progress and user cancellation requests.

Virtual?	Yes
Class	ClientProgress
Arguments	long units Total number of progress units processed, if known
Returns	int

Notes

The API calls the [Update\(\)](#) method periodically during the life of a command and reports on the number of client progress units processed. (Because a million calls for an update of one million 1024-byte files would be prohibitive, not every unit of progress is reported.) Instead, the API calls this method periodically depending on a combination of elapsed time and number of client progress units processed.

In addition to reporting progress in terms of the units defined by [Description\(\)](#), if [Update\(\)](#) returns non-zero, the API interprets it as a user request to cancel the operation.

See also

[ClientUser::CreateProgress\(\)](#)
[ClientUser::ProgressIndicator\(\)](#)
[ClientProgress::Description\(\)](#)
[ClientProgress::Done\(\)](#)
[ClientProgress::Total\(\)](#)

Example

To report on units processed, create a subclass of `ClientProgress` and define an alternate implementation of [Update\(\)](#). A trivial implementation ignores cancel requests by always returning 0; a more useful implementation might resemble the following:

```
void MyProgress::Update( long units )
{
    if ( cancelclicked() ) // has anyone clicked the Cancel button?
    {
        return 1; // yes, user wishes to cancel
    }
    else
    {
        displayGUI( units ); // show how many units have been processed
        return 0; // user has not requested cancel, continue processing
    }
}
```

ClientUser methods

ClientUser::CreateProgress(int)

Create a [ClientProgress](#) object by subclassing, or null if no progress indicator is desired.

Virtual?	Yes	
Class	ClientUser	
Arguments	int ProgressType	the type of progress to be reported
Returns	*ClientProgress	a pointer to the new ClientProgress object.

Notes

To enable progress reporting for a command, create a [ClientProgress](#) object and then implement [ProgressIndicator\(\)](#) to return 0 or 1 depending on whether or not you want to enable the progress indicator. (You typically implement [ProgressIndicator\(\)](#) to return 1, and call it only when a progress indicator is desired.)

The API calls this method with the appropriate ProgressType as defined in `clientprog.h`. The following ProgressTypes can be reported:

Client Progress Type	Value	Meaning
CPT_SENDFILE	1	Files sent to server
CPT_RECVFILE	2	Files received from server
CPT_FILESTRANS	3	Files transmitted
CPT_COMPUTATION	4	Computation performed server-side

See also

[ClientUser::ProgressIndicator\(\)](#)
[ClientProgress::Description\(\)](#)
[ClientProgress::Done\(\)](#)
[ClientProgress::Total\(\)](#)
[ClientProgress::Update\(\)](#)

ClientUser::Diff(FileSys *, FileSys *, int, char *, Error *)

Diff two files, and display the results.

Virtual?	Yes										
Class	ClientUser										
Arguments	<table> <tr> <td><code>FileSys *f1</code></td> <td>the first file to be diffed</td> </tr> <tr> <td><code>FileSys *f2</code></td> <td>the second file to be diffed</td> </tr> <tr> <td><code>int doPage</code></td> <td>should output be paged?</td> </tr> <tr> <td><code>char *diffFlags</code></td> <td>flags to diff routine</td> </tr> <tr> <td><code>Error *e</code></td> <td>an <code>Error</code> object</td> </tr> </table>	<code>FileSys *f1</code>	the first file to be diffed	<code>FileSys *f2</code>	the second file to be diffed	<code>int doPage</code>	should output be paged?	<code>char *diffFlags</code>	flags to diff routine	<code>Error *e</code>	an <code>Error</code> object
<code>FileSys *f1</code>	the first file to be diffed										
<code>FileSys *f2</code>	the second file to be diffed										
<code>int doPage</code>	should output be paged?										
<code>char *diffFlags</code>	flags to diff routine										
<code>Error *e</code>	an <code>Error</code> object										
Returns	<code>void</code>										

Notes

This method is used by `p4 diff` and to display diffs from an interactive `p4 resolve`. If no external diff program is specified, the diff is carried out with a `Diff` object (part of the Perforce C/C++ API); otherwise, [Diff\(\)](#) simply calls the specified external program.

As with [Merge\(\)](#), the external program is invoked with [ClientUser::RunCmd\(\)](#).

If `doPage` is nonzero and the `P4PAGER` environment variable is set, the output is piped through the executable specified by `P4PAGER`.

See also

[ClientUser::RunCmd\(\)](#)

Example

In its default implementation, this method is called by an application when `p4 diff` is run. For example:

`p4 diff -dc file.c`

results in a call to [Diff\(\)](#) with the arguments:

Argument	Value
<code>f1</code>	a temp file containing the head revision of depot file <code>file.c</code>
<code>f2</code>	the local workspace version of file <code>file.c</code>
<code>doPage</code>	0

Argument	Value
diffFlag	c
e	a normal <code>Error</code> object

The diff is performed by creating a `Diff` object, giving it `f1` and `f2` as its inputs, and `-c` as its flag. The end result is sent to `stdout`. If either of the files is binary, the message "files differ" is printed instead.

Selecting the "d" option during an interactive `p4 resolve` also calls the [Diff\(\)](#) method, with the `doPage` argument set to 1.

If the environment variable `P4PAGER` or `PAGER` is set, then setting `doPage` to 1 causes the diff output to be fed through the specified pager. If `P4PAGER` and `PAGER` are unset, `dopage` has no effect and the `resolve` routine displays the diff output normally.

To enable an application to override the default diff routine, create a subclass of `ClientUser` that overrides the [Diff\(\)](#) method, and use this subclass in place of `ClientUser`.

As an example, suppose that you have a special diff program designed for handling binary files, and you want `p4 diff` to use it whenever asked to diff binary files (rather than display the default "files differ...").

Furthermore, you want to keep your current `P4DIFF` setting for the purpose of diffing text files, so you decide to use a new environment variable called `P4DIFFBIN` to reference the binary diff program. If `P4DIFFBIN` is set and one of the files is non-text, the `P4DIFFBIN` program is invoked as `P4DIFF` is in the default implementation. Otherwise, the default implementation is called.

Most of the following code is copied and pasted from the default implementation.

```
MyClientUser::Diff( FileSys *f1, FileSys *f2, int doPage, char *df, Error *e )
{
    const char *diff = enviro->Get( "P4DIFFBIN" );
    if ( diff && ( !f1->IsTextual() || !f2->IsTextual() ) ) // binary diff
    {
        if ( !df || !*df )
        {
            RunCmd( diff, 0, f1->Name(), f2->Name(), 0, pager, e );
        }
        else
        {
            StrBuf flags;
            flags.Set( "-", 1 );
            flags << df;
            RunCmd( diff, flags.Text(), f1->Name(), f2->Name(), 0, pager, e );
        }
    }
    else ClientUser::Diff( f1, f2, doPage, df, e );
}
```

ClientUser::Diff(FileSys *, FileSys *, FileSys *, int, char *, Error *)

Diff two files, and output the results to a third file.

Virtual?	Yes
Class	ClientUser
Arguments	FileSys *f1 the first file to be diffed
	FileSys *f2 the second file to be diffed
	FileSys *fout the target file for diff output
	int doPage should output be paged?
	char *diffFlags flags to diff routine
	Error *e an Error object
Returns	void

Notes

This method works like [Diff\(\)](#), but instead of sending data to the standard output, writes the data to the specified output file.

ClientUser::Edit(FileSys *, Error *)

Bring up the given file in a text editor. Called by all **p4** commands that edit specifications.

Virtual?	Yes	
Class	ClientUser	
Arguments	FileSys *f1	the file to be edited
	Error *e	an Error object
Returns	void	

Notes

The **FileSys *** argument to [Edit\(\)](#) refers to a client temp file that contains the specification that is to be given to the server. [Edit\(\)](#) does not send the file to the server; its only job is to modify the file. In the default implementation, [Edit\(\)](#) does not return until the editor has returned.

There is also a three-argument version of [Edit\(\)](#), for which the default two-argument version is simply a wrapper. The three-argument version takes an **Enviro** object as an additional argument, and the two-argument version simply passes the member variable **enviro** as this argument. Only the two-argument version is virtual.

Example

The **p4 client** command is one of several Perforce commands that use [ClientUser::Edit\(\)](#) to allow the user to modify a specification. When the command is executed, the server sends the client specification to the client machine, where it is held in a temp file. [Edit\(\)](#) is then called with that file as an argument, and an editor is spawned. When the editor closes, [Edit\(\)](#) returns, and the temp file is sent to the server.

To allow modification of a specification by other means, such as a customized dialog or an automated process, create a subclass of **ClientUser** that overrides the [Edit\(\)](#) method and use this subclass in place of **ClientUser**.

Suppose that you have already written a function that takes a **FileSys** as input, opens a custom dialog, and returns when the file has been modified. Replace the body of [Edit\(\)](#) in your subclass with a call to your function, as follows:

```
void MyClientUser::Edit( FileSys *f1, Error *e )
{
    MyDialog( f1 );
}
```

ClientUser::ErrorPause(char *, Error *)

Outputs an error and prompts for a keystroke to continue.

Virtual?	Yes	
Class	ClientUser	
Arguments	<code>char *errBuf</code>	the error message to be printed
	<code>Error *e</code>	an <code>Error</code> object
Returns	<code>void</code>	

Notes

The default implementation of [ErrorPause\(\)](#) consists solely of calls to [OutputError\(\)](#) and [Prompt\(\)](#).

Example

One situation that results in a call to [ErrorPause\(\)](#) is an incorrectly edited specification; for example:

```
> p4 client
...
Error in client specification.
Error detected at line 31.
Wrong number of words for field 'Root'.
Hit return to continue...
```

In this instance, the first three lines of output were the `errBuf` argument to [ErrorPause\(\)](#); they were displayed using [OutputError\(\)](#).

To display an error and prompt for confirmation within a GUI application, create a subclass of `ClientUser` that overrides [ErrorPause\(\)](#) and use this subclass in place of `ClientUser`.

Suppose that you have a function `MyWarning()` that takes a `char *` as an argument, and displays the argument text in an appropriate popup dialog that has to be clicked to be dismissed. You can implement [ErrorPause\(\)](#) as a call to this function, as follows:

```
void MyClientUser::ErrorPause( char *errBuf, Error *e )
{
    MyWarning( errBuf );
}
```

Within a GUI, the warning text and "OK" button are probably bundled into a single dialog, so overriding [ErrorPause\(\)](#) is a better approach than overriding [OutputError\(\)](#) and [Prompt\(\)](#) separately.

ClientUser::File(FileSysType)

Create a **FileSys** object for reading and writing files in the client workspace.

Virtual?	Yes	
Class	ClientUser	
Arguments	FileSysType <code>type</code>	the file type of the file to be created
Returns	FileSys *	a pointer to the new FileSys .

Notes

This method is a wrapper for **FileSys::Create()**.

Example

[ClientUser::File\(\)](#) is generally called whenever it's necessary to manipulate files in the client workspace. For example, a **p4 sync**, **p4 edit**, or **p4 revert** makes one call to [File\(\)](#) for each workspace file with which the command interacts.

An alternate implementation might return a subclass of **FileSys**. For example, if you have defined a class **MyFileSys** and want your **MyClientUser** class to use members of this class rather than the base **FileSys**, reimplement [File\(\)](#) to return a **MyFileSys** instead:

```
FileSys * MyClientUser::File( FileSysType type )
{
    return MyFileSys::Create( type );
}
```

ClientUser::Finished()

Called after client commands finish.

Virtual?	Yes
Class	ClientUser
Arguments	None
Returns	void

Notes

This function is called by the server at the end of every Perforce command, but in its default implementation, it has no effect. The default implementation of this function is empty - it takes nothing, does nothing, and returns nothing.

Example

To trigger an event after the completion of a command, create a subclass of `ClientUser` and provide a new implementation of [Finished\(\)](#) that calls that event.

For example, if you want your application to beep after each command, put the command into [Finished\(\)](#), as follows.

```
void MyClientUser::Finished()
{
    printf( "Finished!\n%c", 7 );
}
```

ClientUser::HandleError(Error *)

Process error data after a failed command.

Virtual?	Yes	
Class	ClientUser	
Arguments	<code>Error *e</code>	an <code>Error</code> object
Returns	<code>void</code>	

Notes

The default implementation formats the error with [Error::Fmt\(\)](#) and outputs the result with [OutputError\(\)](#).

2002.1 and newer servers do not call [HandleError\(\)](#) to display errors. Instead, they call [Message\(\)](#). The default implementation of [Message\(\)](#) calls [HandleError\(\)](#) if its argument is a genuine error; as a result, older code that uses [HandleError\(\)](#) can be used with the newer API and newer servers so long as the default implementation of [Message\(\)](#) is retained.

Example

[HandleError\(\)](#) is called whenever a command encounters an error. For example:

```
> p4 files nonexistent
nonexistent - no such file(s).
```

In this case, the `Error` object given to [HandleError\(\)](#) contains the text "nonexistent - no such file(s)." and has a severity of 2 (`E_WARN`).

To handle errors in a different way, create a subclass of `ClientUser` with an alternate implementation of [HandleError\(\)](#).

For example, if you want an audible warning on a fatal error, implement [HandleError\(\)](#) as follows:

```
void MyClientUser::HandleError( Error *err )
{
    if ( err->IsFatal() ) printf ( "Fatal error!\n%c", 7 );
```

ClientUser::Help(const char *const *)

Displays a block of help text to the user. Used by `p4 resolve` but not `p4 help`.

Virtual?	Yes
Class	ClientUser
Arguments	<code>const char *const *help</code> an array of arrays containing the help text.
Returns	<code>void</code>

Notes

This function is called by `p4 resolve` when the "?" option is selected during an interactive resolve. The default implementation displays the help text given to it, one line at a time.

Example

The default implementation is called in order to display the "merge options" block of help text during a resolve by dumping the text to `stdout`.

To display the resolve help text in another manner, create a subclass of `ClientUser` with an alternate implementation of [Help\(\)](#).

For example, suppose you'd like a helpful message about the meaning of "yours" and "theirs" to be attached to the help message. Define the method as follows:

```
void MyClientUser::Help( const char *const *help )
{
    for ( ; *help; help++ )
        printf( "%s\n", *help );
    printf( "Note: In integrations, yours is the target file, \
            theirs is the source file.\n" );
}
```

ClientUser::InputData(StrBuf *, Error *)

Provide data from `stdin` to `p4 < command> -i`.

Virtual?	Yes	
Class	ClientUser	
Arguments	<code>StrBuf *strbuf</code>	the <code>StrBuf</code> which is to hold the data
	<code>Error *e</code>	an <code>Error</code> object
Returns	<code>void</code>	

Notes

Any command that edits a specification can take the `-i` option; this method supplies the data for the specification. In the default implementation, the data comes from `stdin`, but an alternate implementation can accept the data from any source. This method is the only way to send a specification to the server without first putting it into a local file.

Example

The default implementation is called during a normal invocation of `p4 client -i`.

```
p4 client -i < clispec.txt
```

In this example, `clispec.txt` is fed to the command as `stdin`. Its contents are appended to the `StrBuf` that is given as an argument to [InputData\(\)](#), and this `StrBuf` is given to the server after [InputData\(\)](#) returns.

To read the data from a different source, create a subclass of `ClientUser` with an alternate implementation of [InputData\(\)](#).

For example, suppose that you want to be able to edit a client specification without creating a local temp file. You've already written a function which generates the new client specification and stores it as a `StrBuf` variable in your `ClientUser` subclass. To send your modified client specification to the server when running `p4 client -i` with your modified `ClientUser`, implement [InputData\(\)](#) to read data from that `StrBuf`.

The example below assumes that the subclass `MyClientUser` has a variable called `mySpec` that already contains the valid client specification before running `p4 client -i`.

```
void MyClientUser::InputData( StrBuf *buf, Error *e )
{
    buf->Set( mySpec );
}
```

ClientUser::Merge(FileSys *, FileSys *, FileSys *, FileSys *, Error *)

Call an external merge program to merge three files during resolve.

Virtual?	Yes	
Class	ClientUser	
Arguments	<code>FileSys *base</code>	the "base" file
	<code>FileSys *leg1</code>	the "theirs" file
	<code>FileSys *leg2</code>	the "yours" file
	<code>FileSys *result</code>	the final output file
	<code>Error *e</code>	an <code>Error</code> object
Returns	<code>void</code>	

Notes

[Merge\(\)](#) is called if the "m" option is selected during an interactive resolve. [Merge\(\)](#) does not call the Perforce merge program; it merely invokes external merge programs (including P4Merge as well as third-party tools). External merge programs must be specified by an environment variable, either `P4MERGE` or `MERGE`. [Merge\(\)](#) returns after the external merge program exits.

As in [Diff\(\)](#), the external program is invoked using [ClientUser::RunCmd\(\)](#).

See also

[ClientUser::RunCmd\(\)](#)

Example

When the "merge" option is selected during an interactive resolve, the file arguments to [Merge\(\)](#) are as follows:

Argument	Value
<code>base</code>	A temp file built from the depot revision that is the "base" of the resolve.
<code>leg1</code>	A temp file built from the depot revision that is the "theirs" of the resolve.
<code>leg2</code>	The local workspace file that is the "yours" of the resolve.
<code>result</code>	A temp file in which to construct the new revision of "yours".

These file arguments correspond exactly to the command-line arguments passed to the merge tool.

After you "accept" the merged file (with "ae"), the "result" temp file is copied into the "leg2" or "yours" workspace file, and this is the file that is submitted to the depot.

To change the way that external merge programs are called during a resolve, create a subclass of **ClientUser** with an alternate implementation of [Merge\(\)](#).

For example, suppose that one of your favorite merge tools, "yourmerge", requires the "result" file as the first argument. Rather than wrapping the call to the merge tool in a script and requiring your users to set P4MERGE to point to the script, you might want to provide support for this tool from within your application as follows:

```
void MyClientUser::Merge(
    FileSys *base,
    FileSys *leg1,
    FileSys *leg2,
    FileSys *result,
    Error *e )
{
    char *merger;

    if ( !( merger = enviro->Get( "P4MERGE" ) ) &&
        !( merger = getenv( "MERGE" ) ) )
    {
        e->Set( ErrClient::NoMerger );
        return;
    }

    if ( strcmp( merger, "yourmerge" ) == 0 )
    {
        RunCmd( merger, result->Name(), base->Name(),
                leg1->Name(), leg2->Name(), 0, e );
    }
    else
    {
        RunCmd( merger, base->Name(), leg1->Name(),
                leg2->Name(), result->Name(), 0, e );
    }
}
```

ClientUser::Message(Error *)

Output information or errors.

Virtual?	Yes	
Class	ClientUser	
Arguments	Error *e	an Error object containing the message
Returns	void	

Notes

[Message\(\)](#) is used by 2002.1 and later servers to display information or errors resulting from Perforce commands. Earlier versions of the Perforce server call [OutputInfo\(\)](#) to display information, and [HandleError\(\)](#) to display errors.

The default implementation of [Message\(\)](#) makes calls to [OutputInfo\(\)](#) or [HandleError\(\)](#) as appropriate. If you want your application to be compatible with pre-2002.1 servers, use this default implementation of [Message\(\)](#) - newer servers will call [Message\(\)](#), and older servers will call [OutputInfo\(\)](#) and [HandleError\(\)](#) directly.

If you re-implement [Message\(\)](#) to handle errors and information in a different way, be advised that older servers will still call [OutputInfo\(\)](#) and [HandleError\(\)](#) rather than your [Message\(\)](#) method.

Example

```
> p4 files //depot/proj/...
//depot/proj/file.c#1 - add change 456 (text)
```

In this example, the server passes a single `Error` object to the `ClientUser`'s [Message\(\)](#) method, with a severity of `E_INFO` and text "`//depot/proj/file.c#1 - add change 456 (text)`". The default [Message\(\)](#) method detects that this was an "info" message, and passes the text to [OutputInfo\(\)](#), which by default sends the text to `stdout`.

To handle messages differently, subclass `ClientUser` and re-implement the [Message\(\)](#) method (see the preceding note on interoperability with old servers if you do this).

For example, to take all server messages and load them into a `StrBuf` that is a member of your `ClientUser` class, use the following:

```
void MyClientUser::Message( Error *err )
{
    StrBuf buf;
    err->Fmt( buf, EF_PLAIN );
    myBuf.Append( buf );
}
```

ClientUser::OutputBinary(const char*, int)

Output binary data.

Virtual?	Yes	
Class	ClientUser	
Arguments	<code>const char *data</code>	a pointer to the first byte of data to output
	<code>int length</code>	the number of bytes to output
Returns	<code>void</code>	

Notes

The default implementation of [OutputBinary\(\)](#) writes the contents of a binary file to `stdout`. A call to [OutputBinary\(\)](#) is typically the result of running `p4 print` on a binary file:

```
p4 print //depot/file.jpg > newfile.jpg
```

Example

To modify the way in which binary files are output with `p4 print`, create a subclass of `ClientUser` with an alternate implementation of [OutputBinary\(\)](#).

For example, suppose that you want PDF files to be printed to `stdout` as plain text. Add the following code (that checks to see if the file is PDF and, if so, calls a hypothetical `OutputPDF()` function to output PDFs to `stdout`) to the beginning of your implementation of [OutputBinary\(\)](#).

```
void MyClientUser::OutputBinary( const char *data, int length )
{
    static unsigned char pdfFlag[] = { '%', 'P', 'D', 'F', '-' };
    if ( length >= 5 && memcmp( data, pdfFlag, sizeof( pdfFlag ) ) )
        OutputPDF( data, length );
    else
        ClientUser::OutputBinary( data, length );
}
```

ClientUser::OutputError(const char*)

Display a message as an error.

Virtual?	Yes
Class	ClientUser
Arguments	<code>const char *errBuf</code> the error message
Returns	<code>void</code>

Notes

The default implementation sends its argument to `stderr`. [OutputError\(\)](#) is called by functions like [HandleError\(\)](#).

Example

Because the default implementation of [HandleError\(\)](#) calls it, [OutputError\(\)](#) is responsible for printing every error message in Perforce. For example:

```
p4 files //nonexistent/...
nonexistent - no such file(s).
```

In this case, the argument to [OutputError\(\)](#) is the array containing the error message "nonexistent - no such file(s)."

To change the way error messages are displayed, create a subclass of `ClientUser` and define an alternate implementation of [OutputError\(\)](#).

For example, to print all error messages to `stdout` rather than `stderr`, and precede them with the phrase "!!ERROR!!", implement [OutputError\(\)](#) as follows:

```
void MyClientUser::OutputError( const char *errBuf )
{
    printf( "!!ERROR!! " );
    fwrite( errBuf, 1, strlen( errBuf ), stdout );
}
```

ClientUser::OutputInfo(char, const char *)

Output tabular data.

Virtual?	Yes	
Class	ClientUser	
Arguments	char level	the indentation "level" of the output
	const char *data	one line of output
Returns	void	

Notes

[OutputInfo\(\)](#) is called by the server during most Perforce commands; its most common use is to display listings of information about files. Any output not printed with [OutputInfo\(\)](#) is typically printed with [OutputText\(\)](#). Running p4 -s <command> indicates whether any given line of output is "info" or "text".

In the default implementation of [OutputInfo\(\)](#), one "..." string is printed per "level". Values given as "levels" are either 0, 1, or 2. The "data" passed is generally one line, without a line break; [OutputInfo\(\)](#) adds the newline when it prints the output.

To capture information directly from Perforce commands for parsing or storing rather than output to `stdout`, it is usually necessary to use an alternate implementation of [OutputInfo\(\)](#).

2002.1 and newer servers do not call [OutputInfo\(\)](#) to display information. Instead, they call [Message\(\)](#). The default implementation of [Message\(\)](#) calls [OutputInfo\(\)](#) if its argument represents information instead of an error; older code that uses [OutputInfo\(\)](#) can be used with the newer API and newer servers, so long as the default implementation of [Message\(\)](#) is retained.

Example

The p4 filelog command produces tabular output:

```
> p4 filelog final.c
//depot/final.c
... #3 change 703 edit on 2001/08/24 by testuser@shire (text) 'fixed'
... ... copy into //depot/new.c#4
... #2 change 698 edit on 2001/08/24 by testuser@shire (text) 'buggy'
... ... branch into //depot/middle.c#1
... #1 change 697 branch on 2001/08/24 by testuser@shire (text) 'test'
... ... branch from //depot/old.c#1,#3
```

Each line of output corresponds to one call to [OutputInfo\(\)](#). The first line of output has a level of '0', the line for each revision has a level of '1', and the integration record lines have levels of '2'. (The actual "data" text for these lines does not include the "..." strings.)

To alter the way in which "info" output from the server is handled, create a subclass of `ClientUser` and provide an alternate implementation of [OutputInfo\(\)](#).

For example, to capture output in a set of `StrBuf` variables rather than display it to `stdout`, your `ClientUser` subclass must contain three `StrBufs`, one for each level of info output, as follows:

```
void MyClientUser::OutputInfo( char level, const char *data )
{
    switch( level )
    {
        default:
        case '0':
            myInfo0.Append( data );
            myInfo0.Append( "\n" );
            break;
        case '1':
            myInfo1.Append( data );
            myInfo1.Append( "\n" );
            break;
        case '2':
            myInfo2.Append( data );
            myInfo2.Append( "\n" );
            break;
    }
}
```

ClientUser::OutputStat(StrDict *)

Process tagged output.

Virtual?	Yes	
Class	ClientUser	
Arguments	StrDict *varList	a StrDict containing the information returned by the command
Returns	void	

Notes

Normally, the only Perforce command that sends output through [OutputStat\(\)](#) is **p4 fstat**, which always returns tagged output. Some other commands can be made to return tagged output by setting the "tag" protocol variable, in which case the output is in the form of a **StrDict** suitable for passing to [OutputStat\(\)](#) for processing.

It is generally easier to deal with tagged output than it is to parse standard output. The default implementation of [OutputStat\(\)](#) passes each variable/value pair in the **StrDict** to [OutputInfo\(\)](#) as a line of text with a level of "1", with the exception of the "func" var, which it skips. Alternate implementations can use tagged output to extract the pieces of information desired from a given command.

Example

Consider the following output from **p4 fstat**:

```
> p4 fstat file.c
... depotFile //depot/file.c
... clientFile c:\depot\file.c
... isMapped
... headAction integrate
... headType text
... headTime 998644337
... headRev 10
... headChange 681
... headModTime 998643970
... haveRev 10
```

The **StrDict** passed to [OutputStat\(\)](#) consists of eight variable/value pairs, one for each line of output, plus a "func" entry, which is discarded by the default implementation of [OutputStat\(\)](#). Other commands can be made to return tagged output through [OutputStat\(\)](#) by using the **-Ztag** global option at the command line.

To process tagged output differently, create a subclass of **ClientUser** with an alternate implementation of [OutputStat\(\)](#). The following simple example demonstrates how the "headRev" and "haveRev" variables resulting from an "**fstat**" command can be easily extracted and manipulated.

Other commands provide **StrDicts** with different variable/value pairs that can be processed in similar ways; use **p4 -Ztag command** to get an understanding for what sort of information to expect.

```
void MyClientUser::OutputStat( StrDict *varList )
{
    StrPtr *headrev;
    StrPtr *haverev;

    headrev = varList->GetVar( "headRev" );
    haverev = varList->GetVar( "haveRev" );

    printf( "By default, revision numbers are returned as strings:\n" );
    printf( "  Head revision number: %s\n", headrev->Text() );
    printf( "  Have revision number: %s\n", haverev->Text() );

    printf( "but revision numbers can be converted to integers:\n" );
    printf( "  Head revision number: %d\n", headrev->Atoi() );
    printf( "  Have revision number: %d\n", haverev->Atoi() );
}
```

ClientUser::OutputText(const char *, int)

Output textual data.

Virtual?	Yes
Class	ClientUser
Arguments	const char *errBuf the block of text to be printed int length the length of the data
Returns	void

Notes

The most common usage of [OutputText\(\)](#) is in running p4 print on a text file.

Example

```
> p4 print -q file.txt
This is a text file.
It is called "file.txt"
```

The arguments to [OutputText\(\)](#) in the preceding example are the pointer to the first character in the file contents, and the length of the file in bytes.

To alter the way in which [OutputText\(\)](#) handles text data, create a subclass of [ClientUser](#) and provide an alternate implementation of [OutputText\(\)](#).

For example, suppose that your [ClientUser](#) subclass contains a [StrBuf](#) called [myData](#), and you want to store the data in this [StrBuf](#) rather than dump it to [stdout](#).

```
void MyClientUser::OutputText( const char *data, int length )
{
    myData.Set( data, length );
}
```

ClientUser::ProgressIndicator()

Returns nonzero if progress is to be reported, otherwise returns 0.

Virtual?	Yes
Class	ClientUser
Arguments	None
Returns	int returns non-zero if progress indicators are desired, 0 otherwise

Notes

After you have created a [ClientProgress](#) object with [CreateProgress\(\)](#), you must also implement [ProgressIndicator\(\)](#) to return 0 or 1 depending on whether or not you want to report progress.

See also

[ClientUser::CreateProgress\(\)](#)
[ClientProgress::Description\(\)](#)
[ClientProgress::Done\(\)](#)
[ClientProgress::Total\(\)](#)
[ClientProgress::Update\(\)](#)

Example

The typical implementation of [ProgressIndicator\(\)](#) returns 1, and you call it when you wish to enable progress reporting:

```
MyUserProgress::ProgressIndicator()
{
    return 1;
}
```

ClientUser::Prompt(const StrPtr &, StrBuf &, int, Error *)

Prompt the user and get a response.

Virtual?	Yes	
Class	ClientUser	
Arguments	const StrPtr &msg	the message with which to prompt the user
	StrBuf &rsp	where to put the user's response
	int noEcho	specifies whether echo should be turned off at the console
	Error *e	an Error object
Returns	void	

Notes

[Prompt\(\)](#) is used in the default implementation of [HandleError\(\)](#) to prompt the user to correct the error. [Prompt\(\)](#) is also used by the interactive resolve routine to prompt for options.

Example

Consider the following user interaction with p4 resolve:

```
> p4 resolve file.c
c:\depot\file.c - merging //depot/file.c#2,#10
Diff chunks: 0 yours + 1 theirs + 0 both + 0 conflicting
Accept(a) Edit(e) Diff(d) Merge (m) Skip(s) Help(?) [at]: at
```

In the above example, the "msg" argument to [Prompt\(\)](#) is the "Accept...[at]:" string. The response, "at", is placed into the "rsp" **StrBuf**, which is sent to the server and processed as "accept theirs".

To alter the behavior of [Prompt\(\)](#), create a subclass of **ClientUser** and provide an alternate implementation of [Prompt\(\)](#).

For example, suppose that you are writing a GUI application and want each option in the interactive resolve to appear in a dialog box. A function called **MyDialog()** to create a dialog box containing the text of its argument and a text field, and return a character array with the user's response, would look like this:

```
void MyClientUser::Prompt( const StrPtr &msg, StrBuf &buf, \
                           int noEcho, Error *e )
{
    buf.Set( MyDialog( msg.Text() ) );
}
```

ClientUser::RunCmd(const char *, const char *, [...], Error *)

Call an external program.

Virtual?	No														
Class	ClientUser (static)														
Arguments	<table> <tr> <td>const char *command</td> <td>the executable to be called</td> </tr> <tr> <td>const char *arg1</td> <td>the first argument</td> </tr> <tr> <td>const char *arg2</td> <td>the second argument</td> </tr> <tr> <td>const char *arg3</td> <td>the third argument</td> </tr> <tr> <td>const char *arg4</td> <td>the fourth argument</td> </tr> <tr> <td>const char *pager</td> <td>a pager, if any</td> </tr> <tr> <td>Error *e</td> <td>an Error object to hold system errors</td> </tr> </table>	const char *command	the executable to be called	const char *arg1	the first argument	const char *arg2	the second argument	const char *arg3	the third argument	const char *arg4	the fourth argument	const char *pager	a pager, if any	Error *e	an Error object to hold system errors
const char *command	the executable to be called														
const char *arg1	the first argument														
const char *arg2	the second argument														
const char *arg3	the third argument														
const char *arg4	the fourth argument														
const char *pager	a pager, if any														
Error *e	an Error object to hold system errors														
Returns	void														

Notes

[RunCmd\(\)](#) is called when the client needs to call an external program, such as a merge or diff utility. [RunCmd\(\)](#) stores any resulting errors in the specified **Error** object.

Example

If you select "d" for "Diff" during an interactive resolve, and both **P4DIFF** and **P4PAGER** are set in your environment, [RunCmd\(\)](#) is called with the following arguments:

Argument	Value
command	P4DIFF
arg1	local file name
arg2	temp file name (depot file)
arg3	null
arg4	null
pager	P4PAGER

The **P4DIFF** program is called with the two file names as arguments, and the output is piped through the **P4PAGER** program.

See the examples for [Diff\(\)](#) and [Merge\(\)](#) for code illustrating the use of [RunCmd\(\)](#).

Error methods

Error::Clear()

Remove any error messages from an **Error** object.

Virtual?	No
Class	Error
Arguments	None
Returns	void

Notes

[Clear\(\)](#) can be used if you need to clear an **Error** after having handled it in a way that does not automatically clear it.

Example

The following code attempts to establish a connection to a nonexistent server, displays the error's severity, clears the error, and shows that the error has been cleared:

```
ClientApi client;
Error e;

client.SetPort( "bogus:12345" );
client.Init( &e );

printf( "Error severity after Init() is %d.\n", e.GetSeverity() );
e.Clear();
printf( "Error severity after Clear() is %d.\n", e.GetSeverity() );
```

Executing the preceding code produces the following output:

```
Error severity after Init() is 4.
Error severity after Clear() is 0.
```

Error::Dump(const char *)

Display an **Error** struct for debugging.

Virtual?	No
Class	Error
Arguments	<code>const char * trace</code> a string to appear next to the debugging output
Returns	<code>void</code>

Notes

[Dump\(\)](#) can be used to determine the exact nature of an **Error** that is being handled. Its primary use is in debugging, as the nature of the output is more geared towards informing the developer than helping an end user.

Example

The following code attempts to establish a connection to a nonexistent server, and dumps the resulting error:

```
ClientApi client;
Error e;

client.SetPort( "bogus:12345" );
client.Init( &e );

e.Dump( "example" );
```

Executing the preceding code produces the following output:

```
Error example 0012FF5C
Severity 4 (error)
Generic 38
Count 3
0: 1093012493 (sub 13 sys 3 gen 38 args 1 sev 4 code 3085)
0: %host%: host unknown.
1: 1093012492 (sub 12 sys 3 gen 38 args 1 sev 4 code 3084)
1: TCP connect to %host% failed.
2: 1076240385 (sub 1 sys 8 gen 38 args 0 sev 4 code 8193)
2: Connect to server failed; check $P4PORT.
host = bogus
host = bogus:12345
```

Error::Fmt(StrBuf *)

Format the text of an error into a **StrBuf**.

Virtual?	No
Class	Error
Arguments	StrBuf *buf a pointer to the StrBuf to contain the formatted error
Returns	void

Notes

The result of [Fmt\(\)](#) is suitable for displaying to an end user; this formatted text is what the command line client displays when an error occurs.

If an error has no severity ([E_EMPTY](#)), [Fmt\(\)](#) returns with no change to the **StrBuf**.

If the error has severity of info ([E_INFO](#)), the **StrBuf** is formatted.

If the error has any higher severity, the **StrBuf** argument passed to [Fmt\(\)](#) is cleared and then replaced with the formatted error.

Example

The following example code displays an error's text:

```
if ( e.Test() )
{
    StrBuf msg;
    e.Fmt( &msg );
    printf( "ERROR:\n%s", msg.Text() );
}
```

Error::Fmt(StrBuf *, int)

Format the text of an error into a `StrBuf`, after applying formatting.

Virtual?	No
Class	Error
Arguments	<code>StrBuf *buf</code> a pointer to the <code>StrBuf</code> to contain the formatted error
	<code>int opts</code> formatting options
Returns	<code>void</code>

Notes

The result of [Fmt\(\)](#) is suitable for displaying to an end user; this formatted text is what the command line client displays when an error occurs.

If an error has no severity (`E_EMPTY`), [Fmt\(\)](#) returns with no change to the `StrBuf`.

If the error has severity of info (`E_INFO`), the `StrBuf` is formatted.

If the error has any higher severity, the `StrBuf` argument passed to [Fmt\(\)](#) is cleared and then replaced with the formatted error.

The `opts` argument is a flag or combination of flags defined by the `ErrorFmtOpts` enum. The default is `EF_NEWLINE`, which puts a newline at the end of the buffer.

Formatting options are as follows:

Argument	Value	Meaning
<code>EF_PLAIN</code>	<code>0x00</code>	perform no additional formatting.
<code>EF_INDENT</code>	<code>0x01</code>	indent each line with a tab (<code>\t</code>)
<code>EF_NEWLINE</code>	<code>0x02</code>	default - terminate buffer with a newline (<code>\n</code>)
<code>EF_NOXLATE</code>	<code>0x04</code>	ignore <code>P4LANGUAGE</code> setting

Example

The following example code displays an error's text, indented with a tab.

```
if ( e.Test() )
{
    StrBuf msg;
    e.Fmt( &msg, EF_INDENT );
    printf( "ERROR:\n%s", msg.Text() );
}
```

Error::GetGeneric()

Returns generic error code of the most severe error.

Virtual?	No
Class	Error
Arguments	None
Returns	int the "generic" code of the most severe error

Notes

For more sophisticated handling, use a "switch" statement based on the error number to handle different errors in different ways.

The generic error codes are not documented at this time.

Example

The following example attempts to establish a connection to a nonexistent server, and displays the resulting generic error code.

```
ClientApi client;
Error e;

client.SetPort( "bogus:12345" );
client.Init( &e );

if ( e.Test() ) printf( "Init() failed, error code %d.\n", e.GetGeneric() );
```

Executing the preceding code produces the following output:

```
Init() failed, error code 38.
```

Error::GetSeverity()

Returns severity of the most severe error.

Virtual?	No
Class	Error
Arguments	None
Returns	int the severity of the most severe error

Notes

The severity can take the following values:

Severity	Meaning
E_EMPTY (0)	no error
E_INFO (1)	information, not necessarily an error
E_WARN (2)	a minor error occurred
E_FAILED (3)	the command was used incorrectly
E_FATAL (4)	fatal error, the command can't be processed

Example

The following code attempts to establish a connection to a server, and beeps if the severity is a warning or worse:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.GetSeverity() > E_INFO ) printf( "Uh-oh!%c\n", 13 );
```

Error::IsFatal()

Tests whether there has been a fatal error.

Virtual?	No
Class	Error
Arguments	None
Returns	int nonzero if error is fatal

Notes

This function returns nonzero if [GetSeverity\(\)](#) == E_FATAL.

Example

The following code attempts to establish a connection to a server, and beeps if the severity is fatal:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.IsFatal() ) printf( "Fatal error!%c\n", 13 );
```

Error::IsWarning()

Tests whether the error is a warning.

Virtual?	No
Class	Error
Arguments	None
Returns	int nonzero if the most severe error is a warning

Notes

This function returns nonzero if [GetSeverity\(\)](#) == E_WARN.

Example

The following code attempts to establish a connection to a server, and beeps if the severity is a warning:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.IsWarning() ) printf( "Warning!%c\n", 13 );
```

Error::Net(const char *, const char *)

Add a network-related error to an **Error**.

Virtual?	No	
Class	Error	
Arguments	<code>const char *op</code>	the network operation that was attempted
	<code>const char *arg</code>	relevant information about that operation
Returns	<code>void</code>	

Notes

To use an **Error** object to track network-related errors, use [Net\(\)](#). Note that network communication with the Perforce server and related errors are already handled by lower levels of the client API.

Example

The following example adds an error message, related to a failure to bind to a network interface, to an **Error** object.

```
e.Net( "bind", service.Text() );
```

Error::operator << (int)

Add data to the text of an error message.

Virtual?	No	
Class	Error	
Arguments	int arg	text to be added to this Error
Returns	Error &	a reference to the modified Error

Notes

The "<<" operator can be used to add text to an error as if the error is an output stream. This operator is typically used in the implementation of other **Error** methods.

Note that an **Error** consists of more than its text, it's more useful to use [Set\(\)](#) to establish a base **Error** and then add text into that, rather than merely adding text to an empty **Error** object.

Example

The following example creates an **Error** using [Set\(\)](#) and the << operator.

```
e.Set( E_WARN, "Warning, number " ) << myErrNum;
```

Error::operator << (char *)

Add data to the text of an error message.

Virtual?	No	
Class	Error	
Arguments	char *arg	text to be added to this Error
Returns	Error &	a reference to the modified Error

Notes

The "<<" operator can be used to add text to an error as if the error is an output stream. This operator is typically used in the implementation of other **Error** methods.

Note that an **Error** consists of more than its text, it's more useful to use [Set\(\)](#) to establish a base **Error** and then add text into that, rather than merely adding text to an empty **Error** object.

Example

The following example creates an **Error** using [Set\(\)](#) and the << operator.

```
e.Set( E_WARN, "Warning! " ) << "Something bad happened";
```

Error::operator << (const StrPtr &)

Add data to the text of an error message.

Virtual?	No	
Class	Error	
Arguments	<code>const StrPtr &arg</code>	text to be added to this Error
Returns	<code>Error &</code>	a reference to the modified Error

Notes

See [Error::operator << \(int\)](#) for details.

Error::operator=(Error &)

Copy an error.

Virtual?	No
Class	Error
Arguments	<code>Error & source</code> the <code>Error</code> to be copied
Returns	<code>void</code>

Notes

The "`=`" operator copies one `Error` into another.

Example

The following example sets `Error e1` to equal `e2`.

```
Error e1, e2;  
e1 = e2;
```

Error::Set(enum ErrorSeverity, const char *)

Add an error message to an `Error`.

Virtual?	No
Class	Error
Arguments	<code>enum ErrorSeverity s</code>
	<code>const char *fmt</code>
Returns	<code>void</code>

Notes

An `Error` can hold multiple error messages; [Set\(\)](#) adds the error message to the `Error`, rather than replacing the `Error`'s previous contents.

An `ErrorSeverity` is an `int` from 0-4 as described in the documentation on [GetSeverity\(\)](#).

Example

The following example adds a fatal error to an `Error` object.

```
Error e;
e.Set( E_FATAL, "Fatal error!");
```

Error::Set(ErrorId &)

Add an error message to an `Error`.

Virtual?	No
Class	Error
Arguments	<code>ErrorId& id</code> the severity and text of the error message
Returns	<code>void</code>

Notes

See [Error::Set\(enum ErrSeverity, const char * \)](#) for details.

An `ErrorId` is a `struct` containing an `int` (`s`) and a `const char *` (`fmt`).

Error::Sys(const char *, const char *)

Add a system error to an **Error**.

Virtual?	No	
Class	Error	
Arguments	<code>const char *op</code>	the system call that was attempted
	<code>const char *arg</code>	relevant information about that call
Returns	<code>void</code>	

Notes

To use an **Error** object to track errors generated by system calls such as file operations, use [`Sys\(\)`](#).

Example

The following example adds an error message, related to a failure to rename a file, to an **Error** object.

```
e.Sys( "rename", targetFile->Name() );
```

Error::Test()

Test whether an **Error** is non-empty.

Virtual?	No
Class	Error
Arguments	None
Returns	int nonzero if the error is non-empty

Notes

`Test()` returns nonzero if [GetSeverity\(\)](#) != `E_EMPTY`.

Example

The following code attempts to establish a connection to a server, and beeps if an error occurs:

```
ClientApi client;
Error e;

client.SetPort( "magic:1666" );
client.Init( &e );

if ( e.Test() ) printf( "An error has occurred.%c\n", 13 );
```

ErrorLog methods

ErrorLog::Abort()

Abort with an error status if an error is detected.

Virtual?	No
Class	ErrorLog
Arguments	None
Returns	void

Notes

If the error is empty (severity is `E_EMPTY`), [Abort\(\)](#) returns. Otherwise [Abort\(\)](#) causes the program to exit with a status of -1.

Example

[Abort\(\)](#) is typically called after [Init\(\)](#) or [Run\(\)](#) to abort the program with a non-zero status if there has been a connection problem. The code in `p4api.cc` is one example:

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::Abort();
```

If any errors are generated during `ClientApi::Init()`, the `Error` object is non-empty, and [Abort\(\)](#) reports the connection error before terminating the program.

ErrorLog::Report()

Print the text of an error to `stderr`.

Virtual?	No
Class	ErrorLog
Arguments	None
Returns	<code>void</code>

Notes

[Report\(\)](#) functions similarly to [Error::Fmt\(\)](#), but displays the text on `stderr` rather than copying it into a `StrBuf`.

Example

The following example displays the contents of an error.

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::Report();
```

ErrorLog::SetLog(const char *)

Redirects this Error's [Report\(\)](#) output to a file.

Virtual?	No
Class	ErrorLog
Arguments	<code>const char *file</code> the file to serve as an error log
Returns	<code>void</code>

Notes

After [SetLog\(\)](#) is called on a given Error object, [Report\(\)](#) directs its output to the specified file rather than `stderr`. This setting applies only to the specified Error object.

Example

The following example redirects an Error's output to a log file, and then writes the Error's text to that log file.

```
ClientApi client;
Error e;

ErrorLog::SetLog( "C:\\Perforce\\errlog" );
client.Init( &e );
ErrorLog::Report();
```

ErrorLog::SetSyslog()

Redirects this Error's [Report\(\)](#) output to **syslog** on UNIX only.

Virtual?	No
Class	ErrorLog
Arguments	None
Returns	void

Notes

This method is only valid on UNIX. After it is called, the output of [Report\(\)](#) is redirected to **syslog**, similar to [SetLog\(\)](#).

Example

The following example redirects an Error's output to **syslog**, and then outputs the Error's text to **syslog**.

```
ClientApi client;
Error e;

ErrorLog::SetSyslog();
client.Init( &e );
ErrorLog::Report();
```

ErrorLog::SetTag(const char *)

Changes the standard tag used by this `Error`'s [Report\(\)](#) method.

Virtual?	No
Class	ErrorLog
Arguments	<code>const char *tag</code> the text of the new tag
Returns	<code>void</code>

Notes

The default tag is "Error". [SetTag\(\)](#) sets the new tag for the specified `Error` object only.

Example

The following example resets the tag on an `Error` to be "NewError".

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::SetTag( "NewError" );
```

ErrorLog::UnsetSyslog()

Stop writing errors to `syslog`.

Virtual?	No
Class	ErrorLog
Arguments	None
Returns	<code>void</code>

Notes

[UnsetSyslog\(\)](#) reverses the effect of [SetSyslog\(\)](#) by resetting the `Error` object to output to `stderr`.

Example

The following example prints an error message to `syslog` and then resets the `Error` back to using `stderr` for output.

```
ClientApi client;
Error e;

client.Init( &e );
ErrorLog::SetSyslog();
ErrorLog::Report();
ErrorLog::UnsetSyslog();
```

FileSys methods

FileSys::Chmod(FilePerm, Error *)

Modify the file mode bits of the file specified by the `path` protected `FileSys` member.

Virtual?	Yes	
Class	FileSys	
Arguments	<code>FilePerm perms</code>	permissions to change the file, either <code>FPM_RO</code> (read only) or <code>FPM_RW</code> (read / write)
	<code>Error *error</code>	returned error status
Returns	<code>void</code>	

Notes

This method is called to make a client file writable (`FPM_RW`) when it is opened for `edit`, or to change it to read-only (`FPM_RO`) after a `submit`.

A `FilePerm` is an `enum` taking one of the following values:

Argument	Value	Meaning
<code>FPM_RO</code>	<code>0x00</code>	leave file read-only.
<code>FPM_RW</code>	<code>0x01</code>	allow read and write operations

Example

To use [Chmod\(\)](#) to create a configuration file and set its permissions to read-only:

```
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "c:\\configfile.txt" );
f->Chmod( FPM_RO, &e );
```

To reimplement [Chmod\(\)](#) under UNIX:

```
void FileSysDemo::Chmod( FilePerm perms, Error *e )
{
    int bits = IsExec() ? PERM_0777 : PERM_0666;

    if ( perms == FPM_RO )
        bits &= ~PERM_0222;

    if ( chmod( Name(), bits & ~myumask ) < 0 )
        e->Sys( "chmod", Name() );

    if ( DEBUG )
        printf( "Debug (Chmod): %s\n", Name() );
}
```

FileSys::Close(Error *)

Close the file specified by the `path` protected `FileSys` member and release any OS resources associated with the open file.

Virtual?	Yes
Class	FileSys
Arguments	<code>Error *error</code> returned error status
Returns	<code>void</code>

Notes

The default implementation of [Close\(\)](#) is called every time a file that is currently [Open\(\)](#) is no longer required. Typically, the handle that was returned for the [Open\(\)](#) call is used to free up the resource.

Your implementation must correctly report any system errors that may occur during the close.

Example

To use [Close\(\)](#) to close an open file:

```
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "c:\\configfile.txt" );
f->Open( FOM_WRITE, &e );
f->Close( &e );
```

To reimplement [Close\(\)](#) to report errors using [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Close( Error *e )
{
    if ( close( fd ) == -1 )
        e->Sys( "close", Name() );

    if ( DEBUG )
        printf( "Debug (Close): %s\n", Name() );
}
```

FileSys::Create(FileSysType)

Create a new FileSys object.

Virtual?	Yes	
Class	FileSys	
Arguments	FileSysType type	file type
Returns	FileSys *	a pointer to the new FileSys.

Notes

A FileSysType is an enum taking one of the values defined in `filesys.h`. The most commonly used FileSysTypes are as follows:

Argument	Value	Meaning
FST_TEXT	0x0001	file is text
FST_BINARY	0x0002	file is binary
FST_ATEXT	0x0011	file is text, open only for append

Example

To use [Create\(\)](#) to create a FileSys object for a log file (text file, append-only):

```
FileSys *f = FileSys::Create( FST_ATEXT );
```

FileSys::Open(FileOpenMode, Error *)

Open the file name specified by the `path` protected `FileSys` member for reading or writing as specified by the argument `FileOpenMode`.

Virtual?	Yes	
Class	FileSys	
Arguments	<code>FileOpenMode mode</code>	Mode to open the file, either <code>FOM_READ</code> (open for read) or <code>FOM_WRITE</code> (open for write)
	<code>Error *error</code>	returned error status
Returns	<code>void</code>	

Notes

The default implementation of [Open\(\)](#) is called every time there is a need to create or access a file on the client workspace.

Operating systems typically return a handle to the opened file, which is then used to allow future read/write calls to access the file.

Your implementation must correctly report any system errors that may occur during the open.

Example

To use [open\(\)](#) to open a log file for writing:

```
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;
StrBuf m;
m.Append( "example: text to append to a log file\r\n" );

f->Set( "C:\\logfile.txt" );
f->Open( FOM_WRITE, &e );
f->Write( m.Text(), m.Length(), &e );
f->Close( &e );
```

To reimplement [Open\(\)](#) to report errors with [Error::Sys\(\)](#), provide debugging output, and use the `FileSysDemo` member "fd" to hold the file handle returned from the `open()` system call:

```
void FileSysDemo::Open( FileOpenMode mode, Error *e )
{
    this->mode = mode;

    int bits = ( mode == FOM_READ ) ? O_RDONLY
                                    : O_WRONLY|O_CREAT|O_APPEND;

    if ( ( fd = open( Name(), bits, PERM_0666 ) ) < 0 )
    {
        e->Sys( mode == FOM_READ ? "open for read" : "open for write",
                 Name() );
    }

    if ( DEBUG )
    {
        printf( "Debug (Open): '%s' opened for '%s'\n", Name(),
                mode == FOM_READ ? "read" : "write" );
    }
}
```

FileSys::Read(const char *, int, Error *)

Attempt to read `len` bytes of data from the object referenced by the file handle (returned by the [Open\(\)](#) method) to the buffer pointed to by `buf`. Upon successful completion, [Read\(\)](#) returns the number of bytes actually read and placed in the buffer.

Virtual?	Yes	
Class	FileSys	
Arguments	<code>const char *buf</code>	pointer to buffer into which to read data
	<code>int len</code>	length of data to read
	<code>Error *error</code>	returned error status
Returns	<code>int</code>	number of bytes actually read

Notes

The default implementation of [Read\(\)](#) is called every time there is a need to read data from the file referenced by the [Open\(\)](#) call.

Your implementation must correctly report any system errors that may occur during I/O.

Example

To use [Read\(\)](#) to read a line from a log file:

```
char line[80];
m.Set( msg );
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "C:\\logfile.txt" );
f->Open( FOM_READ, &e );
f->Read( line, 80, &e );
f->Close( &e );
```

To reimplement [Read\(\)](#) to report errors with [Error::Sys\(\)](#), provide debugging output, and use the `FileSysDemo` member "fd" to hold the file handle returned from the `read()` system call:

```
int FileSysDemo::Read( char *buf, int len, Error *e )
{
    int bytes;

    if ( ( bytes = read( fd, buf, len ) ) < 0 )
        e->Sys( "read", Name() );

    if ( DEBUG )
    {
        printf( "debug (Read): %d bytes\n", bytes );
    }

    return( bytes );
}
```

FileSys::Rename(FileSys *, Error *)

Rename the file specified by the `path` protected `FileSys` member to the file specified by the target `FileSys` object.

Virtual?	Yes	
Class	FileSys	
Arguments	<code>FileSys *target</code>	name of target for rename
	<code>Error *error</code>	returned error status
Returns	<code>void</code>	

Notes

On some operating systems, an unlink might be required before calling [Rename\(\)](#).

Your implementation must correctly report any system errors that may occur during the rename.

Example

To use [Rename\(\)](#) to rename `/usr/logs/log2` to `/usr/logs/log1`:

```
FileSys *f1 = FileSys::Create( FST_TEXT );
FileSys *f2 = FileSys::Create( FST_TEXT );
Error e;

f1->Set( "/usr/logs/log1" );
f2->Set( "/usr/logs/log2" );

f1->Rename( f2, &e );
```

To reimplement [Rename\(\)](#) to report errors with [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Rename( FileSys *target, Error *e )
{
    if ( rename( Name(), target->Name() ) < 0 )
        e->Sys( "rename", Name() );

    if ( DEBUG )
        printf( "Debug (Rename): %s to %s\n", Name(), target->Name() );
}
```

FileSys::Set(const StrPtr *)

Initializes the protected **StrBuf** variable **path** to the supplied filename argument; this **path** is used by other **FileSys** member functions when reading and writing to a physical file location.

Virtual?	Yes	
Class	FileSys	
Arguments	const StrPtr *name filename for this FileSys object	
Returns	void	

Notes

After creating a **FileSys** object, call [Set\(\)](#) to supply it with a **path**.

Example

To use [Set\(\)](#) to set a filename:

```
FileSys *f = FileSys::Create( FST_BINARY );
f->Set( "/tmp/file.bin" );
```

To reimplement [Set\(\)](#) to provide debugging output:

```
void FileSysDemo::Set( const StrPtr &name )
{
    // Set must initialize the protected variable "path"
    // with the filename argument "name".

    path.Set( name );

    if ( DEBUG )
        printf( "debug (Set): %s\n", path.Text() );
}
```

FileSys::Stat()

Obtain information about the file specified by the `path` protected `FileSys` member.

Virtual?	Yes	
Class	FileSys	
Arguments	None	
Returns	<code>int</code>	0 for failure, or status bits as defined below

The status bits have the following meanings:

Status	Meaning
0	failure
FSF_EXISTS (0x01)	file exists
FSF_WRITEABLE (0x02)	file is user-writable
FSF_DIRECTORY (0x04)	file is a directory
FSF_SYMLINK (0x08)	file is symlink
FSF_SPECIAL (0x10)	file is a special file (in the UNIX sense)
FSF_EXECUTABLE (0x20)	file is executable
FSF_EMPTY (0x40)	file is empty
FSF_HIDDEN (0x80)	file is invisible (hidden)

Notes

The default implementation of [Stat\(\)](#) is called to obtain file status every time a file is opened for read.

Example

To use [Stat\(\)](#) to verify the existence of `/usr/bin/p4`:

```
FileSys *f = FileSys::Create( FST_BINARY );
f->Set( "/usr/bin/p4" );
int state = f->Stat();

if ( state & FSF_EXISTS )
    printf( "File found\n" );
```

To reimplement [Stat\(\)](#) to provide debugging output:

```
int FileSysDemo::Stat()
{
    int flags = 0;
    struct stat st;

    if ( DEBUG )
        printf( "Debug (Stat): %s\n", Name() );

    if ( stat( Name(), &st ) < 0 )
        return( flags );

    // Set internal flags

    flags |= FSF_EXISTS;

    if ( st.st_mode & S_IWUSR ) flags |= FSF_WRITEABLE;
    if ( st.st_mode & S_IXUSR ) flags |= FSF_EXECUTABLE;
    if ( S_ISDIR( st.st_mode ) ) flags |= FSF_DIRECTORY;
    if ( !S_ISREG( st.st_mode ) ) flags |= FSF_SPECIAL;
    if ( !st.st_size ) flags |= FSF_EMPTY;
    return flags;
}
```

FileSys::StatModTime()

Return the last modified time of the file specified by the `path` protected `FileSys` member.

Virtual?	Yes
Class	FileSys
Arguments	None
Returns	<code>int</code> 0 for failure, or last modified time in seconds since 00:00:00, January 1, 1970, GMT.

Notes

The default implementation of [StatModTime\(\)](#) is called every time a client file is submitted or synced.

Example

To use [StatModTime\(\)](#) to obtain the modification time on a log file:

```
FileSys *f = FileSys::Create( FST_ATEXT );
f->Set( "/usr/logs/logfile.txt" );
int time = f->StatModTime();

if ( time )
    printf( "%d", time );
```

To reimplement [StatModTime\(\)](#) to provide debugging output:

```
int FileSysDemo::StatModTime()
{
    struct stat st;

    if ( stat( Name(), &st ) < 0 )
        return( 0 );

    if ( DEBUG )
        printf( "Debug (StatModTime): %s\n", Name() );

    return (int)( st.st_mtime );
}
```

FileSys::Truncate()

Truncate the file specified by the `path` protected `FileSys` member to zero length.

Virtual?	Yes
Class	FileSys
Arguments	None
Returns	<code>void</code>

Notes

The default implementation of [Truncate\(\)](#) is only called by the Perforce server.

FileSys::Unlink(Error *)

Remove the file specified by the `path` protected `FileSys` member from the filesystem.

Virtual?	Yes
Class	FileSys
Arguments	<code>Error *error</code> returned error status
Returns	<code>void</code>

Notes

The default implementation of [Unlink\(\)](#) is always called if the file created is temporary.

Your implementation must correctly report any system errors that may occur during removal.

Example

To use [Unlink\(\)](#) to delete an old log file:

```
FileSys *f = FileSys::Create( FST_TEXT );
Error e;

f->Set( "/usr/logs/oldlog" );
f->Unlink( &e );
```

To reimplement [Unlink\(\)](#) to report errors with [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Unlink( Error *e )
{
    if ( unlink( Name() ) < 0 )
        e->Sys( "unlink", Name() );

    if ( DEBUG )
        printf( "Debug (Unlink): %s\n", Name() );
}
```

FileSys::Write(const char *, int, Error *)

Attempt to write "len" bytes of data to the object referenced by the file handle (returned by the [Open\(\)](#) method) from the buffer pointed to by "buf".

Virtual?	Yes	
Class	FileSys	
Arguments	const char *buf	pointer to buffer containing data to be written
	int len	length of data to write
	Error *error	returned error status
Returns	void	

Notes

The default implementation of [Write\(\)](#) is called every time there is a need to write data to the file created by the [Open\(\)](#) call.

Your implementation must correctly report any system errors that may occur during I/O.

Example

To use [Write\(\)](#) to write an error to a log file:

```
StrBuf m;
m.Set( "Unknown user\r\n" );
FileSys *f = FileSys::Create( FST_ATEXT );
Error e;

f->Set( "C:\\logfile.txt" );
f->Open( FOM_WRITE, &e );
f->Write( m.Text(), m.Length(), &e );
f->Close( &e );
```

To reimplement [Write\(\)](#) to report errors with [Error::Sys\(\)](#) and provide debugging output:

```
void FileSysDemo::Write( const char *buf, int len, Error *e )
{
    int bytes;

    if ( ( bytes = write( fd, buf, len ) ) < 0 )
        e->Sys( "write", Name() );

    if ( DEBUG )
        printf( "debug (Write): %d bytes\n", bytes );
}
```

Ignore methods

Ignore::Reject(const StrPtr &, const StrPtr &)

Tests whether the provided path will be rejected when it is opened for add because it matches an entry in the provided ignore file.

Virtual?	No	
Class	Ignore	
Arguments	<code>const StrPtr &path</code>	the path to check
	<code>const StrPtr &ignoreFile</code>	the full path to the ignore file
Returns	<code>int</code>	nonzero if path is ignored

Notes

Calling [Reject\(\)](#) provides a preview of what will happen when files are opened for add.

If the ignore file does not exist, or is not readable, no files are rejected.

Example

The following example demonstrates the usage of [Reject\(\)](#).

```
# include "clientapi.h"
# include "ignore.h"

int main()
{
    ClientApi client;
    StrBuf clientPath;

    client.SetIgnoreFile( ".p4ignore" );
    clientPath = "ignore.txt";
    if ( client->GetIgnore()->Reject( *clientPath,
                                         client->GetIgnoreFile() ) )
    {
        printf( "%s is to be ignored.\n", clientPath.Text() );
    }
}
```

Ignore::RejectCheck(const StrPtr &)

Tests whether the provided path will be rejected when it is opened for add because it matches an ignore file entry.

Virtual?	No	
Class	Ignore	
Arguments	const StrPtr &path	the path to check
Returns	int	nonzero if path is ignored

Notes

Calling [RejectCheck\(\)](#). provides a preview of what will happen the file is opened for add.

Use `RejectCheck()` when you have to test multiple paths that may be rejected. First call [Reject\(\)](#) to parse the ignore file, and then call `RejectCheck()` for each additional path that needs to be checked.

Example

The following example demonstrates the usage of [RejectCheck\(\)](#).

```
# include "clientapi.h"
# include "ignore.h"

int main()
{
    ClientApi client;
    StrBuf clientPath;

    client.SetIgnoreFile( ".p4ignore" );
    clientPath = "ignore.txt";
    if ( client->GetIgnore()->Reject( *clientPath,
                                         client->GetIgnoreFile() ) )
    {
        printf( "%s is to be ignored.\n", clientPath.Text() );
    }

    clientPath = "ignore2.txt";
    if ( client->GetIgnore()->Reject( *clientPath,
                                         client->GetIgnoreFile() ) )
    {
        printf( "%s is to be ignored.\n", clientPath.Text() );
    }
}
```

KeepAlive methods

KeepAlive::IsAlive()

The only method of the [KeepAlive](#) class, [IsAlive\(\)](#) is used in applications to request that the current command be terminated by disconnecting.

Virtual?	Yes
Class	KeepAlive
Arguments	None
Returns	int 0 to terminate connection, 1 to continue processing

Notes

Use [ClientApi::SetBreak\(\)](#) to establish a callback to be called every 0.5 seconds during command execution.

See also

[ClientApi::SetBreak\(\)](#)

Example

The following example implements a custom [IsAlive\(\)](#) that can be called three times before returning 0 and terminating the connection. If the call to run the `changes` command takes less than 1.5 seconds to complete on the server side, the program outputs the list of changes. If the call to run the `changes` command takes more than 1.5 seconds, the connection is interrupted.

```
#include <clientapi.h>

// subclass KeepAlive to implement a customized IsAlive function.
class MyKeepAlive : public KeepAlive
{
public:
    int IsAlive();
};

// Set up the interrupt callback. After being called 3 times,
// interrupt 3 times, interrupt the current server operation.
int MyKeepAlive::IsAlive()
{
    static int counter = 0;
    if ( ++counter > 3 )
    {
        counter = 0;
        return( 0 );
    }
    return( 1 );
}

// Now test the callback
ClientUser ui;
ClientApi client;
MyKeepAlive cb;
Error e;

client.Init( &e );
client.SetBreak( &cb ); // SetBreak must happen after the Init
client.Run( "changes", &ui );
client.Final( &e );
```

MapApi methods

MapApi::Clear()

Empties a mapping.

Virtual?	No
Class	MapApi
Arguments	None
Returns	void

Notes

After this method has been called on a **MapApi** object, the object is indistinguishable from a freshly-constructed object.

MapApi::Count()

Returns the number of entries currently in the mapping.

Virtual?	No
Class	MapApi
Arguments	None
Returns	int The number of entries currently in the mapping

Notes

The number returned by [Count\(\)](#) may be different from the number of times that [Insert\(\)](#) has been called. This is because **MapApi** automatically disambiguates itself, adding new exclusions to eliminate ambiguity between partially overlapping entries and removing entries that are redundant.

Example

The following example demonstrates [Count\(\)](#), [GetType\(\)](#), [GetLeft\(\)](#), and [GetRight\(\)](#) being used to iterate over a **MapApi** that contains four entries after two calls to [Insert\(\)](#).

This code produces the following output:

```
//depot/... //client/...
-//depot/d2/... //client/d2/...
-//depot/d1/... //client/d1/...
//depot/d1/... //client/d2/...
```

```
MapApi clientmap;

clientmap.Insert( StrRef( "//depot/..." ), StrRef( "//client/..." ) );
clientmap.Insert( StrRef( "//depot/d1/..." ), StrRef( "//client/d2/..." ) );

char c = ' ';
for ( int i = 0; i < clientmap.Count(); i++ )
{
    switch( clientmap.GetType( i ) )
    {
        case MapInclude:
            c = ' '; break;
        case MapExclude:
            c = '-'; break;
        case MapOverlay:
            c = '+'; break;
    }

    printf( "%c%s %s\n", c,
            clientmap.GetLeft( i )->Text(),
            clientmap.GetRight( i )->Text() );
}
```

MapApi::GetLeft(int)

Returns the left side of the specified view entry.

Virtual?	No	
Class	MapApi	
Arguments	<code>int i</code>	the index of the desired entry
Returns	<code>const StrPtr *</code>	a string representing the left side of the entry

Notes

The index should be between 0 and one less than the number of mapping entries.

See also

[MapApi::Count\(\)](#)

Example

See the example for [MapApi::Count\(\)](#).

MapApi::GetRight(int)

Returns the right side of the specified view entry.

Virtual?	No	
Class	MapApi	
Arguments	<code>int i</code>	the index of the desired entry
Returns	<code>const StrPtr *</code>	a string representing the right side of the entry

Notes

The index should be between 0 and one less than the number of mapping entries.

See also

[MapApi::Count\(\)](#)

Example

See the example for [MapApi::Count\(\)](#).

MapApi::GetType(int)

Returns the type of the specified view entry.

Virtual?	No	
Class	MapApi	
Arguments	int i	the index of the desired entry
Returns	MapType	the entry type

Notes

The entry type is one of `MapInclude`, `MapExclude`, and `MapOverlay`.

`MapExclude` entries negate earlier `MapInclude` and `MapOverlay` entries that map the same paths, and `MapOverlay` entries are not disambiguated if they overlap with earlier `MapInclude` entries.

In human-readable Perforce view specifications, `MapExclude` lines are indicated with a - character, and `MapOverlay` lines are indicated with a + character.

See also

[MapApi::Count\(\)](#)

Example

See the example for [MapApi::Count\(\)](#).

MapApi::Insert(const StrPtr &, MapType)

Adds a new entry to the mapping.

Virtual?	No	
Class	MapApi	
Arguments	StrPtr & lr MapType t	the path to which the entry applies the mapping type (by default, MapInclude)
Returns	void	

Notes

This [Insert\(\)](#) overload is a convenience function that adds an entry with identical left and right sides. It is meant to represent mappings whose sole purpose is to include and exclude files, such as protection tables and label views.

Example

The following example demonstrates the construction and use of a protection table mapping.

```
MapApi protect;
protect.Insert( StrRef( "//..." ) );
protect.Insert( StrRef( "//private/..." ), MapExclude );

StrBuf to;
StrBuf file1( "//depot/file.txt" );
StrBuf file2( "//private/file.txt" );

printf( "%s - access %d\n", file1.Text(), protect.Translate( file1, to ) );
printf( "%s - access %d\n", file2.Text(), protect.Translate( file2, to ) );
```

This produces the following output:

```
//depot/file.txt - access 1
//private/file.txt - access 0
```

MapApi::Insert(const StrPtr &, const StrPtr &, MapType)

Adds a new entry to the mapping.

Virtual?	No						
Class	MapApi						
Arguments	<table> <tr> <td>StrPtr & l</td> <td>the left side of the entry</td> </tr> <tr> <td>StrPtr & r</td> <td>the right side of the entry</td> </tr> <tr> <td>MapType t</td> <td>the mapping type (by default, <code>MapInclude</code>)</td> </tr> </table>	StrPtr & l	the left side of the entry	StrPtr & r	the right side of the entry	MapType t	the mapping type (by default, <code>MapInclude</code>)
StrPtr & l	the left side of the entry						
StrPtr & r	the right side of the entry						
MapType t	the mapping type (by default, <code>MapInclude</code>)						
Returns	<code>void</code>						

Notes

[Insert\(\)](#) adds one new entry to a mapping at the "bottom" (highest precedence) position in the map. The `MapType` parameter indicates whether the entry is a standard inclusion (the default), an exclusion, or an overlay mapping (only useful when modeling a client view).

Example

The following example demonstrates the construction and use of a branch view mapping.

```
MapApi branch;
branch.Insert( StrRef( "//depot/main/..." ), StrRef( "//depot/rel1/..." ) );

StrBuf source( "//depot/main/file.c" );
StrBuf target;

branch.Translate( source, target );
printf( "%s -> %s\n", source.Text(), target.Text() );
```

This produces the following output:

```
//depot/main/file.c -> //depot/rel1/file.c
```

MapApi::Join(MapApi *, MapApi *) [static]

Joins two `MapApis` together to produce a combined mapping.

Virtual?	No	
Class	MapApi	
Arguments	<code>MapApi *left</code>	the first mapping
	<code>MapApi *right</code>	the second mapping
Returns	<code>MapApi *</code>	a new <code>MapApi</code> representing the joined maps

Notes

This overload of [Join\(\)](#) links the right side of the first mapping to the left side of the second mapping, as if the two mappings were laid out left to right and glued together in the middle. The resulting `MapApi`'s left side corresponds to the first mapping's left side, and its right side corresponds to the second mapping's right side.

If the right side of the first mapping does not have anything in common with the left side of the second mapping, the resulting map is empty.

The other [Join\(\)](#) overload allows more control over which side of each mapping is joined to the other, and the direction of the resulting mapping.

This function allocates a new `MapApi` object on the heap; the caller is responsible for deleting it.

Example

The following example demonstrates a join between a branch view and a client view.

```
MapApi branchmap;
branchmap.Insert( StrRef( "//depot/main/..." ), StrRef( "//depot/rel1/..." ) );

MapApi clientmap;
clientmap.Insert( StrRef( "//depot/..." ), StrRef( "//client/depot/..." ) );

MapApi *branch_to_client = MapApi::Join( &branchmap, &clientmap );

StrBuf source( "//depot/main/file.c" );
StrBuf target;

branch_to_client->Translate( source, target );
printf( "%s -> %s\n", source.Text(), target.Text() );
delete branch_to_client;
```

This produces the following output:

```
//depot/main/file.c -> //client/depot/rel1/file.c
```

MapApi::Join(MapApi *, MapDir, MapApi *, MapDir) [static]

Joins two `MapApis` together to produce a combined mapping.

Virtual?	No	
Class	MapApi	
Arguments	<code>MapApi *m1</code>	the first mapping
	<code>MapDir d1</code>	the orientation of the first mapping
	<code>MapApi *m2</code>	the second mapping
	<code>MapDir d2</code>	the orientation of the second mapping
Returns	<code>MapApi *</code>	a new <code>MapApi</code> representing the joined maps

Notes

This overload of [Join\(\)](#) works exactly like the simpler two-argument overload, but allows the caller to reverse either or both mappings before they are joined together. Specifying `MapLeftRight` as the direction for both mappings will produce the same result as the two-argument [Join\(\)](#).

If the two mappings do not have anything in common at the join point, the result is an empty mapping.

This function allocates a new `MapApi` object on the heap; the caller is responsible for deleting it.

Example

The following example demonstrates a join between a branch view and a client view, with both mappings reversed so that the client path is on the left side of the result and the branch source is on the right side.

```
MapApi branchmap;
branchmap.Insert( StrRef( "//depot/main/..." ), StrRef( "//depot/rel1/..." ) );

MapApi clientmap;
clientmap.Insert( StrRef( "//depot/..." ), StrRef( "//client/depot/..." ) );

MapApi *client_to_branch = MapApi::Join
    ( &clientmap, MapRightLeft, &branchmap, MapRightLeft );

StrBuf clientFile( "//client/depot/rel1/file.c" );
StrBuf branchFile;

client_to_branch->Translate( clientFile, branchFile );
printf( "%s -> %s\n", clientFile.Text(), branchFile.Text() );
delete client_to_branch;
```

Executing the preceding code produces the following output:

```
//client/depot/rel1/file.c -> //depot/main/file.c
```

MapApi::Translate(const StrPtr &, StrBuf&, MapDir)

Translates a file path from one side of a mapping to the other.

Virtual?	No
Class	MapApi
Arguments	const StrPtr & from the input path
	StrBuf & to the output path
	MapDir d the direction in which to translate (by default, MapLeftRight)
Returns	bool whether or not the translation succeeded

Notes

The [Translate\(\)](#) function is used to determine the effect of the mapping on any particular file. In the case of a two-sided mapping (such as a client view), it indicates where any given depot file maps in the client, or vice versa. In the case of a one-sided mapping (such as a protection table), it simply indicates whether a particular file is mapped at all.

If the specified **MapDir** is [MapLeftRight](#), the input path is translated from the left side of the mapping to the right side of the mapping. If the **MapDir** is [MapRightLeft](#), the mapping is effectively inverted, so that the input path is translated from the right side to the left.

If the input path does not match anything in the left side of the mapping (or the right side in the [MapRightLeft](#) case), the translation fails just as if the input path had been excluded from the mapping.

[Translate\(\)](#) is designed to map single files. To model the effect of passing a broader path through a mapping, create a new one-sided mapping that represents that path and [Join\(\)](#) it with the other mapping.

Examples

See the examples for [Insert\(\)](#) and [Join\(\)](#).

Options methods

Options::GetValue(char opt, int subopt)

Returns the value of a flag previously stored by [Options::Parse\(\)](#).

Virtual?	No	
Class	Options	
Arguments	char opt	The flag to check
	int subopt	Return the argument associated with the subopt -th occurrence of the opt flag on the command line.
Returns	StrPtr *	The value of the flag. This is "true" for flags which, when provided, do not take a value, and NULL if the flag is not provided

Notes

You must call [Options::Parse\(\)](#) before calling [GetValue\(\)](#).

If a flag does not occur on the command line, [GetValue\(\)](#) returns **NULL**.

If a flag is provided without a value, [GetValue\(\)](#) returns "true".

If a flag appears only once on a command line, extract the value of its arguments by calling [GetValue\(\)](#) with a **subopt** of zero, or use the `[]` operator.

If a flag occurs more than once on a command line, extract the value supplied with each occurrence by calling [Options::GetValue\(\)](#) once for each occurrence, using different **subopt** values.

See also

[Options::Parse\(\)](#)
[Options::operator\[\]](#)

Example

Executing the following code produces the following output:

```
$ getvalue -h -c1 -c2 -d3

opts.GetValue( h, 0 ) value is true
opts.GetValue( c, 0 ) value is 1
opts.GetValue( c, 1 ) value is 2
opts.GetValue( d, 0 ) value is 3
```

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <error.h>
#include <options.h>

int main( int argc, char **argv )
{
    // Parse options.
    Error *e = new Error();
    ErrorId usage = { E_FAILED, "Usage: getvalue -h for usage." };

    Options opts;

    // strip out the program name before parsing
    argc--;
    argv++;

    char *ParseOpts = "ha:b:c:d:e:f:";
    opts.Parse( argc, argv, ParseOpts, OPT_ANY, usage, e );

    if ( e->Test() )
    {
        StrBuf msg;
        e->Fmt( &msg ); // See Error::Fmt()
        printf( "ERROR:\n%s", msg.Text() );
        return 1;
    }

    char *iParseOpts = ParseOpts;
    int isubopt;
    StrPtr *s;

    // Print values for options.
    while( *iParseOpts != '\0' )
    {
        if ( *iParseOpts != ':' )
        {
            isubopt = 0;
            while( s = opts.GetValue( *iParseOpts, isubopt ) )
            {
                printf( "opts.GetValue( %c, %d ) value is %s\n",
                        *iParseOpts, isubopt, s->Text() );
                isubopt++;
            }
            iParseOpts++;
        }
    }
    return 0;
}
```

Options::operator[](char opt)

Returns the value of a flag previously stored by [Options::Parse\(\)](#).

Virtual?	No
Class	Options
Arguments	char opt The flag to check
Returns	StrPtr *

Notes

You must call [Options::Parse\(\)](#) before using the [] operator.

If a flag does not occur on the command line, the [] operator returns NULL.

If a flag is provided without a value, the [] operator returns "true".

If a flag appears once on a command line, the [] operator returns its argument. This is equivalent to calling [Options::GetValue\(\)](#) with a subopt of zero.

The [] operator is sufficient for extracting the value of any flag which does not have more than one value associated with it. If a flag appears more than once on the same command line, you must use [Options::GetValue\(\)](#), specifying a different subopt value for each appearance.

See also

[Options::Parse\(\)](#)
[Options::GetValue\(\)](#)

Example

The following code parses some of the standard Perforce global options and stores them in a `ClientApi` object.

If the `-h` option is supplied, the program also displays a brief message.

```
#include <iostream>
#include <clientapi.h>
#include <error.h>
#include <errornum.h>
#include <msgclient.h>
#include <options.h>

int main( int argc, char **argv )
{
    Error *e = new Error();
    ErrorId usage = { E_FAILED, "Usage: myapp -h for usage." };

    // Bypass argv[0] before parsing
    argc--;
    argv++;

    Options opts;
    opts.Parse( argc, argv, "hc:H:d:u:p:P:", OPT_ANY, usage, e );

    if ( e->Test() )
    {
        StrBuf msg;
        e->Fmt( &msg ); // See Error::Fmt()
        printf( "Error: %s", msg.Text() );
        return 1;
    }

    ClientApi client;
    StrPtr *s;

    // Get command line overrides of client, host, cwd, user, port, pass
    if ( s = opts[ 'h' ] ) printf( "User asked for help\n" );
    if ( s = opts[ 'c' ] ) client.SetClient( *s );
    if ( s = opts[ 'H' ] ) client.SetHost( *s );
    if ( s = opts[ 'd' ] ) client.SetCwd( *s );
    if ( s = opts[ 'u' ] ) client.SetUser( *s );
    if ( s = opts[ 'p' ] ) client.SetPort( *s );
    if ( s = opts[ 'P' ] ) client.SetPassword( *s );

    // Perform desired operation(s) with your ClientApi here
    return 0;
}
```

Options::Parse(int &, char ** &, const char *, int, const ErrorId &, Error *)

Manipulate `argc` and `argv` to extract command line arguments and associated values.

Virtual?	No												
Class	Options												
Arguments	<table> <tr> <td><code>int &argc</code></td> <td>Number of arguments</td> </tr> <tr> <td><code>char ** &argv</code></td> <td>An array of arguments to parse</td> </tr> <tr> <td><code>const char *opts</code></td> <td>The list of valid options to extract</td> </tr> <tr> <td><code>int flag</code></td> <td>A flag indicating how many arguments are expected to remain when parsing is complete</td> </tr> <tr> <td><code>const ErrorId &usage</code></td> <td>An error message containing usage tips</td> </tr> <tr> <td><code>Error *e</code></td> <td>The <code>Error</code> object to collect any errors encountered</td> </tr> </table>	<code>int &argc</code>	Number of arguments	<code>char ** &argv</code>	An array of arguments to parse	<code>const char *opts</code>	The list of valid options to extract	<code>int flag</code>	A flag indicating how many arguments are expected to remain when parsing is complete	<code>const ErrorId &usage</code>	An error message containing usage tips	<code>Error *e</code>	The <code>Error</code> object to collect any errors encountered
<code>int &argc</code>	Number of arguments												
<code>char ** &argv</code>	An array of arguments to parse												
<code>const char *opts</code>	The list of valid options to extract												
<code>int flag</code>	A flag indicating how many arguments are expected to remain when parsing is complete												
<code>const ErrorId &usage</code>	An error message containing usage tips												
<code>Error *e</code>	The <code>Error</code> object to collect any errors encountered												
Returns	<code>void</code>												

Notes

You must bypass `argv[0]` (that is, the name of the calling program) before calling [Options::Parse\(\)](#). This is most easily done by decrementing `argc` and incrementing `argv`.

An argument by be of the form `-avalue` or `-avalue`. Although an argument of the form `-avalue` is passed as two entries in `argv`, the [Options::Parse\(\)](#) method parses it as one logical argument.

As arguments are scanned from the caller's `argv`, the caller's `argc` and `argv` are modified to reflect the arguments scanned. Scanning stops when the next argument either:

- does not begin with a `-`, or
- is a `-` only, or
- is not in the array of expected options.

Once scanning has stopped, `argc` and `argv` are returned "as-is"; that is, they are returned as they were when scanning stopped. There is no "shuffling" of arguments.

The `opts` argument is a format string indicating which options are to be scanned, and whether these options are to have associated values supplied by the user. Flags with associated values must be followed by a colon (`:`) or a period (`.`) in the format string. Using a colon allows arguments to be specified in the form `-avalue` or `-avalue`; using a period allows only the `-avalue` form.

If, based on the expectation set in the format string, the actual option string in `argv` does not provide a value where one is expected, an error is generated.

For instance, the p4 Command Line Client's -V and -? flags are expected to be supplied without values, but the -p flag is expected to be accompanied with a setting for P4PORT. This is the format string used by the p4 Command Line Client:

```
"?c:C:d:GRhH:p:P:l:L:su:v:Vx:z:Z:"
```

Characters followed by colons (c, C, and so on) are command line flags that take values; all characters not followed by colons (? , G, R, h, s, and V) represent command line flags that require no values.

There is a limit of 20 options per command line, as defined in `options.h` by the constant `N_OPTS`.

The `flag` argument should be one of the following values (defined in `options.h`):

Argument	Value	Meaning
OPT_ONE	0x01	Exactly one argument is expected to remain after parsing
OPT_TWO	0x02	Exactly two arguments are expected to remain after parsing
OPT_THREE	0x04	Exactly three arguments are expected to remain after parsing
OPT_MORE	0x08	More than two arguments (three or more) are to remain after parsing
OPT_NONE	0x10	Require that zero arguments remain after parsing; if arguments remain after parsing, set an error.
OPT_MAKEONE	0x20	If no arguments remain after parsing, create one that points to <code>NULL</code> .
OPT_OPT	0x11	NONE, or ONE.
OPT_ANY	0x1F	ONE, TWO, THREE, MORE, or NONE.
OPT_DEFAULT	0x2F	ONE, TWO, THREE, MORE, or MAKEONE.
OPT_SOME	0x0F	ONE, TWO, THREE, or MORE.

See also

[Options::GetValue\(\)](#)
[Options::operator\[\]\(\)](#)

Example

The following code and examples illustrate how [Options::Parse\(\)](#) works.

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <error.h>
#include <options.h>

int main( int argc, char **argv )
{
    // Parse options.
```

```

Error *e = new Error();
ErrorId usage = { E_FAILED, "Usage: parse optionstring flag args" };

Options opts;

// strip out the program name before parsing
argc--;
argv++;

// next argument is options to be parsed
char *ParseOpts = argv[ 0 ];
argc--;
argv++;

// next argument is number of arguments remaining after parse
int flag = strtol( argv[ 0 ], NULL, 0 );
argc--;
argv++;

// Echo pre-parse values
int iargv;
printf( "Prior to Options::Parse call:\n" );
printf( " ParseOpts is %s\n", ParseOpts );
printf( " flag is 0%2.2X\n", flag );
printf( " argc is %d\n", argc );
for ( iargv = 0; iargv < argc; iargv++ )
{
    printf( " argv[ %d ] is %s\n", iargv, argv[ iargv ] );
}
printf( "\n" );

opts.Parse( argc, argv, ParseOpts, flag, usage, e );
if ( e->Test() )
{
    // See example for Error::Fmt()
    StrBuf msg;
    e->Fmt( &msg );
    printf( "ERROR:\n%s\n", msg.Text() );
}

char *iParseOpts = ParseOpts;
int isubopt;
StrPtr *s;

// Print values for options.
while( *iParseOpts != '\0' )
{
    if ( *iParseOpts != ':' )
    {
        isubopt = 0;
        while( s = opts.GetValue( *iParseOpts, isubopt ) )
        {
            printf( "opts.GetValue( %c, %d ) value is %s\n",
                    *iParseOpts, isubopt, s->Text() );
            isubopt++;
        }
    }
}

```

```
        }
    }

    iParseOpts++;

}

// Echo post-parse values
printf( "\n" );
printf( "After Options::Parse call:\n" );
printf( " argc is %d\n", argc );
for ( iargv = 0; iargv < argc; iargv++ )
{
    printf( " argv[ %d ] is %s\n", iargv, argv[ iargv ] );
}

return 0;
}
```

Invoke `parsedemo` with a format string, a flag (as defined in `options.h`) to specify the number of options expected, and a series of arguments.

For instance, to allow arguments `-a`, `-b` and `-c`, where `-a` and `-b` take values, but `-c` does not take a value, and to use a flag of `OPT_NONE` (`0x10`) to require that no options remain unparsed after the call to [Options::Parse\(\)](#), invoke `parsedemo` as follows.

```
$ parsedemo a:b:c 0x10 -a vala -b valb -c
```

Arguments of the form `-c one` are passed as two entries in `argv`, but parsed as one logical argument:

```
$ parsedemo ha:b:c:d:e: 0x10 -cone
Prior to Options::Parse call:
ParseOpts is ha:b:c:d:e:
flag is 0x10
argc is 1
argv[ 0 ] is -cone

opts.GetValue( c, 0 ) value is one

After Options::Parse call:
argc is 0

$ parsedemo ha:b:c:d:e: 0x10 -c one
Prior to Options::Parse call:
ParseOpts is ha:b:c:d:e:
flag is 0x10
argc is 2
argv[ 0 ] is -c
argv[ 1 ] is one

opts.GetValue( c, 0 ) value is one

After Options::Parse call:
argc is 0
```

Use of a period in the options string disallows the **-c one** form for the **c** option:

```
$ parsedemo ha:b:c.d:e: 0x10 -c one
Prior to Options::Parse call:
ParseOpts is ha:b:c.d:e:
flag is 0x10
argc is 2
argv[ 0 ] is -c
argv[ 1 ] is one

ERROR:
Usage: parse optionstring flag args
Unexpected arguments.

opts.GetValue( c, 0 ) value is

After Options::Parse call:
argc is 1
argv[ 0 ] is one
```

Arguments not in the format string are permitted or rejected with the use of different flag values; **OPT_NONE** (0x10) requires that no arguments remain after the call to [Options::Parse\(\)](#), while **OPT_ONE** (0x01) requires that one argument remain.

```
$ parsedemo ha:b:c:d:e: 0x10 -c one two
Prior to Options::Parse call:
ParseOpts is ha:b:c:d:e:
flag is 0x10
argc is 3
argv[ 0 ] is -c
argv[ 1 ] is one
argv[ 2 ] is two

ERROR:
Usage: parse optionstring flag args
Unexpected arguments.

opts.GetValue( c, 0 ) value is one

$ parse ha:b:c:d:e: 0x01 -c one two
Prior to Options::Parse call:
ParseOpts is ha:b:c:d:e:
flag is 0x01
argc is 3
argv[ 0 ] is -c
argv[ 1 ] is one
argv[ 2 ] is two

opts.GetValue( c, 0 ) value is one

After Options::Parse call:
argc is 1
argv[ 0 ] is two
```

Options::Parse(int &, StrPtr * &, const char *, int, const ErrorId &, Error *)

Extract command line arguments and associated values.

Virtual?	No
Class	Options
Arguments	int &argc Number of arguments
	StrPtr * &argv An array of arguments to parse
	const char *opts The list of valid options to extract
	int flag A flag indicating how many arguments are expected to remain when parsing is complete
	const ErrorId &usage An error message containing usage tips
	Error *e The Error object to collect any errors encountered
Returns	void

Notes

See the notes for the `char ** &argv` version of [Options::Parse\(\)](#) for details.

See also

[Options::Parse\(\)](#)

Signaler methods

Signaler::Block()

Cause interrupt signals from the user to be ignored until a subsequent call to [Signaler::Catch\(\)](#).

Virtual?	No
Class	Signaler
Arguments	None
Returns	void

Notes

[Block\(\)](#) does not actually block the signals, but causes the process to ignore them.

For portability reasons, [Block\(\)](#) and [Catch\(\)](#) use the BSD / ANSI C `signal(2)` function rather than the POSIX `sigaction()`.

See also

[Signaler::Catch\(\)](#)
[Signaler::OnIntr\(\)](#)

Example

```
#include <unistd.h> // for sleep()
#include <stdhdrs.h>
#include <strbuf.h>
#include <signaler.h>

int main( int argc, char **argv )
{
    // Block ^C
    printf( "For the next 5 seconds, ^C will be ignored\n" );
    signaler.Block();
    sleep( 5 );

    printf( "Enabling ^C again\n" );
    signaler.Catch();
    for ( ; ; )
        sleep( 60 );
    exit( 0 );
}
```

Signaler::Catch()

Allow interrupt signals from the user to be delivered once more following a previous call to [Signaler::Block\(\)](#).

Virtual?	No
Class	Signaler
Arguments	None
Returns	void

Notes

[Catch\(\)](#) does not replace your signal handler if you have already replaced the **Signaler** class' handler with one of your own using the ANSI **signal(2)** function.

For portability reasons, [Block\(\)](#) and [Catch\(\)](#) use the BSD/ANSI C **signal(2)** function rather than the POSIX **sigaction()**.

See also

[Signaler::Block\(\)](#)
[Signaler::OnIntr\(\)](#)

Example

```
int main( int argc, char **argv )
{
    // Block ^C
    printf( "For the next 5 seconds, ^C will be ignored\n" );
    signaler.Block();
    sleep( 5 );

    printf( "Enabling ^C again\n" );
    signaler.Catch();
    for ( ; )
        sleep( 60 );
    exit( 0 );
}
```

Signaler::DeleteOnIntr(void *)

Removes a function previously registered using [OnIntr\(\)](#) from the list.

Virtual?	No
Class	Signaler
Arguments	void *ptr Pointer to the data item with which the original function was registered
Returns	void

See also

[Signaler::OnIntr\(\)](#)
[Signaler::Intr\(\)](#)

Example

```
#include <unistd.h>    // for sleep()
#include <stdhtrs.h>
#include <strbuf.h>
#include <signaler.h>

class MyClass
{
public:
    void      Set( StrPtr *d ) { data = *d; }
    const StrPtr *Get()          { return &data; }
    void      Identify()        { printf( "I'm %s\n", data.Text() ); }

private:
    StrBuf    data;
};

static void InterruptHandler( void *p )
{
    MyClass     *m = ( MyClass * )p;
    m->Identify();
}

int main( int argc, char **argv )
{
    StrBuf    data;
    MyClass   *list[ 5 ];

    for ( int i = 1; i <= 5; i++ )
    {
        data.Set( "Object" );
        data << i;

        MyClass   *p = new MyClass;
        list[ i - 1 ] = p;

        p->Set( &data );
        signaler.OnIntr( InterruptHandler, (void *)p );
    }

    // Unregister Object 3
    signaler.DeleteOnIntr( list[ 2 ] );

    printf( "Hit ^C to fire the interrupt handler\n" );
    for ( ; )
        sleep( 60 );

    exit( 0 );
}
```

Signaler::Intr()

Coordinate execution of all functions registered by [Signaler::OnIntr\(\)](#).

Virtual?	No
Class	Signaler
Arguments	None
Returns	void

Notes

[Intr\(\)](#) is the [Signaler](#) class's main handler for interrupt signals.

Most Perforce client applications do not need to call [Intr\(\)](#) directly, because it is called directly from the internal handler function that catches the interrupt signals.

This internal handler function also causes the process to exit, returning an exit status of -1 to the operating system. (For instance, [signaler.Intr\(\)](#); `exit(-1)`)

If you require more flexible or complex interrupt handling, replace the default interrupt handler function with your own by using the ANSI C `signal(2)` function, and call [Intr\(\)](#) to execute the registered functions.

Caveat

[Intr\(\)](#) does not deregister functions after they have been called. When calling a registered function twice might cause a failure, immediately deregister it using [DeleteOnIntr\(\)](#) after the function has been called.

See also

[Signaler::OnIntr\(\)](#)

Example

```
#include <unistd.h>    // for sleep()
#include <signal.h>
#include <stdhdrs.h>
#include <strbuf.h>
#include <signaler.h>

class MyClass
{
public:
    void      Set( StrPtr *d ) { data = *d; }
    const StrPtr *Get()          { return &data; }
    void      Identify()        { printf( "I'm %s\n", data.Text() ); }

private:
```

```

        StrBuf      data;
    };

    static int intrCount = 0;
    static const int maxIntr = 3;

    // Replacement handler for SIGINT signals. Overrides Signaler class's
    // default handler to avoid immediate exit.

    static void trap_interrupt( int sig )
    {
        intrCount++;
        printf( "Received SIGINT. Calling registered functions...\n" );
        signaler.Intr();
        printf( "All functions done\n\n" );
        if ( intrCount >= maxIntr )
        {
            printf( "Interrupt limit hit. Exiting...\n" );
            exit( 0 );
        }
    }

    static void InterruptHandler( void *p )
    {
        MyClass     *m = ( MyClass * )p;
        m->Identify();

        // Don't identify this object again
        signaler.DeleteOnIntr( p );
    }

    int main( int argc, char **argv )
    {
        signal( SIGINT, trap_interrupt );
        signaler.Catch();

        int objCount = 5;
        int nextId = 1;
        for ( ; ; )
        {
            int i;
            for ( i = nextId; i < nextId + objCount; i++ )
            {
                StrBuf data;

                data.Set( "Object" );
                data << i;

                MyClass *p = new MyClass;
                p->Set( &data );

                printf( "Registering %s\n", data.Text() );
                signaler.OnIntr( InterruptHandler, ( void * )p );
            }

            nextId = i;
        }
    }
}

```

```
    printf( "\n" );
    printf( "Hit ^C to fire the interrupt handler [%d to go]\n",
            maxIntr - intrCount );
    sleep( 10 );
}

exit( 0 );
}
```

Signaler::OnIntr(SignalFunc, void *)

Register a function and argument to be called when an interrupt signal is received.

Virtual?	No
Class	Signaler
Arguments	SignalFunc callback Pointer to a function to call on receipt of an interrupt signal. The function must have the prototype <code>voidfunc(void *ptr)</code>
	void *ptr Pointer to a data item to pass to the callback function when invoking it.
Returns	void

Notes

Functions are called in the reverse order that they are registered.

See also

[Signaler::DeleteOnIntr\(\)](#)
[Signaler::Intr\(\)](#)

Example

```
#include <unistd.h>      // for sleep()
#include <stdhdrs.h>
#include <strbuf.h>
#include <signaler.h>

class MyClass
{
public:
    void      Set( StrPtr *d ) { data = *d; }
    const StrPtr *Get()          { return &data; }
    void      Identify()        { printf( "I'm %s\n", data.Text() ); }

private:
    StrBuf     data;
};

static void InterruptHandler( void *p )
{
    MyClass     *m = ( MyClass * )p;
    m->Identify();
}

int main( int argc, char **argv )
{
    for ( int i = 1; i <= 5; i++ )
    {
        StrBuf data;

        data.Set( "Object" );
        data << i;

        MyClass *p = new MyClass;
        p->Set( &data );

        signaler.OnIntr( InterruptHandler, ( void * )p );
    }

    printf( "Hit ^C to fire the interrupt handler\n" );
    for ( ; ; )
        sleep( 60 );

    exit( 0 );
}
```

Signaler::Signaler() (constructor)

Constructs a new `Signaler` object.

Virtual?	No
Class	Signaler
Arguments	N/A
Returns	N/A

Notes

There is rarely a need for API users to construct `Signaler` objects themselves. Use the global `Signaler` variable `signaler` instead.

See also

[Signaler::OnIntr\(\)](#)
[Signaler::DeleteOnIntr\(\)](#)

StrBuf methods

StrBuf::Alloc(int)

Allocate an additional specified number of bytes to a StrBuf. The string pointed to by the StrBuf's **buffer** is logically extended.

Virtual?	No	
Class	StrBuf	
Arguments	int len	number of bytes to be allocated
Returns	char *	pointer to the first additional byte allocated

Notes

The length of the StrBuf is incremented by the **len** argument.

If the memory for the StrBuf's **buffer** is not large enough, enough new memory is allocated to contiguously contain the extended string. If new memory is allocated, the old memory is freed. (All StrBuf member functions with the potential to increase the length of a StrBuf manage memory this way.)

A call to [Alloc\(\)](#) might change the string pointed to by the StrBuf's **buffer**; do not rely on pointer arithmetic to determine the new pointer, because the call to [Alloc\(\)](#) might have moved the buffer location.

Example

```
#include <iostream>
#include <iomanip>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    char *p;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Alloc( 70 ) returns ";
    cout << "\"" << sb.Text() << "\n";
    cout << "(int)sb.Text() prior to sb.Alloc( 70 ) returns 0x" << hex;
    cout << setw( 8 ) << setfill( '0' ) << (int)sb.Text() << dec << "\n";
    cout << "sb.Length() prior to sb.Alloc( 70 ) returns ";
    cout << sb.Length() << "\n\n";

    p = sb.Alloc( 70 ); // allocate in StrBuf

    cout << "sb.Text() after sb.Alloc( 70 ) returns (first three bytes) ";
    cout << "\"" << setw( 3 ) << sb.Text() << "\n";
    cout << "(int)sb.Text() after sb.Alloc( 70 ) returns 0x" << hex;
    cout << setw( 8 ) << setfill( '0' ) << (int)sb.Text() << dec << "\n";
    cout << "(int)sb.Alloc( 70 ) returned 0x" << hex;
    cout << setw( 8 ) << setfill( '0' ) << (int)p << dec << "\n";
    cout << "sb.Length() after sb.Alloc( 70 ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Alloc( 70 ) returns "xyz"
(int)sb.Text() prior to sb.Alloc( 70 ) returns 0x0804a9a0
sb.Length() prior to sb.Alloc( 70 ) returns 3

sb.Text() after sb.Alloc( 70 ) returns (first three bytes) "xyz"
(int)sb.Text() after sb.Alloc( 70 ) returns 0x0804a9b0
(int)sb.Alloc( 70 ) returned 0x0804a9b3
sb.Length() after sb.Alloc( 70 ) returns 73
```

StrBuf::Append(const char *)

Append a null-terminated string to a StrBuf. The string is logically appended to the string pointed to by the StrBuf's buffer.

Virtual?	No
Class	StrBuf
Arguments	<code>const char *buf</code> pointer to the first byte of the null-terminated string
Returns	<code>void</code>

Notes

The StrBuf's `length` is incremented by the number of bytes prior to the first null byte in the string.

If the memory for the StrBuf's `buffer` is not large enough, new memory to contiguously contain the results of appending the null-terminated string is allocated. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

Example

```
int main( int argc, char **argv )
{
    char chars[] = "zy";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Append( chars ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb.Append( chars ) returns ";
    cout << sb.Length() << "\n\n";

    sb.Append( chars ); // append char * to StrBuf

    cout << "sb.Text() after sb.Append( chars ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb.Append( chars ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Append( chars ) returns "xyz"
sb.Length() prior to sb.Append( chars ) returns 3

sb.Text() after sb.Append( chars ) returns "xyzzy"
sb.Length() after sb.Append( chars ) returns 5
```

StrBuf::Append(const char *, int)

Append a string of a specified length to a **StrBuf**. The string is logically appended to the string pointed to by the **StrBuf**'s **buffer**.

Virtual?	No	
Class	StrBuf	
Arguments	const char *buf	pointer to the first byte of the string
	int len	length of the string
Returns	void	

Notes

Exactly **len** bytes are appended to the **StrBuf** from the string. The **length** of the **StrBuf** is incremented by the **len** argument.

If the memory for the **StrBuf**'s **buffer** is not large enough, new memory to contiguously contain the results of appending the string of specified length is allocated. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "zyx";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Append( chars, 2 ) returns ";
    cout << "\" " << sb.Text() << "\n";
    cout << "sb.Length() prior to sb.Append( chars, 2 ) returns ";
    cout << sb.Length() << "\n\n";

    sb.Append( chars, 2 ); // append len bytes of char * to StrBuf

    cout << "sb.Text() after sb.Append( chars, 2 ) returns ";
    cout << "\" " << sb.Text() << "\n";
    cout << "sb.Length() after sb.Append( chars, 2 ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Append( chars, 2 ) returns "xyz"  
sb.Length() prior to sb.Append( chars, 2 ) returns 3
```

```
sb.Text() after sb.Append( chars, 2 ) returns "xyzzy"  
sb.Length() after sb.Append( chars, 2 ) returns 5
```

StrBuf::Append(const StrPtr *)

Append a **StrPtr** to a **StrBuf**. The argument is passed as a pointer to the **StrPtr**. The string pointed to by the **StrPtr**'s **buffer** is logically appended to the string pointed to by the **StrBuf**'s **buffer**. Arguments are commonly addresses of instances of classes derived from the **StrPtr** class, such as **StrRef** and **StrBuf**.

Virtual?	No
Class	StrBuf
Arguments	const StrPtr *s pointer to the StrPtr instance
Returns	void

Notes

Initialize the **StrBuf** and the **StrPtr** before calling [Append\(\)](#).

Exactly the number of bytes specified by the **length** of the **StrPtr** are appended to the **StrBuf** from the **StrPtr**. The **length** of the **StrBuf** is incremented by the **length** of the **StrPtr**.

If the memory for the **StrBuf**'s **buffer** is not large enough, new memory to contiguously contain the results of appending the **StrPtr** is allocated. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the **StrPtr**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "zy" );
    StrPtr *sp = &sr;
    StrBuf sba;
    StrBuf sbb;

    sba.Set( "xyz" );
    sbb.Set( "xyz" );

    cout << "sba.Text() after sba.Set( \"xyz\" ) returns ";
    cout << "\"" << sba.Text() << "\n";
    cout << "sba.Length() after sba.Set( \"xyz\" ) returns ";
    cout << sba.Length() << "\n";
    cout << "sbb.Text() after sbb.Set( \"xyz\" ) returns ";
    cout << "\"" << sbb.Text() << "\n";
    cout << "sbb.Length() after sbb.Set( \"xyz\" ) returns ";
    cout << sbb.Length() << "\n\n";

    sba.Append( sp ); // append StrPtr * to StrBuf

    cout << "sba.Text() after sba.Append( sp ) returns ";
    cout << "\"" << sba.Text() << "\n";
    cout << "sba.Length() after sba.Append( sp ) returns ";
    cout << sba.Length() << "\n\n";

    sbb.Append( &sr ); // append &StrRef to StrBuf

    cout << "sbb.Text() after sbb.Append( &sr ) returns ";
    cout << "\"" << sbb.Text() << "\n";
    cout << "sbb.Length() after sbb.Append( &sr ) returns ";
    cout << sbb.Length() << "\n\n";

    sba.Append( &sbb ); // append &StrBuf to StrBuf

    cout << "sba.Text() after sba.Append( &sbb ) returns ";
    cout << "\"" << sba.Text() << "\n";
    cout << "sba.Length() after sba.Append( &sbb ) returns ";
    cout << sba.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sba.Text() after sba.Set( "xyz" ) returns "xyz"
sba.Length() after sba.Set( "xyz" ) returns 3
sbb.Text() after sbb.Set( "xyz" ) returns "xyz"
sbb.Length() after sbb.Set( "xyz" ) returns 3

sba.Text() after sba.Append( sp ) returns "xyzzy"
sba.Length() after sba.Append( sp ) returns 5
sbb.Text() after sbb.Append( &sr ) returns "xyzzy"
sbb.Length() after sbb.Append( &sr ) returns 5
sba.Text() after sba.Append( &sbb ) returns "xyzzyxyzzy"
sba.Length() after sba.Append( &sbb ) returns 10
```

StrBuf::Clear()

Clear the `length` member of a `StrBuf`.

Virtual?	No
Class	StrBuf
Arguments	None
Returns	<code>void</code>

Notes

Only the `length` member of the `StrBuf` is zeroed.

To set the `buffer` member to a zero-length string, call [Terminate\(\)](#) after calling [Clear\(\)](#).

See also

[StrBuf::Terminate\(\)](#)

Example

```
#include <iostream>

#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "Prior to sb.Clear() and sb.Terminate():\n";
    cout << "    sb.Length() returns " << sb.Length() << "\n";
    cout << "    sb.Text() returns \" " << sb.Text() << "\"\n\n";

    sb.Clear(); // zero out the length

    cout << "After sb.Clear() but prior to sb.Terminate():\n";
    cout << "    sb.Length() returns " << sb.Length() << "\n";
    cout << "    sb.Text() returns \" " << sb.Text() << "\"\n\n";

    sb.Terminate();

    cout << "After sb.Clear() and sb.Terminate():\n";
    cout << "    sb.Length() returns " << sb.Length() << "\n";
    cout << "    sb.Text() returns \" " << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
Prior to sb.Clear() and sb.Terminate():
    sb.Length() returns 3
    sb.Text() returns "xyz"

After sb.Clear() but prior to sb.Terminate():
    sb.Length() returns 0
    sb.Text() returns "xyz"

After sb.Clear() and sb.Terminate():
    sb.Length() returns 0
    sb.Text() returns ""
```

StrBuf::StrBuf() (Constructor)

Construct a StrBuf.

Virtual?	No
Class	StrBuf
Arguments	None
Returns	N/A

Notes

The StrBuf constructor initializes the StrBuf to contain a zero-length null buffer.

Example

```
int main( int argc, char **argv )
{
    StrBuf sb; // constructor called

    cout << "sb.Text() returns \"\" << sb.Text() << "\n";
    cout << "sb.Length() returns " << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() returns ""
sb.Length() returns 0
```

StrBuf::StrBuf(const StrBuf &) (Copy Constructor)

Construct a copy of a **StrBuf**.

Virtual?	No	
Class	StrBuf	
Arguments	<code>const StrBuf &s</code>	(implied) reference of the StrBuf from which copying occurs
Returns	N/A	

Notes

The **StrBuf** copy constructor creates a copy of a **StrBuf**. The **StrBuf** from which copying occurs must be initialized before calling the copy constructor.

The **StrBuf** copy constructor initializes the new **StrBuf** to contain a zero-length null buffer, and sets the contents of the new **StrBuf** using the contents of the original **StrBuf**. Any memory allocated for the **buffer** of the copy is separate from the memory for the **buffer** of the original **StrBuf**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

void called( StrBuf csb )
{
    csb << "zy";

    cout << "called() csb.Text() returns \""
        << csb.Text() << "\"\n";
}

int main( int argc, char **argv )
{
    StrBuf sb;
    sb.Set( "xyz" );
    called( sb ); // copy constructor called
    cout << "main() sb.Text() returns \""
        << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
called() csb.Text() returns "xyzzy"
main() sb.Text() returns "xyz"
```

StrBuf::~StrBuf() (Destructor)

Destroy a StrBuf.

Virtual?	No
Class	StrBuf
Arguments	None
Returns	N/A

Notes

The StrBuf destructor destroys a StrBuf.

If the **buffer** points to allocated memory other than **nullStrBuf**, the allocated memory is freed.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf *psb;
    psb = new StrBuf;
    psb->Set( "xyz" );
    cout << "psb->Text() returns \"" << psb->Text() << "\"\n";
    delete psb; // destructor called and allocated memory freed
}
```

Executing the preceding code produces the following output:

```
psb->Text() returns "xyz"
```

StrBuf::Extend(char)

Extend a **StrBuf** by one byte. The string pointed to by the **StrBuf**'s **buffer** is logically extended.

Virtual?	No
Class	StrBuf
Arguments	char c the byte copied to the extended string
Returns	void

Notes

One byte is copied to the extended **StrBuf**. The **length** of the **StrBuf** is incremented by one.

[Extend\(\)](#) does not null-terminate the extended string pointed to by the **StrBuf**'s **buffer**. To ensure that the extended string is null-terminated, call [Terminate\(\)](#) after calling [Extend\(\)](#).

If the memory for the **StrBuf**'s **buffer** is not large enough, enough new memory is allocated to contiguously contain the extended string. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the byte.

See also

[StrBuf::Terminate\(\)](#)

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xy" );

    cout << "sb.Text() prior to sb.Extend( 'z' ) returns ";
    cout << "\" " << sb.Text() << "\n";
    cout << "sb.Length() prior to sb.Extend( 'z' ) returns ";
    cout << sb.Length() << "\n\n";

    sb.Extend( 'z' ); // extend StrBuf from char
    sb.Terminate();

    cout << "sb.Text() after sb.Extend( 'z' ) returns ";
    cout << "\" " << sb.Text() << "\n";
    cout << "sb.Length() after sb.Extend( 'z' ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Extend( 'z' ) returns "xy"
sb.Length() prior to sb.Extend( 'z' ) returns 2

sb.Text() after sb.Extend( 'z' ) returns "xyz"
sb.Length() after sb.Extend( 'z' ) returns 3
```

StrBuf::Extend(const char *, int)

Extend a **StrBuf** by a string of a specified length. The string pointed to by the **StrBuf**'s **buffer** is logically extended.

Virtual?	No	
Class	StrBuf	
Arguments	const char *buf	pointer to the first byte of the string
	int len	length of the string
Returns	void	

Notes

Exactly **len** bytes are copied from the string to the extended **StrBuf**. The **length** of the **StrBuf** is incremented by **len** bytes.

[Extend\(\)](#) does not null-terminate the extended string pointed to by the **StrBuf**'s **buffer**. To ensure that the extended string is null-terminated, call [Terminate\(\)](#) after calling [Extend\(\)](#).

If the memory for the **StrBuf**'s **buffer** is not large enough, enough new memory is allocated to contiguously contain the extended string. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

See also

[StrBuf::Terminate\(\)](#)

Example

```
int main( int argc, char **argv )
{
    char chars[] = "zyx";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb.Extend( chars, 2 ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb.Extend( chars, 2 ) returns ";
    cout << sb.Length() << "\n\n";

    sb.Extend( chars, 2 ); // extend StrBuf from len bytes of char *
    sb.Terminate();

    cout << "sb.Text() after sb.Extend( chars, 2 ) returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb.Extend( chars, 2 ) returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb.Extend( chars, 2 ) returns "xyz"
sb.Length() prior to sb.Extend( chars, 2 ) returns 3
sb.Text() after sb.Extend( chars, 2 ) returns "xyzzy"
sb.Length() after sb.Extend( chars, 2 ) returns 5
```

StrBuf::operator=(const char *)

Assign a **StrBuf** from a null-terminated string.

Virtual?	No
Class	StrBuf
Arguments	const char *buf (implied) pointer to the first byte of the null-terminated string
Returns	void

Notes

Initialize the **StrBuf** before the assignment.

The **length** is set to the number of bytes prior to the first null byte in the string.

Any memory allocated for the **StrBuf**'s **buffer** is separate from the memory for the string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyz";
    StrBuf sb;

    sb = chars; // assign StrBuf from char *

    cout << "chars[] = \"" << chars << "\n";
    cout << "sb.Text() returns \"" << sb.Text() << "\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyz"
sb.Text() returns "xyz"
```

StrBuf::operator=(const StrBuf &)

Assign a **StrBuf** from another **StrBuf**.

Virtual?	No
Class	StrBuf
Arguments	const StrBuf &buf (implied) reference of the StrBuf from which assignment occurs
Returns	void

Notes

Initialize both **StrBufs** before the assignment.

Any memory allocated for the assigned **StrBuf's buffer** is separate from the memory for the **StrBuf's buffer** from which assignment occurs.

Do not assign a **StrBuf** to itself.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sba;
    StrBuf sbb;

    sba.Set( "xyz" );

    sbb = sba; // assign StrBuf to StrBuf

    cout << "sba.Text() returns \" " << sba.Text() << "\"\n";
    cout << "sbb.Text() returns \" " << sbb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sba.Text() returns "xyz"
sbb.Text() returns "xyz"
```

StrBuf::operator=(const StrPtr &)

Assign a **StrBuf** from a **StrPtr**.

Virtual?	No
Class	StrBuf
Arguments	const StrPtr &s (implied) reference of the StrPtr instance
Returns	void

Notes

Initialize the **StrBuf** and the **StrPtr** before assignment.

Any memory allocated for the **StrBuf**'s **buffer** is separate from the memory for the **StrPtr**'s **buffer**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "xyz" );
    StrPtr *sp = &sr;
    StrBuf sb;

    sb = *sp; // assign StrBuf from StrPtr

    cout << "sp->Text() returns \" " << sp->Text() << "\"\n";
    cout << "sb.Text() returns \" " << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sp->Text() returns "xyz"
sb.Text() returns "xyz"
```

StrBuf::operator=(const StrRef &)

Assign a **StrBuf** from a **StrRef**.

Virtual?	No
Class	StrBuf
Arguments	const StrRef &s (implied) reference of the StrRef instance
Returns	void

Notes

Initialize the **StrBuf** and **StrRef** before assignment.

Any memory allocated for the **StrBuf**'s **buffer** is separate from that of the **StrRef**'s **buffer**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "xyz" );
    StrBuf sb;

    sb = sr; // assign StrBuf from StrRef

    cout << "sr.Text() returns \" " << sr.Text() << "\"\n";
    cout << "sb.Text() returns \" " << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sr.Text() returns "xyz"
sb.Text() returns "xyz"
```

StrBuf::operator << (const char *)

Append a null-terminated string to a StrBuf. The string is logically appended to the string pointed to by the StrBuf's buffer.

Virtual?	No	
Class	StrBuf	
Arguments	<code>const char *s</code>	(implied) pointer to the first byte of the null-terminated string
Returns	<code>StrBuf &</code>	reference of the StrBuf

Notes

The StrBuf's `length` is incremented by the number of bytes prior to the first null byte in the string.

If the memory for the StrBuf's `buffer` is not large enough, new contiguous memory is allocated to contain the results of appending the null-terminated string. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "zy";
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb << chars returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb << chars returns ";
    cout << sb.Length() << "\n\n";

    sb << chars; // append char * to StrBuf

    cout << "sb.Text() after sb << chars returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb << chars returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb << chars returns "xyz"  
sb.Length() prior to sb << chars returns 3
```

```
sb.Text() after sb << chars returns "xyzzy"  
sb.Length() after sb << chars returns 5
```

StrBuf::operator << (int)

Append a formatted integer to a **StrBuf**. The formatted integer is logically appended to the string pointed to by the **StrBuf**'s **buffer**.

Virtual?	No
Class	StrBuf
Arguments	int v (implied) integer
Returns	StrBuf & reference of the StrBuf

Notes

The integer is formatted with the logical equivalent of `sprintf(buf, "%d", v)`.

The **length** is incremented by the number of bytes of the formatted integer.

If the memory for the **StrBuf**'s **buffer** is not large enough, new contiguous memory is allocated to contain the results of appending the formatted integer. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the formatted integer.

Example

```
#include <iostream>
#include <stddhtrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    int i;

    sb.Set( "xyz" );
    i = 73;

    cout << "sb.Text() prior to sb << i returns ";
    cout << "\" " << sb.Text() << "\n";
    cout << "sb.Length() prior to sb << i returns ";
    cout << sb.Length() << "\n\n";

    sb << i; // append (formatted) int to StrBuf

    cout << "sb.Text() after sb << i returns ";
    cout << "\" " << sb.Text() << "\n";
    cout << "sb.Length() after sb << i returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb << i returns "xyz"  
sb.Length() prior to sb << i returns 3  
  
sb.Text() after sb << i returns "xyz73"  
sb.Length() after sb << i returns 5
```

StrBuf::operator << (const StrPtr *)

Append a **StrPtr** to a **StrBuf**. The string pointed to by the **StrPtr**'s **buffer** is logically appended to the string pointed to by the **StrBuf**'s **buffer**.

Virtual?	No
Class	StrBuf
Arguments	const StrPtr *s (implied) pointer to the StrPtr instance
Returns	StrBuf & reference of the StrBuf

Notes

Exactly the number of bytes specified by the **StrPtr**'s **length** are appended to the **StrBuf**. The **StrBuf**'s **length** is incremented by the **StrPtr**'s **length**.

If the memory for the **StrBuf**'s **buffer** is not large enough, new contiguous memory is allocated to contain the results of appending the **StrPtr**. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the **StrPtr**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "zy" );
    StrPtr *sp = &sr;
    StrBuf sb;

    sb.Set( "xyz" );

    cout << "sb.Text() prior to sb << sp returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() prior to sb << sp returns ";
    cout << sb.Length() << "\n\n";

    sb << sp; // append StrPtr * to StrBuf

    cout << "sb.Text() after sb << sp returns ";
    cout << "\"" << sb.Text() << "\"\n";
    cout << "sb.Length() after sb << sp returns ";
    cout << sb.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sb.Text() prior to sb << sp returns "xyz"  
sb.Length() prior to sb << sp returns 3
```

```
sb.Text() after sb << sp returns "xyzzy"  
sb.Length() after sb << sp returns 5
```

StrBuf::operator << (const StrPtr &)

Append a **StrPtr** to a **StrBuf**. The argument is passed as a reference of the **StrPtr**. The string pointed to by the **StrPtr**'s **buffer** is logically appended to the string pointed to by the **StrBuf**'s **buffer**.

Virtual?	No	
Class	StrBuf	
Arguments	const StrPtr &s	(implied) reference of the StrPtr instance
Returns	StrBuf &	reference of the StrBuf

Notes

Arguments are typically instances of classes derived from the **StrPtr** class, such as **StrRef** and **StrBuf**.

Exactly the number of bytes specified by the **length** of the **StrPtr** are appended to the **StrBuf** from the **StrPtr**. The **length** of the **StrBuf** is incremented by the **length** of the **StrPtr**.

If the memory for the **StrBuf**'s **buffer** is not large enough, new contiguous memory is allocated to contain the results of appending the **StrPtr**. If new memory is allocated, the old memory is freed. Any memory allocated is separate from the memory for the **StrPtr**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "zy" );
    StrPtr *sp = &sr;
    StrBuf sba;
    StrBuf sbb;

    sba.Set( "xyzzy" );
    sbb.Set( "xyz" );

    cout << "sba.Text() after sba.Set( \"xyzzy\" ) returns ";
    cout << "\"";
    cout << sba.Text() << "\n";
    cout << "sba.Length() after sba.Set( \"xyzzy\" ) returns ";
    cout << sba.Length() << "\n";
    cout << "sbb.Text() after sbb.Set( \"xyz\" ) returns ";
    cout << "\"";
    cout << sbb.Text() << "\n";
    cout << "sbb.Length() after sbb.Set( \"xyz\" ) returns ";
    cout << sbb.Length() << "\n";

    sbb << sr; // append StrRef to StrBuf

    cout << "sbb.Text() after sbb << sr returns ";
    cout << "\"";
    cout << sbb.Text() << "\n";
    cout << "sbb.Length() after sbb << sr returns ";
    cout << sbb.Length() << "\n";

    sba << sbb; // append StrBuf to StrBuf

    cout << "sba.Text() after sba << sbb returns ";
    cout << "\"";
    cout << sba.Text() << "\n";
    cout << "sba.Length() after sba << sbb returns ";
    cout << sba.Length() << "\n";
}
```

Executing the preceding code produces the following output:

```
sba.Text() after sba.Set( "xyzzy" ) returns "xyzzy"
sba.Length() after sba.Set( "xyzzy" ) returns 5
sbb.Text() after sbb.Set( "xyz" ) returns "xyz"
sbb.Length() after sbb.Set( "xyz" ) returns 3
sbb.Text() after sbb << sr returns "xyzzy"
sbb.Length() after sbb << sr returns 5
sba.Text() after sba << sbb returns "xyzzyxyzzy"
sba.Length() after sba << sbb returns 10
```

StrBuf::Set(const char *)

Set a **StrBuf** from a null-terminated string.

Virtual?	No
Class	StrBuf
Arguments	<code>const char *buf</code> pointer to the first byte of the null-terminated string
Returns	<code>void</code>

Notes

Initialize the **StrBuf** before calling [Set\(\)](#).

The **length** of the **StrBuf** is set to the number of bytes prior to the first null byte in the string.

Any memory allocated for the **StrBuf**'s **buffer** is separate from the memory for the string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "string";
    StrBuf sb;

    sb.Set( chars ); // set StrBuf from char *

    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sb.Text() returns \"" << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "string"
sb.Text() returns "string"
```

StrBuf::Set(const char *, int)

Set a **StrBuf** from a string of a specified length.

Virtual?	No	
Class	StrBuf	
Arguments	const char *buf pointer to the first byte of the string int len length of the string	
Returns	void	

Notes

Initialize the **StrBuf** before calling [Set\(\)](#).

Exactly **len** bytes are copied from the string to the **StrBuf**. The **length** of the **StrBuf** is set to the **len** argument.

Any memory allocated for the **StrBuf's buffer** is separate from the memory for the string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzzy";
    StrBuf sb;

    sb.Set( chars, 3 ); // set StrBuf from len bytes of char *
    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sb.Text() returns \"\" << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzzy"
sb.Text() returns "xyz"
```

StrBuf::Set(const StrPtr *)

Set a **StrBuf** from a pointer to a **StrPtr**.

Virtual?	No
Class	StrBuf
Arguments	<code>const StrPtr *s</code> pointer to the StrPtr instance
Returns	<code>void</code>

Notes

Initialize the **StrBuf** and the **StrPtr** before calling [Set\(\)](#).

Any memory allocated for the **StrBuf**'s **buffer** is separate from the memory for the **StrPtr**'s **buffer**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr( "xyz" );
    StrPtr *sp = &sr;
    StrBuf sb;

    sb.Set( sp ); // set StrBuf from StrPtr *

    cout << "sp->Text() returns \" " << sp->Text() << "\"\n";
    cout << "sb.Text() returns \" " << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sp->Text() returns "xyz"
sb.Text() returns "xyz"
```

StrBuf::Set(const StrPtr &)

Set a **StrBuf** from a reference of a **StrPtr**. Arguments are commonly instances of classes derived from the **StrPtr** class, such as **StrRef** and **StrBuf**.

Virtual?	No
Class	StrBuf
Arguments	const StrPtr &s reference of the StrPtr instance
Returns	void

Notes

Initialize the **StrBuf** and the **StrPtr** before calling [Set\(\)](#).

Any memory allocated for the **StrBuf**'s **buffer** is separate from the memory for the **StrPtr**'s **buffer**.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr;
    StrBuf sbs;
    StrBuf sbt;

    sr.Set( "xyz" );
    sbt.Set( sr ); // set StrBuf from StrRef

    cout << "sr.Text() returns \" " << sr.Text() << "\n";
    cout << "sbt.Text() returns \" " << sbt.Text() << "\n\n";

    sbs.Set( "abc" );
    sbt.Set( sbs ); // set StrBuf from StrBuf

    cout << "sbs.Text() returns \" " << sbs.Text() << "\n";
    cout << "sbt.Text() returns \" " << sbt.Text() << "\n";
}
```

Executing the preceding code produces the following output:

```
sr.Text() returns "xyz"  
sbt.Text() returns "xyz"  
  
sbs.Text() returns "abc"  
sbt.Text() returns "abc"
```

StrBuf::StringInit()

Initialize a **StrBuf**.

Virtual?	No
Class	StrBuf
Arguments	None
Returns	void

Notes

[StringInit\(\)](#) initializes the **StrBuf** to contain a zero-length null buffer.

Normally when a **StrBuf** is created, it is initialized using the **StrBuf** constructor. However, there may be specialized cases where memory has already been allocated for a **StrBuf** instance, but the memory was not allocated through the normal mechanisms that would result in the **StrBuf** constructor initializing the instance. For these specialized cases, [StringInit\(\)](#) is appropriate for initializing a **StrBuf** instance.

After a **StrBuf** has been used, calling [StringInit\(\)](#) for the instance can result in a memory leak. Specifically, once the **buffer** member has been pointed to memory other than **nullStrBuf**, calling [StringInit\(\)](#) for the instance will abandon the memory.

In most cases, it is preferable to use an alternative such as one of the following:

```
sb1 = StrRef::Null();  
  
sb2.Clear();  
sb2.Terminate();  
  
sb3.Set( "" );  
  
sb4 = "";
```

See also

[StrBuf::Clear\(\)](#)
[StrBuf::Set\(\)](#)
[StrBuf::Terminate\(\)](#)
[StrBuf::operator =\(char * \)](#)
[StrRef::Null\(\)](#)

Example

```

#include <iostream>
#include <errno.h>

#include <stdhdrs.h>
#include <strbuf.h>

#define NSTRBUFS      5
#define CHUNKSIZE    1024
#define STRBUFSIZE   sizeof( StrBuf )

int main( int argc, char **argv )
{
    char chunk[ CHUNKSIZE ];
    int chunkFree = CHUNKSIZE;
    char *pchunkStart = &chunk[ 0 ];
    char *pchunk;

    int iStrBuf;

    // Initialize the StrBufs in the chunk.

    for ( iStrBuf = 0, pchunk = pchunkStart;
          iStrBuf < NSTRBUFS;
          iStrBuf++, pchunk += STRBUFSIZE )
    {
        // Ensure that there's enough free left in the chunk for a StrBuf.
        if ( (chunkFree -= STRBUFSIZE) < 0 )
        {
            cout << "Not enough free left in the chunk!\n";
            return ENOMEM;
        }

        // Initialize and set the value of the StrBuf.

        ((StrBuf *)pchunk)->StringInit();
        *(StrBuf *)pchunk << iStrBuf + 73;
    }

    // Print the StrBufs. Do this in a separate loop so as to provide
    // some evidence that the above loop didn't corrupt adjacent StrBufs.
    for ( iStrBuf = 0, pchunk = pchunkStart;
          iStrBuf < NSTRBUFS;
          iStrBuf++, pchunk += STRBUFSIZE )
    {
        cout << "StrBuf " << iStrBuf + 1 << " contains \"";
        cout << ((StrBuf *)pchunk)->Text() << "\"\n";
    }
}

```

Executing the preceding code produces the following output:

```
StrBuf 1 contains "73"
StrBuf 2 contains "74"
StrBuf 3 contains "75"
StrBuf 4 contains "76"
StrBuf 5 contains "77"
```

StrBuf::Terminate()

Null-terminate the string pointed to by the **buffer** member of a **StrBuf**. The null byte is placed in the buffer at the location indicated by the **length** member.

Virtual?	No
Class	StrBuf
Arguments	None
Returns	void

Notes

Initialize the **StrBuf** before calling [Terminate\(\)](#).

The **length** member of the **StrBuf** is effectively unchanged by [Terminate\(\)](#).

Example

[Terminate\(\)](#) is defined in **strbuf.h** as follows:

```
void Terminate()
{
    Extend( 0 ); --length;
}
```

[Terminate\(\)](#) null-terminates the string by calling **Extend(0)**, which also increments the **length** member; the **length** is then decremented within [Terminate\(\)](#), leaving it unchanged.

See also

[StrBuf::StringInit\(\)](#)

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xyzzy" );

    cout << "Prior to sb.SetLength( 3 ) and sb.Terminate():\n";
    cout << "    sb.Length() returns " << sb.Length() << "\n";
    cout << "    sb.Text() returns \" " << sb.Text() << "\"\n\n";

    sb.SetLength( 3 );

    cout << "After sb.SetLength( 3 ) but prior to sb.Terminate():\n";
    cout << "    sb.Length() returns " << sb.Length() << "\n";
    cout << "    sb.Text() returns \" " << sb.Text() << "\"\n\n";

    sb.Terminate();      // null-terminate the string at length

    cout << "After sb.SetLength( 3 ) and sb.Terminate():\n";
    cout << "    sb.Length() returns " << sb.Length() << "\n";
    cout << "    sb.Text() returns \" " << sb.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
Prior to sb.SetLength( 3 ) and sb.Terminate():
sb.Length() returns 5
sb.Text() returns "xyzzy"

After sb.SetLength( 3 ) but prior to sb.Terminate():
sb.Length() returns 3
sb.Text() returns "xyzzy"

After sb.SetLength( 3 ) and sb.Terminate():
sb.Length() returns 3
sb.Text() returns "xyz"
```

StrDict methods

StrDict::GetVar(const StrPtr &)

Return the value of the specified variable, or `NULL` if not defined.

Virtual?	No
Class	StrDict
Arguments	<code>const StrPtr &var</code> the name of the variable to look up
Returns	<code>StrPtr *</code> the value, or <code>NULL</code> if not defined

Notes

For the most part, all of the following methods are equivalent:

- `StrDict::GetVar(const StrPtr &)`
- `StrDict::GetVar(const char *)`
- `StrDict::GetVar(const char *, Error *)`
- `StrDict::GetVar(const StrPtr &, int)`
- `StrDict::GetVar(const StrPtr &, int, int)`
- `StrDict::GetVar(int, StrPtr &, StrPtr &)`

The `var` argument must specify the name of a variable in the `StrDict` that you're trying to look up. In some instances, variables in a `StrDict` are named according to the convention `F00x` or `F00x,y` - one example is the tagged output of `p4 filelog`. Calling [GetVar\(\)](#) with these numbers as arguments saves you the work of manually constructing the variable name by using `itoa()` and [Append\(\)](#).

The version of [GetVar\(\)](#) that returns an `int` is useful for iterating through a `StrDict`; the `int` argument is an index into the `StrDict`, and the two `StrPtr` arguments are set to contain the variable and value found at that index, if any. This method returns zero if there was no variable at the specified index.

Example

The implementation of [ClientUser::OutputStat\(\)](#) in `clientuser.cc` provides a good source example:

```

void ClientUser::OutputStat( StrDict *varList )
{
    int i;
    StrBuf msg;
    StrRef var, val;

    // Dump out the variables, using the GetVar( x ) interface.
    // Don't display the function, which is only relevant to rpc.
    for ( i = 0; varList->GetVar( i, var, val ); i++ )
    {
        if ( var == "func" ) continue;

        // otherAction and otherOpen go at level 2, as per 99.1 + earlier
        msg.Clear();
        msg << var << " " << val;
        char level = strncmp( var.Text(), "other", 5 ) ? '1' : '2';
        OutputInfo( level, msg.Text() );
    }

    // blank line
    OutputInfo( '0', "" );
}

```

An example of output:

```

% p4 -Ztag filelog file.c
... depotFile //depot/depot/source/file.c
... rev0 3
... change0 1949
... action0 integrate
... type0 text
... time0 1017363022
... user0 testuser
... client0 testuser-luey
... desc0 <enter description here>
... how0,0 ignored
... file0,0 //depot/depot/source/old.c
... srev0,0 #1
... erev0,0 #2
... how0,1 ignored

...

```

StrDict::GetVar(const char *)

Return the value of the specified variable, or **NULL** if not defined.

Virtual?	No	
Class	StrDict	
Arguments	<code>const char *var</code>	the name of the variable to look up
Returns	<code>StrPtr *</code>	the value, or NULL if not defined

Notes

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\(const StrPtr & \)](#)

StrDict::GetVar(const char *, Error *)

Return the value of the specified variable, or `NULL` if not defined.

Virtual?	No	
Class	StrDict	
Arguments	<code>const char *var</code>	the name of the variable to look up
	<code>Error *e</code>	an error message indicating that the required parameter <code>var</code> was not set
Returns	<code>StrPtr *</code>	the value, or <code>NULL</code> if not defined

Notes

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\(const StrPtr & \)](#)

StrDict::GetVar(const StrPtr &, int)

Return the value of the specified variable, or `NULL` if not defined.

Virtual?	No	
Class	StrDict	
Arguments	<code>const StrPtr &var</code>	the name of the variable to look up
	<code>int x</code>	appended to the variable's name
Returns	<code>StrPtr *</code>	the value, or <code>NULL</code> if not defined

Notes

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\(const StrPtr & \)](#)

StrDict::GetVar(const StrPtr &, int, int)

Return the value of the specified variable, or `NULL` if not defined.

Virtual?	No	
Class	StrDict	
Arguments	<code>const StrPtr &var</code>	the name of the variable to look up
	<code>int x</code>	appended to the variable's name
	<code>int y</code>	appended to the variable's name
Returns	<code>StrPtr *</code>	the value, or <code>NULL</code> if not defined

Notes

For the most part, all of the [GetVar\(\)](#) methods are equivalent.

For details, see [StrDict::GetVar\(const StrPtr & \)](#)

StrDict::GetVar(int, StrPtr &, StrPtr &)

Return the value of the specified variable, or `NULL` if not defined.

Virtual?	No	
Class	StrDict	
Arguments	<code>int i</code>	the index of a variable in the <code>StrDict</code>
	<code>StrPtr &var</code>	the name of the variable at that index, if any
	<code>StrPtr &val</code>	the value found at that index, if any
Returns	<code>int</code>	the value, or zero if no variable found

Notes

This method is typically used when iterating through a `StrDict`.

For the most part, all of the [`GetVar\(\)`](#) methods are equivalent.

For details, see [`StrDict::GetVar\(const StrPtr & \)`](#)

StrDict::Load(FILE *)

Unmarshals the StrDict from a file.

Virtual?	No	
Class	StrDict	
Arguments	FILE *i	the file to load from
Returns	int	always equals 1

Notes

[Load\(\)](#) loads a StrDict from a file previously created by [Save\(\)](#).

Example

The following example "loads" a StrDict by reading it from `stdin`.

```
MyStrDict sd;
ClientUser ui;

sd.Load( stdin );
ui.OutputStat( &sd );
```

Given a marshaled StrDict on `stdin`, the code produces the following output:

```
> cat marshaled.strdict

depotFile=/depot/file.c
clientFile=c:\test\depot\file.c
headAction=edit
headType=text
headTime=1020067607
headRev=4
headChange=2042
headModTime 1020067484
func=client-FstatInfo

> a.out < marshaled.strdict

... depotFile //depot/file.c
... clientFile clientFile=c:\test\depot\file.c
... headAction edit
... headType text
... headTime 1020067607
... headRev 4
... headChange 2042
... headModTime 1020067484
```

StrDict::Save(FILE *)

Marshals the StrDict into a text file.

Virtual?	No	
Class	StrDict	
Arguments	FILE *out	the file to save to
Returns	int	always equals 1

Notes

[Save\(\)](#) stores the StrDict in a marshalled form to a text file, which can be recovered by using [Load\(\)](#).

Example

The following example "saves" a StrDict by writing it to `stdout`.

```
void MyClientUser::OutputStat( StrDict *varList )
{
    varList->Save( stdout );
}
```

Executing the preceding code produces the following output:

```
> a.out fstat //depot/file.c

depotFile=//depot/file.c
clientFile=c:\test\depot\file.c
headAction=edit
headType=text
headTime=1020067607
headRev=4
headChange=2042
headModTime=1020067484
func=client-FstatInfo
```

StrDict::SetArgv(int, char *const *)

Set a list of values, such as the arguments to a Perforce command.

Virtual?	No	
Class	StrDict	
Arguments	int argc	the number of variables (arguments)
	char *const *argv	the variables (arguments) themselves
Returns	void	

Notes

[SetArgv\(\)](#) is typically used when setting command arguments in [ClientApi](#).

Example

`p4api.cc` provides an example of using [SetArgv\(\)](#) to set arguments.

```
int main( int argc, char **argv )
{
    ClientUser ui;
    ClientApi client;
    Error e;

    // Any special protocol mods
    // client.SetProtocol( "tag", "" );

    // Connect to server
    client.Init( &e );

    // Run the command "argv[1] argv[2...]"
    client.SetArgv( argc - 2, argv + 2 );
    client.Run( argv[1], &ui );

    // Close connection
    client.Final( &e );

    return 0;
}
```

StrNum methods

StrNum::StrNum(int) (constructor)

Create a **StrNum**, either unset or with a value.

Virtual?	No
Class	StrNum
Arguments	int v the number to store (optional)
Returns	StrNum

Notes

A **StrNum** always stores numbers using base ten.

To create a **StrNum** without a value, call [StrNum\(\)](#) without an argument.

Example

The following example creates a **StrNum** and displays it:

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrNum sn = StrNum( 1666 );
    cout << "sn.Text() returns \"" << sn.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sn.Text() returns "1666"
```

StrNum::Set(int)

Set a StrNum's value.

Virtual?	No
Class	StrNum
Arguments	int v the number to store
Returns	void

Notes

A StrNum always stores numbers using base ten.

Example

```
#include <iostream>
#include <sthdtrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrNum sn;
    sn.Set ( 1666 );
    cout << "sn.Text() returns \"\" << sn.Text() << "\n";
}
```

Executing the preceding code produces the following output:

```
sn.Text() returns "1666"
```

StrOps methods

StrOps::Caps(StrBuf &)

Convert the first character in a string (in place) to uppercase.

Virtual?	No
Class	StrOps
Arguments	StrBuf &o the string to capitalize
Returns	void

Example

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <strops.h>

int main( int argc, char **argv )
{
    StrBuf sb;

    sb.Set( "xyzzy" );
    printf( "Before: %s\n", sb.Text() );

    StrOps::Caps( sb );
    printf( "After: %s\n", sb.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
Before: xyzzy
After: Xyzzy
```

StrOps::Dump(const StrPtr &)

Pretty-print a string to `stdout`

Virtual?	No
Class	StrOps
Arguments	<code>StrPtr &o</code> the string to dump
Returns	<code>void</code>

Notes

Unprintable characters are displayed as hexadecimal ASCII values, surrounded by greater-than/less-than characters.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <strops.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    sb.Set( "\tXyzzy" );

    StrOps::Dump( sb );

    return 0;
}
```

Executing the preceding code produces the following output:

```
<09>Xyzzy
```

StrOps::Expand(StrBuf &, StrPtr &, StrDict &)

Expand "%var%" strings into corresponding "val" strings from a **StrDict**.

Virtual?	No	
Class	StrOps	
Arguments	StrBuf &o	the output string
	StrPtr &s	the input string
	StrDict &d	the var/value pairs to look up
Returns	void	

Notes

This function provides a way to quickly expand variables from a **StrDict** into a **StrBuf**.

Example

This small program demonstrates the [Expand\(\)](#) method in an [OutputStat\(\)](#) implementation:

```
void MyClientUser::OutputStat( StrDict *varList )
{
    StrBuf s = StrBuf();
    s.Set( "File: %depotFile% Rev: %rev%" );
    StrBuf o = StrBuf();
    StrOps::Expand( o, s, *varList );
    StrOps::Dump( o );
}

int main( int argc, char **argv )
{
    ClientApi client;
    MyClientUser ui;
    Error e;

    client.SetProtocol( "tag", "" );
    client.Init( &e );
    client.SetArgv( 1, ++argv );
    client.Run( "files", &ui );
    return client.Final( &e );
}
```

Executing the preceding code produces the following output:

```
% a.out *
File: //depot/src/file1.c Rev: 4
File: //depot/src/file2.c Rev: 2
```

StrOps::Expand2(StrBuf &, StrPtr &, StrDict &)

Expand "[%var%|alt]" strings into corresponding "val" strings from a **StrDict**, or "alt" if "var" is undefined.

Virtual?	No	
Class	StrOps	
Arguments	StrBuf &o	the output string
	StrPtr &s	the input string
	StrDict &d	the var/value pairs to look up
Returns	void	

Notes

Like [Expand\(\)](#), this function provides a way to quickly expand variables from a **StrDict** into a **StrBuf**, with the additional feature of providing alternate text if the value is not defined.

The exact syntax of the expression to be expanded is:

```
[ text1 %var% text2 | alt ]
```

If variable "var" has value "val" in the **StrDict** *d*, the expression expands to:

text1 val text2

otherwise, it expands to:

alt

See the example for details.

Example

This small program demonstrates the [Expand2\(\)](#) method in an [OutputStat\(\)](#) implementation:

```
void MyClientUser::OutputStat( StrDict *varList )
{
    StrBuf s = StrBuf();
    s.Set( "stat: [File: %depotFile%|No file]!" );

    StrBuf o = StrBuf();
    StrOps::Expand2( o, s, *varList );

    StrOps::Dump( o );
}

int main( int argc, char **argv )
{
    ClientApi client;
    MyClientUser ui;
    Error e;

    client.SetProtocol( "tag", "" );
    client.Init( &e );

    client.SetArgv( argc - 2, argv + 2 );
    client.Run( argv[1], &ui );

    return client.Final( &e );
}
```

Executing the preceding code produces the following output:

```
% a.out files *
stat: File: //depot/src/file1.c!
stat: File: //depot/src/file2.c!

% a.out labels
stat: No file!
```

StrOps::Indent(StrBuf &, const StrPtr &)

Make a copy of a string, with each line indented.

Virtual?	No	
Class	StrOps	
Arguments	StrBuf &o	the output string
	StrPtr &s	the input string
Returns	void	

Notes

This function reads the input string **s** and copies it to the output string **o**, with each line indented with a single tab.

Example

```
StrBuf s = StrBuf();
s.Set( "abc\ndef\nghi\n" );

StrBuf o = StrBuf();
StrOps::Indent( o, s );

printf( "Before:\n%s", s.Text() );
printf( "After:\n%s", o.Text() );
```

Executing the preceding code produces the following output:

```
Before:
abc
def
ghi
After:
    abc
    def
    ghi
```

StrOps::Lines(StrBuf &, char *[], int)

Break a string apart at line breaks.

Virtual?	No	
Class	StrOps	
Arguments	StrBuf &o	the input string
	char *vec[]	the output array
	int maxVec	the maximum number of lines to handle
Returns	int	the actual number of lines handled

Notes

This function handles all types of line breaks: "\r", "\n", and "\r\n".

Example

```
StrBuf o = StrBuf();
o.Set( "abc\ndef\nghi\n" );

printf( "Input StrBuf:\n%s\n", o.Text() );

char *vec[4];
int l = StrOps::Lines( o, vec, 4 );

for ( ; l ; l-- )
{
    printf( "Line %d: %s\n", l, vec[l-1] );
}
```

Executing the preceding code produces the following output:

```
Input StrBuf:
abc
def
ghi

Line 3: abc
Line 2: def
Line 1: ghi
```

StrOps::Lower(StrBuf &)

Convert each character in a string (in place) to lowercase

Virtual?	No	
Class	StrOps	
Arguments	<code>StrBuf &o</code>	the string to convert to lowercase
Returns	<code>void</code>	

Notes

This function modifies an original string in place by converting all uppercase characters to lowercase.

Example

```
StrBuf o = StrBuf();
o.Set( "xYzZy" );

printf( "Before: %s\n", o );
StrOps::Lower( o );
printf( "After:  %s\n", o );

return 0;
```

Executing the preceding code produces the following output:

```
% a.out
Before: xYzZy
After: xyzzy
```

StrOps::OtoX(const unsigned char *, int, StrBuf &)

Convert an octet stream into hex.

Virtual?	No	
Class	StrOps	
Arguments	<code>char *octet</code>	the input stream
	<code>int len</code>	length of the input in bytes
	<code>StrBuf &x</code>	the output string
Returns	<code>void</code>	

Notes

This function converts the input stream into a string of hexadecimal numbers, with each byte from the input being represented as exactly two hex digits.

Example

```
const unsigned char stream[3] = { 'f', 'o', 'o' };
StrBuf hex;
StrOps::OtoX( stream, 3, hex );
StrOps::Dump( hex );
return 0;
```

Executing the preceding code produces the following output:

```
% a.out
666F6F
```

StrOps::Replace(StrBuf &, const StrPtr &, const StrPtr &, const StrPtr &)

Replace substrings in a **StrPtr** and store the result to a **StrBuf**.

Virtual?	No	
Class	StrOps	
Arguments	StrBuf &o	the output string
	StrPtr &i	the input string
	StrBuf &s	the substring to match
	StrPtr &r	the substring to replace s
Returns	void	

Notes

This function reads the input string **i** and copies it to the output string **o**, after replacing each occurrence of the string **s** with string **r**.

Example

```
StrBuf i = StrBuf();
i.Set( "PerForce is PerForce, of course, of course!" );

StrBuf wrong, right;
wrong.Set( "PerForce" );
right.Set( "Perforce" );

StrBuf o = StrBuf();

StrOps::Replace( o, i, wrong, right );

StrOps::Dump( o );
```

Executing the preceding code produces the following output:

```
% a.out
Perforce is Perforce, of course, of course!
```

StrOps::Sub(StrPtr &, char, char)

Substitute instances of one character for another.

Virtual?	No						
Class	StrOps						
Arguments	<table> <tr> <td>StrPtr &string</td><td>the string on which to operate</td></tr> <tr> <td>target</td><td>the target character</td></tr> <tr> <td>replace</td><td>the character with which to replace target</td></tr> </table>	StrPtr &string	the string on which to operate	target	the target character	replace	the character with which to replace target
StrPtr &string	the string on which to operate						
target	the target character						
replace	the character with which to replace target						
Returns	void						

Notes

This function substitutes the **replace** character for every instance of the **target** character in the input **string**. The substitution is performed in place.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>
#include <strops.h>

int main( int argc, char **argv )
{
    StrBuf sb;
    sb.Set( "\tPassword" );

    StrOps::Sub( sb, 'o', '0' );
    StrOps::Sub( sb, 'a', '4' );

    StrOps::Dump( sb );

    return 0;
}
```

Executing the preceding code produces the following output:

```
P4ssw0rd
```

StrOps::Upper(StrBuf &)

Convert each character in a string (in place) to uppercase

Virtual?	No
Class	StrOps
Arguments	<code>StrBuf &o</code> the string to convert to uppercase
Returns	<code>void</code>

Notes

This function modifies an original string in place by converting all lowercase characters to uppercase.

Example

```
StrBuf o = StrBuf();
o.Set( "xYzZy" );

printf( "Before: %s\n", o );
StrOps::Upper( o );
printf( "After:  %s\n", o );

return 0;
```

Executing the preceding code produces the following output:

```
% a.out
Before: xYzZy
After:  XYZZY
```

StrOps::Words(StrBuf &, const char *[], char *[], int)

Break a string apart at whitespace.

Virtual?	No	
Class	StrOps	
Arguments	StrBuf &tmp	a temporary string
	const char *buf	the input string
	char *vec[]	the output array
	int maxVec	the maximum number of words to handle
Returns	int	the actual number of words handled

Notes

This function uses the `isAspace()` function to define whitespace.

Example

```
StrBuf o = StrBuf();
StrBuf tmp = StrBuf();
o.Set( "abc\ndef    ghi\nxyz xyzzy plugh" );

printf( "Input StrBuf:\n%s\n", o.Text() );

char *vec[5];
int w = StrOps::Words( tmp, o, vec, 5 );

for ( ; w ; w-- )
{
    printf( "Word %d: %s\n", w, vec[w-1] );
}

return 0;
```

Executing the preceding code produces the following output:

```
Input StrBuf:
abc      def    ghi
xyz xyzzy plugh

Word 5: xyzzy
Word 4: xyz
Word 3: ghi
Word 2: def
Word 1: abc
```

StrOps::Xto0(char *, unsigned char *, int)

Convert a hex string into an octet stream.

Virtual?	No	
Class	StrOps	
Arguments	<code>char *x</code>	the input hex string
	<code>char *octet</code>	the output stream
	<code>int octlen</code>	the length of the output, in bytes
Returns	<code>void</code>	

Notes

This function converts the input hexadecimal string into the stream of bytes that it represents.

Example

```
char *hex = "666F6F";
unsigned char oct[4];

StrOps::Xto0( hex, oct, 3 );
oct[3] = '\0';

printf( "%s", oct );

return 0;
```

Executing the preceding code produces the following output:

```
% a.out
foo
```

StrPtr methods

StrPtr::Atoi()

Return the numeric value, if any, represented by this StrPtr's buffer.

Virtual?	No
Class	StrPtr
Arguments	None
Returns	int integer value of the string

Notes

[StrPtr::Atoi\(\)](#) is equivalent to calling `atoi(StrPtr::Text())`. Non-numeric strings typically return a value of zero.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;
    StrBuf str2;

    str1.Set( "123" );
    str2.Set( "234" );

    printf( "%s + %s = %d\n",
            str1.Text(), str2.Text(), str1.Atoi() + str2.Atoi() );
}
```

Executing the preceding code produces the following output:

```
123 + 234 = 357
```

StrPtr::CCompare(const StrPtr &)

Case insensitive comparison of two StrPtrs.

Virtual?	No
Class	StrPtr
Arguments	const StrPtr &s the StrPtr to compare this one with
Returns	int zero if identical, nonzero if different

Notes

[StrPtr::CCompare\(\)](#) is a wrapper for `stricmp()` or `strcasecmp()`. Its return value, if nonzero, indicates which of the two strings is "greater" in the ASCII sense.

See also

[StrPtr::XCompare\(\)](#)
[StrPtr::Compare\(\)](#)

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2, str3;

    str1.Set( "abc" );
    str2.Set( "Abc" );
    str3.Set( "xyz" );

    if ( str1.CCompare( str2 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str2.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str2.Text() );

    if ( str1.CCompare( str3 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str3.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str3.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
abc == Abc  
abc != xyz
```

StrPtr::Compare(const StrPtr &)

Comparison of two `StrPtr`s, with case sensitivity based on client platform.

Virtual?	No		
Class	StrPtr		
Arguments	<code>const StrPtr &s</code>	the <code>StrPtr</code> to compare this one with	
Returns	<code>int</code>	zero if identical, nonzero if different	

Notes

`StrPtr::Compare()` is a wrapper for `zstrcmp()`. Its return value, if nonzero, indicates which of the two strings is "greater" in the ASCII sense.

See also

[StrPtr::CCompare\(\)](#)
[StrPtr::XCompare\(\)](#).

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2, str3;
    str1.Set( "abc" );
    str2.Set( "Abc" );
    str3.Set( "xyz" );

    if ( str1.Compare( str2 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str2.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str2.Text() );

    if ( str1.Compare( str3 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str3.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str3.Text() );

    return 0;
}
```

Executing the preceding code produces the following output on Windows:

```
abc == Abc  
abc != xyz
```

and on Unix::

```
abc != Abc  
abc != xyz
```

StrPtr::Contains(const StrPtr &)

Look for a substring and, if found, return it.

Virtual?	No	
Class	StrPtr	
Arguments	<code>const StrPtr &s</code>	the substring to look for
Returns	<code>char *</code>	the start of the substring if found, otherwise <code>NULL</code>

Notes

[StrPtr::Contains\(\)](#) returns a pointer to the StrPtr's buffer, rather than allocating a new buffer for the substring. If it cannot find the substring, [Contains\(\)](#) returns `NULL`.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2;

    str1.Set( "the quick brown fox jumps over the lazy dog" );
    str2.Set( "brown fox" );

    printf( "%s\n", str1.Contains( str2 ) );
}

return 0;
}
```

Executing the preceding code produces the following output:

```
brown fox jumps over the lazy dog
```

StrPtr::Length()

Return the length of this StrPtr.

Virtual?	No
Class	StrPtr
Arguments	None
Returns	int the length of this StrPtr

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "This string" );

    printf( "%s is %d bytes long\n", str1, str1.Length() );
    return 0;
}
```

Executing the preceding code produces the following output:

```
This string is 11 bytes long
```

StrPtr::operator [](int)

Return the character at the specified index.

Virtual?	No	
Class	StrPtr	
Arguments	int x	the index to look in
Returns	char	the character at that index

Notes

This operator does no bounds checking, and can therefore return data from beyond the end of the string.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "the quick brown fox jumps over the lazy dog" );
    printf( "%c%c%c%c\n", str1[1], str1[2], str1[35], str1[35], str1[12] );

    return 0;
}
```

Executing the preceding code produces the following output:

```
hello
```

StrPtr::operators ==, !=, >, <, <=, >= (const char *)

Case-sensitive comparison operators between StrPtr and char *.

Virtual?	No	
Class	StrPtr	
Arguments	<code>const char *buf</code>	the string to compare with
Returns	<code>int</code>	zero if the comparison is false, nonzero if true.

Notes

These operators are typically used in simple comparisons between StrPtrs, such as to see whether two StrPtrs contain the same string, or whether one is greater than the other, ASCII-wise. The comparison is always case-sensitive.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "This string" );

    printf( "%s", str1.Text());
    if ( str1 == "that string" ) printf( " == " );
    if ( str1 > "that string" ) printf( " > " );
    if ( str1 < "that string" ) printf( " < " );
    printf( "that string" );
    return 0;
}
```

Executing the preceding code produces the following output:

```
This string < that string
```

(Note that "t" > "T" in ASCII.)

StrPtr::operators ==, !=, >, <, <=, >= (const StrPtr &)

Case-sensitive comparison operators between `StrPtr` and `StrPtr`.

Virtual?	No
Class	StrPtr
Arguments	<code>const StrPtr & buf</code> the string to compare with
Returns	<code>int</code> zero if the comparison is false, nonzero if true.

Notes

These operators are typically used in simple comparisons between `StrPtrs`, such as to see whether two `StrPtrs` contain the same string, or whether one is greater than the other, ASCII-wise. The comparison is always case-sensitive.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2;

    str1.Set( "This string" );
    str2.Set( "that string" );

    printf( "%s", str1.Text() );
    if ( str1 == str2 ) printf( " == " );
    if ( str1 > str2 ) printf( " > " );
    if ( str1 < str2 ) printf( " < " );
    printf( "%s\n", str2.Text() );
    return 0;
}
```

Executing the preceding code produces the following output:

```
This string < that string
```

(Note that "t" > "T" in ASCII.)

StrPtr::Text()

Return the `char *` containing this `StrPtr`'s text.

Virtual?	No
Class	StrPtr
Arguments	None
Returns	<code>char *</code> This <code>StrPtr</code> 's buffer

Notes

`StrPtr::Text()` and `StrPtr::Value()` are exactly equivalent. Their most typical use is converting a `StrPtr` to a `char *` for functions outside of the client API to use.

Example

```
#include <sthdhrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "the quick brown fox jumps over the lazy dog" );
    printf( "%s\n", str1.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
the quick brown fox jumps over the lazy dog
```

StrPtr::Value()

Return the `char *` containing this `StrPtr`'s text.

Virtual?	No
Class	StrPtr
Arguments	None
Returns	<code>char *</code> This <code>StrPtr</code> 's buffer

Notes

`StrPtr::Value()` is the deprecated form of `StrPtr::Text()`. The two functions are equivalent. Their most typical use is converting a `StrPtr` to a `char *` for functions outside of the client API to use.

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "the quick brown fox jumps over the lazy dog" );
    printf( "%s\n", str1.Value() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
the quick brown fox jumps over the lazy dog
```

StrPtr::XCompare(const StrPtr &)

Case sensitive comparison of two StrPtrs.

Virtual?	No
Class	StrPtr
Arguments	const StrPtr &s the StrPtr to compare this one with
Returns	int zero if identical, nonzero if different

Notes

[StrPtr::XCompare\(\)](#) is a wrapper for `strcmp()`. Its return value, if nonzero, indicates which of the two strings is "greater" in the ASCII sense.

See also

[StrPtr::CCompare\(\)](#)
[StrPtr::Compare\(\)](#)

Example

```
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1, str2, str3;

    str1.Set( "abc" );
    str2.Set( "Abc" );
    str3.Set( "xyz" );

    if ( str1.XCompare( str2 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str2.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str2.Text() );

    if ( str1.XCompare( str3 ) == 0 )
        printf( "%s == %s\n", str1.Text(), str3.Text() );
    else
        printf( "%s != %s\n", str1.Text(), str3.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
abc != Abc  
abc != xyz
```

StrRef methods

StrRef::StrRef() (constructor)

Construct a **StrRef**, and leave it unset.

Virtual?	No
Class	StrRef
Arguments	None
Returns	StrRef

Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

StrRef::StrRef(const StrPtr &) (constructor)

Construct a **StrRef**, referencing an existing string.

Virtual?	No
Class	StrRef
Arguments	const StrPtr & a StrPtr to reference
Returns	StrRef

Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "abc" );
    StrRef sr = StrRef( str1 );

    cout << "str1 = \"" << str1.Text() << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
str1 = "abc"
sr.Text() returns "abc"
```

StrRef::StrRef(const char *) (constructor)

Construct a **StrRef**, referencing an existing string.

Virtual?	No
Class	StrRef
Arguments	char *buf a null-terminated string to reference
Returns	StrRef

Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "abc";
    StrRef sr = StrRef( chars );

    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "abc"
sr.Text() returns "abc"
```

StrRef::StrRef(const char * , int)(constructor)

Construct a **StrRef**, referencing an existing string.

Virtual?	No	
Class	StrRef	
Arguments	char *buf	a null-terminated string to reference
	int len	the string length
Returns	StrRef	

Notes

If arguments are provided, the constructor calls [Set\(\)](#) with them.

[StrRef::Set\(\)](#) does not copy the target string; it simply creates a pointer to it. Be sure that the **StrRef** pointing to the target string does not outlive the target string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzzy";
    StrRef sr = StrRef( chars, 3 );
    StrBuf sb;
    sb.Set( sr );

    printf( "chars[] = \"%s\"\n", chars );
    printf( "sr.Text() returns \"%s\"\n", sr.Text() );
    printf( "sb.Text() returns \"%s\"\n", sb.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzzy"
sr.Text() returns "xyzzy"
sb.Text() returns "xyz"
```

StrRef::Null()

Return a null StrPtr.

Virtual?	No	
Class	StrRef	
Arguments	None	
Returns	StrPtr	an empty StrPtr

Notes

[StrRef::Null\(\)](#) is a static function.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "abc" );
    StrRef sr = StrRef( str1 );

    if ( sr == StrRef::Null() )
        cout << "str1 was null\n";
    else
        cout << "str1 was not null\n";
}
```

Executing the preceding code produces the following output:

```
str1 was not null
```

StrRef::operator =(StrPtr &)

Set a **StrPtr** to reference an existing **StrPtr** or null-terminated string.

Virtual?	No
Class	StrRef
Arguments	StrPtr &s the StrPtr to reference
Returns	void

Notes

The = operator is equivalent to calling [Set\(\)](#).

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;

    str1.Set( "xyz" );
    StrRef sr = str1;

    cout << "str1 = \"" << str1.Text() << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
str1 = "xyz"
sr.Text() returns "xyz"
```

StrRef::operator=(char*)

Set a StrPtr to reference an existing StrPtr or null-terminated string.

Virtual?	No
Class	StrRef
Arguments	char *buf the null-terminated string to reference.
Returns	void

Notes

The = operator is equivalent to calling [Set\(\)](#).

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyz";
    StrRef sr;

    sr = chars;

    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyz"
sr.Text() returns "xyz"
```

StrRef::operator+=(int)

Increase a **StrRef**'s pointer and decrease its length.

Virtual?	No
Class	StrRef
Arguments	int len the amount by which to move the pointer
Returns	void

Notes

This method has the effect of removing **len** characters from the beginning of the **StrRef**. It does not, however, free the memory allocated to those characters.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzzy";
    StrRef sr = StrRef( chars );

    sr += 3;

    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sr.Text() returns \"\" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzzy"
sr.Text() returns "zy"
```

StrRef::Set(char*)

Set a **StrRef** to reference an existing null-terminated string.

Virtual?	No
Class	StrRef
Arguments	char *buf the null-terminated string to reference
Returns	void

Notes

[StrRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the **StrRef** pointing to the target string does not outlive the target string.

Example

```
#include <iostream>
#include <stddhtrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyz";
    StrRef sr;

    sr.Set( chars );

    cout << "chars[] = \"" << chars << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyz"
sr.Text() returns "xyz"
```

StrRef::Set(char* , int)

Set a **StrRef** to reference an existing null-terminated string.

Virtual?	No	
Class	StrRef	
Arguments	<code>char *buf</code>	the null-terminated string to reference
	<code>int len</code>	the length of the string
Returns	<code>void</code>	

Notes

[StrRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the **StrRef** pointing to the target string does not outlive the target string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    char chars[] = "xyzzy";
    StrBuf sb;
    StrRef sr;
    sb.Set( chars );
    sr.Set( chars, 3 );

    printf( "chars[] = \"%s\"\n", chars );
    printf( "sr.Text() returns \"%s\"\n", sr.Text() );
    printf( "sb.Text() returns \"%s\"\n", sb.Text() );

    return 0;
}
```

Executing the preceding code produces the following output:

```
chars[] = "xyzzy"
sr.Text() returns "xyzzy"
sb.Text() returns "xyz"
```

StrRef::Set(const StrPtr *)

Set a **StrRef** to reference an existing **StrPtr**.

Virtual?	No
Class	StrRef
Arguments	<code>const StrPtr *s</code> the value to set
Returns	<code>void</code>

Notes

[StrRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the **StrRef** pointing to the target string does not outlive the target string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrRef sr;
    sr.Set( "xyz" );
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
sr.Text() returns "xyz"
```

StrRef::Set(const StrPtr &)

Set a **StrRef** to reference an existing **StrPtr**.

Virtual?	No
Class	StrRef
Arguments	<code>const StrPtr &s</code> the StrPtr to reference
Returns	<code>void</code>

Notes

[StrRef::Set\(\)](#) does not copy the target string; it simply establishes a pointer to it. Be sure that the **StrRef** pointing to the target string does not outlive the target string.

Example

```
#include <iostream>
#include <stdhdrs.h>
#include <strbuf.h>

int main( int argc, char **argv )
{
    StrBuf str1;
    StrRef sr;

    str1.Set( "xyz" );
    sr.Set( str1 );

    cout << "str1 = \"" << str1.Text() << "\"\n";
    cout << "sr.Text() returns \"" << sr.Text() << "\"\n";
}
```

Executing the preceding code produces the following output:

```
str1 = "xyz"
sr.Text() returns "xyz"
```


Perforce software includes software developed by the University of California, Berkeley and its contributors. This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

Perforce software includes software from the Apache ZooKeeper project, developed by the Apache Software Foundation and its contributors. (<http://zookeeper.apache.org/>)

