

This presentation will discuss the new route, DatabaseRoute and DatabaseRetrieve nodes in Message Broker Version 6.1



This presentation covers the topics shown on this slide.

A recurring theme with the node enhancements in version 6.1 is as much as possible to remove the need for programming with ESQL or with Java[™]. To that end, these three new nodes have been designed to enable these basic functions without the need to write application code. The routing decisions that are taken are built using the Message Broker toolkit, and provide an intuitive way to create the appropriate expressions.



The new Route node provides a graphical technique to enable incoming requests to be examined, and flow sent down the appropriate part of the message flow, depending on the specified criteria.

The Route node matches the incoming data to a set of specified criteria. Based on this criteria, the message can be routed to output terminals on the Route node. These terminals can be specified by the application developer, as shown on the next slide.

The filter criteria are specified by the generation of an X-Path statement in the Filter pattern for each required match. An example of this is shown on the next few slides.



To configure the Route node, first drop a node onto the message flow editor. Then, rightclick the Route node, and select "Add Output Terminal". When the dialogue box opens, provide a name for the new output terminal. This example creates a new terminal called "CICS".

You can define as many output terminals as you like. This will be determined by the profile of your message flow. When you have more than four output terminals, the node will consolidate all terminals into the combined display, as shown on this slide. To connect these terminals, click on the terminal arrow, select the required terminal, and wire to the next node as needed.

IBM Software G	iroup		IRM
Configuring th	ne route	node (2)	
Properties × Problems Pro	gress		
Description Route No	de Properties - Route		
Basic 🚫 Filter table: .	A value must be set for this pro	perty.	
Filter table*	Filter pattern	Routing output terminal	Add Cda
Distribution mode	First		
Hiter pattern	table entry *	6	Edt
		a and Database Patriava no das	© 2008 IPM Comparation

Once all terminals have been defined, you need to specify the filter properties for each condition. The first screen capture shows the properties of the Route node, before any filters have been defined.

To create a filter, click the Add button. This can be done for each of the filter that are required.

When you have clicked the Add button, the second window will open. First, select the appropriate output terminal by using the pull-down. This will be populated with all of the output terminals that you have created on the Route node.

Then click the "Edit" button to specify the filter.

IBM Software Group			IRM
Configuring the r ^{® XPath Expression Builder} Select the target from the Schema vie	voute node (3	nodes in the source viewer below.	
Performance view	XDath Functions	Onerators	
(Add bast prevention of the state of th	: complexType2 the CustomerInfo : complexType1 : complexType1 : complexType1 : complexType1 : complexType2 : customerInfo mithumber : complexType2 : complexType3 :		
 Namespace settings 			
Prefix tro	Nemespace http://www.ibm.lab.com	Add Folk Delete	
0		Finish Cancel	
Route	DatabaseRoute and DatabaseRetrie	ve nodes ©	6 2008 IBM Corporation

The Edit button brings you to the Expression Builder. There are many ways in which a valid XPath expression can be built.

As a simple example, expand the Variables structure in the "Data Types Viewer", then expand \$Body (pronounced dollar-body). Then expand an appropriate part of the message tree. When you have located the required part of the message tree, drag this component onto the XPath Expression pane in the middle section of the window. The example on this slide uses the field customerAccountNumber. Then complete the expression, either by manually adding the criteria, or by dragging and dropping the required operator. You can also match fields from other parts of the incoming message, and you are not restricted to the Body of the message.

IBM	I Software Group	TEM
Configur	ing the route node (4)	
 Distribut Propag all that i 	ion mode ate message to the first terminal that mat match	ches, or to
Description	Problems Progress	
FI	ter table* Filter pattern Rou \$Body/tns:CustomerInfo/customerAccountNumber < 100	Add Add Call the second secon
D		Evaluation order Up/down

Finally, on the Route node properties, you need to specify how you want each criteria to be checked.

The default value for Distribution Mode is "All". This means that all Filter patterns are checked, and every filter condition that is true results in the message being passed to the specified output terminal. In this case, multiple paths in the message flow will be executed.

If the Distribution Mode is changed to "First", each filter pattern will be evaluated in turn, starting from the top of the list. When the first matching filter is encountered, control will be passed to the specified terminal.

The order in which filter patterns can be evaluated can be changed by using the UP and DOWN buttons. These will be shown in color when there are two or more defined filter patterns, and when one of the filter patterns is highlighted by clicking on the filter.



The DatabaseRoute node provides a similar function to the Route node, but the routing decision is based on the contents of a relational database. In the example shown on this slide, the incoming message is a customer record, containing a customer number. This request needs to be routed to a certain part of the flow, depending on the STATUS of the customer. However, this information is held on a relational database, which needs to be read by the DatabaseRoute node.



Prior to building a message flow with the DatabaseRoute node, you need to prepare the database environment. This can vary significantly between environments, and depends on both the platform where the broker and database reside, and the database that is being used.

This slide shows a very simple example, where the database is IBM DB2, and where the DB2 database is installed on the same Windows platform as the Message Broker. The JDBC configuration needs to be created within the Broker environment, and this is done using Configurable Services. In this case, the "mqsi-change-properties" command is used to set the database name and the location of the database server, so that the Broker can locate the database at runtime. The second and third commands on this slide are used to do this.

In a Windows environment, this JDBC configuration is stored in the Windows registry. In this example, you will see that the databaseName has been set to "DBASE AIR".

For more complex scenarios, ensure you review the Message Broker Information Center for details on JDBC configuration.

ļ.	BM Software	Group					IRM
Configu	uring t	he Data	baseRo	oute	nod	e (2)	
Properties X Pro Description Basic Filter Expression Table	blems Progress Databasel Query element Data source name* Query elements*	Table name	- DatabaseRoute s property.	Operator	Value Type	Value	Add Delete
	SQL statement	<u>۱</u>					
							11

When the DatabaseRoute node is dropped on to the flow, the properties of the node will look like this.

The Basic tab is shown by default, and this is used to specify the database access statement to query the database.

Later, the Filter Expression Tab will be used to specify the routing decision.

Clicking Add on this screen opens a dialogue window, as shown on the next slide.

IBM Software	Group	IRM
Configuring t	he DatabaseRoute node (3)	
4	Add Query elements entry	
	Table name	
	Operator	
1	-	
	Value Type	
	Element	
	Value \$Body/Purchase/Customer/LastName	
	OK Cancel	
		_ 11
	Table name ADMIN.CUSTOMER Column name SS Operator Substrate State Stat	≥ 2008 IBM Corpora

The Add Query window opens.

The values shown in this example are as follows:

"ADMIN" is the database schema, and CUSTOMER is the database table name.

"LAST" is the column of the database table that the DatabaseRoute node will read.

Operator is a Boolean value which specifies how the required row should be retrieved. This example is requesting a direct match on the element value.

Finally, value contains the XPath expression which identifies the data in the incoming message. This data is used to read the required database row. This value can either be typed in manually, or can be automatically included by clicking the button to the right side of this field, and following the dialogue. This will be a similar dialogue to the Route node.

Click OK to move to the next window.

	IBM Software	Group					IRM
Configu	uring (the Data	baseR	oute	nod	e (4)	
📰 Properties 🗙 Prob	lems Progress						~ - 8
Description Basic Filter Expression Table	Data source name*	Route Node Properties - I	DatabaseRoute				T
	Query elements*	ADMIN.CUSTOMER	Column name LAST	Operator =	Value Type Element	Value \$Body/AirlineRequest/Page	Add
	SQL statement	Rom ADMIN.CUSTOMER					
		WHERE ADMINICOSTONER.EA	51 — :				
_			_				40
						@ 2008 II	12

This has now created a new query element for the DatabaseRoute node, and the details are shown in the properties. The generated SQL statement is shown at the bottom of these properties.

To ensure the query statement retrieves at least one valid row, there needs to be a query element with a null value type. If you do not do this, the SQL statement will not be valid.

Click Add again, as shown on this slide.

This will again open the Query Elements entry, as shown on the next slide.

IBM Software Group	IEM
Configuring the DatabaseRoute node (5)	
Add Query elements entry Table name	
ADMIN.CUSTOMER	
STATUS Operator	
ASC Value Type	
Value	
None	
OK Cancel	
	13

On this window, the Table name and column name are as before. However, the Operator value is "ASC", and the remaining values are defaulted.

1	BM Softwa	are Group					TRM
Configu	uring	the D	atal	oas	seR	oute node (6))
Properties X Problem Description	*DatabaseF	Coute Node Propertie	es - Databas	eRoute			
	Query elements*	Table name	Column name	Operator	Value Type	Value	
		ADMIN.CUSTOMER ADMIN.CUSTOMER	STATUS	ASC	None	soury/emilerequest/rurtilase/customer/castvalue	Edit
	SQL statement	SELECT ADMIN.CUSTOME FROM ADMIN.CUSTOMER WHERE ADMIN.CUSTOME ORDER BY ADMIN.CUSTO	R.STATUS R.LAST = ? MER.STATUS AS	5C			×
	Distribution mode	All					
							14

This creates a second entry in the Query Elements table. The resulting SQL statement is shown at the bottom.

The Query Elements are now complete. Click on "Filter Expression Table" to construct the filter part of the properties. This will show the window on the next slide.

	IBM Software G	roup			TRM
Config	uring th	e Dat	tabaseRoute n	ode (7)	
Properties X Pro Description Basic Filter Expression Table	blems Progress DatabaseRoul S Filter table* Filter table*	te Node Proper or must be set for thi	ties - DatabaseRoute s property. Routing output terminal		Add Edit Delete
		Routo Datab		@ 200	15 8 IBM Corporation

Now click "Add" to create a new filter expression.

IBM Software Group	IRM
Configuring the DatabaseRoute node (8)	
💠 Add Filter table entry	
Filter pattern*	
\$ADMIN CUSTOMER STATUS = 'Bronze '	
Routing output terminal	
Bronze T	
Bronze Silver	
Gold Platinum	
Route, DatabaseRoute and DatabaseRetrieve nodes © 2008 I	16 BM Corporation

The "Add Filter" dialogue will open. Specify the Filter pattern that is required. In this example, ADMIN is the schema, CUSTOMER is the table, and STATUS is the column. These are all connected using an underscore character, which is not clearly visible on this screen capture.

Using the pull-down, select the appropriate output terminal. This list is generated from the new terminals that were defined earlier.

Click OK to complete the dialogue for one filter pattern.

1	BM Softw	are Group		IEM
Confia	irino	the Databas	eRoute node	(9)
.......		,		
	-			
Properties X Proble	ems Progress			· []
Description	🕽 Databa	aseRoute Node Properties - Database	Route	
Basic				
Filter Expression Table	, Filter table* 🖡	Eilley pattern	Douting output torminal	
		\$ADMIN_CUSTOMER_STATUS = 'Bronze_'	Bropze	Add
		\$ADMIN CUSTOMER STATUS = 'Silver '	. Silver	Edit
		\$ADMIN_CUSTOMER_STATUS = 'Gold '	Gold	
		\$ADMIN_CUSTOMER_STATUS = 'Platinum '	Platinum	Delete
	K			
				17
		Deute Detabase Deute and D	atabaga Batriova nadag	© 2009 IBM Comparation

If necessary, add further filter patterns by using the Add button. Existing filter patterns can be edited or deleted from this window.

The filter expressions are evaluated in the order shown. If you need to change the order, use the colored buttons on the bottom right hand side of this window.



A similar node is the DatabaseRetrieve node. This node enables data to be retrieved from one of more relational databases, and use a similar dialogue to the DatabaseRoute node.

It uses JDBC to connect to the database, so the same base configuration as with the DatabaseRoute node needs to be built.

This example uses the DatabaseRetrieve node to look up the record of employee number 00002. Two values are retrieved from the database, which are then used to populate the Body of the message, which is passed down the message flow. Follow the example shown on the DatabaseRoute node to understand how to configure the node itself.



When accessing a database, the requested record may not be found. In this case, or if the message fails to be updated correctly, control will be passed to the "keyNotFound" terminal.

If a more general error occurs, control will be passed to the failure terminal, as normal.



This presentation has covered the new Route, DatabaseRoute and DatabaseRetrieve nodes in Message Broker Version 6.1



You can help improve the quality of IBM Education Assistant content by providing feedback.



Trademarks, copyrights, and disclaimers

The following terms are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both: DB2 IBM WebSphere

Windows, and the Windows logo are registered trademarks of Microsoft Corporation in the United States, other countries, or both.

JDBC, Java, and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Product data has been reviewed for accuracy as of the date of initial publication. Product data is subject to change without notice. This document could include technical inaccuracies or typographical errors. IBM may make improvements or changes in the products or programs described herein at any time without notice. Any statements regarding IBM's future direction and intent are subject to change or withdrawal without notice, and represent goals and objectives only. References in this document to IBM products, programs, or services does not imply that IBM intends to make such products, programs or services available in all countries in which IBM operates or does business. Any reference to an IBM Program Product in this document is not intended to state or imply that only that program product may be used. Any functionally equivalent program, that does not infringe IBM's intellectual property rights, may be used instead.

Information is provided "AS IS" without warranty of any kind. THE INFORMATION PROVIDED IN THIS DOCUMENT IS DISTRIBUTED "AS IS" WITHOUT ANY WARRANTY, EITHER EXPRESS OR IMPLIED. IBM EXPRESSLY DISCLAIMS ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NONINFRINGEMENT. IBM shall have no responsibility to update this information. IBM products are warranted, if at all, according to the terms and conditions of the agreements (for example, IBM Customer Agreement, Statement of Limited Warranty, International Program License Agreement, etc.) under which they are provided. Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products in connection with this publication and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products.

IBM makes no representations or warranties, express or implied, regarding non-IBM products and services.

The provision of the information contained herein is not intended to, and does not, grant any right or license under any IBM patents or copyrights. Inquiries regarding patent or copyright licenses should be made, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 U.S.A.

Performance is based on measurements and projections using standard IBM benchmarks in a controlled environment. All customer examples described are presented as illustrations of how those customers have used IBM products and the results they may have achieved. The actual throughput or performance that any user will experience will vary depending upon considerations such as the amount of multiprogramming in the user's job stream, the I/O configuration, the storage configuration, the and the workload processed. Therefore, no assurance can be given that an individual user will achieve throughput or performance improvements equivalent to the ratios stated here.

© Copyright International Business Machines Corporation 2008. All rights reserved.

Note to U.S. Government Users - Documentation related to restricted rights-Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract and IBM Corp.

