# MacApp 2.0b5 View Architecture Release Notes

# **Curt Bianchi**

# Introduction

This document describes the architecture for MacApp 2.0's view classes, and describes all methods and fields of the view classes defined in UMacApp. This represents the major change between MacApp 1.x and MacApp 2.0. The motivations for introducing the new architecture are

- To simplify the architecture
- To provide a class that is suitable as the basis for all displayed objects, from windows to controls
- To have a single nesting and layering mechanism for display objects
- To support large coordinate systems
- To simplify the implementation of display objects within views, including controls and fields

# The MacApp 1.x Display Achitecture

If you're already familiar with the MacApp 1.x display architecture, you should skip this section. If you're not, here it is in a nutshell.

The old display architecture consists basically of three classes: TWindow, TFrame, and TView.

- TWindow A TWindow object represents a Window Manager window. As such, it handles opening, closing, moving, resizing, activating, and deactivating a window.
- TFrame A TFrame object is a rectangular area within a window, handling scrolling and coordinate transformations. TFrame objects are similar to QuickDraw grafports in that each has its own coordinate system. Frames typically tile windows. In the simplest case, windows have a single frame whose size is that of the window's content rectangle. However, windows can be subdivided into sections by using multiple frames. Furthermore, frames can be nested inside one another. Within frames are displayed Control Manager controls (for example, scroll bars) and a portion of a view, or a collection of subframes, or both.
- TView A TView object renders the display image of a document's data and responds to mouse clicks and keystrokes in the display image. It is a rectangular area of any size up to 30,000 pixels in each dimension. A view is always displayed in a frame. The frame's scroll bars determine what part of the view is actually visible, since large views cannot be displayed in their entirety.




Figure 1: Old MacApp Display Architecture

Figure 1 shows a typical text edit window and the MacApp objects used to build it. Here, the TWindow object displays the grow icon (the rest of the window frame is drawn by the Window Manager) and handles mouse clicks outside the window's content region. The TFrame object draws the scroll bar, handles mouse clicks in the scroll bar, and focuses the window so that the framed portion of the view is drawn. Focusing consists of setting the port, its origin, and its clipping region. Setting the port origin determines what part of the view is visible in the frame. The frame responds to clicks in the scroll bar by changing the port origin, thereby changing the visible part of the view, and causing the view to be redrawn. The view draws the text, and handles keystrokes and mouse clicks in the text.

As part of MacApp's dialog box support, the display architecture is augmented to incorporate nested views. TCatView, a descendant of TView, is a type of view that contains a collection of subviews. Thus you can have frames within frames, each of which can contain a single view, which in turn can contain views within views.

This brings us to the shortcomings of the old architecture. First, having two separate nesting models complicates and duplicates much functionality. Neither nesting scheme is totally satisfactory, and it isn't clear to the user which scheme to use. Second, given that each frame has its own set of controls, MacApp has three different ways of layering the contents of a window (frames, views, and controls). Third, it is difficult to deal with Control Manager controls as separate entities (for example, buttons in a dialog box). Fourth, it is cumbersome to use views as the basis for display objects such as icons or form fields, since each must be placed in its own frame or must be used with cat views. Either way adds an unneeded layer of abstraction. Furthermore, TCatViews have been regarded as temporary citizens in the MacApp object library, and users are warned not to use them as they may be done away with "any time now."

Another source of trouble with the old MacApp architecture is dialog boxes. They are implemented with a descendant of the TWindow class, and with TCatViews. In many cases, it is more difficult to deal with MacApp's dialog box support than to implement dialog boxes from scratch.

# The MacApp 2.0 Display Architecture

So how does the new architecture differ from the old? Primarily by providing a robust display object class, called TView, from which all other display classes descend. The fundamental difference between the new architecture and the old is this: All display objects descend from the same class. (All subsequent references to TView are to the new TView.) The role of the TView class is to define a set of properties common to all display objects. These properties include nesting, focusing, drawing, and event handling. MacApp also defines a number of standard views that are subclasses of TView. These include TWindow, TControl, TCtlMgr, TScrollBar, TSScrollBar and TScroller. These classes will be described in more detail later.

# Nesting

A view is a rectangular display object of a given size and position with respect to its background view. Any view can serve as the background for any other view. A set of views related in this way forms a tree, in which all but the leaf views serve as backgrounds for other views. This relationship is called the *superview/subview relationship*. Each view can be contained in another view, called its *superview*. Each view can contain any number of views, called *subviews*. A view's subviews form an ordered list, allowing overlapping views to have a front-to-back order.

The benefit of this arrangement is that views can be tiled or layered. Tiling separates logically distinct portions of a window or view into individual sections. Layering organizes groups of display objects in layers from "front" to "back," much like the way the Window Manager layers windows.

Figure 2 at the end of this section shows the same window as Figure 1 did, but this time decomposed into MacApp 2.0 objects. The window consists of four views: the window itself, a standard "scroller" and scroll bar, and a standard text editing view. There are three layers: the bottom layer consists of the window view; the middle layer consists of the scroller and scroll bar; and the top layer consists of the text.

# Focusing


Focusing is the act of setting up the graphics environment to draw the visible part of a view. This entails setting the QuickDraw grafport, setting the port's coordinate system, and clipping a view's drawing to the margins of its superview. Each view has a local coordinate system whose top-left corner is coordinate (0, 0).

# Drawing

The TView class implements a simple algorithm for drawing a collection of views. Beginning with the view representing the window, each view draws itself and then tells its subviews to draw themselves. Each subview in turn draws itself and tells its subviews to draw themselves. This continues until there are no subviews to draw. Effectively, views are drawn from the bottom to the top. Changing the drawing algorithm is a matter of overriding a single TView method.

# **Event Handling**

The TView class is a subclass of TEvtHandler, so it inherits the ability to handle keystrokes and menu commands. In addition, TView has the ability to handle mouse clicks. A simple algorithm is used to determine which view receives the mouse click. Basically, mouse clicks are handled from the top layer of views down. This is done by finding the topmost view containing the mouse point, and then working back to the bottom until a view has handled the click.





# Large Coordinate Systems

One of the limitations of MacApp 1.x is that the maximum size of a view is 30,000 pixels horizontally and vertically, or about 40 8-1/2 by 11 pages. This makes it difficult to use MacApp for applications like word processors and spreadsheets. For example, consider a spreadsheet with 8,000 rows. If each row is 16 pixels high, then its view height is 8,000 \* 16, or 128,000 pixels.

To overcome this, we've introduced a large coordinate system where coordinates are represented by 32 bits rather than 16 bits. A large coordinate is defined by the VCoordinate type. VPoint and VRect define large points and rectangles:

```
VCoordinate = LONGINT;
VPoint = RECORD
CASE INTEGER OF
0: (v, h: VCoordinate);
1: (vh: ARRAY [VHSelect] OF VCoordinate);
END;
VRect = RECORD
CASE INTEGER OF
0: (top, left, bottom, right: VCoordinate);
1: (topLeft, botRight: VPoint);
END;
```

(V stands for view. We would have used LPoint, LRect, and so on, had the List Manager not defined LRect.)

Implementing a large coordinate system on top of QuickDraw requires mapping view coordinates to QuickDraw coordinates. This is different from scaling, which condenses the entire view into QuickDraw's coordinate system, transforming *many* view coordinates to one QuickDraw coordinate. Mapping as discussed here overlays QuickDraw's coordinates space on some part of the view, transforming *one* view coordinate to one QuickDraw coordinate.


Two possibilities exist for handling coordinate mapping. MacApp can either implicitly map views to QuickDraw coordinates, or the programmer must explicitly map them. The former requires implementing an entire set of drawing and calculation routines for large coordinates, as was done for the Lisa Toolkit. This approach has the advantage of being clean and simple, but it has the disadvantages of slowing all drawing, forcing the developer to adopt a new set of drawing routines, and, of course, forcing us to implement all of those routines.

Operating under the assumption that most views do not require a large coordinate system, we chose the latter approach. Implementing views smaller than QuickDraw's coodinate system imposes little to no burden on the programmer, since coordinate mapping is not necessary. For views larger than QuickDraw's coordinate system, the burden is on the programmer to map between view and QuickDraw coordinates as necessary, using view methods for this purpose.

MacApp provides a unit, UViewCoords, for manipulating VPoints and VRects. It includes routines to convert between Points, Rects, VPoints and VRects and for performing various operations on VPoints and VRects similar to those found in QuickDraw.

# The New Classes

Figure 3 shows a hierarchy of the primary MacApp 2.0 display object classes.



Additional display classes are included in the building blocks UTEView, UDialog and UGridView. A brief description of each class follows:

TView = OBJECT(TEvtHandler)

As described above, TView is the basic display object class of MacApp, from which all other display classes descend. As a descendant of TEvtHandler, it inherits the ability to handle keystroke events and menu commands. In addition, it provides these general capabilities: nesting, drawing, focusing, and mouse handling. This class forms the basis for all other MacApp display objects.

#### TScroller = OBJECT(TView)

TScroller is a subclass of TView that applies a coordinate translation to its contents. Changing the translation effectively scrolls the scroller's contents. A scroller may refer to a vertical and/or horizontal scroll bar, which the scroller keeps in sync. It is also possible to scroll without scroll bars.

#### TWindow = OBJECT (TView)

TWindow is a class that represents a Window Manager window. It responds to mouse clicks outside the window's content region, draws the window's grow box, and overrides other view methods where appropriate. Since TWindow objects represent windows, they never have superviews. They must have at least one subview or nothing will be drawn in the window's content region.

#### TControl = OBJECT(TView)

TControl is an abstract class (one that must be subclassed to obtain useful instances) that represents a MacApp control, of which Control Manager controls are a subset. Properties of MacApp controls are as follows: they can be tracked with the mouse without explicitly creating a command object; they have an optional adornment (frame); they are limited in size to QuickDraw's coordinate space; and they can pass messages (known as choices) to their superviews.

```
TCtlMgr = OBJECT(TControl)
```

TCtlMgr is an abstract class that represents Control Manager controls.

```
TScrollBar = OBJECT(TCtlMgr)
```

TScrollBar is a class that represents generic scroll bars. It contains references to one or more scrollers, which it sends messages to when the user clicks in the scroll bar.

```
TSScrollBar = OBJECT (TScrollBar)
```

TSScrollBar is a class that represents scroll bars used in conjunction with TScroller views. It contains references to one or more scrollers, which it sends messages to when the user clicks in the scroll bar.

# The TView Class

The TView class is the ancestor of all other display classes. As mentioned above, the TView class is used to define a set properties common to all display objects. These properties include nesting, focusing, drawing and event handling.

# Fields

fDocument	The document whose data this view represents, or NIL if the view is not associated with a document. Usually this is NIL if the view does not directly represent a document's data. Thus, views such as scrollers and controls typically have a NIL fDocument.
fSuperView	The view in which this view is contained. The fSuperView field of a window is

	NIL.	
fSubViews	demand and is NIL until fSubViews field of the has an implied ordering v subview in cases where s superview). The last sub first subview is behind th	in this view, implemented as a TList. It is created on the first subview is added to the view. Thus the frontmost views are NIL. Note that the list of subviews which determines which subview is in front of another subviews overlap (that is, occupy the same space in their view in the list is in front of all other subviews while the se other subviews. This has ramifications for cursor and he subview list is searched from last to first to determine mouse.
fLocation	The location of this view	in its superview's coordinate space.
fSize	The horizontal and vertic	al size of the view.
fSizeDeterminer	Indicates the techniques technique use to compute choices are	used to compute the view's width and height. (The e the width may be different than for the height.) The
	sizeFixed	The view's width or height is constant.
	sizeVariable	The view determines its width or height by overriding the CalcMinSize method.
	sizePage	The view's width or height is exactly one page. (The page size is determined by the view's print handler.)
	sizeFillPages	The view overrides CalcMinSize to determine its minimum size, which is then rounded up to fill the last page in the given direction.
	sizeSuperView	The view's width or height is the same as its superview. When its superview changes size, the view's size changes as well.
	sizeRelSuperView	The view's width or height changes relative to its superview's size. When the superview's size changes, the view's size changes an equal amount.
fHLDesired	The type of highlighting when the view is activate	used to draw the view's selection. This field is set to hlon ed, and to hloff when the view is deactivated.
fIdentifier		er of type IDType (PACKED ARRAY [14] OF identifier, you can obtain a reference to the view by using iew method.
fShown		s shown, false indicates the view is hidden. This field is not Instead use the Show and IsShown methods.
fViewEnabled		esponds to mouse clicks, false indicates the view does not This field is not usually accessed directly. Instead use the iewEnabled methods.
fPrintHandler	A reference to the print h	andler associated with this view.

s

# **Coordinate Conversion Methods**

These methods convert between QuickDraw and view coordinates. For views whose width and height is smaller than kMaxCoord (30,000), this amounts to nothing more than converting coordinates between short and long data structures. (Note: It would have been much more natural and convenient for routines of this type to be functions. Unfortunately, the code generated for function calls is less efficient than that generated for procedures with var parameters. Therefore, we felt there the better choice was to use procedures and var parameters.)

PROCEDURE TView.QDToViewPt (qdPoint: Point; VAR viewPt: VPoint);

Returns in viewPt the view point corresponding to the given QuickDraw point. For views whose height and width is less than kMaxCoord (30, 000), qdPoint and viewPt will have the same value. For views whose height or width is greater than kMaxCoord, qdPoint and viewPt will have different values. QDToViewPt assumes the view is focused.

FUNCTION TView.ViewToQDPt (viewPt: VPoint): Point;

Returns the QuickDraw point corresponding to the given view point. For views whose height or width is greater than kMaxCoord, the point returned will have a different value than viewPt. ViewToQDPt assumes the view is focused.

PROCEDURE TView.QDToViewRect (qdRect: Rect; VAR viewRect: VRect);

Returns in viewRect the view rectangle corresponding to the given QuickDraw rectangle. For views whose height or width is greater than kMaxCoord, qdPoint and viewPt will have different values, and QDToViewRect assumes the view is focused.

PROCEDURE TView.ViewToQDRect (viewRect: VRect; VAR qdRect: Rect);

Returns in qdRect the QuickDraw rect corresponding to the given view rectangle. For views whose height or width is greater than kMaxCoord, qdPoint and viewPt will have different values, and ViewToQDRect assumes the view is focused.

PROCEDURE TView.SuperToLocal (VAR thePoint: VPoint);

Analogous to the Toolbox routine GlobalToLocal, SuperToLocal converts the given point from superview coordinates to view coordinates, without changing the focused view.

PROCEDURE TView.LocalToSuper (VAR thePoint: VPoint);

Analogous to the Toolbox routine LocalToGlobal, LocalToSuper converts the given point from local view coordinates to superview coordinates, without changing the focused view.

PROCEDURE TView.WindowToLocal (VAR thePoint: VPoint);

WindowToLocal converts the given point from window coordinates to view coordinates, without changing the focused view.

PROCEDURE TView.LocalToWindow (VAR thePoint: VPoint);

LocalToWindow converts the given point from local view coordinates to window coordinates, without changing the focused view.

# **Subview Management Methods**

Note that the subviews are maintained in an ordered list in which the order determines which subview is in front of another subview when they overlap (that is occupy the same space in their superview). The last subview in the list is in front of all other subviews in the list while the first subview is behind the other subviews. This has ramifications for cursor and mouse handling in that the list is searched from last to first to determine which view contains the mouse.

#### PROCEDURE TView.AddSubView (theSubView: TView);

This method adds theSubView to the end of a view's list of subviews and sets theSubView's fSuperView field to its new superview. If the subview list is NIL, then it is created. If the view is in a grafport, then the subview's BeInGrafPort method is called to notify the subview that it too is in a grafport. If theSubView's fNextHandler is NIL then it is set to its new superview.

PROCEDURE TView.RemoveSubView (theSubView: TView);

This method removes a subview from a view's list of subviews and sets the SubView's fSuperView field to NIL. If the SubView's fNextHandler is the superview then it is set to NIL.

PROCEDURE TView.EachSubView (PROCEDURE DoToSubView (aSubView: TView));

This method calls the procedure DoToSubView for each subview, in order of their occurrence in fSubViews. (Analogous to TList.Each.)

FUNCTION TView.FirstSubViewThat (FUNCTION TestSubView (theSubView: TView):
BOOLEAN): TView;

This method returns the first subview for which TestSubView returns true, or NIL if TestSubView never returns true. The subviews are tested in order of occurance in fSubViews, from first to last. (Analogous to TList.FirstThat.)

FUNCTION TView.LastSubViewThat (FUNCTION TestSubView (theSubView: TView): BOOLEAN): TView;

This method returns the last subview for which TestSubView returns true, or NIL if TestSubView never returns true. The subviews are tested in reverse order of occurrence in fSubViews, from last to first.

#### PROCEDURE TView.MakeFirstSubView (theSubView: TView);

This method makes the given subview the first subview in fSubViews, if it isn't already the first. For debugging purposes, a ProgramBreak is generated if the given subview is not in fSubViews. The purpose of this method is to allow ordering of overlapping views.

#### PROCEDURE TView.MakeLastSubView (theSubView: TView);

This method makes the given subview the last subview in fSubViews, if it isn't already the last. For debugging purposes, a ProgramBreak is generated if the given subview is not in fSubViews. The purpose of this method is to allow ordering of overlapping views.

#### FUNCTION TView.CountSubViews: INTEGER;

This method returns the number of subviews for a view. Using this method avoids depending on the implementation of the subview lists.

### FUNCTION TView.FindSubView (itsIdentifier: IDType): TView;

This method returns the view whose fIdentifier field is equal to itsIdentifier, and that is directly or indirectly a subview of SELF.

# **Open/Close/Activate Methods**

#### PROCEDURE TView.Open;

This method is called when the window containing this view is opened. It simply calls the Open method for each of its subviews. It is intended to be overridden by views that need special processing when they are opened, in which case the override should call INHERITED Open.

#### PROCEDURE TView.Close;

This method is called when the window containing this view is closed. It simply calls the Close method for each of its subviews. It is intended to be overridden by views that need special processing when they are closed, in which case the override should call INHERITED Close.

#### PROCEDURE TView.Activate (entering: BOOLEAN);

This method is called when the window containing this view is activated (entering is true) or deactivated (entering is false). It focuses the view, calls the view's DoHighlightSelection method to change the selection from inactive to active or vice versa, and sets fHLDesired to hlOn when activating or to hlDim when deactivating. Finally, the Activate method is called for each subview. This method is overridden by views that require special processing when their windows are activated or deactivated, in which case the override normally calls INHERITED Activate.

PROCEDURE TView.ShowReverted;

This method is called when a document containing this view is reverted. It calls the view's AdjustSize and ForceRedraw methods. It is overridden by views that need to take more action when a document is reverted, in which case the override normally calls INHERITED ShowReverted.

#### PROCEDURE TView.BeInPort (itsPort: GrafPtr);

This method is called when the view is placed into, or removed from a grafport. itsPort is either the grafport the view is being placed in (as a result of adding it as a subview of another view), or NIL if the

view is being removed from a grafport. BeInPort simply calls BeInPort for each of its subviews. This method is intended to be overridden by views that must be notified when they are in a port, in which case the override should call INHERITED BeInPort. (The reason a view may require this notification is that it may not be in a port when it is initialized.)

PROCEDURE TView.BeInScroller (itsScroller: TScroller);

This method is called when the view becomes a subview of a scroller, or when a view is no longer a subview of a scroller (itsScroller is NIL). If itsScroller is not NIL then the scroller's SetScrollLimits method is called, passing the view's fSize as the scroll limits. You may need to override this if you have a scroller containing more than one view and you don't want the scroller's scroll limits to be set by each view.

# **Size Management Methods**

This section describes the methods related to setting or changing a view's size. In many cases the size of a view is dictated by the data it represents. For example, the size of a text-editing view depends on the amount of text it displays. In such a case the size determiners of the view are usually sizeVariable, and the CalcMinSize method is overridden to compute the view's current size. On the other hand, many views are not dependent upon the data they display, and in those cases overridding CalcMinSize is not required. An example is a scroller whose size is usually sizeFixed or sizeRelSuperView, both of which are handled by MacApp.

For views that vary in size, you must notify the view when its size *may* have changed. This is done by calling the view's AdjustSize method. This in turn calls ComputeSize, which calls CalcMinSize to find out what the view's size should be. If that is different from the view's current size, then AdjustSize calls Resize to set the new size. Thus, for views whose size varies, the key to using these methods is to override CalcMinSize and to call AdjustSize whenever some action takes place that may change the view's size. (In the case of a text editing view, AdjustSize would have to be called after every keystroke, for example.)

PROCEDURE TView.Resize (width, height: VCoordinate; invalidate: BOOLEAN);

This method sets the view's size to width and height, only if the new size is different than the current size. If invalidate is true, then the difference between the view's old and new size is invalidated. (This strategy will not work for a view that needs to be entirely redrawn when its size changes. In this case you should override Resize to call ForceRedraw to invalidate the old size, call INHERITED Resize with invalidate false, then call ForceRedraw to invalidate the new size. Or you can override Resize completely.) If the view has a superview, the superview's SubViewChangeSize method is called. Similarly, the SuperViewChangeSize method is called for each subview. Typically, you don't call Resize directly. Instead, you call AdjustSize. (If you do call Resize directly, be aware that it may change the focused view.)

### PROCEDURE TView.AdjustSize;

You call this method whenever a change is made that may affect the size of the view, typically when the data represented by the view changes. AdjustSize calls ComputeSize to find out what the view's size should be. If this is different from the view's current size, then Resize is called with the invalidate parameter set to true; and if the view has a print handler, then the view's DoPaginiation method is called. Note that AdjustSize may change the focused view.

PROCEDURE TView.ComputeSize (VAR newSize: VPoint);

This method computes the view's size by calling its CalcMinSize method and then applying the view's<br/>size determiners and returning that size in newSize. The action taken is determined by the view's size<br/>determiners:sizePageThe new size is set to the page size.sizeFillPagesThe view's "minimum" is computed by calling CalcMinSize, and then

sizeFillPages	The view's "minimum" is computed by calling CalcMinSize, and then
-	rounded up to fill the last page.
sizeVariable	The new size is the same as that returned by CalcMinSize.
sizeFixed	The new size is the same as the view's existing size.
sizeSuperView	The new size is set to the superview's size.
sizeRelSuperView	The new size is the same as that passed to ComputeSize in the newSize parameter

ComputeSize is called from AdjustSize and SuperViewChangedSize. It is rarely overridden.

PROCEDURE TView.CalcMinSize (VAR minSize: VPoint);

This method returns in minSize the view's minimum size. This method is frequently overridden to compute the view's size. Unless overridden, the view's current size is returned. CalcMinSize is called from ComputeSize.

PROCEDURE TView.SuperViewChangedSize (delta: VPoint; invalidate: BOOLEAN);

This method informs a view that its superview has changed size, where delta is the amount of change. If either the horizontal or vertical size determiner of the view is sizeSuperView or sizeRelSuperView, then the view's size is adjusted accordingly by calling ComputeSize and Resize. This method may be overridden to enhance or change this behavior. The invalidate parameter indicates whether the view should be invalidated (and redrawn) if it needs resizing. Because this method is called whenever the view's superview is resized, you don't ordinarily call it directly.

PROCEDURE TView.SubViewChangedSize (theSubView: TView; delta: VPoint);

This method informs a view that one of its subviews has changed size, where delta is the amount of change. It does nothing, but may be overridden by views that need to take action when a subview changes size. Because this method is called whenever one of the view's subviews is resized, you don't ordinarily call this directly.

PROCEDURE TView.GetExtent (VAR itsExtent: VRect);

This method returns the view's current extent, which is a rectangle defining the view's coordinate system. The top-left is (0, 0) and the bottom-right is the view's size. This method is rarely overridden.

PROCEDURE TView.GetQDExtent (VAR qdExtent: Rect);

This method returns the view's extent, converted to QuickDraw coordinates. For views whose extent is larger than kMaxCoord (30,000) the rectangle returned will be smaller than the view's actual extent. This method is simply for convenience so that you don't have to call GetExtent and ViewToQDRect everytime you want to get a view's extent and convert it to QuickDraw coordinates. This method assumes that the view is focused.

# **Location Management Methods**

PROCEDURE TView.Locate (h, v: VCoordinate; invalidate: BOOLEAN);

This method changes the location of a view within its superview, where h and v are the view's new horizontal and vertical location expressed in the superview's coordinate system. If invalidate is true, then the view is invalidated in both its old and new locations. The superview's SubViewMoved method is called. Similarly, SuperViewMoved is called for each of the view's subviews. If invalidate is true, then the view is invalidated in both its old and new positions.

PROCEDURE TView.SuperViewMoved (invalidate: BOOLEAN);

This method informs a view that its superview has moved. It does nothing, but it may be overridden for views that need to take action when their superview moves. invalidate indicates whether the view should be invalidated if it moves. Because this method is called whenever the view's superview moves, you don't ordinarily call this directly.

PROCEDURE TView.SubViewMoved (theSubView: TView);

This method informs a view that one of its subviews has moved. It does nothing, but it may be overridden by views that need to take action when a subview changes size. Because this method is called whenever one of the view's subviews move, you don't ordinarily call this directly.

PROCEDURE TView.GetFrame (VAR itsFrame: VRect);

This method returns the view's frame, which is a rectangle defining the view's coordinate system *in* superview coordinates. The top-left is the view's location and the bottom-right is the view's size added to its location.

### **Focusing Methods**

#### FUNCTION TView.Focus: BOOLEAN;

This method establishes the drawing environment for the view. A view must be focused before any graphical operations can be performed it. Because the location of a view is relative to its superview, the method FocusOnSuperView is called to establish the superview's drawing environment. Then the current grafport's origin and clipping is set so that drawing can be done in the view's coordinate system. If it is not possible to focus the view (e.g. because its fShown flag is false or it isn't visible in its grafport), then Focus returns false and the current port's clipping region is set to an empty rectangle. The algorithm for focusing is complicated by the fact that views may have a larger coordinate space than QuickDraw, and this method takes that into account when setting the port's origin. Focus is rarely overridden.

#### FUNCTION TView.FocusOnSuperView: BOOLEAN;

This method focuses on the view's superview by calling the superview's Focus method and returning its result. If there is no superview, this method returns false.

PROCEDURE TView.ClipFurtherTo (r: Rect; hDeltaOrg, vDeltaOrg: INTEGER);

This is an internal utility method that sets the window clipping region when a view is being focused.

# **Drawing Methods**

#### PROCEDURE TView.DrawContents;

This method implements MacApp's drawing algorithm. If the view can be focused, and if any part of the view is visible, then 1) the view's Draw method is called; 2) if the application is not printing (gPrinting is false) and not writing to the desk scrap (gDrawingPictScrap is false) then the view's DoHighlightSelection and DoDrawPrintFeedback methods are called; and 3) DrawContents is called for each subview. Though it is rarely done, this method can be overridden to change the drawing algorithm.

#### PROCEDURE TView.Draw (area: Rect);

This method draws the view itself. It is nearly always overridden; otherwise the view is considered transparent. The parameter area indicates what part of the view needs to be drawn, in QuickDraw coordinates. If the view is larger than kMaxCoord (30,000) pixels then the method QDToViewRect can be used to convert area into view coordinates.

#### PROCEDURE TView.DoHighlightSelection (fromHL, toHL: HLState);

This method is intended to be overridden to highlight the view's selection, if any. It does nothing unless overridden. fromHL and toHL can be one of hlOff, hlDim, or hlOn. Your DoHighlightSelection method should be prepared to handle any plausable combination of these states. The common combinations are:

fromHL, toHL:

hlOff, hlOn:	The selection is being turned on while the view is active.
hlOn, hlOff:	The selection is being turned off while the view is active.
hlOn, hlDim:	The view's window has been made inactive so the highlighting should be changed to inactive highlighting. If this view doesn't support dim (inactive) highlighting then it can treate hlDim as hlOff.
hlDim, hlOn:	The view's window has been made active so the highlighting should bemade active. If this view doesn't support dim (inactive) highlighting then it can treate hlDim as hlOff.
hlDim, hlOff: hlOff, hlDim:	The selection is being turned off while the view is inactive. The selection is being turned on while the view is inactive.

#### PROCEDURE TView.Update;

This method redraws invalidated portions of a view (and its subviews) by calling the DrawContents method sandwiched between the Window Manager routines BeginUpdate and EndUpdate. This method is called for a window when responding to an update event. You can call this method yourself if you are careful: you should be aware that this method clears all pending updates in a window regardless of whether the invalid areas of the window are drawn or not. Therefore, only use this method when you know the portion of the window to be updated is completely contained in the view in which it is being called.

© 1988 Apple Computer

This method adorns the view according to the given parameters. Adornment essentially consists of drawing a frame around a rectangle. area is the rectangle around which the frame is drawn. itsPenSize is the size of the pen used to draw the adornment. itsAdornment indicates the type of adornment to be drawn.

### **Display Validation/Invalidation Methods**

PROCEDURE TView.InvalidVRect (viewRect: VRect);

This method invalidates the given rectangle in view coordinates.

PROCEDURE TView.ValidateVRect (viewRect: VRect);

This method validates the given rectangle in view coordinates.

PROCEDURE TView.InvalidRect (r: Rect);

This method invalidates the given rectangle in QuickDraw coordinates.

PROCEDURE TView.ValidateRect (r: Rect);

This method validates the given rectangle in QuickDraw coordinates.

#### PROCEDURE TView.ForceRedraw;

This method invalidates the entire view by calling InvalidVRect(the view's extent).

PROCEDURE TView.RevealRect (rectToReveal: VRect; minToSee: Point; isVisible: BOOLEAN);

This method is intended to ensure that a specific part of the view's extent is visible. (It may be invisible because the view is clipped to its superview's margins.) rectToReveal is the rectangle to be made visible, in view coordinates. minToSee is the minimum amount of the rectangle to be made visible. TView.RevealRect calls its superview's RevealRect. As you will see later, if the superview is a scroller, then it scrolls the given rectangle into view. If isVisible is false, then the scroll is not immediately made visible. You should set isVisible to false only in situations in which you know the view will be redrawn and you want to avoid extraneous drawing.

PROCEDURE TView.RevealTop (isVisible: BOOLEAN);

This method attempts to reveal the top-left corner of the view's extent by calling RevealRect with a rectangle of (0, 0)/(0, 0). If isVisible is false, then the scroll is not immediately made visible. You should set isVisible to false only in situations in which you know the view will be redrawn and you want to avoid extraneous drawing.

PROCEDURE TView.RevealBottom (isVisible: BOOLEAN);

This method attempts to reveal the bottom-right corner of the view's extent. If isVisible is false, then

Wed, Aug 3, 1988

the scroll is not immediately made visible. You should set isVisible to false only in situations in which you know the view will be redrawn and you want to avoid extraneous drawing.

# **Mouse-Handling Methods**

FUNCTION TView.ContainsMouse (theMouse: VPoint): BOOLEAN;

This method returns true if the view is shown and the given point in view coordinates intersects the view's extent. However, this method can be overridden for views that respond to mouse clicks only in *part* of the extent, rather than *anywhere* in the extent. For example, if a view is circular, then it could override ContainsMouse to return true when the point lies within the circle, rather than within its rectangular extent.

```
FUNCTION TView.HandleMouseDown ( theMouse: VPoint; VAR info: PEventInfo; VAR hysteresis: Point; VAR theCommand: TCommand): BOOLEAN;
```

This method implements MacApp's mouse-handling logic. It returns true if this view or one of its subviews handles the mouse click. The logic is such that each of the subviews is given the opportunity to handle the click first. If no subview handles the click, then the view itself may handle it and return true. The following pseudo-code shows how this works:

```
FUNCTION TestMouse (theSubView: TNewView): BOOLEAN;
BEGIN
{Convert theMouse to view's QuickDraw coords};
TestMouse := theSubView.HandleMouseDown(theMouse, info,
hysteresis, theCommand);
```

END;

```
BEGIN
HandleMouseDown := FALSE;
theCommand := gNoChanges;
IF ContainsMouse(theMouse) THEN
BEGIN
viewThatHandledMouse := LastSubViewThat(TestMouse);
IF viewThatHandledMouse = NIL THEN
theCommand := DoMouseCommand(theMouse);
HandleMouseDown := TRUE;
END;
END;
```

Wed, Aug 3, 1988

FUNCTION TView.DoMouseCommand (VAR theMouse: Point; VAR info: EventInfo; VAR hysteresis: Point): TCommand;

Once HandleMouseDown has determined which view should handle the mouse click, it calls the view's DoMouseCommand method. DoMouseCommand simply returns gNoChanges, so it must be overridden by views that respond to mouse clicks. Note that theMouse is in QuickDraw coordinates. info is the EventInfo record for the mouse-down event.

Mouse clicks are handled in one of two ways. For clicks that do not require tracking and are not undoable, DoMouseCommand takes the appropriate action and returns gNoChanges. For clicks that require tracking or *are* undoable, DoMouseCommand should create a command object and return the command as its result. In this case, hysteresis can be set to the number of pixels the mouse must move before tracking begins.

## **Cursor Handling Methods**

FUNCTION TView.HandleCursor (theMouse: VPoint; cursorRgn: RgnHandle): TView;

This method implements the algorithm used to determine which view sets the cursor and the cursor region. It simply finds the most deeply nested, enabled subview that contains the mouse and calls its DoSetCursor method. If DoSetCursor returns false, then the DoSetCursor method for the view's superview is called, and so on, until DoSetCursor returns true. You can override HandleCursor for a view that needs to force the cursor to a given shape regardless of its subviews.

FUNCTION TView.DoSetCursor (localPoint: Point; cursorRgn: RgnHandle): BOOLEAN;

This method is used to set the cursor shape. localPoint is the cursor's current location in QuickDraw coordinates. To set the cursor, call the Toolbox routine SetCursor (or SetCCursor for a color cursor), return true, and optionally set cursorRgn to a region in which the cursor shape will remain the same. If this view does not set the cursor, then DoSetCursor should return false, in which case the view's superview will be given a chance to set the cursor. Upon entry, cursorRgn is set to an empty region.

## **Clipboard-Handling Methods**

```
FUNCTION TView.ContainsClipType (aType: ResType): BOOLEAN;
```

This method is used to determine whether a view installed in the Clipboard represents a particular kind of data. It simply returns true if the desk scrap contains data of the given type by calling the Scrap Manager routine GetScrap. This method is intended to be overridden by views that can be installed in the Clipboard and may maintain a local version of the Clipboard data rather than installing it in the desk scrap.

```
FUNCTION TView.GivePasteData (aDataHandle: Handle; dataType: ResType):
LONGINT;
```

This method returns a handle to data that is represented by a view installed in the Clipboard. dataType indicates the type of data to be returned, and aDataHandle is a handle in which to store the data. Note that aDataHandle is either NIL, in which case GivePasteData simply returns the size of the data, or is already allocated. GivePasteData returns the length of the data in the handle, or a negative value indicating an error. TView.GivePasteData returns the data by calling the Scrap Manager routine

GetScrap, but it may be overridden by views that can be installed in the Clipboard and may maintain a local version of the Clipboard data rather than installing it in the desk scrap.

#### PROCEDURE TView.WriteToDeskScrap;

This method is called on a view installed in the Clipboard, when the application is losing control to a desk accessory or another application. Its purpose is to write the contents of the Clipboard to the desk scrap for Clipboard views that maintain their data locally. TView.WriteToDeskScrap simply creates a QuickDraw picture of the clipboard view and writes the picture to the desk scrap. This method is intended to be overridden by views that can be installed in the Clipboard and that write data other than pictures to the desk scrap.

### **Printing Methods**

The view printing methods are described in the MacApp 2.0b5 Printing Release Notes.

# **Miscellaneous Methods**

#### FUNCTION TView.GetGrafPort: GrafPtr;

This method returns a pointer to the grafport in which the view is contained, or NIL if the view is not in a grafport.

FUNCTION TView.GetWindow: TWindow;

This method returns a reference to the window object in which this view is contained, or NIL if the view is not in a window.

FUNCTION TView.GetScroller (immediateSuperView: BOOLEAN): TScroller;

This method returns a reference to the scroller object in which the view is contained, or NIL if the view is not in a scroller. If immediateSuperView is true and the scroller is not the view's immediate superview then GetScroller returns NIL.

#### FUNCTION TView.GetDialogView: TView;

This method returns a reference to the dialog view object in which the view is contained, or NIL if the view is not in a dialog view. Note that the function result is of type TView, so you must cast the result in order to use it as a dialog view (for example, aDialogView := TDialogView (GetDialogView)). The reason for this is that the dialog views are not defined in the main MacApp unit.

#### PROCEDURE TView.GetVisibleRect (VAR visQDRect: Rect);

This method returns the part of the view's extent that is visible within its superview. This may not be the entire extent since views are clipped to their superview's margins. The rectangle returned is in QuickDraw coordinates. It can be converted to view coordinates with the QDToViewRect method.

```
PROCEDURE TView.DoChoice (origView: TView; itsChoice: INTEGER);
```

The purpose of calling DoChoice is to propogate information up the view hierarchy. Consider the case of clicking on a radio button. The radio button itself may take some action, such as toggling its value. But the radio button may be contained in a view that is responsible for ensuring that other related radio buttons are turned off. If the radio button calls DoChoice, its superview can take additional action above and beyond that taken by the radio button itself.

PROCEDURE TView.ViewEnable (state: BOOLEAN; redraw: BOOLEAN);

This method enables (state is true) or disables (state is false) the view's ability to handle mouse clicks by setting its fViewEnable flag to the value of state. If redraw is true, then the view is redrawn by calling its ForceRedraw method.

FUNCTION TView.IsViewEnabled: BOOLEAN;

This method returns true if the view is able to handle mouse clicks, or false if the view is unable to handle mouse clicks.

PROCEDURE TView.Show (state, redraw: BOOLEAN);

This method shows the view (state is true) or hides the view (state is false) and sets the view's fShown flag to state. It is analagous to the Window Manager routine ShowHide. If the redraw parameter is true then the view is redrawn to reflect its new state.

#### FUNCTION TView.IsShown: BOOLEAN;

This method returns true if the view is shown, and false if it is hidden. Note that the issue of whether a view is hidden or shown is different from whether the view is invisible or visible. The view may be shown but still not be visible, because it is clipped from view by its superview.

### **Resource Writing Methods**

PROCEDURE TView.WRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr);

This method writes the TView portion of the view's resource template. It is the inverse of TView. IRes and is only used by programs that write 'view' resources.

PROCEDURE TView.WriteRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr);

This method serves as a wrapper for WRes. If you want to write a view object as part of a 'view' resource, then you would call this method, which calls the appropriate WRes methods.

# **Creation/Destruction Methods**

This method initializes a view by calling IEvtHandler (itsSuperView), setting its document, superview, location, size, and size determiners, setting fHLDesired to hlDim, and adding the view to its superview by calling its superview's AddSubView method.

```
PROCEDURE TView.IRes (itsDocument: TDocument; itsSuperView: TView;
VAR itsParams: Ptr);
```

This method initializes a view from a resource. itsDocument is the view's document, itsSuperView is the view's superview, itsParams is a pointer to the TView section of a view's resource. IRes initilizes the view and offsets itsParams by the length of the TView parameters.

PROCEDURE TView.Free; OVERRIDE;

This method frees its subviews, removes itself from its superview (by calling fSuperView.RemoveSubView), and calls INHERITED Free to free itself. It also frees the view's print handler if it has one.

```
PROCEDURE TView.FreeFromClipboard;
```

Called when a view installed in the Clipboard is freed. If the view's document is not NIL then the document's FreeFromClipboard method is called (which will free the view). Otherwise the view's Free method is called.

# The TScroller Class

The TScroller class implements a transparent view that performs coordinate translation. By changing the translation values, the subviews of a scroller are "scrolled" through the scroller. For example, given a scroller whose size is 100 pixels in both directions, and a subview located at (0, 0), whose size is 1000 pixels, then a translation value of (300, 500) will display the part of the subview defined by the rectangle (300, 500)/(400, 600). A scroller may refer to a vertical and horizontal scroll bar, whose values and are kept in sync with the scroller's translation values. Furthermore, it is possible to scroll without scroll bars by calling the appropriate scroller methods to change the translation value.

Fi	elds	

fTranslation	The number of pixels by which all coordinates in the scroller are translated, in both the horizontal and vertical direction.
fScrollLimit	The maximum point that can be displayed in the scroller.
fMaxTranslation	The maximum values that fTranslation can take. This is computed by

subtracting the scroller's size from fScrollLimit.

fScrollBarsA reference to the horizontal and vertical scroll bars, or NIL if they don't exist.fScrollUnitThe amount of change to be made in the translation values when the scroller receives a<br/>"scroll-by-arrow" message, for both the horizontal and vertical directions.fConstrainIndicates whether the translation values should be constrained to even multiples of<br/>fScrollUnits in either the horizontal and vertical direction.fSBarOffsetsWhen a scroller is resized, this field is used to determine how to resize the associated<br/>scroll bars. fSBarOffsets.top and bottom are offsets indicating where the top<br/>and bottom of the vertical scroll bar is in relation to the top and bottom of the scroller.<br/>fSBarOffsets.left and right are offsets indicating where the left and right of<br/>the horizontal scroll bar is in relation to the left and right of the scroller.

# **Coordinate Conversion Methods**

PROCEDURE TScroller.LocalToSuper (VAR thePoint: VPoint); OVERRIDE;

This method converts the given point from local view coordinates to superview coordinates. It is overridden to take into account the scroller's coordinate translation.

PROCEDURE TScroller.SuperToLocal (VAR thePoint: VPoint); OVERRIDE;

This method converts the given point from superview coordinates to local view coordinates. It is overridden to take into account the scroller's coordinate translation.

### **Subview Management Methods**

PROCEDURE TScroller.AddSubView (theSubView: TView); OVERRIDE;

This method calls INHERITED AddSubView, and then notifies the subview that it's in a scroller by calling theSubView.BeInScroller(SELF).

PROCEDURE TScroller.RemoveSubView (theSubView: TView); OVERRIDE;

This method notifies the subview that it is no longer in a scroller by calling theSubView.BeInScroller (NIL), and then calls INHERITED RemoveSubView.

## Size/Location Management Methods

This method calls INHERITED Resize, and then calls AdjustScrollBars to resize and move the scroller's scroll bars. It can be overridden if you don't want automatic adjustment of the scroll bars when a scroller is resized.

PROCEDURE TScroller.Locate (h, v: VCoordinate; invalidate: BOOLEAN); OVERRIDE;

This method calls INHERITED Locate, and then calls AdjustScrollBars to move the scroller's scroll bars. It can be overridden if you don't want automatic adjustment of the scroll bars when a scroller is moved.

PROCEDURE TScroller.GetExtent (VAR itsExtent: VRect); OVERRIDE;

This method calls INHERITED GetExtent, and then offsets itsExtent by fTranslation. Thus, itsExtent is the scroller's extent translated by the translation values.

PROCEDURE TScroller.AdjustScrollBars;

This method is called when a scroller moves or changes size. It erases the scroll bars, and then moves and resizes them appropriately. This method can be overridden for scrollers whose scroll bars don't depend on this scroller's location or size.

This method is called to change the scroller's maximum translation values. This entails setting the fScrollLimit field to scrollLimit, recomputing the fMaxTranslation field, and setting the scroll bar maximums by calling each scroll bar's SetMaximum method. The drawScrollBars parameter is passed to SetMaximum to indicate whether the control should be immediately redrawn. Ordinarily this is true. Furthermore, if the new maximum translation is less than the current translation, then the scrollr's ScrollTo method is called to scroll to the maximum translation.

## **Focusing Methods**

#### FUNCTION TScroller.Focus: BOOLEAN;

This method calls INHERITED Focus and puts into effect the coordinate translation of fTranslation. Thus, the scroller's coordinates and those of its subviews are translated by this amount.

## **Low-Level Scrolling Methods**

These methods are rarely overridden, and even more rarely called from application code.

PROCEDURE TScroller.ScrollDraw (delta: VPoint);

This method carries out the graphic activity associated with a scroll, where delta is the number of pixels to scroll. The scroll is done by using QuickDraw's ScrollRect to scroll the contents of the scroller, and then simulating an update event to draw the vacated area. This is done by calling the Window Manager routine BeginUpdate, erasing the vacated area, calling the scroller's DrawContents method, and then calling the Window Manager's EndUpdate.

PROCEDURE TScroller.DoScroll (delta: VPoint; isVisible: BOOLEAN);

This method changes the scroller's translation by the delta amount. If isVisible is true, then ScrollDraw is called to carry out the scroll graphically. Furthermore, when isVisible is true DoScroll checks to see if there is a pending update event on the scroller's window. If so, the window is updated before changing the scroller's translation values.

## **Intermediate-Level Scrolling Routines**

These methods are usually called from scroll bar objects, though they may also be called from application code to simulate the behavior of scroll bars. These methods are occasionally overridden as described below.

FUNCTION TScroller.Scrollstep (vhs: VHSelect; partCode: INTEGER): VCoordinate;

This method is called by one of the scroller's scroll bars, when the user clicks in an arrow or page area of the scroll bar. It may be called in other contexts to effect the same action as clicking a scroll bar arrow or page area. whs indicates the scrolling direction (horizontal or vertical) and partCode indicates the part of the scroll bar that was clicked (inUpButton, inDownButton, inPageUp, or inPageDown).

This method determines how many pixels to scroll the view, calls DoScroll to carry out the scroll, and returns the change in the scroll bar's value. For inUpButton and inDownButton, the amount of scrolling is the same as the scroller's fScrollUnit[vhs] value. For inPageUp and inPageDown, the amount of scrolling is equal to the scroller's size in the vhs direction, constrained to a multiple of fScrollUnit [vhs] is true. This method may be overridden to change the scrolling behavior, or if the scroll bar units are not the same as the scroller's translation units.

```
FUNCTION TScroller.ScrollRelative (vhs: VHSelect; sBarValue: VCoordinate):
VCoordinate;
```

This method is called by a scroll bar object when its thumb is released. (It may also be called from other parts of the application in order to simulate thumb scrolling.) whs indicates the scrolling direction and sBarValue indicates the scroll bar's value when the thumb was released. This method determines the scroller's new translation values, calls DoScroll to carry out the scroll, and may return a nonzero value which is added to the scroll bar's value as described below.

The new translation value is set to sBarValue, unless fConstrain[vhs] is true, in which case the translation value is rounded to an even multiple of fScrollUnit[vhs], and the difference between this value and sBarValue is returned as ScrollRelative's result. This method may be overridden to change the scrolling behavior, or if the scroll bar units are not the same as the scroller's translation units.

# **High Level Scrolling Methods**

These methods are frequently called by application code. They are rarely overridden.

PROCEDURE TScroller.ScrollBy (deltaH, deltaV: VCoordinate; isVisble: BOOLEAN);

This method changes the scroller's translation and scroll bar values by deltaH and deltaV pixels. This is done by calling each scroll bar's DeltaValue method and then calling the scroller's DoScroll method. If isVisible is true then the contents of the scroller are redrawn to reflect the new translation. Passing false for isVisible is useful in situations where you wish to avoid screen flashing (that is, drawing the same view twice). This method must be overridden if the scroll bar units are not the same as the scroller's translation units.

PROCEDURE TScroller.ScrollTo (h, v: VCoordinate; isVisible: BOOLEAN);

This method sets the scroller's translation and scroll bar values to the horizontal and vertical values in h and v. This is done by calling each scroll bar's SetValue method and then calling the scroller's DoScroll method. If isVisible is true then the contents of the scroller are redrawn to reflect the new translation. Passing false for isVisible is useful in situations where you wish to avoid screen flashing (that is, drawing the same view twice).

```
PROCEDURE TScroller.RevealRect (rectToReveal: VRect; minToSee: Point;
isVisible: BOOLEAN); OVERRIDE;
```

This method ensures at least minToSee pixels of the given rectangle are visible in the scroller. This is done by calling ScrollBy if necessary to change the translation values such that the given rectangle is made visible. This method is typically used to ensure that a selection is visible (for example, making the caret visible in a text edit view when the user starts typing). If isVisible is false, then the scroll is not immediately made visible. You should set isVisible to false only in situations in which you know the view will be redrawn and you want to avoid extraneous drawing.

PROCEDURE TScroller.AutoScroll (viewPt: VPoint; VAR delta: VPoint);

This method is used to implement automatic scrolling when the mouse is being tracked and has strayed outside a scroller. viewPt is the location of the mouse in view coordinates. delta returns the number of pixels to scroll in the horziontal and vertical directions. It is computed by determining where viewPt is in relation to the scroller. If viewPt is "above" the scroller (that is, viewPt.v < extent.top), then delta.v is set such that the contents of the scroller are scrolled down. If viewPt is "below" the scroller, then delta.v is set such that the contents of the scroller are scrolled up. delta.h is set similarly. The number of pixels to scroll is determined by the scroller's fScrollUnit values. AutoScroll can be overridden to use a different method to determine the value of delta.

# **Miscellaneous Methods**

This method calls SetScrollLimits to set the scroller's fMaxTranslation and fScrollLimit to reflect the size of theSubView. This method should be overridden in cases where a scroller has subviews of varying size.

This method attaches a scroll bar to a scroller. It is called from the scroll bar's initialization method. You can also use it to detach a scroll bar by passing NIL in the ScrollBar.

PROCEDURE TScroller.SetScrollParameters (horzUnits, vertUnits: VCoordinate; horzConstraint, vertConstraint: BOOLEAN);

This method sets the scroller's fScrollUnits and fConstrain fields to the given parameters.

FUNCTION TScroller.GetScroller (immediateSuperView: BOOLEAN): TScroller; OVERRIDE;

This method returns SELF.

PROCEDURE TScroller.CreateScrollBars (wantHorzSBar, wantVertSBar: BOOLEAN);

This method is an internal utility that creates the scroll bars as indicated by the parameters. It is called from IScrollBar and IRes.

### **Resource-Writing Methods**

PROCEDURE TScroller.WRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method writes the TScroller portion of the view's resource template. It is the inverse of TScroller. IRes and is only used by programs that write 'view' resources.

This method serves as a wrapper for WRes. If you want to write a scroller object as part of a 'view' resource you would call this method, which calls the appropriate WRes methods.

# **Creation/Destruction Methods**

This method initializes a scroller object. it calls IView to set the scroller's superview, location, size, and size determiners. (The scroller's document is set to NIL.) It sets fTranslation and fMaxTranslation to (0, 0), creates the scroll bars if necessary, sets fSBarOffsets to (0, 0, 0, 0), sets the scroll units to kStdScrollUnit (16), sets fConstrain to false, and calls SetScrollLimits with itsHorzMax and itsVertMax.

```
PROCEDURE TScroller.IRes (itsDocument: TDocument; itsSuperView: TView;
VAR itsParams: Ptr);
```

This method initializes a scroller from a resource. itsDocument is ignored: the scroller's document is set to NIL. itsSuperView is the view's superview, while itsParams is a pointer to the TView section of a view's resource. IRes calls INHERITED IRes to initialize the inherited data (that of TView), initilizes the TScroller data, and offsets itsParams by the length of the TScroller parameters.

#### PROCEDURE TScroller.Free; OVERRIDE;

If the scroller has scroll bars, then the scroll bars are freed. Then INHERITED Free is called.

# **The TWindow Class**

The TWindow class implements windows. This section describes those fields and methods that are in addition to or that override TView.

# Fields

fWMgrWindow	The Window Manager window pointer.	
fIsActive	Indicates whether this window is active. This may differ from testing if fWMgrWindow = FrontWindow because of a pending activate event that hasn't been processed yet.	
fIsResizable	True if the window has a grow box.	
fIsClosable	If true, the Close menu item is enabled when this window is active. If the window has a close box then this field is initially set to true.	
fFreeOnClosing	If true, then this object is freed when the window is closed. The default setting is false.	
fDisposeOnFree	If true, then DisposeWindow (fWMgrWindow) is called when this window is freed.	
fClosesDocument	If true, then when this window is closed, it also calls fDocument.Close. The default setting is true.	

fOpenInitially	If true, then when the window's document is opened, this window is opened as well. The default setting is true.
fMoveBounds	A rectangle defining this window's move bounds. It is passed to the Window Manager routine DragWindow and is initially set to gStdWMoveBounds.
fResizeLimits	A rectangle defining the minimum and maximum size of the window. It is passed to the Window Manager routine GrowWindow and is initially set to gStdWSizeRect.
fTarget	The event handler, usually a view, that becomes the application's target (gTarget) when this window is active.
fPreDocname	Used to parse the window title into a constant part and a part replaced by the window's document name.
fConstTitle	Used to parse the window title into a constant part and a part replaced by the window's document name.
fIsModal	True indicates that the window is modal (that is, no other window can be activated while this one is active, although the menu bar is available). False indicates that the window is modeless.
fDoFirstClick	True indicates that the window responds to mouse clicks even when it isn't the front window. The default value is false.
fTargetId	The identifier of the view that will be the window's initial target when it is created from a resource template.
fAdapted	Set to true if the window is "adapted to the screen" by calling TWindow.AdaptToScreen.
fHorzCentered	Set to true if the window is horizontally centered by its Center method.
fVertCentered	Set to true if the window is vertically centered by its Center method.
fStaggered	Set to true if the window is staggered by its Stagger method.
fForcedOnScreen	Set to true if the window is "forced onto the screen" by its ForceOnScreen method.
fProcId	The proc ID of the Window Manager window that represents this window.

# **Open/Close/Activation Methods**

PROCEDURE TWindow.Activate (entering: BOOLEAN); OVERRIDE;

This method is called to activate (entering is true) or deactivate (entering is false) a window. First, if entering is different from the window's flsActive field, then the window's DrawContents (TRUE) method is called. Then INHERITED Activate is called to activate or deactivate the window's subviews. What happens next depends on the value of entering.

If entering is true, then gFrontWindow is set to SELF, the application's target is set to the window's fTarget, and gDocument is set to the window's fDocument.

If entering is false, then the window's fTarget is set to the application's current target, the

application's target is set to gApplication, gFrontWindow and gDocument are set to NIL, and the cursor is set to the arrow.

Finally, the window's grow box is redrawn and fIsActive is set to the value of entering. This method can be overridden for windows that require additional activation or deactivation logic, in which case you usually call INHERITED Activate.

#### PROCEDURE TWindow.Open; OVERRIDE;

This method calls the window's Resize method, resizing the window to its portRect, calls its Show (TRUE, kRedraw) method to show the window, and calls INHERITED Open to inform all of its subviews that they are now in an open window. This method can be overridden for windows that need extra processing when they're opened, in which case INHERITED Open is usually called.

#### PROCEDURE TWindow.Close; OVERRIDE;

This method calls its Show (FALSE, kRedraw) method to hide the window and then deactivates the window by calling its Activate (FALSE) method. Next it calls INHERITED Close to inform its subviews that their window is being closed. And finally it calls its Free method if ffreeOnClosing is true. This method can be overridden for windows that need extra processing when they're opened, in which case INHERITED Close is usually called.

#### PROCEDURE TWindow.CloseByUser;

This method is called when the user clicks the window's go-away box or chooses the Close menu command while this window is active. Before calling Close, CloseByUser determines whether it should also close the window's document. It closes the document if the window's fClosesDocument field is true, or if this is the document's only window.

## **Size Management Methods**

This method calls the Toolbox routine SizeWindow to change the window size, invalidates the old and new positions of the window's grow box, and then calls INHERITED Resize.

PROCEDURE TWindow.ResizeByUser (globalMouse: Point);

This method calls the Window Manager routine GrowWindow and, if the result is non-zero calls Resize to resize the window.

#### PROCEDURE TWindow.Zoom (partCode: INTEGER);

This method zooms a window from it existing size to fill the screen, or from screen size back to its previous size. partCode is either inZoomIn or inZoomOut, indicating which way to zoom. The window is zoomed by focusing itself and erasing its portRect, calling the Window Manager routine ZoomWindow, and then calling its Resize method to set the window's size.

## **Location Management Methods**

PROCEDURE TWindow.MoveByUser (globalMouse: Point);

This method calls the Window Manager routine DragWindow. MacApp calls this method when the user clicks in the window's title bar.

PROCEDURE TWindow.Locate (h, v: VCoordinate; invalidate: BOOLEAN); OVERRIDE;

This method moves the window to the horizontal and vertical global coordinates specified by h and v, by calling the Window Manager routine MoveWindow.

### **Focusing Methods**

FUNCTION TWindow.Focus: BOOLEAN; OVERRIDE;

If the window's fWMgrWindow is not NIL, this method focuses the window by setting the port to the window's port, setting the port's origin to (0, 0), setting gLongOffset to (0, 0), and setting the port's clipping region to the entire portRect. It returns true if the window could be focused and the window is visible. Returns false if the window's fWMgrWindow is NIL or the window is invisible.

FUNCTION TWindow.FocusOnSuperView: BOOLEAN; OVERRIDE;

This method simply calls Focus.

### **Drawing Methods**

PROCEDURE TWindow.DrawContents; OVERRIDE;

This method calls INHERITED DrawContents and then draws the grow box (if the window has one) by calling DrawResizeIcon.

PROCEDURE TWindow.Draw (area: Rect); OVERRIDE;

This method calls the QuickDraw routine EraseRect on the window's portRect.

PROCEDURE TWindow.DrawResizeIcon;

This method draws the window's grow box.

## **Mouse-Handling Methods**

FUNCTION TWindow.HandleMouseDown (theMouse: VPoint; VAR info: EventInfo; VAR hysteresis: Point; VAR theCommand: TCommand): BOOLEAN; OVERRIDE;

If the window is currently the front window, then INHERITED HandleMouseDown is called. Otherwise the window is brought to the front by calling its Select method and if fDoFirstClick is true, the window is updated and INHERITED HandleMouseDown is called.

# **Menu Handling Methods**

```
FUNCTION TWindow.AllowsMenuAcces: BOOLEAN;
```

Indicates whether the menus are accessable when this window is the front window. The standard behavior is to always return true, regardless of whether the window is modal or modeless.

PROCEDURE TWindow.DoSetupMenus; OVERRIDE;

Calls INHERITED DoSetupMenus only if the window is not modal (i.e. flsModal is false). For modal windows this prevents enabling menus whose scope is beyond that of the window itself.

# **Miscellaneous Methods**

```
FUNCTION TWindow.GetGrafPort: GrafPtr; OVERRIDE;
```

This method returns the window's fWMgrWindow field.

FUNCTION TWindow.GetWindow: TWindow; OVERRIDE;

This method returns a reference to itself.

FUNCTION TWindow.IsShown: BOOLEAN; OVERRIDE;

This method returns true if the window is currently shown on the screen. This is determined by checking the fWMgrWindow<sup>^</sup>.visible flag.

PROCEDURE TWindow.Show (state, redraw: BOOLEAN); OVERRIDE;

This method shows (or hides if state is false) the window on the screen by calling the Window Manager routine ShowWindow (or HideWindow) and sets the window's fShown flag to state. The redraw parameter is ignored.

PROCEDURE TWindow.GetGlobalBounds (VAR globalBounds: Rect);

This method returns the window's bounding rectangle in global coordinates.

PROCEDURE TWindow.SetTarget (newTarget: TEvtHandler);

This method sets the event handler object that is to be the target when this window is activated by setting the window's fTarget field to newTarget. Furthermore, if the window is already the front window, then the application's SetTarget method is called to make newTarget the application's target.

PROCEDURE TWindow.SetTitleForDoc (newDocTitle: Str255);

This method sets the window's title to reflect the name of its document.

PROCEDURE TWindow.SimpleStagger (dh, dv: INTEGER; VAR counter: INTEGER);

This method is used to produce a "stagger effect" when creating windows. It basically offsets the location of the window by dh and dv pixels multiplied by counter.

PROCEDURE TWindow.Center (horizontally, vertically: BOOLEAN);

This method horizontally and/or vertically centers the window on the main screen.

#### PROCEDURE TWindow.AdaptToScreen;

This method adjusts the size of the window to the primary screen of the computer on which the application is being run. This is done by adding to the window size the difference between the primary screen and the standard screen size (512x342 pixels). This method is intended to be called before the window is opened, so it does not change the window's fSize field. Rather, it calls the Toolbox routine SizeWindow and adjusts fSize during Open.

PROCEDURE TWindow.ForceOnScreen;

This method ensures that at least some part of the window is visible on the primary screen. This is useful for applications that save window locations and attempt to reopen windows in the last saved location. Problems can occur when the application is run on a system with a large screen, and then run on a system with a small screen. In such cases, it is possible for a window to be visible on the large screen, but not visible on the small screen. ForceOnScreen prevents this problem. This method is intended to be called before the window is opened, so it does not change the window's fSize field. Rather, it calls the Toolbox routine SizeWindow and adjusts fSize during Open.

PROCEDURE TWindow.SetResizeLimits (minSize, maxSize: Point);

This methods sets the minimum and maximum sizes for the window so that the user cannot grow the window larger than maxSize nor shrink it smaller than minSize. maxSize also determines what the window's size will be if it is zoomed.

#### PROCEDURE TWindow.Select;

This method selects this window (brings it to the front) by calling the application's SelectWMgrWindow method.

PROCEDURE TWindow.InstallDocument (itsDocument: TDocument);

Associates the given document with the window. This is called from IWindow and IRes. If itsDocument is not nil then the window is added to the document's window list. Otherwise the window is added to the application's free window list.

### **Resource-Writing Methods**

PROCEDURE TWindow.WRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method writes the TWindow portion of the view's resource template. It is the inverse of TWindow. IRes and is only used by programs that write 'view' resources.

PROCEDURE TWindow.WriteRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method serves as a wrapper for WRes. If you want to write a window object as part of a 'view' resource you would call this method, which calls the appropriate WRes methods.

# **Creation/Destruction**

This method calls IView, sets its fields to their default values, and either adds the window to its document's window list, or adds the window to the application's free window list if itsDocument is NIL. Note that the window's fSize is set to (0, 0): TWindow.Open resizes the window to the size of its fWMgrWindow^.portrect.

PROCEDURE TWindow.IRes (itsDocument: TDocument; itsSuperView: TView; VAR itsParams: Ptr);

This method initializes a window from a resource. itsDocument is the window's document. itsSuperView should be NIL, and itsParams is a pointer to the TView section of a view's resource. INHERITED IRes is called to initialize the inherited data (in this case the TView data), then the TWindow data is initialized, and finally itsParams is offset by the length of the TWindow data.

#### PROCEDURE TWindow.Free; OVERRIDE;

This method removes the window from either its document's window list, or the application's free window list (if fDocument is NIL), then calls INHERITED Free and calls the global routine FreeWMgrWindow.

# **The TControl Class**

The TControl class represents the MacApp notion of a control. MacApp controls include Control Manager controls (i.e. radio buttons, push buttons, check boxes, and scroll bars) as well as non-Control Manager controls (either of your own creation or as defined in the UDialog unit.).

Controls have the following properties:

. .

- They are limited to QuickDraw's coordinate space.
- The can be tracked with the mouse without you having to create a command object. TControl methods can be overridden to implement behavior while tracking the mouse rather than implementing the behavior in a separate command object.
- They can be adorned with one of a set of standard adornments, such as a rectangular frame.
- They have a text style used to draw the control's label if it has one.
- They have insets or margins in which mouse clicks are ignored.

This section describes those fields and methods that are in addition to or that override TView.

Fields	
fDefChoice	The code that is passed to DoChoice. The default value is the constant mOKHit.
fInset	Used to define which part of the view is considered to be the active control area. The active control area is determined by insetting the view's extent by flnset. Generally, controls respond to mouse clicks only in the active area, and adornments are drawn in the inactive area. The default inset is $(0, 0, 0, 0)$ .
fHilite	Whether the control is highlighted or not. The default setting is false.
fDimmed	Whether the control is dimmed or not. The default setting is false.
fSizeable	False indicates that the active control area is of a fixed size, regardless of whether the view's size changes. (In this case, changing the view size simply changes the bottom and right insets from the view's size to the control's size.) True indicates that the active control area changes in proportion to the view's size. The default setting is true.
fDismissesDialog	Whether clicking on this control dismisses a dialog. The default setting is false.
fAdornment	The type of adornment for this control. The default setting is no adornment.
fPenSize	The pen size used to draw the control's adornment. The default setting is $(1, 1)$ .
fTextStyle	The font style used to draw the control's label, if any. The default setting is the system style.

# **Open/Close/Activate Methods**

PROCEDURE TControl.Activate (entering: BOOLEAN); OVERRIDE;

This method is overridden to do nothing since controls have no subviews.

# **Size Management Methods**

PROCEDURE TControl.ComputeSize (VAR newSize: VPoint); OVERRIDE;

This method is overridden to adjust the control insets appropriately.

Overridden to force the entire view to be redrawn if invalidate is true.

## **Drawing Methods**

PROCEDURE TControl.Draw (area: Rect); OVERRIDE;

This method draws the control's adornment, calls its Dim method the control if fDimmed is true, and calls its Hilite method if fHilite is true.

### **Focusing Methods**

FUNCTION TControl.Focus: BOOLEAN; OVERRIDE;

This method is overridden to set the current port's text style when the control is focused.

## **Mouse-Handling Methods**

FUNCTION TControl.ContainsMouse (theMouse: VPoint): BOOLEAN; OVERRIDE;

This method is overridden to return true only if the Mouse is in the control's active area (that is, the view's extent is inset by fInsets).

FUNCTION TControl.DoMouseCommand (VAR theMouse: Point; VAR info: EventInfo; VAR hysteresis: Point): TCommand); OVERRIDE;

This method tracks the control using a TControlTracker object. It in turn calls the TControl methods TrackConstrain, TrackFeedback, and TrackMouse. Returns the tracker object.

The following methods are used to implement custom-control mouse tracking.

PROCEDURE TControl.TrackConstrain (anchorPoint, previousPoint: VPoint; VAR nextPoint: VPoint);

As with TCommand.TrackConstrain, overriding this method allows a control to constrain the mouse while it is being tracked. anchorPoint is the location of the mouse when it was clicked in the control. previousPoint is the location of the mouse when it was last tracked. nextPoint is the current location of the mouse. Constraint of the mouse is accomplished by changing nextPoint appropriately. The standard behavior of TrackConstrain is to not constrain the mouse.

PROCEDURE TControl.TrackFeedback (anchorPoint, nextPoint: VPoint; turnItOn, mouseDidMove: BOOLEAN);

This method may be overridden to provide mouse-tracking feedback. This method is called twice for every call to TrackConstrain and TrackMouse. The first time it is called with turnItOn false, the second time with turnItOn true. This technique makes it easy to implement feedback such as a drawing the outline of a box from the anchor point to the current mouse location. (Note that not all feedback is done this way. For example, tracking a push button calls for highlighting the button when the mouse enters the button, and unhighlighting the button when the mouse leaves it. Sometimes it is more convenient to implement feedback in the TrackMouse method.) The standard behavior of this method is to provide no feedback.

This method is intended to be overridden to carry out any mouse-tracking activity required by the control, other than that implemented in TrackConstrain and TrackFeedback. aTrackPhase has one of three values: TrackPress, which indicates that mouse tracking has just begun; TrackMove, which indiates that mouse tracking is in progress; and TrackRelease, which indicates that the mouse button has been released. anchorPoint is the location of the mouse when it was clicked. previousPoint is the location of the mouse the last time TrackMouse was called. nextPoint is the current location of the mouse. mouseDidMove is true if the mouse has moved since the last time TrackMouse was called. The standard behavior of TrackMouse is to do nothing. Therefore you must override this method to implement mouse tracking behavior specific to this control.

#### **Dimming Methods**

PROCEDURE TControl.DimState (state, redraw: BOOLEAN);

This method dims (state is true) or undims (state is false) the control. It sets fDimmed to state and, if redraw is true the control is redrawn.

PROCEDURE TControl.Dim;

This method draws the control's dim effect by painting a gray pattern over the control. It is called only when the control is dimmed. This method can be overridden to change the way the dim effect is drawn for a control.

FUNCTION TControl. IsDimmed: BOOLEAN;

This method returns true if the control is currently dimmed; otherwise it returns false.

### **Highlighting Methods**

PROCEDURE TControl.HiliteState (state, redraw: BOOLEAN);

This method highlights (state is true) or unhighlights (state is false) the control. It sets fHilite to state and, if redraw is true the control is focused and calls its Hilite method is called.

Wed, Aug 3, 1988

© 1988 Apple Computer

37

#### PROCEDURE TControl.Hilite;

This method draws the control's highlighting effect. It is called from HiliteState to highlight or unhighlight the control, and from Draw when the control's fHilite is true. Since this method is responsible for both highlighting and unhighlighting it can examine the fHilite field to see whether it should highlight or unhighlight. The standard behavior is to simply invert the control, but you can override this method to change the way highlighting is drawn.

### **Miscellaneous Methods**

#### PROCEDURE TControl.ControlArea (VAR theArea: Rect);

This method returns the active control area of the view as a QuickDraw rectangle. This is computed by taking the view's extent and insetting it by fInset.

PROCEDURE TControl.InstallColor (theColor: RGBColor; redraw: BOOLEAN);

This method sets the color of the control's text to theColor. If redraw if true, then the control will be redrawn to reflect its new color. If redraw is false, then the control will not be redrawn even though the new color affects its appearance. Set redraw to false only in situations in which you know the control will eventually be redrawn and you want to avoid flickering or flashing.

#### PROCEDURE TControl.InstallTextStyle (theTextStyle: TextStyle; redraw: BOOLEAN);

This method sets the text style of the control to theTextStyle. If redraw if true, then the control will be redrawn to reflect its new text style. If redraw is false, then the control will not be redrawn even though the new style affects its appearance. Set redraw to false only in situations in which you know the control will eventually be redrawn and you want to avoid flickering or flashing.

PROCEDURE TControl.Inset (dh, dv: INTEGER; redraw: BOOLEAN);

This method insets the active control area of the control by dh and dv pixels. If redraw if true, then the control will be redrawn to reflect its new text style. If redraw is false, then the control will not be redrawn even though the new insets may affect its appearance. Set redraw to false only in situations in which you know the control will eventually be redrawn and you want to avoid flickering or flashing.

PROCEDURE TControl.SetInset (newInset: Rect; redraw: BOOLEAN);

This method sets the control's insets to those defined in newInset. If redraw if true, then the control will be redrawn to reflect its new text style. If redraw is false, then the control will not be redrawn even though the new insets may affect its appearance. Set redraw to false only in situations in which you know the control will eventually be redrawn and you want to avoid flickering or flashing.

#### FUNCTION TControl.Validate: BOOLEAN;

This method returns true if the control's contents are valid. Validation generally applies to controls that accept keyboard entry, but it is not necessarily restricted as such. The default behavior is to return true.

#### **Resource-Writing Methods**

PROCEDURE TControl.WRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method writes the TControl portion of the view's resource template. It is the inverse of TControl. IRes and is only used by programs that write 'view' resources.

PROCEDURE TControl.WriteRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method serves as a wrapper for WRes. If you want to write a window object as part of a 'view' resource you would call this method, which calls the appropriate WRes methods.

# **Creation/Destruction Methods**

This method initializes a TControl object. It calls IView to initialize the fields inherited from TView, and then sets the control fields to their default values as described in the section on TControl fields above.

```
PROCEDURE TControl.IRes (itsDocument: TDocument; itsSuperView: TView;
VAR itsParams: Ptr); OVERRIDE;
```

This method initializes a control from a 'view' resource. itsDocument is the document for which this control is being created. itsSuperView is the control's superview, and itsParams is a pointer to the TView section of the control's resource. INHERITED IRes is called to initialize the inherited data (in this case the TView data), then the TControl data is initialized, and finally itsParams is offset by the length of the TControl data.

# The TCtlMgr Class

This class is an abstract class used to represent Control Manager controls (push buttons, radio buttons, check boxes, and scroll bars). It is a subclass of TControl.

### Fields

fCMgrControl The Control Manager control represented by this view.

## **Drawing Methods**

PROCEDURE TCtlMgr.Draw (area: Rect); OVERRIDE;

If the control is visible, this method draws the control by setting the control's contrlVis to 0, and calling the Control Manager routine ShowControl to draw it. (It would be easier to use DrawlControl but it isn't supported on 64K ROMs.) Furthermore, the fCMgrControl's contrlOwner is temporarily set to the current port in case the control is being printed.

#### **Mouse Handling Methods**

FUNCTION TCtlMgr.DoMouseCommand (VAR theMouse: Point; VAR info: EventInfo; VAR hysteresis: Point): TCommand; OVERRIDE;

This method calls the Control Manager routine TrackControl to track the control. If TrackControl returns a nonzero result, then DoChoice (SELF, fDefChoice) is called so that any of the control's superviews can respond to the choice code. You may also override this method to implement specific behavior for specific Control Manager controls.

#### Size Management Methods

PROCEDURE TCtlMgr.Resize (width, height: VCoordinate; invalidate: BOOLEAN); OVERRIDE;

If fSizeable is true then fCMgrControl is resized by calling the Control Manager routine SizeControl. This is done after setting the clipping rectangle to (0, 0, 0, 0) to prevent the Control Manager from drawing when SizeControl is called. If invalidate is true, then the ForceRedraw method is called to ensure that the entire control is redraw. Then INHERITED Resize is called.

#### **Dimming Methods**

PROCEDURE TCtlMgr.DimState (state, redraw: BOOLEAN); OVERRIDE;

This method is overridden to dim the control using the Control Manager routine HiliteControl.

### **Highlighting Methods**

PROCEDURE TCtlMgr.HiliteState (state, redraw: BOOLEAN); OVERRIDE;

This method hilites the control by calling the Control Manager routine HiliteControl and passing either 0 if state if false or 10 if state is true. This has the effect of hiliting the control as though the mouse is clicked in the control.

40

### Current, Minimum, and Maximum Value Methods

FUNCTION TCtlMgr.GetVal: INTEGER;

This method returns the control's current value.

PROCEDURE TCtlMgr.SetVal (newVal: INTEGER; redraw: BOOLEAN);

This method sets the control's current value. If redraw is true, then the control will be redrawn to reflect its new value. If redraw is false, then the control will not be redrawn even though the new value may affect its appearance. Set redraw to false only in situations where you know the control will eventually be redrawn and you want to avoid flickering or flashing.

#### FUNCTION TCtlMgr.GetMin: INTEGER;

This method returns the control's minimum value.

PROCEDURE TCtlMgr.SetMin (itsMin: INTEGER; redraw: BOOLEAN);

This method sets the control's minimum value. If redraw is true, then the control will be redrawn to reflect its new minimum. If redraw is false, then the control will not be redrawn even though the new minimum may affect its appearance. Set redraw to false only in situations where you know the control will eventually be redrawn and you want to avoid flickering or flashing.

FUNCTION TCtlMgr.GetMax: INTEGER;

This method returns the control's maximum value.

PROCEDURE TCtlMgr.SetMax (itsMax: INTEGER; redraw: BOOLEAN);

This method sets the control's maximum value. If redraw is true, then the control may be redrawn to reflect its new maximum. If redraw is false, then the control will not be redrawn even though the new maximum may affect its appearance. Set redraw to false only in situations where you know the control will eventually be redrawn and you want to avoid flickering or flashing.

```
PROCEDURE TCtlMgr.SetValues (itsVal, itsMin, itsMax: INTEGER; redraw:
BOOLEAN);
```

This method sets the control's current, minimum, and maximum values. If redraw if true then the control will be redrawn to reflect its new values. If redraw is false then the control will not be redrawn even though the new values may affect its appearance. Set redraw to false only in situations where you know the control will eventually be redrawn and you want to avoid flickering or flashing.

41

## **Miscellaneous Methods**

PROCEDURE TCtlMgr.SetText (itsText: Str255; redraw: BOOLEAN);

This method sets the control's title. If redraw if true, then the control will be redrawn to reflect its new title. If redraw is false, then the control will not be redrawn even though the new title will affect its appearance. Set redraw to false only in situations where you know the control will eventually be redrawn and you want to avoid flickering or flashing.

PROCEDURE TCtlMgr.GetText (VAR theText: Str255);

This method returns the control's title in theText.

PROCEDURE TCtlMgr.BeInPort (itsPort: GrafPtr); OVERRIDE;

This method keeps the Control Manager control in sync with the port in which the control is being placed. It sets fCMgrControl^^.contrlOwner to itsPort, or to gWorkPort if itsPort is NIL. contrlOwner is the Control Manager field that indicates in which port the control is to be drawn.

PROCEDURE TCtlMgr.WhileFocused (PROCEDURE DoToControl; redraw: BOOLEAN);

IF beVisible is true, then WhileFocused attempts to focus the control, and then calls DoToControl. If redraw is false, then DoToControl is called with clipping temporarily set to an empty rectangle so that any drawing done by DoToControl will not be visible.

```
PROCEDURE TCtlMgr.CreateCMgrControl (itsBounds: Rect; itsTitle: Str255;
itsValue, itsMin, itsMax, itsProcID: INTEGER);
```

This is an internal method used to create the Control Manager control associated with this view. The given parameters are passed to the Control Manager routine NewControl, the result of which is assigned to fCMgrControl.

#### **Resource-Writing Methods**

This method writes the TCtlMgr portion of the view's resource template. It is the inverse of TCtlMgr.IRes and is only used by programs that write 'view' resources.

PROCEDURE TCtlMgr.WriteRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method serves as a wrapper for WRes. If you want to write a window object as part of a 'view' resource you would call this method, which calls the appropriate WRes methods.

### **Creation/Destruction Methods**

This method initializes a TCtlMgr object. It calls IControl to initialize its inherited data, and then calls CreateCMgrControl to create the Control Manager control.

PROCEDURE TCtlMgr.IRes (itsDocument: TDocument; itsSuperView: TView; VAR itsParams: Ptr); OVERRIDE;

This method initializes a TCtlMgr object from a 'view' resource. itsDocument is the document for which the control is being created. itsSuperView is the control's superview, and itsParams is a pointer to the TView section of the object's resource. INHERITED IRes is called to initialize the inherited data (in this case the TView and TControl data), then the TCtlMgr data is initialized, and finally itsParams is offset by the length of the TCtlMgr data.

#### PROCEDURE TCtlMgr.Free; OVERRIDE;

This method frees fCMgrControl, and then calls INHERITED Free.

# **The TScrollBar Class**

The TScrollBar class represents standard Macintosh scroll bars, but whose values are expressed as VCoordinates rather than integers.

#### Fields

fDirection	The scroll bar's direction (horizontal or vertical).
fLongVal	The scroll bar's current value in VCoordinate units.
fLongMin	The scroll bar's minimum value in VCoordinate units. The default value is zero.
fLongMax	The scroll bar's maximum value in VCoordinate units.
fBitsToShift	The number of bits to shift to convert the scroll bar's long values into Control Manager control values.

### **Mouse-Handling Methods**

PROCEDURE TScrollBar.DoMouseCommand (VAR theMouse: Point; VAR info: EventInfo; VAR hysteresis: Point): TCommand; OVERRIDE;

This method differentiates between tracking the thumb and tracking any other part of the scroll bar. For the thumb, the Control Manager routine TrackControl is called to track the mouse, and the scroll bar's new value is set to reflect the final position of the thumb. For the arrows and page areas, TrackControl is called with an action procedure that calls the scroll bar's TrackScrollBar method.

PROCEDURE TScrollBar.TrackScrollBar (partCode: INTEGER);

This method is intended to be overridden so that action can be taken while tracking the scroll bar's arrows or page areas. Typically the action taken is to change the scroll bar's value appropriately. The standard behavior is to do nothing.

# **Current/Minimum/Maximum Methods**

PROCEDURE TScrollBar.SetLongVal (itsVal: VCoordinate; redraw: BOOLEAN);

This method sets the scroll bar's value to newValue. It sets fLongVal to itsVal and calls SetValue with itsVal scaled to an integer. If redraw if true, then the scroll bar will be redrawn to reflect its new value. If redraw is false, then the scroll bar will not be redrawn even though the new value may affect its appearance. Set redraw to false only in situations in which you know the scroll bar will eventually be redrawn and you want to avoid flickering or flashing.

FUNCTION TScrollBar.GetLongVal: VCoordinate;

This method returns the scroll bar's long value.

PROCEDURE TScrollBar.SetLongMin (itsMin: VCoordinate; redraw: BOOLEAN);

This method sets the scroll bar's long minimum. It sets fLongMin to itsMin and calls SetMin with itsMin scaled to an integer. If redraw if true, then the scroll bar will be redrawn to reflect its new minimum. If redraw is false, then the scroll bar will not be redrawn even though the new minimum may affect its appearance. Set redraw to false only in situations in which you know the scroll bar will eventually be redrawn and you want to avoid flickering or flashing.

FUNCTION TScrollBar.GetLongMin: VCoordinate;

This method returns the scroll bar's long minimum.

PROCEDURE TScrollBar.SetLongMax (itsMax: VCoordinate; redraw: BOOLEAN);

This method sets the scroll bar's long maximum. It sets fLongMax to itsMax and calls SetMax with itsMax scaled to an integer. If redraw if true, then the scroll bar will be redrawn to reflect its new maximum. If redraw is false, then the scroll bar will not be redrawn even though the new maximum may affect its appearance. Set redraw to false only in situations in which you know the scroll bar will

eventually be redrawn and you want to avoid flickering or flashing.

FUNCTION TScrollBar.GetLongMax: VCoordinate;

This method returns the scroll bar's long maximum.

```
PROCEDURE TScrollBar.SetLongValues (itsVal, itsMin, itsMax: VCoordinate;
redraw: BOOLEAN);
```

This method sets the scroll bar's current, minimum, and maximum long values. If redraw if true, then the scroll bar will be redrawn to reflect its new values. If redraw is false, then the scroll bar will not be redrawn even though the new values may affect its appearance. Set redraw to false only in situations in which you know the scroll bar will eventually be redrawn and you want to avoid flickering or flashing.

PROCEDURE TScrollBar.DeltaValue (delta: VCoordinate);

This method offsets the current value of the scroll bar by delta, by ensuring that delta is within the scroll bar's minimum and maximum and calling SetVal.

## **Resource-Writing Methods**

```
PROCEDURE TScrollBar.WRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr);
OVERRIDE;
```

This method writes the TScrollBar portion of the view's resource template. It is the inverse of TScrollBar. IRes and is only used by programs that write 'view' resources.

PROCEDURE TScrollBar.WriteRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method serves as a wrapper for WRes. If you want to write a window object as part of a 'view' resource you would call this method, which calls the appropriate WRes methods.

### **Creation/Destruction Methods**

This method initializes a scroll bar by calling ICtlMgr to initialize the inherited data, and then sets its fields to the given parameters.

PROCEDURE TScrollBar.IRes (itsDocument: TDocument; itsSuperView: TView; VAR itsParams: Ptr); OVERRIDE;

This method initializes a TScrollBar object from a 'view' resource. itsDocument is the document for which the scroll bar is being created. itsSuperView is the scroll bar's superview, and itsParams is a pointer to the TView section of the object's resource. INHERITED IRes is called to initialize the

© 1988 **\*** Apple Computer

inherited data (in this case the TView, TControl, and TCtlMgr data), then the TScrollBar data is initialized, and finally itsParams is offset by the length of the TScrollBar data.

# The TSScrollBar Class

The TSScrollBar class represents scroll bars used in conjunction with TScroller objects. A single scroll bar can be associated with any number of scrollers. Each scroller is responsible for scrolling itself based upon messages sent to it from its scroll bars.

### Fields

fScrollers

A list of the scroller views associated with this scroll bar.

#### **Activation Methods**

PROCEDURE TSScrollBar.Activate (entering: BOOLEAN); OVERRIDE;

After focusing the scroll bar, this method either draws the scroll bar (entering is true) by calling the Control Manager routine ShowControl (fCMgrControl) or hides the scroll bar (entering is false) by calling the Control Manager routine HideControl and the Draw method to frame its rectangle. In both cases, the scroll bar's rectangle is validated to avoid unnecessary window updates.

### **Drawing Methods**

PROCEDURE TSScrollBar.Draw (area: Rect); OVERRIDE;

This method is overridden so that if the scroll bar is invisible (and assumed to be inactive), its rectangle is framed. Otherwise, INHERITED Draw is called.

#### **Mouse-Handling Methods**

FUNCTION TSScrollBar.DoMouseCommand (VAR theMouse: Point; VAR info: EventInfo; VAR hysteresis: Point): TCommand; OVERRIDE;

This method is overridden to handle the thumb. If the thumb is tracked, then when the thumb is released, the scroll bar's value is passed to each controlled view's ScrollRelative method. The values returned by each ScrollRelative method is added to the scroll bar's value. If a part other than the thumb is clicked, then INHERITED DoMouseCommand is called.

PROCEDURE TSScrollBar.TrackScrollBar (partCode: INTEGER);

This method is used to track the cursor while it's in an arrow or page area of a scroll bar. It simply calls each scroller's ScrollStep method and adds the values returned by each ScrollStep to the scroll bar's value.

### **Resource-Writing Methods**

PROCEDURE TSScrollBar.WRes (theResource: ViewRsrcHndl; VAR itsParams: Ptr); OVERRIDE;

This method writes the TSScrollBar portion of the view's resource template. It is the inverse of TSScrollBar. IRes and is only used by programs that write 'view' resources.

This method serves as a wrapper for WRes. If you want to write a window object as part of a 'view' resource you would call this method, which calls the appropriate WRes methods.

## **Creation/Destruction Methods**

This method initializes a scroll bar. It calls IControl, and then sets its fields to the given parameters. fLongMin is set to zero.

This method initializes a TSScrollBar object from a 'view' resource. itsDocument is the document for which the scroll bar is being created. itsSuperView is the scroll bar's superview, and itsParams is a pointer to the TView section of the object's resource. INHERITED IRes is called to initialize the inherited data (in this case, the TView, TControl, and TCtlMgr data), then the TScrollBar data is initialized, and finally itsParams is offset by the length of the TScrollBar data.

#### PROCEDURE TSScrollBar.Free; OVERRIDE;

This method frees the fScrollers list, and then calls INHERITED Free.

