

**File No. S370-36
Order No. SY20-0884-3**

Systems

**IBM Virtual Machine
Facility/370:
Data Areas and Control
Block Logic**

| Release 6 PLC 1

This publication, together with the *VM/370 System Logic and Problem Determination Guide, Volumes 1, 2, and 3*, is intended for use by system programmers responsible for updating VM/370. This publication contains descriptions of the major data areas and control blocks used by three of the components of VM/370, the Control Program (CP), the Conversational Monitor System (CMS), and the Remote Spooling Communications Subsystem (RSCS).

To use this publication effectively and to understand it thoroughly, the following publications are prerequisite:

IBM System/370 Principles of Operation
Order No. GA22-7000
IBM OS/VS, DOS/VS, and VM/370 Assembler Language,
Order No. GC33-4010



| Fourth Edition (March 1979)

| This is a major revision of, and obsoletes, SY20-0884-2 and Technical
| Newsletters SN25-0413, SN25-0453, and SN25-0466. This edition applies
| to Release 6 PLC 1 (Program Level Change) of the IBM Virtual Machine
Facility/370, and to all subsequent releases unless otherwise indicated
in new editions or Technical Newsletters.

Technical changes and additions to text and illustrations are indicated
by a vertical bar to the left of the change.

Changes are periodically made to the information herein; before using
this publication in connection with the operation of IBM systems,
consult the latest IBM System/370 Bibliography, Order No. GC20-0001, for
the editions that are applicable and current.

Publications are not stocked at the address given below; requests for
copies of IBM publications should be made to your IBM representative or
to the IBM branch office serving your locality.

A form for readers' comments is provided at the back of this
publication. If the form has been removed, comments may be addressed to
IBM Corporation, VM/370 Publications, Dept. D58, Bldg. 706-2, P.O. Box
390, Poughkeepsie, New York 12602. IBM may use or distribute any of the
information you supply in any way it believes appropriate without
incurring any obligation whatever. You may, of course, continue to use
the information you supply.

| This publication contains descriptions of major data areas and control blocks used by the three major components of VM/370. The three components are:

- | • The Control Program (CP)
- | • The Conversational Monitor System (CMS)
- | • The Remote Spooling Communications Subsystem (RSCS)

There are three sections and five appendixes, as follows:

- "Section 1. CP Data Areas and Control Blocks" contains information about CP data areas and control blocks.
- "Section 2. CMS Data Areas and Control Blocks" contains information on CMS data areas and control blocks.
- "Section 3. RSCS Data Areas and Control Blocks" contains information on RSCS data areas and control blocks.
- "Appendix A. CP and RSCS Equate Symbols" contains assembler language equate symbols used by CP and RSCS to reference data.
- "Appendix B. RSCS Control Areas" contains RSCS control areas that define constants and variables used during execution.
- "Appendix C. RSCS Request Elements" contains RSCS request elements that are the tables used by RSCS for task-to-task communication.
- "Appendix D. CMS Equate Symbols" contains CMS equate symbols.
- "Appendix E. Data Areas and Control Block References" contains information on the modules that reference data areas and control blocks.

OTHER VM/370 DATA AREAS AND CONTROL BLOCKS

Some data areas and control blocks that affect VM/370 service and support programs are not included in this publication. Information on these data areas and control blocks can be found in the IBM Virtual

Machine Facility/370: Service Routines Program Logic, Order No. SY20-0882.

RELATED PUBLICATIONS

This publication should be used in conjunction with:

IBM Virtual Machine Facility/370:

System Logic and Problem Determination Guide,

Volume 1 Control Program (CP), Order No. SY20-0886

Volume 2 Conversational Monitor System (CMS), Order No. SY20-0887

Volume 3 Remote Spooling Communication Subsystem (RSCS), Order No. SY20-0888

System Programmer's Guide, Order No. GC20-1807

Glossary and Master Index, Order No. GC20-1813.

For information on how to use the fourth component -- interactive problem control system -- and its facilities, the hardware and software support personnel or the installation system programmer should use:

IBM Virtual Machine Facility/370: Interactive Problem Control System (IPCS) User's Guide, Order No. GC20-1823.

HOW TO USE THIS PUBLICATION

This publication addresses and describes the major control blocks associated with CP, CMS, and RSCS. Generally, data areas, or scratch areas that are created and exist only during the execution of a particular module are not described in this publication. In this publication, the data areas and control blocks are arranged in alphabetical order by DSECT name.

The CMS and RSCS components operate under control of CP. Each component creates, updates, and erases its own control blocks and data areas.

Control blocks and data areas are blocks of related information applicable to one or more system functions. They are usually defined by the DSECT instruction. The blocks can reflect current status, history information, or combinations of both, applicable to VM/370 functions. Control blocks and data areas provide the linkage and information for the user, the hardware, and the programs to work as one entity for the successful execution of a job, task, or process.

For every data area or control block, a statement is given that defines the use of the data area or control block. This statement is followed by a formatted block showing the fields defined in the data area or control block and the displacement into the DSECT of that field.

The formatted blocks for CP and CMS control areas are 8 bytes wide, showing two fullwords per line. RSCS control blocks are 4 bytes wide.

Note: One exception to this width rule is the formatting for PSA, where the control areas are given in 16-byte width.

When the name of a field is too large to fit into the formatted line, a pointer to the definition of the field is used instead of the name of the field. This pointer usually takes the form A*1, A*2, etc. When there is a particularly large field (one that uses more than three or four lines of the formatted block), ellipses are used in the block to show that the displacement of this field is larger than can be shown in the block.

The use of slashes in a field indicates that the field is reserved for IBM's use.

The formatted block is followed by listing-related information such as the hexadecimal displacement of the field into the DSECT, the name of the field and its definition in the listing, and a brief description of the contents and meaning of the field.

The following terms in this publication, refer to the indicated support devices:

- "2305" refers to IBM 2305 Fixed Head Storage, Models 1 and 2.
- "270x" refers to IBM 2701, 2702, and 2703 Transmission Control Units or the Integrated Communications Adapter (ICA) on the System/370 Model 135.
- "2741" refers to the IBM 2741 and the 3767, unless otherwise specified.
- "3270" refers to a series of display devices, namely, the IBM 3275, 3276, 3277, and 3278 Display Stations. A specific device type is used only when a distinction is required between device types.

Information about display terminal usage also applies to the IBM 3138, 3148, and 3158 Display Consoles when used in display mode, unless otherwise noted.

Any information pertaining to the IBM 3284 or 3286 Printer also pertains to the IBM 3287, 3288, and 3289 printers, unless otherwise noted.

- "3330" refers to the IBM 3330 Disk Storage, Models 1, 2, or 11; the IBM 3333 Disk Storage and Control, Models 1 or 11; and the 3350 Direct Access Storage operating in 3330/3333 Model 1 or 3330/3333 Model 11 compatibility mode.
- "3340" refers to the IBM 3340 Disk Storage, Models A2, B1, and B2, and the 3344 Direct Access Storage Model B2.
- "3350" refers to the IBM 3350 Direct Access Storage Models A2 and E2 in native mode.
- "370x" refers to IBM 3704 and 3705 Communications Controllers.
- The term "3705" refers to the 3705 I and the 3705 II unless otherwise noted.

Contents

SUMMARY OF AMENDMENTS.	ix	MN602: VM/370 Monitor DASTAP Utilization Record.	52
SECTION 1. CP DATA AREAS and CONTROL BLOCKS.	1	MN700: VM/370 Monitor Seeks Class Record	53
ACCTELOK: User Accounting Block.	2	MN802: VM/370 Monitor System Profile Class	54
ACNTBLOK: Accounting Card Buffer Block	2	MNDEVLST: VM/370 Monitor Class 6 (DASTAP) Device List.	55
ALOCBLOK: DASD Cylinder Allocation Block	4	MNCOM: VM/370 Monitor Communications Area	56
ESCBLOK: Binary Synchronous Communication Control Block	6	MSSCOM: MSS Communications Control Block	59
BUFFER	8	NCPtbl: Named 370X Control Program Table	60
CCHREC: Channel Check Handler Record	9	NICBLOK: Network Interface Control Block	61
CCPARM: Communications Controller Parameter List.	11	NPRTBL: Named 3800 Image Library Table	63
CHXBLOK and CHYBLOK: Virtual Channel-to-Channel Adapter Control Blocks.	12	OBRRECN: Unit Check Error Record (long Outboard Record)	64
CKPBLOK: Telecommunications Checkpoint Block	14	OBFREC: Unit Check Error Record (Short Cutboard Record)	66
CONTASK: Console I/O Package	15	OWNDLIST: CP-Owned Volumes List	67
CORTABLE: Storage Allocation Table	17	PAGTABLE: Translation Page Table	67
CPEXBLOK: CP Execute Block	18	PGBLOK: Pseudo Page Fault Stack Block	68
DDRREC: Reconfiguration Macro.	19	PSA: Prefix Storage Area (Low Storage Locations)	69
DMPINREC: Dump File Information Record	20	FWDIBLOK: Password Invalid Block	78
DMPKYREC: Dump File Key Storage Record	21	REAL I/O CONTROL BLOCKS.	79
DMPTBREC: Dump File Symbol Table Record.	21	Real Channel Control Blocks.	79
ECBLOK: Extension to VMELOK for Virtual Machine with Relocate	22	Real Control Unit Blocks	79
ERRBLOK: Error Block Used to Build OBR/MDR	24	Real Device Control Blocks	79
ICBLOK: I/O Task Control Block	25	Input/Output Blocks.	79
IOERBLOK: I/O Error Information Block.	27	Network Interface Control Block	80
IRMBLOK: Intensive Error Recording Mode Block	31	RCHBLOK: Real Channel Block	81
JPSCBLOK: Journaling and Password Suppression Control Block	32	RCUBLOK: Real Control Unit Block	82
LOCKBLOK: Userid Lock Control Block.	33	RCWTASK: Translated Virtual I/O CCW	84
MCHAREA: Machine Check Save Area	34	RDEVBLok: Real Device Block	85
MCRECORD: Machine Check Handler Record	37	RECBLOK: DASD Page (Slot) Allocation Block	89
MDRREC: Miscellaneous Data Recording Record.	38	RECPAG: Error Recording Page Record	90
MICBLOK: Virtual Machine Pointer List for VM/370 Hardware Assist.	39	RSFLCTL: Real Spooling Control Block	91
MIHREC: Missing Interrupt Handler Error Record.	40	RSPXELOK: Real Device Extension Block	91
MNHDR: VM/370 Monitor Record Header.	41	SAVEAREA	92
MN000: VM/370 Monitor Perform Class Record.	42	SAVTABLE: First Page on Saved System DASD	93
MN001: VM/370 Monitor Perform Class Record.	45	SDRBLOK: Statistical Data Recording Block	94
MN097: VM/370 Monitor Header Records	46	SEGTABLE: Translation Segment Table	95
MN098: VM/370 Monitor Trailer Record	46	SFBLOK: Spool File Block	96
MN099: VM/370 Monitor Suspension Record.	47	SHQBLOK: Spool Hold Queue Block	98
MN10X: VM/370 Monitor Response Class Records	47	SHRTABLE: Named-Shared Segment Systems Table	99
MN20X: VM/370 Monitor Schedule Class Records	48	SPLINK: Spool Page Buffer Linkage Block	100
MN400: VM/370 Monitor User Class Record.	49	SWPTABLE: Swap Table for Virtual Machine Paging	101
MN500: VM/370 Monitor Instruction Simulation Class Record	50	SYSLOCS: System Low Storage Information Block	102
MN600: VM/370 Monitor DASTAP I/O Count Records	51	SYSTBL: Named System Table	103

UMACEBLOK: User Machine Block	111	NICL: Number in Class.	204
VIRTUAL I/O CONTROL BLOCKS	113	NUCCON: Nucleus Constant Area	205
Virtual Channel Blocks	113	OPSECT: Major CSECT for all I/O	
Virtual Control Unit Blocks.	113	Operation Lists	219
Virtual Device Blocks.	113	OSFST: OS File Status Table.	222
VCHBLOK: Virtual Channel Block	114	OVSECT: Describes the First Few	
VCONCTL: Virtual Console Control Block .	115	Locations of DMSOVS	224
VCUBLOK: Virtual Control Unit Block. .	116	PCTAB: Program Check Option Table. . . .	224
VEVBLOK: Virtual Device Block	117	PDSSECT: Directory Table for EPAM	
VFCBEBLOK: Virtual Forms Control Buffer		Simulation.	225
Block	120	PGMSECT: Program Interrupt Work Area .	226
VMBLOK: Shared Systems Control		PIBADR: Program Information Block . .	227
Addition to VMBLOK.	120	PIB2TAB: Program Information Block	
VMBLOK: Virtual Machine Control Block.	121	Extension	228
VMCBLOK: Virtual Machine Communication		PUBADR: Physical Unit Block Table. . .	229
Block	128	PUBCOWNER: Physical Unit Block Ownership	
VMCMHDR: VMCF Message Header	129	Table	230
VMCPARM: VMCF Parameter List	130	SSAVE: System Save Area.	231
VRRBLOK: Virtual Reserve/Release Block .	131	SUBSECT: Subset Work Area.	233
VSPLCTL: Virtual Spooling Control Block.	132	SVCSECT: SVC Interrupt Storage	234
VSPXBLOK: Virtual Spool Extension Block.	133	SVEARA: LTA and PP Save Area DSECT . .	238
XINTELOK: External Interrupt Block . . .	134	SYSCOM: System Communication Region. .	239
XOBR3211: Extended Outboard Recording		SYSNAMES: Saved Systems Names.	242
Block	135	TSCBLKS: TSO Control Blocks.	243
SECTION 2. CMS DATA AREAS AND CONTROL		USAVER: User Save Area.	245
BLOCKS.	137	USERSECT: User Work Area	245
AETAB: Abend Termination Option Table. .	138		
AEWSECT: Abend Recovery Workspace. . . .	139		
ADTSECT: Active Disk Table	140		
AFTSECT: Active File Table	143		
ANCHSECT: Anchor Table	145		
BATLSECT: CMS Batch User Job Limits. . .	146		
BBOX: Boundary Box	146		
EGCOM: DOS/VS Partition Communication			
Region.	147		
CMSTAXE: Terminal Attention Exit			
Element	149		
CVTSECT: Communication Vector Table as			
supported by CMS.	150		
DEGSECT: Debug Work Area	152		
DEVSECT: Device Table DSECT.	156		
DEVTAE: Device Table	157		
DIOSECT: Disk I/O Work Area.	160		
DMSCCB: Command Control Block.	162		
DOSSECT: DOS Simulation Control Block.	164		
EDCDB: Edit Control Block	166		
ERDSECT: Error Handling Routine DSECT. .	174		
EXTSECT: External Interrupt Work Area. .	177		
EXTUAREA: External User Area	179		
FCBSECT: Simulated OS Control Blocks .	180		
FCHTAB: Fetch Table.	184		
FICL: First In Class Block	185		
FRDSECT: Free Chain Element Header			
Blocks.	186		
FSCBD: File System Control Block	188		
FSTD: File Status Table Entry DSECT. .	189		
FSTSECT: File Status Table	190		
FVSECT: Fixed Variable Storage Work			
Area for CMS File System.	191		
IHADECB: Data Event Control Block. . .	195		
IOSECT: I/O Interrupt Save Area.	196		
KEYSECT: Disk Key Table DSECT for BDAM			
Simulation.	197		
LERST: Loader Storage Area	198		
LUETAB and LUEPR: Logical Unit Block			
Table	202		
SECTION 3. RSCS DATA AREAS AND CONTROL			
BLOCKS.	247		
ASYNE: Asynchronous Exit Element	248		
BUFDSECT: SML Telecommunications Buffer	249		
COMDSECT: Address Constants as Pointers	250		
DEVTABLE: NPT Device Table	251		
FREEE: A Free Element on the Supervisor			
Element Queue	252		
GIVE Request Table	253		
GIVEEE: A GIVE Element.	253		
IOE: An I/O Element.	254		
IOTABLE: An I/O Table.	255		
LINKTABL: Link Table	256		
REQBLOCK: NPT Request Block.	258		
ROUTE: Routing Table Entry	259		
SVECTORS: Low Storage Definitions. . .	260		
TAG: RSCS File Descriptor.	263		
TAGAREA.	265		
TAKE Request Table	265		
TANKDSEC: SML Unit Record Tank	266		
TAREA: A Task Save Area.	267		
TASKE: A Task Element.	269		
TCTDSECT: Task Control Table	270		
APPENDIXES	273		
APPENDIX A. CP and RSCS EQUATE SYMBOLS	275		
VM/370 Device Classes, Types, Models,			
and Features.	276		
VM/370 EQUATE SYMBOLS -- Machine Usage	278		
VM/370 EQUATE SYMBOLS -- Extended			
Control Registers	279		
VM/370 EQUATE SYMBOLS -- CP Usage. . .	280		
VM/370 Registers	283		
APPENDIX E. RSCS CONTROL AREAS	285		
AXS Monitor Control Area	286		
REX Monitor Control Area	287		
SML Monitor Control Area	288		

APPENDIX C. RSCS REQUEST ELEMENTS.	291	Message Request Element.	303
Command ALERT Element Format A1.	292	Operational Notes.	303
Operational Notes.	292	Pcrt Table	304
Command ALFRT Element Format A2.	293	Operational Notes.	304
Operational Notes.	293	Terminate Request Element.	305
Command ALERT Element Format L0.	294	Operational Notes.	305
Operational Notes.	294		
Command ALFRT Element Format L1.	296	APPENDIX D. CMS EQUATE SYMBOLS	307
Operational Notes.	296	CMS Usage Equates.	308
Command ALERT Element Format L2.	297	CMS Register Equates	309
Operational Notes.	297		
Command ALERT Element Format L3 (also Message Alert Element).	298	APPENDIX E. DATA AREAS AND CONTROL BLOCK REFERENCES.	311
Operational Notes.	298	CP Control Block References.	312
Command Request Element.	299	CMS Control Block References	321
Operational Notes.	299	RSCS Control Block References.	326
File Request Element	300		
Operational Notes.	300		
Line Alert Element	302		
Operational Notes.	302		

FIGURES

Figure 1.	CP Control Block Relationships.....	1
Figure 2.	CMS Control Block Relationships.....	137

3800-1 PRINTER SUPPORT

New: Documentation and Program Support

VM/370 now offers support for the 3800-1 unit as a dedicated virtual machine printer. The 3800-1 is also supported as a VM/370 spooling device.

3850-2 VIRTUAL MACHINE MSS SUPPORT

New: Program and Documentation

VM/370 now supports the 3850-2 MSS to permit most operating systems that are running in the virtual machine environment access to data on MSS virtual volumes.

PASSWORD-ON-THE-COMMAND-LINE SUPPRESSION

New: Program Feature

VM/370 now supports the suppression of the entering of passwords on the command line for LOGON, AUTOLOG, and LINK. The intent is to force passwords to be typed upon a mask. The new support is specified via the SYSJRL macro in DMKSYS. It is optional and must be implemented at system generation time. Privilege class A users can use the JOURNAL operand of either the SET or QUERY commands.

MULTIPLE ALTERNATE CONSOLE SUPPORT

New: Program and Documentation

VM/370 supports the specification of multiple alternate consoles at system generation time.

MONITOR ENHANCEMENTS SUPPORT

New: Program and Documentation

VM/370 supports the enhancement to the Monitor module which permits the analyst the option to specify periodic closing

of the active Monitor spool file frequently enough to support real time data reduction and display.

SECURITY JOURNALING SUPPCRT

New: Program Feature

VM/370 now supports the journaling of LOGONS and AUTOLOGS specifying invalid passwords and the journaling of all linkages. This is accomplished via the generation of type 04, 05, and 06 accounting records. The new support is specified in the SYSJRL macro in DMKSYS.

4331 AND 4341 PROCESSOR SUPPORT

New: Program and Documentation

VM/370 supports 4331 and 4341 processors offering compatibility with the new model IDs as well as the S/370 RAS function subset.

MISCELLANEOUS

New: Documentation and Program

The following features and enhancements are now supported by VM/370.

- 3203-5 Unit
- Special Messages facility
- Trace Table size as a system generation option
- Modification of Shared Segment handling
- 3031 Alternate Processor
- 12 and 16 Megabyte Processors
- Directory hooks

Summary of Amendments
for SY20-0884-2
as updated by SN25-0461
VM/370 Release 5 PLC 12

VARY PROCESSOR SUPPORTED BY VM/370

New: Documentation and Program Support

When a system has been generated for attached processor operations, use of a new command, VARY PROCESSOR ONLINE/OFFLINE, facilitates the transition to or from uniprocessor mode on the main processor. This command can be used to vary a specified processor offline or online without any serious disruption to system users.

ALTERNATE TRACK FOR 3340/3344
NOW SUPPORTED BY VM/370

New: Documentation and Program Support

New code has been added for VM/370 support of 3340/3344 alternate track facility. These changes affected the following modules:

IOBLOK
IOERBLOK

Section 1. CP Data Areas and Control Blocks

This section contains descriptions of the major CP data areas and control blocks. Figure 1 shows the relationships of control blocks to each other.





Figure 1. CP Control Block Relationships

ACCTBLOK, ACNTBLOK

ACCTBLOK: USER ACCOUNTING BLOCK


ACCTBLOK provides header information for spool files. The VMACCOUNT field in the VMBLOCK points to ACCTBLOK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	ACCTUSER DS	CL8 Virtual machine identification
8	ACCTACNO DS	CL8 Virtual machine accounting number
10	ACCTDIST DS	CL8 Virtual machine distribution number
	ACCTLENG EQU	(*-ACCTBLOK)/8 Size of ACCTBLOK in doublewords (X'03')

ACNTEBLOK: ACCOUNTING CARD BUFFER BLOCK


ACNTBLOK provides accounting and statistical information on each user that has used VM/370 facilities. The ARSPAC field in the Prefix Storage Area (PSA) points to the start of the chain of ACNTBLOKS.



Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	ACNTCCW	DS D	Punch CCW for accounting card
8	ACNTNEXT	DS F	Address of next ACNTBLOK in chain
C	ACNTDATA	DS CL80	Accounting information (see "Format for User Cards")
5C	ACNTBACK	DS F	Address of previous ACNTBLOK in chain
	ACNTSIZE EQU	(*-ACNTBLOK)/8	Size of ACNTBLOK in doublewcrds (X'0C')

- Format for User Cards

The fields below represent the 80 bytes defined by ACNTDATA in the ACNTBLCK data area.




Hexadecimal Displacement	Field Name	ORG	ACNTDATA	Field Description, Contents, Meaning
C	ACNTUSER	DS	CL8	Virtual machine identification
14	ACNTNUM	DS	CL8	Virtual machine accounting number
1C	ACNTSTOP	DS	CL12	Date and time of accounting MMDDYYHHSS
28	ACNTCONT	DS	1F	Number of seconds connected
2C	ACNTTIME	DS	1F	Milliseconds of processor time used
30	ACNTVTIM	DS	1F	Milliseconds of virtual processor time used
		ORG	ACNTTIME	
2C	ACNTDEVC	DS	XL4	Device code (CTFM); see the DEVTYPE copy file
30	ACNTNCYL	DS	1H	Number of cylinders of T-disk space
34	ACNTPGRD	DS	1F	Total page reads
38	ACNTPGWT	DS	1F	Total page writes
3C	ACNTIOCT	DS	1F	Virtual SIO count for nonspoiled I/O
40	ACNTPNCH	DS	1F	Virtual card count for spooled punch
44	ACNTLINS	DS	1F	Virtual line count for spooled printer
48	ACNTCRDS	DS	1F	Virtual card count for spooled reader
4C	ACNTRSV1	DS	2F	Reserved for IBM use
54	ACNTRSV2	DS	XL6	Reserved for IBM use
5A	ACNTCODE	DS	1H	Accounting card identification code
	<u>Card Codes for ACNTCODE</u>			
	DC	C'C0'		User formatted accounting card
	DC	C'x1'		User virtual machine accounting card
	DC	C'x2'		User dedicated device accounting card
	DC	C'x3'		User temporary disk space accounting card
	<u>where:</u>			
	x = C if the card is initiated via a DIAGNOSE Code X'4C'			
	x = 0 if the card is initiated via CP command processing			

ALOCBLOK

ALOCBLOK: DASD CYLINDER ALLOCATION BLOCK

ALOCBLOK provides information on the temporary disk space available to a virtual machine. The RDEVALLN field in the RDEVBLOK points to the ALOCBLCK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	ALOCPNT DS 1F	Pointer to next ALOCBLOK on chain
4	ALOCUSED DS 1H	Number of nontemporary cylinders
6	ALOCMAX DS 1H	Maximum number of cylinders available
8	ALOCNTMP DS 1H	Number of nontemporary cylinders
A	DS 3H	Reserved for IBM use
10	ALOCMAP DS 0F	Cylinder allocation bit map

Bits defined in ALOCMAP
0 = Cylinder is available
1 = Cylinder has been assigned

Note: The size of ALOCMAP is variable and depends upon the number of cylinders on the device. Generally, the size of the ALOCBLCK is determined by the following formula:

$$\text{ALOCSIZE (doublewords)} = \frac{(\text{ALOCMAX}+63)}{64} + 2 = \frac{\text{No. of Cylinder}}{\text{Bits per doubleword}} + \text{header}$$

where:

ALOCMAX for 2305-1	= 48 cylinders
for 2305-2	= 96 cylinders
for 2314	= 203 cylinders
for 3330-1	= 404 cylinders
for 3330-2	= 404 cylinders
for 3330-11	= 808 cylinders
for 3333-1	= 404 cylinders
for 3333-11	= 808 cylinders
for 3340-35	= 349 cylinders
for 3340-70	= 698 cylinders
for 3350	= 555 cylinders
for all others	= 1 cylinder

Note that any bits in the map that represent cylinders not present on the device are set to 1.

For Temporary Disk Allocation Blocks

4	ORG	ALOCUSED	
	ALOCCYL1 DS	1H	First cylinder of T-disk area
6	ALOCCYL2 DS	1H	Last cylinder of T-disk area

Bytes defined in ALOCMAP
X'00' = Cylinder is available

X'AA' = Cylinder has been allocated

Note: The size of the T-disk ALCCMAP is variable and depends upon the number of cylinders in the range ALOCCYL1 to ALOCCYL2. Generally, the size of a given block is determined by the following formula:

$$\text{ALOCSIZE(doublewords)} = \left\{ \frac{(ALOCCYL2-ALOCCYL1+1)*7}{8} \right\} + 2 = \\ \left\{ \frac{\text{Number of Cylinder (inclusive)}}{\text{Bytes per doubleword}} \right\} + \text{header}$$

Note that bytes for cylinders that are not available are marked assigned.

BSCBLOK

BSCBLOK: BINARY SYNCHRONOUS COMMUNICATION CONTROL BLOCK

BSCBLOK provides status, control information buffers (necessary for polling and addressing), and channel programs for 3270 remote equipment. The RDEVESC field in the RDEVBLOK points to the BSCBLOK.


0	BSCSCCW1										
8	BSCSCCW2										
10	BSCSCCW3										
18	BSCPCCW1										
20	BSCPCCW2										
28	BSCPCCW3										
30	BSCPCCW4										
38	BSCECCW1										
40	BSCECCW2										
48	BSCUECCW										
50	BSCSEL										
58	B*2		B*3		BSCINDEX		//////////	BSCRESVD	//////////		
60	BSCSPTR					BSCAUSER					
68	BSCUCOPY					BSCRSTRT					
70	BSCCNT		BSCSENSE		BSCRCVD		BSCSEND				
78	//////////				BSCUSER1	//////////		BSCRROBN			
80	BSCTMRQ					BSCRESP					
88	BSCREAD				.						
					.						
					.						

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	BSCSCCW1	DS 1D	CCW for write reset operation
8	BSCSCCW2	DS 1D	CCW for addressing or selection
10	BSCSCCW3	DS 1D	CCW for read response to selection
18	BSCPCCW1	DS 1D	CCW for write reset operation
20	BSCPCCW2	DS 1D	CCW for general/specific polling
28	BSCPCCW3	DS 1D	CCW for NOP command
30	BSCPCCW4	DS 1D	CCW for read text
38	BSCECCW1	DS 1D	CCW for write error response
40	BSCECCW2	DS 1D	CCW to transfer control to read CCW
48	BSCUECCW	DS 1D	CCW for read response on time-out
50	BSCSEL	DS 7X	Addressing/polling entry
57	BSCFLAG	DS 1X	B*1 ESCELOK flags
	<u>Bits defined in BSCFLAG</u>		
	BSCRVI	EQU X'80'	Sending RVI response
	BSCENQ	EQU X'40'	Enqueued in data from station
	BSCCOPY	EQU X'20'	COPY function is active
	BSCOPIED	EQU X'10'	Initiate COPY function
	BSCREGEN	EQU X'08'	Regeneration error
	BSCTSTRQ	EQU X'04'	Ignore input processing
	BSCLOG	EQU X'02'	Bypass FORCE message at logcff
	BSCSCAN	EQU X'01'	Second scan for write request
58	BSCFLAG1	DS 1X	B*2 BSCELOK flags
	<u>Bits defined in BSCFLAG1</u>		
	BSCETB	EQU X'80'	Station transmitted block record
	BSCIGN	EQU X'40'	Ignore block record
	BSCPA1	EQU X'20'	Indicator to call DMKCFMBK
	BSCINBID	EQU X'10'	Initial bid sequence required
	BSCFORCE	EQU X'08'	User FORCE in progress
	BSCHALT	EQU X'04'	Halt I/O has been issued fcr this device
59	BSCLINE	DS 1X	B*3 Line coordinate for input area
5A	BSCINDEX	DS 1H	Index value for available space in input buffer
5C	BSCRESVD	DS 4X	Reserved for IBM use
60	BSCSPTR	DS 1F	Write CCW string address and/cr address of buffer
64	BSCAUSER	DS 1F	Address of active resource
68	BSCUCOPY	DS 1F	Address of COPY requestor's NICBLOK
6C	BSCRSTRT	DS 1F	Address of restart CCW string
70	BSCCNT	DS 1H	Retry count
72	BSCSENSE	DS 1H	Sense bytes from remote statcn
74	BSCRCVD	DS 1H	Expected received ACK (ACK-0/ACK-1)
76	BSCSEND	DS 1H	Sending ACK (ACK-0/ACK-1)
78	BSCUSER1	DS 1F	Reserved for IBM use
7C	BSCRRROBN	DS 1F	Address of active user in queue
80	BSCTMRQ	DS 1F	Pointer to TRQBLOK for poll delay
84	BSCRESP	DS 1H	Response buffer for selectcn
86	BSCREAD	DS CL264	Read buffer for polling
	BSCSIZE1	EQU *-(BSCREAD+1)	Read buffer size in bytes
	BSCSIZE2	EQU (BSCREAD-ESCBLOK)	ESCB header size in bytes
	BSCSIZE	EQU (*-ESCBLOK+7)/8	ESCB blocksize in doublewords (X'19')

BUFFER

BUFFER

BUFFER is a buffer area that contains console input to be used by CP. The VCONRUEF field in the VCONCTRL block points to BUFFER.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	BUFIN	DS CL136 Input line
88	BUFNXT	DS 1F Pointer to next byte in BUFFER
8C	BUFCNT	DS 1F Count of characters in input line
	<u>Bits defined in BUFCNT</u>	
	BUFLNLTH EQU L'BUFIN'	Size of input line in bytes (136)
	BUFSIZE EQU (*-BUFFER)/8	Size of console buffer in doublewords (X'12')

CCHREC: CHANNEL CHECK HANDLER RECORD

CCHREC provides statistical data for error recovery and/or error recording related to a previously performed channel operation that did not successfully complete.

0	C*1		C*2		C*3		C*4	///CCSW2REV//	C*5	/C*6//
CCDATE										
10	CCCPUID					CCHMDL			CCHMCEL	
CCPROGID										
20	FAILADD									
.										.
.										.
30	FAILCCW									
38	FAILCSW									
40	FAILECSW					CCDEVTYPE				
48	C*7		CCHCUA			CCHCHCUA		CCHCLOGL		
50	CCHLOG									
.										.
.										.

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
0	CCRECTYP	DS	1X	C*1 Record type
1	CCOPSYS	DS	1X	C*2 Operating system
2	CCSW1	DS	1X	C*3 Switch 1
3	CCSW2	DS	1X	C*4 Switch 2
4	CCSW2REV	DS	2X	Reserved for IBM use
6	CCRECNT	DS	1X	C*5 Record count
7	CCRECNT1	DS	1X	C*6 Reserved for IBM use
8	CCDATE	DS	1D	Date and time
10	CCCPUID	DS	1F	Processor identification
14	CCHMDL	DS	1H	Processor model number (for example, 0158, 0168, etc.)
16	CCHMCEL	DS	1H	Maximum length of machine extended logout area (model dependent)
18	CCPROGID	DS	1D	User identification
20	FAILADD	DS	8H	Active I/O units
30	FAILCCW	DS	1D	Failing CCW
38	FAILCSW	DS	1D	Failing CSW
40	FAILECSW	DS	1F	Failing ECSV
40	ORG FAILECSW			
	IGPRGFLG	DS	CL1	Program flag bits
	<u>Bits defined in IGPRGFLG</u>			
	CCHSIOB	EQU	X'80'	Start I/O bit
	CCHINTB	EQU	X'40'	Interrupt bit
	CCHTIO	EQU	X'20'	Test I/O bit
	CCHHIO	EQU	X'10'	Halt I/O bit
	CCHSNSB	EQU	X'04'	Sense data stored bit
	CCHCNNTB	EQU	X'02'	Count valid bit
	CCHNRYB	EQU	X'01'	No retry bit

CCHREC

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
41	IGBLAME DS CL1	Probable source of error
	Bits defined in IGBLAME	
	CCHCPU EQU X'80'	Processor is source of error
	CCHCHNL EQU X'40'	Channel is source of error
	CCHSCUB EQU X'20'	Storage control unit is source of error
	CCHSTG EQU X'10'	Storage is source of error
	CCHINTFC EQU X'08'	Control unit is source of error
42	IGVALIDDB DS CL1	Validity indicator bits
	Bits defined in IGVALIDDB	
	CCHINTFV EQU X'80'	Interface address valid
	CCHRCV EQU X'10'	Sequence code valid
	CCHUSV EQU X'08'	Unit status valid
	CCHCMDV EQU X'04'	Command address valid
	CCHCAV EQU X'02'	Channel address valid
	CCHDAV EQU X'01'	Device address valid
43	IGTERMSQ DS CL1	Termination/sequence code bits
	Bits defined in IGTERMSQ	
	COMP SYS EQU X'C0'	System reset
	COMPSEL EQU X'80'	Selective reset
	COMPFES EQU X'40'	Stop, Stack, or normal termination
	CCHIOH EQU X'10'	I/O interface inoperative
	COMPID EQU X'00'	Interface disconnect
	CCHDI EQU X'08'	I/O error alert
	Sequence Code Bits	
	RTCODE0 EQU X'00'	Retry code values for the constructed ECSW
	RTCODE1 EQU X'01'	
	RTCODE2 EQU X'02'	
	RTCODE3 EQU X'03'	
	RTCODE4 EQU X'04'	
	RTCODE5 EQU X'05'	
	RTCODE6 EQU X'06'	
	RTCODE7 EQU X'07'	
44	CCDEVTYP DS 1F	CP device type
48	CCHANID DS CL1	Channel identification
49	CCHCUA DS CL3	Actual failing device address
4C	CCHCHCUA DS 2X	Address from machine location X'EA'
4E	CCHCLOGL DS 2X	Length of channel logout
	CCHSIZE EQU (*-CCHREC)/8	Size in doublewords (X'0B')
50	CCHLOG80 DS OCL112	2880 channel - 112 bytes
50	CCHLOG70 DS OCL24	2870 channel - 24 bytes
50	CCHLOG60 DS OCL24	2860 channel - 24 bytes
50	CCHADDR DS 1F	Unit address stored by integrated channel
	CCHSIZE1 EQU (*-CCHREC)	Size in bytes for integrated channel
54	CCHLOG45 DS OCL96	Model 145 integrated channel (96 bytes)
54	CCHLOG35 DS OCL24	Model 135 integrated channel (24 bytes)

CCPARM: COMMUNICATIONS CONTROLLER PARAMETER LIST

CCPARM provides control information used for loading and controlling the 370X Communication Controller Network Control Program, Emulation Program, and Partitioned Emulation Program and their attached resources.

0	CCPNAME							
8	CCPADDR				CCPSIZE			
10	CCPPSIZE				CCPENTRY			
18	C*1		C*2		C*3	/C*4//	CCFSTOR	
20	CCPHBFSZ		CCPHBFNO		C*5		C*6	CCPMAXID
28	CCPRESID							
.								
.								
.								

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CCPNAME DS	CPNAME specified in NAMENCP macro
8	CCPADDR DS	Origin of control program image
2	CCPSIZE DS	Control program size in bytes
10	CCPPSIZE DS	Parameter list size in bytes
14	CCPENTRY DS	Control program entry point address
18	CCPTYPE DS	Control program type flag
	<u>Bits defined in CCPTYPE</u>	
	CCPTNCP EQU X'01'	Network control program
	CCPTEP EQU X'02'	270x emulation program
	CCPTPEP EQU X'03'	Partitioned emulation program
19	CCPCAONE DS	C*2 First channel adapter type flag
1A	CCPCATWO DS	C*3 Second channel adapter type flag
	<u>Bits defined in CCPAONE and CCPATWC</u>	
	CCPTYPE1 EQU X'01'	Channel adapter type 1
	CCPTYPE2 EQU X'02'	Channel adapter type 2
1B	CCPRSV1 DS	1X C*4 Reserved for IBM use
1C	CCPSTOR DS	1F 370x storage size specified (in bytes)
20	CCPHBFSZ DS	1H Buffer size from HOST macro
22	CCPHBFNO DS	1H Number of buffers in read list
24	CCPPAD0 DS	1X C*5 First buffer pad count (in bytes)
25	CCPPAD1 DS	1X C*6 Subsequent buffer pad count
	<u>HOST Values Required by VM/370 Support for 370x</u>	
	CCPVPA0 EQU 34	34-byte pad in first bisynchronous transmitter buffer
	CCPVPA1 EQU 34	34-byte pad in subsequent buffers
26	CCPMAXID DS	1H Highest resource ID defined
28	CCPRESID DS	1F Resource ID definition
	<u>ORG</u>	
28	CCPRSTYP DS	CCPRESID Definition breakdown
29	CCPRSTAT DS	1X Resource type flag
2A	CCPRSTEP DS	1X Resource initial status flags
	CCPRSTAD DS	1H Subchannel address when in EP mode

CHXBLOK, CHYBLOK

CHXBLOK AND CHYBLOK: VIRTUAL CHANNEL-TO-CHANNEL ADAPTER CONTROL BLOCKS

CHXBLOK and CHYBLOK provide the necessary control for a virtual machine using a virtual channel-to-channel adapter (CTCA). The VDEVREAL field in the VDEVBLCK points to CHXBLOK and CHYBLOK for virtual CTCA.

0	CHXOTHR		CHYOTHR
8	X*1 X*2 X*3 X*4	Y*1 Y*2 Y*3 Y*4	
10	CHXNCCW		CHYNCCW
18	CHXRCNT		CHYRCNT
20	CHXSTAT CHXYADD	CHYSTAT CHYXADD	
28	CHXIDAW		CHYIDAW
30	CHXCNCT		CHYCNCCT
38	CHXDATN		CHYDATN

Note: As indicated in the illustrated block, the CHXBLOK and CHYBLOK are interleaved with a 4-byte displacement. The X-side VDEVBLCK points to the +0 slot, the Y-side VDEVBLCK points to the +4 slot; however, once the virtual connection is made, either side can be the X-side or the Y-side since this interleaved arrangement makes the control block references completely symmetrical. The dual DSFCT definition allows the active adapter (defined to be the X-side, arbitrarily) to reference both adapter sides concurrently without knowing whether it is at +0 or +4.


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning			
	CHXBLOK	X-side channel adapter block			
0	CHXOTHR	DS	2F		VMELOCK address of Y-side adapter user
8	CHXFLAG	DS	1X	X*1	Internal processing flags
<u>Bits defined in CHXFLAG</u>					
	CHBMNOP	EQU	X'80'	Modified NOP command issued (also in CMDT)	
	CHBM370	EQU	X'40'	CTCA operating in System/370 mode	
	CHBATTN	EQU	X'20'	Attention pending from Y-side	
	CHBREST	EQU	X'10'	CTCA has been reset X-side and Y-side	
	CHBEOF	EQU	X'08'	Force EOF to next READ instruction	
	CHBHIO	EQU	X'04'	Halt I/O or halt device issued	
	CHBWAIT	EQU	X'02'	CPEXELOCK available for channel reconnect	
	CHBCENT	EQU	X'01'	Channel end has been preserved on SIO	
9	CHXCMDB	DS	1X	X*2	Active CCW command byte buffer
A	CHXCMDT	DS	1X	X*3	Active CCW command type (RD, WR, etc.)
<u>Bits defined in CHXCMDT</u>					
	CHBCTNL	EQU	X'40'	Control, other than NOP	
	CHBRDBK	EQU	X'20'	Read backward	
	CHBWEOF	EQU	X'10'	Write EOF	
	CHBSCMD	EQU	X'08'	Sense command byte	
	CHBSADS	EQU	X'04'	Sense adapter status	
	CHBREAD	EQU	X'02'	Read	
	CHBWRIT	EQU	X'01'	Write	

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
B	CHXPKEY	DS 1X X*4 Virtual CAW protection key
C		DS 4X "Other" adapter control flags
10	CHXNCCW	DS 2F Next CCW fetch address (real)
18	CHYRCNT	DS 2F Remaining CCW data count
20	CHXSTAT	DS 1H Device status accumulation field
22	CHXYADD	DS 1H Virtual address of Y-side adapter
24		DS 2H "Other" adapter control flags
28	CHYIDAW	DS 2F Active indirect data list word
30	CHYCNCCT	DS 2F CPEXEOK for channel reconnect
38	CHYDATN	DS 2F IOELCK address for deferred I/O interrupt
	CHBSIZE EQU	(*-CHXBLOK)/8 Total block size in doublewords (X'08')
	CHYBLOK	Y-side channel adapter block
0	CHYOTHR	DS 2F VMELCK address of X-side adapter user
8	CHYFLAG	DS 1X Y*1 Internal processing flags
	<u>Bits defined in CHYFLAG</u>	
	CHBMNOP EQU	X'80' Modified NOP command issued (also in CMDT)
	CHBM370 EQU	X'40' CTCA operating in System/370 mode
	CHBATTN EQU	X'20' Attention pending from X-side
	CHBREST EQU	X'10' CTCA has been reset X-side and Y-side
	CHBEEOF EQU	X'08' Force EOF to next READ instruction
	CHBHIO EQU	X'04' Halt I/O or halt device issued
	CHBWAIT EQU	X'02' CPEXEOK available for channel reconnect
	CHBEENT EQU	X'01' Channel end has been preserved on SIO
9	CHYCMDB	DS 1X Y*2 Active CCW command byte buffer
A	CHYCMDT	DS 1X Y*3 Active CCW command type (RD, WR, etc.)
	<u>Bits defined in CHYCMDT</u>	
	CHBCNTL EQU	X'40' Control, other than NOP
	CHBRDBK EQU	X'20' Read backward
	CHBWEOF EQU	X'10' Write EOF
	CHBSCMD EQU	X'08' Sense command byte
	CHBSADS EQU	X'04' Sense adapter status
	CHBREAD EQU	X'02' Read
	CHBWRIT EQU	X'01' Write
B	CHYPKEY	DS 1X Y*4 Virtual CAW protection key
C		DS 4X "Other" adapter control flags
10	CHYNCCW	DS 2F Next CCW fetch address (real)
18	CHYRCNT	DS 2F Remaining CCW data count
20	CHYSTAT	DS 1H Device status accumulation field
22	CHYXADD	DS 1H Virtual address of X-side adapter
24		DS 2H "Other" adapter control flags
28	CHYIDAW	DS 2F Active indirect data list word
30	CHYCNCCT	DS 2F CPEXEOK for channel reconnect
38	CHYDATN	DS 2F IOELCK address for deferred I/O interrupt

CKPBLOK

CKPBLOK: TELECOMMUNICATIONS CHECKPOINT BLOCK

CKPBLOK provides checkpoint information needed for VM/370 warm start recovery for 3704/3705 Communication Controllers and enabled lines and resources. The RDEVCKPT field of the RDEVBLOK points to CKPBLOK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CKPSIZE DS	1H Size of checkpoint block in doublewords
2	CKPRMAX DS	1H Number of resources checkpinted
4	CKPRSV1 DS	1F Reserved for IBM use
8	CKPNAME DS	CL8 370x control program reference name
10	CKPBITS DS	0D Bit map of enabled lines or resources

CKPBKSZ EQU (CKPBITS-CKPBLOK)/8 Header size in doublewords

CONTASK: CONSOLE I/O PACKAGE

CONTASK contains data and control information pertinent to the control and communication between virtual and real terminal console tasks and command streams. The RDEVCON field of the RDEVBLOK and the NICQPNT field of the NICELOK point to CONTASK.

0	CONPNT		CONRETN
8	C*1 C*2 CONTSKSZ		CONUSER
10			CONCCW1
18			CONCCW2
20			CONCCW3
28			CONCCW4
30			CONDATA
.			.
.			(Variable Length)

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CONPNT	DS 1F Pointer to next CONTASK
4	CONRETN	DS 1F Pointer to SAVEAREA for return
8	CONSTAT	DS 1X C*1 CONTASK status control flags
	<u>Bits defined in CONSTAT</u>	
	CONOUTPT	EQU X'80' Generate CONTASK output
	CONRESP	EQU X'40' Response expected from this CCNTASK
	CONACTV	EQU X'20' CONTASK is active on real device
	CONCNTL	EQU X'10' This is a control CONTASK only
	CONESCP	EQU X'08' CONTASK contains device dependent data
	CONTRY	EQU X'04' Retry operation in progress
	CONSPLT	EQU X'02' Output data being split via RDEVLEN
	CONSYNC	EQU X'01' CONTASK for synchronization only
9	CONPARM	DS 1X C*2 DMKQCN parameter flags (see "Appendix A. CP and RSCS Equate Symbols")
A	CONTSKSZ	DS 1H CONTASK size in doublewords
C	CONUSER	DS 1F Address of VMBLOK for destination user
10	CONCCW1	DS 1D First console I/O CCW
	ORG CONCCW1	
10	CONADDR	DS 1F CCW data address
14	CONFAG	DS 1X CCW flag bits
15	CONDWC	DS 1X DIAGNOSE write control
16	CONCNT	DS 1H CCW byte count
	ORG CONADDR	
10	CONCOMND	DS 1X CCW command code
18	CONCCW2	DS 1D Second console I/O CCW
20	CONCCW3	DS 1D Third console I/O CCW
28	CONCCW4	DS 1D Fourth console I/O CCW
30	CONDATA	DS 0C Output data area (variable length)
	CONTSIZE	EQU (*-CONTASK)/8 CONTASK size in doublewords

CONTASK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>Bits redefined in CONCCW for 370x Network Control Program</u>		
	ORG CONCCW3+2	
2A	CONSRID DS 1H	Source identifier
2C	CONDEST DS 1H	Destination resource ID
2E	CONRTAG DS 1H	Request tag for this CONTASK
30	CONSYSR DS 1X	370x system response byte
31	CONEXTR DS 1X	370x extended response byte
32	CONTCMD DS 1H	Bisynchronous terminal command modifier
34	CONFUNC DS 1X	Basic device function control flags
35	CONDFLG DS 1X	Basic device data control flags
36	COND_CNT DS 1H	Text data length
<u>Bits redefined for 3270 Remote Support</u>		
	ORG CONCCW4	
30	CONLABEL DS 1X	Return index value
31	CONSTX DS 1X	Start text character
33	CONESC DS 1X	Escape character
33	CONCMD DS 1X	Command code for remote station
34	CONWCC DS 1X	Write control character
35	CONSBA DS 1X	Start buffer address
36	DS 1H	Buffer address

CORTABLE: STORAGE ALLOCATION TABLE

CORTABLE maintains the status and ownership of each page frame of real storage for use by page management routines. The ACORETBL field of the PSA points to CORTABLE.


0	CORFPNT			COREPNT
8	C*1 CORSWPNT			CORPGPNT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CORFPNT DS 1F	Pointer to next CORTABLE entry in queue
<u>Entry definition for Page Ownership</u>		
	ORG CORFPNT	
	CORVM DS 1F	Pointer to VMBLOK of page owner
4	CORBPN T DS 1F	Pointer to previous CORTABLE entry in queue
8	CORSWPNT DS 1F	Pointer to SWPTABLE for page
C	CORPGPNT DS 1F	Pointer to PAGTABLE for page
<u>Bits defined in CORFLAG</u>		
	CORIOLCK EQU X'80'	Page locked for I/C or CORLCNT is greater than 0
	CORCFLCK EQU X'40'	Page locked by console function
	CORFLUSH EQU X'20'	Page is in FLUSH list
	CORFREE EQU X'10'	Page is in FREE list
	CORSHARE EQU X'08'	Page is shared
	CORRSV EQU X'04'	Page is reserved
	CORCP EQU X'02'	Page belongs to the control program
	CORDISA EQU X'01'	Page disabled, not available
<u>Entry Definition if Page Is Locked</u>		
	ORG COREPNT	
4	CORLCNT DS 1F	Page lock count for CORIOLCK
<u>Entry Definition if Page Is in Transit</u>		
	ORG CORFLAG	
8	CORCODE DS 1X	C*1 DASD operation code for DMKPAGIO

CPEXBLOK

CPEXBLOK: CP EXECUTE BLOCK

CPEXBLOK maintains register values and addressing information (module address or entry point address) to handle a delayed transfer of control. Stacked CPEXBLOKs are queued off DMKDSPRQ.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CPEXFPNT DS	1F Pointer to next CPEXBLOK
4	CPEXBPNT DS	1F Pointer to previous CPEXBLOK
8	CPEXMISC DS	1F Use varies with stacker
<u>Definition for DMKSTK and DMKDSP</u>		
	ORG CPEXMISC	
	CPEXTYPE DS	1X Type of block on CPEXBLOK chain
<u>Bits defined in CPEXTYPE</u>		
	CPEXDEFR EQU	X'80' Deferred interrupt request
	CPEXPRIOR EQU	X'40' CPEXBLOK with priority
	CPEXLPSW EQU	X'20' Load PSW to go to execution address
	DS	1X Reserved for IBM use
	CPEXPROC DS	1H Address of processor related to block
C	CPEXADD DS	1F Return address
10	CPEXREGS DS	16F Execute registers
<u>For CPEXREGS Area</u>		
	ORG CPEXREGS	
10	CPEXR0 DS	1F Registers 0 through 15
14	CPEXR1 DS	1F
18	CPEXR2 DS	1F
1C	CPEXR3 DS	1F
20	CPEXR4 DS	1F
24	CPEXR5 DS	1F
28	CPEXR6 DS	1F
2C	CPEXR7 DS	1F
30	CPEXR8 DS	1F
34	CPEXR9 DS	1F
38	CPEXR10 DS	1F
3C	CPEXR11 DS	1F
40	CPEXR12 DS	1F
44	CPEXR13 DS	1F
48	CPEXR14 DS	1F
4C	CPEXR15 DS	1F
	CPEXSIZE EQU	(*-CPEXBLOK)/8 Size in doublewords (X'0A')

DDRREC: RECONFIGURATION MACRO

DDRREC is used in the SVC 76-initiated error recording process for type 60 DASD dump restore (DDR) dynamic device reallocation records. The reallocation records contain the replacement of the virtual "FROM" and "TO" control unit addresses (CUA) by the real addresses of the real DASD devices.


0	DDRKEYN	D*1 /D*2/ /D*3/ /D*4/ //IDRSPE1 ///////////////
8	DDRDTEM	DDRTMEN
10		DDRCPID
18		DDRJOB
20	DDRVOL1	DDRVOL2
28	DDRVOL2 (cont.)	D*5 DDRCUA1
30	DDRDEV1	D*6 DDRCUA2
38	DDRDEV2	

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DDRKEYN	DS 1H Type and operating system
2	DDRSWS1	DD 1C D*1 Switch byte
3	DDRSWS2	DS 1C D*2 Reserved for IBM use
4	DDRSWS3	DS 1C D*3 Reserved for IBM use
5	DDRRECNT	DS 1C D*4 Reserved for IBM use
6	DDRSPE1	DS 1H Reserved for IBM use
8	DDRDTEM	DS 1F Date
C	DDRTMEN	DS 1F Time
10	DDRCPID	DS 2F Processor identification and model number
<u>Device Dependent Data</u>		
18	DDRJOB	DS 8X Job using FROM device
20	DDRVOL1	DS 6X Volume serial FROM device
26	DDRVOL2	DS 6X Volume serial TO device
2C	DDRDEVP1	DS 1X D*5 Device identification of FROM DASD
2D	DDRCUA1	DS 3X Primary CUA of FROM device
30	DDRDEV1	DS 4X Device type FROM device
34	DDRDEVP2	DS 1X D*6 Device identification TO DASD
35	DDRCUA2	DS 3X Primary CUA of TO device
38	DDRDEV2	DS 4X Device type of TO device
DDRSIZE EQU (*-DDRREC)		
DDR record size		

DMPINREC

DMPINREC: DUMP FILE INFORMATION RECORD


DMPINREC retains vital system register and storage location values necessary for the CPDUMP file. See also DMPKYREC.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DMPGPRS DS	16 general registers
40	DMPCR DS	16 control registers
80	DMPPPRS DS	Four floating-point registers (if floating-point feature is installed on machine)
A0	DMPTODCK DS	Time-of-day clock
A8	DMPCPUTM DS	Processor timer
B0	DMPCCKCOM DS	Time-of-day clock comparator
B8	DMPPFLAG DS	S*1 Flag byte
<u>Bits defined in DMPPFLAG</u>		
	HALFPAGE EQU X'80'	When on, last record in DUMP file is 2K
B9	DMPRSV1 DS	S*2 Reserved for IBM use
BA	DMPPROCA DS	Abending processor address
BC	DMPSYSRV DS	System generated storage size
C0	DMPLCORE DS	Absolute storage locations 0 through 255
1C0	DMPPRFRG DS	Prefix register
1C4	DMPAEND DS	Abend code for failing processor
1C8	DMPPGMAP DS	Bit map indicating which pages appear in the DUMP file (each bit represents a 4K block)

DMPKYREC: DUMP FILE KEY STORAGE RECORD


DMPKYREC contains the storage keys of each 2K block of main storage at the time of SVC 0 or a PSW restart condition. DMPKYREC and DMPIINREC are used for debugging operations.



Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
0	DMPKEYS	DS	4096X	Main storage keys
0	DMPKEY	ORG DS	DMPKEYS 1X	S*1 Storage key for each 2K block

DMPTBREC: DUMP FILE SYMBOL TABLE RECORD

DMPTBREC is a listing of all entry points in the system and their locations.



Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
C	DMPSYMEM	DS	341XL12	Symbol table entries
0	DMPSYMNN	ORG DS	DMPSYMEM CL8	CSECT or entry point name
8	DMPSYMVA	DS	A	Location in main storage of this symbol

ECBLOK

ECBLOK: EXTENSION TO VMBLOK FOR VIRTUAL MACHINE WITH RELOCATE

ECBLOK provides an extension to the VMBLOK for virtual machine operation in System/370 extended control mode. The VMCEEXT field of the VMBLOK points to ECELCK.

0	EXTCR0		EXTCR1
8	EXTCR2		EXTCR3
10	EXTCR4		EXTCR5
18	EXTCR6		EXTCR7
20	EXTCR8		EXTCR9
28	EXTCR10		EXTCR11
30	EXTCR12		EXTCR13
38	EXTCR14		EXTCR15
40	EXTSHCR0		EXTSHCR1
48	EXTSHLEN EXTVSEGS		EXTSTOLD
50	EXTSHSEG		EXTSEGLN EXTARCH
58	EXTPERAD		EXTPERCD EXTCPY
60	EXTCPTMR		
68	EXTCPTRQ		EXTCCTRQ


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	EXTCR0	DS 1F Virtual control register 0; architecture controls
4	EXTCR1	DS 1F Virtual control register 1; segment table pointer
8	EXTCR2	DS 1F }
C	EXTCR3	DS 1F }
10	EXTCR4	DS 1F }
14	EXTCR5	DS 1F }
18	EXTCR6	DS 1F }
1C	EXTCR7	DS 1F }
20	EXTCR8	DS 1F }
24	EXTCR9	DS 1F }
28	EXTCR10	DS 1F }
2C	EXTCR11	DS 1F }
30	EXTCR12	DS 1F }
34	EXTCR13	DS 1F }
38	EXTCR14	DS 1F }
3C	EXTCR15	DS 1F }

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
40	EXTSHCR0	DS 1F	Shadow control register 0
44	EXTSHCR1	DS 1F	Shadow control register 1
48	EXTSHLEN	DS 1H	Length of shadow SEGTABLE in bytes
4A	EXTVSEGS	DS 1H	Length of virtual SEGTABLE in bytes
4C	EXTSTOLD	DS 1F	Control register 1 value corresponding to tables
50	EXTSHSEG	DS 1F	Real address of shadow SEGTABLE
54	EXTSEGLN	DS 1H	Length of shadow SEGTABLE in doublewords
56	EXTARCH	DS 1H	Architecture control index
58	EXTPERAD	DS 1F	Address of instruction PFR interrupt
5C	EXTPERCD	DS 1H	PER code to be reflected
5E	EXTCOPY	DS 1H	Length code from active SEGTABLE entry
60	EXTCPTRM	DS 1D	Virtual processor timer
68	EXTCPTRQ	DS 1F	Address of TRQBLOK for processor timer
6C	EXTCCTRQ	DS 1F	Address of TRQBLOK for clock comparator
	EXTSIZE	EQU $(*-ECBLOK)/8$	ECEBLOK size in doublewords (X'0E')

ERRBLOK

ERRBLOK: ERROR BLOCK USED TO BUILD OER/MDR

ERRBLOK contains data describing an error condition such as a channel failure or a device failure.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	ERRKEY DS 3X	Key used to determine OER/MDR processing
3	ERRSV1 DS 1X	E*1 Reserved for IBM use
4	ERRSV2 DS 1F	Reserved for IBM use
8	ERRTIME DS 1F	Time record was built
C	ERRDATE DS 1F	Date record was built
	ERRHEADR EQU (**-ERRBLOK)	Size of header in bytes
10	ERRCCW DS 1D	Failing CCW
	ORG ERRCCW	
10	ERRMIOB DS (IOBSIZE) D	Copied IOELCK
	ERRMIOER DS (IOBRSIZE) D	Copied IOERELOCK
	ORG ERRCNT	
10	ERRCCNT DS 2X	Size of CONTASK data buffer
10	ERRCONT DS 0C	CONTASK data buffer (variable length)
	ORG ERRVOLID	
18	ERRVOLID DS 6X	Valid of failing device
1E	ERRSDR DS 1X	E*2 SDRFLAGS from SDRBLOK
1F	ERRCORR DS 1X	E*3 Correlation count for MDR record
20	ERRPARM DS 2D	Device dependent parameter string
30	ERRIOB DS (IOBSIZE) D	Copied IOELCK, see IOBLOK for details
70	ERRIOER DS (IOERSIZE) D	Copied IOERELCK, see ICERBLCK for details
	ERRSIZE EQU (**-ERRSIZE)/8	ERRBLOK size in doublewords

IOBLOK: I/O TASK CONTROL BLOCK

IOBLOK contains information required to perform I/O operations. The I/O request initiator for the I/O operation is either a CP-initiated or virtual machine-initiated event. There are five pointers to the IOBLOK: RCHFICB field of the RCHELOK, RCHFICE field of the RCUBLOK, RDEVAIOB field of the RDEVBLOK, VDEVFIOE field of the VDEVBLOK, RDEVFIOB field of the RDEVBLOK.

0	IOBRADD	I*1	I*2		IOBLINK
8	IOBFPNT				IOBEPNT
10	IOBCYL		IOBVADD		IOBMISC
18	IOBUSER				IOBIRA
20	IOBCAW				IOBRCAW
28				IOBCSW	
30	IOBIOER				IOBMISC2
38	I*3		I*4	//IOBRSV2// //////////IOBRSV3//////////	


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	IOBRADD DS 1H	Real device address for SIC
2	IOBFLAG DS 1X I*1	IOBLCK flags
	<u>Bits defined in IOBFLAG</u>	
	IOBCP EQU X'80'	CP-generated I/O operation
	IOBRSTRT EQU X'40'	Restarted operation - IOBRCAW
	IOBSPLT EQU X'20'	DASD - CP split seek operation
	IOBPAG EQU X'10'	IOBLCK created for paging I/O
	IOBRELCU EQU X'08'	Control unit released at initiation
	IOBERP EQU X'04'	I/O task is under control of ERF
	IOBRES EQU X'02'	I/O task has been reset
	IOBHVC EQU X'01'	I/O initiated via DIAGNOSE instruction
3	IOBSTAT DS 1X I*2	IOBLCK status
	<u>Bits defined in IOBSTAT</u>	
	IOBFATAL EQU X'80'	Unrecoverable error in this I/O operation
	IOBFLT EQU X'40'	IOBLCK queued pending completion of a MSS cylinder fault
	IOBPATHF EQU X'20'	Path is fixed, use IOBRADD value
	IOBMINI EQU X'08'	This is a mini-IOBLOK
	IOBALTSK EQU X'04'	DASD channel program has seek to alternate track
	IOBCC3 EQU X'03'	Processing CC 3, not available
	IOBCC2 EQU X'02'	Processing CC 2, channel busy
	IOBCC1 EQU X'01'	Processing CC 1, CSW stored
	IOBCC0 EQU X'00'	Processing I/O interrupt

IOBLOK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
4	IOBLINK DS 1F	Pointer for multipath IOBLCK chain
8	IOBFPNT DS 1F	Pointer to next IOBLOK in queue
C	IOBBPNT DS 1F	Pointer to previous IOBLOK in queue
	IOBMSIZE EQU $(\text{*-IOBLOK})/8$	Multiple path IOBLOK size in doublewords (X'02')
10	IOBCYL DS 1H	DASD - seek cylinder for this IOBLOK
12	IOBVADD DS 1H	Virtual device address
14	IOBMISC DS 1F	Use varies according to caller
18	IOBUSER DS 1F	Pointer to VMBLCK of user
1C	IOBIRA DS 1F	IOBLCK interrupt return address
20	IOBCAW DS 1F	Pointer to CCW chain
24	IOBRCAW DS 1F	Pointer to restart CCW chain
28	IOBCSW DS 1D	Real CSW for I/O operation
30	IOBIOER DS 1F	Pointer to IOERBLOK with sense byte
34	IOBMISC2 DS 1F	Use varies according to caller
38	IOBSPEC DS 1X	I*3 IOBLCK special requests flag
	<u>Bits defined in IOBSPEC</u>	
	IOBTIO EQU X'80'	IOBLCK request for a TIO
	IOBHIQ EQU X'40'	IOBLCK request for a HIO
	IOBSIOF EQU X'20'	Virtual SIO fast release
	IOBIMSTK EQU X'10'	Shut down SIR function
	IOBUNSL EQU X'08'	IOBLCK resulting from unsolicited interrupt
	IOBCOPY EQU X'04'	I/O block associated with a COPY request
	IOBSENS EQU X'02'	Sense operation for COPY request
	IOBTRPND EQU X'01'	Virtual trace pending on this I/O block
39	IOBSPEC2 DS 1X	I*4 IOBLCK special requests flag second byte
	<u>Bits defined in IOBSPEC2</u>	
	IOBWRAP EQU X'80'	Input/output task for AUTOPOLL wrap list
	IOBCLN EQU X'40'	VDEVLOK locked when CCW gct control
	IOBUNREL EQU X'20'	Input/output task contains release, DMKUNT must process
	IOBUCL EQU X'10'	Unit check status
	IOBSNSIO EQU X'08'	Normal sense operation in progress
	IOBREL EQU X'04'	Channel program contains CF release
3A	IOBRSV2 DS 1H	Reserved for IBM use
3C	IOBRSV3 DS 1F	Reserved for IBM use
	IOBSIZE EQU $(\text{*-IOBLOK})/8$	IOBLCK size in doublewords (X'08')
	<u>For CP IOBLOKS</u>	
	ORG IOBVADD	
12	IOBRCNT DS 1H	Retry count

IOERBLOCK: I/O ERROR INFORMATION BLOCK

IOERBLOCK contains information related to I/O and channel errors. This entails error retry, operator message information, and SDR (Statistical Data Recording) IOERBLOCK related to I/O equipment. There are three pointers to the IOERBLOCK: RDEVIOER field of the RDEVBLOK, VDEVIOER field of the VDEVBLOK, IOPIOER field of the ICBLCK.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	IOERPNT DS 1F	Pointer to next IOERBLOCK
4	IOERLOC DS 1F	Address of CCWs used in recovery
8	IOERDW DS 1H	Size (in doublewords) of storage needed to construct CCWs
A	IOERMSG DS XL3	Communications with error recording processor and message writer
	ORG IOERMSG	Breakdown for DMKMSW
A	IOERNUM DS 1X	Message number for message routine
B	IOERIND3 DS 1X	Indicators for message routine
	<u>Bits defined in IOERIND3</u>	
	IOERIGN EQU X'80'	Allow IGNORE response
	IOERTRY EQU X'40'	Allow RETRY response
	IOERCAN EQU X'20'	Allow CANCEL response
	IOERREC EQU X'10'	Error occurred during recovery action
	IOERDASD EQU X'08'	Home address is present
	IOERDEC EQU X'04'	Operator decision is necessary
	IOERINFO EQU X'02'	Informational message
	IOERACT EQU X'01'	Operator action is required

IOERBLOK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
C	IOERIND4 DS 1X	Indicators for message writer
	<u>Bits defined in IOERIND4</u>	
	IOERIGNR EQU X'80'	Operator responded "ignore"
	IOERSTRT EQU X'40'	Operator responded "retry"
	IOERCNCL EQU X'20'	Operator responded "cancel"
D	IOERFLG1 DS 1X	I*1 Flag byte for error recovery routines
	<u>Bits defined in IOERFLG1</u>	
	IOERPEND EQU X'80'	Pending device end interrupt from interrupt request
	IOERCLN EQU X'40'	Tape cleaning in progress
	IOERERP EQU X'40'	Spooling - error routine in control
	IOERFSR EQU X'20'	Forward space record being executed
	IOERDEPD EQU X'20'	Spooling - waiting for device end
	IOERBSR EQU X'10'	Backspace record being executed
	IOERDERD EQU X'10'	Spooling - device end received
	IOERERG EQU X'08'	Erase gap command in progress
	IOERXERP EQU X'08'	Spooling - error routine getting OBR data
	IOERORA EQU X'04'	Opposite recovery action in progress
	IOERSUPP EQU X'02'	CCW has suppress data transfer bit on
	IOERVLD EQU X'01'	Read opposite recovery successful
E	IOERFLG2 DS 1X	I*2 Second flag byte for error recovery program use
	<u>Bits defined in IOERFLG2</u>	
	IOERSTAT EQU X'80'	Statistical data being uncached
	IOERHA EQU X'40'	DASD home address being read
	IOERCAL EQU X'20'	Standalone recalibrate being executed
	IOERECF EQU X'10'	Error correction function
	IOERRBK EQU X'10'	Read backward command
	IOERREW EQU X'08'	Tape rewind being executed
	IOERCYLR EQU X'04'	Cylinder (in sense byte) has been relocated
	IOERMWSW EQU X'04'	Message writer is active
	IOERCEMD EQU X'02'	Intensive recording mode
	IOERVOL1 EQU X'01'	DASD valid being read
F 10 18 20	IOERWRK DS 1X IOERADR DS 1D IOERCSW DS 1D IOERCCW DS 1D	I*3 Miscellaneous work byte Home address for DASD devices CSW associated with error Sense CCW used to sense the real device
20 26	ORG IOERCCW IOERVSER DS CL6 IOERLEN DS 1H	Breakdown of sense CCW field Volume serial number for statistical data Number of sense bytes present
2C	IOERFLG3 DS 1X	I*4 Third flag byte for SDR use
	<u>Bits defined in IOERFLG3</u>	
	IOERREAD EQU X'80'	SDR READ operation flag
	IOERALTR EQU X'40'	Alternate track retry is in progress
	IOERRDRO EQU X'20'	Read home address, read only is in progress
2D	IOERSV1 DS XL3	Reserved for IBM use
30 30	IOERSNSZ EQU 32X IOERDATA DS (IERSNSZ/8) D	Number of sense bytes supported Sense bytes associated with error
30 34	ORG IOERDATA IOERECSW DS 1F IOERCHAN DS 1X	Breakdown for channel check handler ECSW information from channel lcgout Channel type flag
	IOEREND DS OF	Label for end of IOERBLOK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
50	XOBR3211	Area where additional sense bytes may be appended to IOERBLCK. The format for one of these is described in "XOFR3211: Extended Outboard Recording Block" later in this section.

- Channel Check Reflection Extension



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
50	IOERCEXT DS	OD Extension used only for channel check reflection
50	IOERCCRL DS	F Length of channel check record
54	IOERCCRA DS	F Address of channel check record
58	IOERCUID DS	F Processor identification
5C	IOERCMDL DS	H Processor model number (for example, 0158, 0168, etc.)
5E	IOERMCEL DS	H Maximum length of machine check extended logout area (model-dependent)
60	IOERUID DS	D User identification
68	IOERFADD DS	8H Active input/output units
78	IOERCCCW DS	D Failing CCW
80	IOERCCSW DS	D Failing CSW
88	IOERZCSW DS	F Failing ECSW
8C	IOERDTYP DS	F CP device type
90	IOERCHID DS	CL1 I*5 Channel identification
	<u>Channels defined in IOERCHID</u>	
	IOER2860 EQU	X'05' Standalone selector (2860)
	IOER2870 EQU	X'06' Standalone multiplexer (2870)
	IOERB80 EQU	X'07' Standalone block multiplexer (2880)
	IOERS80 EQU	X'08' Selector channel (2880)
91	IOERCCUA DS	CL3 Actual failing device address
94	IOERMCUA DS	CL2 Address from processor location X'BA'
96	IOERLOGL DS	CL2 Length of channel logout

IOERBLOK

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
98	IOERCLOG	DS F	Channel logout area
98	IOERLG80	ORG DS CL112 IOERCLOG	2880 channel (112 bytes)
98	IOERLG70	ORG DS CL24 IOERCLOG	2870 channel (24 bytes)
98	IOERLG60	ORG DS CL24 IOERCLOG	2860 channel (24 bytes)
98 9C	IOERRADDR IOERLG33	ORG DS F CL640 IOERCLOG	Unit address stored by integrated channel 3033 channel (640 bytes)
9C	IOERLG45	ORG DS CL96 IOERLG33	145 integrated channel (96 bytes)
9C	IOERLG35	ORG DS CL24 IOERLG33	135 integrated channel (24 bytes)
	IOERSIZE EQU	(*-IOERBLOK)/8	IOERELOK size in doublewords

IRMBLOK: INTENSIVE ERROR RECORDING MODE BLOCK

IRMBLOK provides the information necessary for the implementation of intensive recording mode via CP SET RECORD command. Intensive recording mode allows the recording of unit check errors from a specified device whose sense data matches the values selected.


0	IRMFWPTR	IRMLADD		IRMLMT	
8	I*1 I*2 I*3 I*4	IRMLMTCT		I*5 I*6	

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	IRMFWPTR DS	1F Reserved for IBM use
4	IRMLADD DS	1H Device address to be monitored
6	IRMLMT DS	1H Limit count - record every <u>n</u> th error
8	IRMBYT1 DS	1X I*1 First sense byte specified
9	IRMBIT1 DS	1X I*2 Sense bit within first sense byte
A	IRMBYT2 DS	1X I*3 Second sense byte specified
B	IRMBIT2 DS	1X I*4 Sense bit within second sense byte
C	IRMLMTCT DS	1H Summary count for limit detection
E	IRMMAXCT DS	1X I*5 Count of recordings made for this request
F	IRMFLG DS	1X I*6 Flag byte
<u>Bits defined in IRMFLG</u>		
	IRMAND EQU X'80'	AND condition specified
	IRMOR EQU X'40'	OR condition specified
	IRMSIZE EQU (*-IRMBLOK)/8	IRMELOK size in doublewords (X'02')

JPSCBLOK

JPSCBLOK: JOURNALING AND PASSWORD SUPPRESSION CONTROL BLOCK


The JPSCBLOK is a part of DMKSYS. It is referenced via the EXTERNAL symbol DMKSYSJR. It is used to control the LOGON/AUTOCLOG/LINK Journaling and Password-on-the-command-line Suppression functions.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	JPSLOGU DS CL8	Userid for LOGON/AUTOCLOG threshold messages
8	JPSLNKU DS CL8	Userid for LINK threshold messages
10	JPSPCHN DS 1F	Anchor for PWDIBLOKS
14	JPSFLAGS DS 1X	J*1 Control flags
<u>Bits defined in JPSFLG</u>		
	LOGONJRL EQU X'80'	LOGON/AUTOLCG journaling ON
	LINKJRL EQU X'40'	Successful LINK journaling ON
	LINKJRL1 EQU X'20'	Invalid password LINK journaling ON
	JRLSQOK EQU X'10'	SET/QUERY JCURNAL enabled
	MASKLOG EQU X'08'	Suppress LOGON password
	MASKLINK EQU X'04'	Suppress LINK password
15	JPSLOGAR DS 1X	J*2 LOGON/AUTOLCG accounting record threshold messages
16	JPSLOGMS DS 1X	J*3 LOGON/AUTOLCG message threshld
17	JPSLOGDS DS 1X	J*4 LOGON/AUTOLCG disable threshold
18	JPSLNKAR DS 1X	J*5 LINK accounting record threshold
19	JPSLNKMS DS 1X	J*6 LINK message threshold
1A	JPSLNKDS DS 1X	J*7 LINK disable threshold
1B	DS XL5	Reserved for IBM use

LOCKBLOK: USERID LOCK CONTROL BLOCK

LOCKBLOK is used to synchronize execution for sections of nonreentrantable code. Locked users are returned to the CPEXBLOK queue when the function being executed completes or no longer requires nonreentrantable resources. LOCKBLOKs are queued off DMKSYSLE.



Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	LOCKNEXT DS	1F	Pointer to the next lock control block
4	LOCKQUE DS	1F	Pointer to CPEXBLOK queue
8	LOCKNAME DS	1D	The name being locked

LOCKSIZE EQU (*-LOCKBLOK)/8 LOCKBLOK size in doublewords (X'02')

MCHAREA

MCHAREA: MACHINE CHECK SAVE AREA

MCHAREA provides CP with statistical data that relates to malfunctions of the real processor, to its buffers, to processor storage for damage assessment, and to the recovery of VM/370.

0	MCHDAMLN		MCHPROCA		MCHREC			
8	MCHCPEX			L*1		MCHRESEV		
10	M*1	M*2	M*3	M*4	M*5	M*6	M*7	M*8
18								
40	N*1	N*2	N*3	N*4	N*5	N*6	N*7	N*8
48	MCHFSAR				MCEFSAV			
50	MCHFSEAV				MCEPDARI			

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MCHDAMGE DS	0H
		Damage assessment area
0	MCHDAMLN DS	1H
		Length of damage assessment area
2	MCHPROCA DS	XL2
		Processor address
4	MCHREC DS	1F
		Machine check record address
8	MCHCPEX DS	1F
		Machine check CPEXBLOCk address
C	MCHMODEL DS	1X
		L*1 Model number for the machine
		<u>Bits defined in MCHMODEL</u>
	MODEL240 EQU	X'18'
	MODEL210 EQU	X'18'
	MODEL200 EQU	X'18'
	MOD3033 EQU	X'14'
	MOD3032 EQU	X'14'
	MOD3031 EQU	X'14'
	MODEL168 EQU	X'10'
	MODEL165 EQU	X'10'
	MODEL158 EQU	X'0C'
	MODEL155 EQU	X'0C'
	MODEL148 EQU	X'08'
	MODEL145 EQU	X'08'
	MODEL138 EQU	X'04'
	MODEL135 EQU	X'04'
	NOMODEL EQU	X'00'
		No support for machine
D	MCHRESEV DS	3X
10	MCHDAMFL DS	OBL8
10	MCHFLAG0 DS	1X
		M*1 System status
		<u>Bits defined in MCHFLAG0</u>
	MCH0HDWR EQU	X'80'
	MCH0SFTR EQU	X'40'
	MCH0USAD EQU	X'20'
	MCH1GERR EQU	X'10'
	MCH0TERM EQU	X'08'
	MCH0QUIT EQU	X'04'
		Hardware recovery
		Software recovery
		User abnormally terminated
		Channel inoperative
		Operating system termination
		Quiet mode in effect


Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
11	MCHFLAG1 DS	1X	M*2	Damage area
	<u>Bits defined in MCHFLAG1</u>			
	MCH1MAIN EQU	X'80'		Main storage
	MCH1BUFF EQU	X'40'		Buffer
	MCH1COST EQU	X'20'		Control storage
	MCH1GERR EQU	X'10'		Indicates channel is inoperative if bit is on
	MCH1PROC EQU	X'08'		Processor
	MCH1TODC EQU	X'02'		Time-of-day clock
	MCH1SYSD EQU	X'01'		System damage
12	MCHFLAG2 DS	1X	M*3	Damage area (continued)
13	MCHFLAG3 DS	1X	M*4	Error type
	<u>Bits defined in MCHFLAG3</u>			
	MCH3INTE EQU	X'80'		Intermittent error
	MCH3SOLD EQU	X'40'		Solid error
	MCH3DATA EQU	X'20'		Data error
	MCH3PROT EQU	X'10'		Protect error
14	MCHFLAG4 DS	1X	M*5	RMS action data
	<u>Bits defined in MCHFLAG4</u>			
	MCH4TOLO EQU	X'80'		Time-out loop
	MCH4REPA EQU	X'40'		Repair
	MCH4STRE EQU	X'20'		Storage reconfiguration
	MCH4BURE EQU	X'10'		Buffer reconfiguration
15	MCHFLAG5 DS	1X	M*6	RMS information status
	<u>Bits defined in MCHFLAG5</u>			
	MCH5INLG EQU	X'80'		Invalid hardware logout
	MCH5INMC EQU	X'40'		Invalid machine check interrupt code
	MCH5IFSA EQU	X'20'		Invalid failing storage address
16	MCHFLAG6 DS	1X	M*7	RMS wait state suffix
17	MCHFLAG7 DS	1X	M*8	DMKMCH status
	<u>Bits defined in MCHFLAG7</u>			
	MCH7SMCR EQU	X'80'		Second machine check recursion
	MCH7VRTM EQU	X'40'		Terminate the virtual machine
	MCH7SYST EQU	X'20'		Terminate the system
	MCH7OPSW EQU	X'10'		Machine check old PSW in problem state
	MCH7VEQR EQU	X'08'		Terminate the virtual=real user
	MCH7SUP EQU	X'04'		DMKMCH under the global system lock
18	MCHLSUM DS	XL40		Summary
40	MCHPDAR DS	OBL8		
40	MCHPDAR0 DS	1X	N*1	Action taken
41	MCHPDAR1 DS	1X	N*2	Failure type
	<u>Bits defined in MCHPDAR1</u>			
	MCHP1SDE EQU	X'80'		Solid storage data error
	MCHP1IDE EQU	X'40'		Intermittent storage data error
	MCHP1SKE EQU	X'20'		Solid SPF key error
	MCHP1IKE EQU	X'10'		Intermittent SPF key error
	<u>Machine Check Communication Area Must Be Cleared Above This Line</u>			
42	MCHPDAR2 DS	1X	N*3	Operating system status
43	MCHPDAR3 DS	1X	N*4	Location of failure
44	MCHPDAR4 DS	1X	N*5	Location of failure
45	MCHPDAR5 DS	1X	N*6	Requested operator awareness
46	MCHPDAR6 DS	1X	N*7	Flag byte

MCHAREA

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
<u>Bits defined in MCHPDAR6</u>			
	MCHP6CBA EQU	X'80'	Change bit active
47	MCHPDAR7 DS	1X	N*8 Flag byte
<u>Bits defined in MCHPDAR7</u>			
	MCH7STCK EQU	X'80'	Interfaces for STACK routine
	MCH7GSTR EQU	X'40'	Interfaces for GETMAIN routine
	MCH7PURG EQU	X'20'	Interfaces for PURGE routine
	MCH7LOGO EQU	X'10'	Interfaces for V=R logoff routine
	MCH7EXIT EQU	X'08'	Interfaces for exit to CP
	MCH7RSRE EQU	X'04'	Interfaces for RELEASE and RESET routines
	MCH7IOEM EQU	X'02'	Interfaces for the recorder
48	MCHFSAR DS	1F	Failing location real address
4C	MCHFSAV DS	1F	Instruction address at failure
50	MCHFSEAV DS	1F	End of the failing location
54	MCHPDARI DS	1F	End of the failing virtual storage address
	MCHLEN1 EQU	*MCHDAMAGE	Length of damage assessment area
	MCHLEN EQU	*MCHRESEV	Length of area to be cleared
	MCHFIX EQU	280+48	Length of the fixed logout and the header record for machine check handler

MCRECORD: MACHINE CHECK HANDLER RECORD


MCRECORD provides the necessary extended logout information for error recording of processor and main storage.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MCREC DS 0D	
0	MCRECTYP DS 1X	M*1 Machine check record type
1	MCOPSYS DS 1X	M*2 Operating system
2	MCSWNONE DS 1X	M*3 Record independent switch
3	MCSWTWO DS 1X	M*4 Record dependent switch
4	MCSWITCH DS 2X	Unused switches
6	MCRECCNT DS 1X	M*5 Record count
7	MCRECCC DS 1X	M*6 Reserved for IBM use
8	MCDATE DS XL8	Date and time
10	MCCPUID DS XL8	Processor identification and model number
18	MCPROGID DS XL8	Program identity
20	MCJOBID DS XL8	Job identity (unused)
28	MCOLDPW DS XL8	Machine check old PSW
30	MCFXDLOG DS 35D	Machine check fixed logout
	FXDLGLH EQU (*-MCFXDLOG)	Length of machine check fixed logout area
148	MCEXTLOG EQU *	Beginning of machine check extended logout (the extended logout length is variable length and machine dependent)
	MCHDAMAG EQU *	Damage assessment area (80 bytes)

MDRREC: MISCELLANEOUS DATA RECORDING RECORD


MDRREC retains information for the VM/370 error recording cylinders.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>24-Byte Header</u>		
0	MDRKEYN	DS 1H Type and operating system
2	MDRSWS1	DS 1C M*1 Switch byte 0
3	MDRSWS2	DS 1C M*2 Reserved for IBM use
4	MDRSWS3	DS 1C M*3 Reserved for IBM use
5	MDRRECNT	DS 1C M*4 Sequence (4 bits) and record (4 bits)
<u>Bits as used in MDRRECNT</u>		
0 through 3		Used for sequence number
4 through 7		Indicates the record total
6	MDRSPE1	DS 1H Reserved for IBM use
8	MDRDTE	DS 1F Date
C	MDRTMEN	DS 1F Time
10	MDRCPID	DS 2F Processor identification and model number
<u>End of 24-Byte Header</u>		
<u>Device Dependent Data</u>		
18	MDRCUA1	DS 2X Primary CUA of device
1A	MDRVOL	DS 6X Volume serial number of device
20	MDRSENS	DS 24X Sense byte data
	MDRSIZE	EQU (*-MDRREC) MDR record size
<u>For 3270 Remote Support</u>		
18	ORG	MDRCUA1
	DS	2X Line address
1A	DS	1X Control unit address
1B	DS	1X Device address
1C	DS	2X Sense and status information
1E	DS	2X Resource identification
20	DS	2X Reserved for IBM use
<u>For 3705 Remote Support</u>		
18	ORG	MDRCUA1
	DS	2X Device address
1A	DS	8X Userid
22	DS	2X Resource identification

MICBLOK: VIRTUAL MACHINE POINTER LIST FOR VM/370 HARDWARE ASSIST

MICBLOK contains pointers to control registers, the segment table, and other values required by the virtual machine assist feature and the VM/370 Extended Control-Program Support (ECPS). This information is needed for the handling of certain instructions and privileged operations requested by the virtual machine. The VMMICRO field of the VMBLCK points to MICBLOK.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MICRSEG	DS 1F Real segment table pointer
4	MICCREG	DS 1F Virtual control register pointer
8	MICVPSW	DS 1F Virtual PSW pointer
8	MICVIP	ORG DS 1X Virtual interrupt pending bit
<u>Bits defined in MICVIP</u> MICPEND EQU X'80'		Virtual interrupt is pending; therefore, the virtual machine assist feature is not to handle change of PSW channel masks or external mask from disabled to enabled. All other bits in this byte must be 0.
9		Address of virtual PSW
C	MICWORK	DS 1F Workspace pointer
10	MICVTMR	DS 1F Location to be decremented when the virtual interval timer assist feature of VM/370 ECPS is being used
14	MICACF	DS 1F Assist controls
14	MICEVMA	ORG DS 1X Expanded virtual machine assist control bits
<u>Bits defined in MICEVMA</u> MICLPSW EQU X'80' MICPTLB EQU X'40' MICSCSP EQU X'20' MICSIO EQU X'10' MICSTSM EQU X'08' MICSTPT EQU X'04' MICTCH EQU X'02'		LPSW simulation PTLB simulation SCKC, SPT simulation SIO simulation STNSM, STOSM, and SSM simulation STPT simulation TCH simulation
15		DS 3X Reserved for IBM Use
	MICSIZE	EQU (*-MICBLOK)/8 Size of DSECT in doublewords (X'03')

MIHREC

MIHREC: MISSING INTERRUPT HANDLER ERROR RECORD


MIHREC is used in the SVC 76-initiated error recording process of type 70 MIH (Missing Interrupt Handler) records.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>24-Byte Header</u>		
0	MIHKEYN	DS 1H
2	MIHSWS1	DS 1C
3	MIHSWS2	DS 1C
4	MIHSWS3	DS 1C
5	MIHRECNT	DS 1C
6	MIHSPE1	DS 1H
8	MIHDTEM	DS 1F
C	MIHTMEN	DS 1F
10	MIHCPID	DS 2F
<u>Device Dependent Data</u>		
18	MIHJOB	DS 8X
20	MIHCUA2	DS 3X
23	MIHCUA1	DS 3X
26	MIHVOL	DS 6X
2C	MIHDEVT	DS 4X
30	MIHINT	DS 8X
MIHSIZE EQU (*-MIHREC)		MIH record size in doublewords (X'07')

MNHDR: VM/370 MONITOR RECORD HEADER

MNHDR provides header information for following monitor records.



Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
0	MNBHDLEN EQU	4		Length of the block header (VB format)
0	MNHRECSZ DS	1H		Record size
2	RSVD DS	1H		Reserved for IBM use
4	MNHCLASS DS	1X	M*1	Monitor class
5	MNHCODE DS	XL2		Monitor code
7	MNHTOD DS	XL5	M*2	Current TOD value
	MNHDRLEN EQU	*-MNHDR		Length of header record

MN000

MN000: VM/370 MONITOR PERFORM CLASS RECORD

MN000 provides an area for the accumulation of records dealing with privilege operations, paging, dispatching, and interrupt activity.

0	MN000WID	
8	MN000WPG	
10	MN000WIO	
18	MN000PRB	
20	MN000PSI	MN000CPA
28	MN000NFL	MN000PSN
30	MN000PRC	MN000RPC
38	MN000SPC	MN000FLF
40	MN000CPT	MN000SS
48	MN000PFF	MN000PRF
50	MN000PCS	MN000NXR
58	MN000CPR	MN000CVI
60	MN000CCW	MN000ITI
68	MN000PTI	MN000CKI
70	MN000CSV	MN000CPG
78	MN000CIO	MN000CDS
80	MN000CDA	MN000CDB
88	MN000CSC	MN000EK
90	MN000IK	MN000MS
98	MN000LP	MN000DI
A0	MN000SI	MN000SF
A8	MN000TI	MN000CI

E0	MN000HI	MN000HD
E8	MN000TC	MN000MN
C0	MN000MO	MN000LR
C8	MN000CP	MN000CH
DC	MN000TE	MN000CE
D8	MN000CT	MN000PE
E0	MN000PT	MN000EP
E8	MN000IP	MN000PB
F0	MN000RR	MN000TCL
F8	MN000LCL	MN000CS
100	MN000CD	MN000HDI
108	MN000NDU	MN000NAU
110	MN000PRD	MN000PWR
118	MN000NPP	MN000SWS
120	MN000Q1N	MN000Q2N
128	MN000Q1E MN000Q2E MN000INT MN000PPA	
130	MN000PPC MN000ISD	
138	MN000GTM	MN000DQM
140	MN000SWP	MN000EXT
148	MN000NXT	MN000ATT
150	MN000CNT	

Hexadecimal Field
Displacement Name

Field Description, Contents, Meaning

0	MN000WID	DS	XL8	Total system idle wait time
8	MN000WPG	DS	XL8	Total system page wait time
10	MN000WIO	DS	XL8	Total system I/O wait time
18	MN000PRB	DS	XL8	Total system problem state time
20	MN000PSI	DS	1F	No. of paging SIOs
24	MN000CPA	DS	1F	No. of calls to DMKPAG
28	MN000NFL	DS	1F	No. of page frames currently on free list
2C	MN000PSN	DS	1F	No. of pages currently being swapped
30	MN000PRC	DS	1F	No. of pages flushed but reclaimed

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
34	MN000RPC DS	No. of reserved pages
38	MN000SPC DS	No. of shared system pages
3C	MN000FLF DS	No. of times the free list was empty
40	MN000CPT DS	No. of calls to DMKPTRFR
44	MN000SS DS	No. of pages stolen from in-queue users
48	MN000PFF DS	No. of pages swapped from the flush list
4C	MN000PRF DS	No. of pages examined in stealing a page
50	MN000PCS DS	No. of full scans done in stealing pages
54	MN000NXR DS	No. of real external interruptions
58	MN000CPR DS	No. of calls to DMKPRVLG
5C	MN000CVI DS	No. of calls to DMKVIOEX
60	MN000CCW DS	No. of calls to DMKCCW from DMKVIO
64	MN000ITI DS	No. of interval timer interruptions reflected
68	MN000PTI DS	No. of processor timer interruptions reflected
6C	MN000CKI DS	No. of clock comparator interruptions reflected
70	MN000CSV DS	No. of SVC interruptions reflected
74	MN000CPG DS	No. of program interruptions handled
78	MN000CIO DS	No. of I/O interruptions handled
7C	MN000CDS DS	No. of calls to DMKDSP (main entry)
80	MN000CDA DS	No. of fast reflects in DMSDSP
84	MN000CDB DS	No. of dispatches for new FSWs
88	MN000CSC DS	No. of calls to DMKSCHDL
8C	MN000EK DS	Instruction count for X'08' SSK
90	MN000IK DS	Instruction count for X'09' ISK
94	MN000MS DS	Instruction count for X'80' SSM
98	MN000LP DS	Instruction count for X'82' LFSW
9C	MN000DI DS	Instruction count for X'83' DIAG
A0	MN000SI DS	Instruction count for X'9CX0' SIO
A4	MN000SF DS	Instruction count for X'9CX1' SIOF
A8	MN000TI DS	Instruction count for X'9DX0' TIO
AC	MN000CI DS	Instruction count for X'9DX1' CLRIO
B0	MN000HI DS	Instruction count for X'9EX0' HIC
B4	MN000HD DS	Instruction count for X'9EX1' HDV
B8	MN000TC DS	Instruction count for X'9F' TCH
BC	MN000MN DS	Instruction count for X'AC' STNSM
C0	MN000MO DS	Instruction count for X'AD' STOSM
C4	MN000LR DS	Instruction count for X'B1' LRA
C8	MN000CP DS	Instruction count for X'B202' STIDP
CC	MN000CH DS	Instruction count for X'B203' STIDC
D0	MN000TE DS	Instruction count for X'B204' SCK
D4	MN000CE DS	Instruction count for X'B206' SCKC
D8	MN000CT DS	Instruction count for X'B207' STCKC
DC	MN000PE DS	Instruction count for X'B208' SPT
E0	MN000PT DS	Instruction count for X'B209' STPT
E4	MN000EP DS	Instruction count for X'B20A' SPKA
E8	MN000IP DS	Instruction count for X'B20B' IPK
EC	MN000PB DS	Instruction count for X'B20D' PTLB
F0	MN000RR DS	Instruction count for X'B213' RRB
F4	MN000TCL DS	Instruction count for X'B6' STCTL
F8	MN000LCL DS	Instruction count for X'B7' LCTL
FC	MN000CS DS	Instruction count for X'BA' CS
100	MN000CD DS	Instruction count for X'EB' CDS
104	MN000HDI DS	Diagnose disk I/O simulation count
108	MN000NDU DS	No. of users dialed to a virtual machine
10C	MN000NAU DS	No. of users logged on
110	MN000PRD DS	No. of page reads
114	MN000PWR DS	No. of page writes
118	MN000NPP DS	No. of system pageable pages

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
11C	MN000SWS DS	1F	Sum of working sets of in-queue users
120	MN000Q1N DS	1F	No. of users in Q1
124	MN000Q2N DS	1F	No. of users in Q2
128	MN000Q1E DS	1H	No. of users eligible for Q1
12A	MN000Q2E DS	1H	No. of users eligible for Q2
12C	MN000INT DS	1H	MONITOR sampling interval (in seconds)
12E	MN000PPA DS	1H	Pseudo-cylinders ¹ of allocated temporary space
130	MN000PPC DS	1H	Pseudo-cylinders ¹ of system temporary space
132	DS	1H	Reserved for IBM use
134	MN000ISD DS	1F	Count of mini I/O block stack depletes
138	MN000GTM DS	1F	Count of mini I/O blocks in the queue
13C	MN000DMQ DS	1F	Count of mini I/O blocks processed
140	MN000SWP DS	1F	Count of SIOs on alternate path
144	MN000EXT DS	1F	Count of free storage extensions
148	MN000NXT DS	1F	Count of release of free storage extensions
14C	MN000ATT DS	1F	Count of TRYPLIT attempt
150	MN000CNT DS	1F	Count of subpool splits
	MN000LEN EQU	*-MN000	Record length in bytes

¹A pseudo-cylinder comprises 100 available page slots for all system-owned volumes. The total available pseudo-cylinders per device is determined by the formula:

(number of cylinders X number of records per cylinder for a device)

MN001: VM/370 MONITOR PERFORM CLASS RECORD

MN001 gives information on the performance of the Attached Processor.

0	MN001WID	
8	MN001WPG	
10	MN001WIO	
18	MN001PRB	
20	MN001NXR	MN001CSV
28	MN001PRD	MN001PWR
30	MN001SSY	MN001NSY
38	MN001SFR	MN001NFR
40	MN001SRN	MN001NRN
48	MN001STM	MN001NTM
50	MN001SDP	MN001NDP
58	MN001NFL	MN001NFS
60	MN001NSD	MN001NVD
68	MN001NRU	

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN001WID DS	L8 Attached processor idle wait time
8	MN001WPG DS	L8 Attached processor page wait time
10	MN001WIO DS	L8 Attached processor I/O wait time
18	MN001PRB DS	L8 Attached processor problem state time
20	MN001NR DS	Number of external interrupts to the attached processor
24	MN001CSV DS	Number of SVCs reflected by the attached processor
28	MN001PRD DS	Number of page reads by attached processor
2C	MN001PWR DS	Number of page writes by the attached processor
30	MN001SSY DS	Total time spin on system lock
34	MN001NSY DS	Total number of spins for system lock
38	MN001SFR DS	Total time spin on DMKFRE lock
3C	MN001NFR DS	Total number of spins for DMKFRE lock
40	MN001SRN DS	Total time spin on RUNLIST lock
44	MN001NRN DS	Total number of spins for RUNLIST lock
48	MN001STM DS	Total time spin on timer request lock
4C	MN001NTM DS	Total number of spins for timer request lock
50	MN001SDP DS	Total time spin on displacement lock
54	MN001NDP DS	Total number of spins for displacement lock
58	MN001NFL DS	Number of times CPFRELK set
5C	MN001NFS DS	Number of times CPFRESW set
60	MN001NSD DS	Number of times system lock request deferred
64	MN001NVD DS	Number of times VMBLCK lock deferred
68	MN001NRU DS	Number of DMKDSPRU entries
	MN001LEN EQU *--MN001	Length of record

MN097, MN098

| MN097: VM/370 MONITOR HEADER RECORD

| MN097 provides header information for a file that contains data accumulated by VM/370
| Monitor. This is the first record of the file.

0	MN097CPU	
8	MN097LEV	
10	MN097DAT	
18	MN097TIM	
20	MN097UID	
28	MN097CR8	MN097NUC
30	MN097FSS	MN097DPA
38	MN097TTS	MN097VR
40	MN097CPL	MN097APL

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	MN097CPU DS	XL8	Processor serial number and model number
8	MN097LEV DS	CL8	Program level change
10	MN097DAT DS	CL8	Current date
18	MN097TIM DS	CL8	Current time
20	MN097UID DS	CL8	Userid of user who invoked MONITOR
28	MN097CR8 DS	1F	Value of control register 8
2C	MN097NUC DS	1F	Size of nucleus
30	MN097FSS DS	1F	Size of free storage
34	MN097DPA DS	1F	Size of dynamic paging area
38	MN097TTS DS	1F	Size of trace table
3C	MN097VR DS	1F	Size of V=R area
40	MN097CPL DS	1H	Logical address of main processor
42	MN097APL DS	1H	Logical address of alternate processor
	MN097LEN EQU	*-MN097	Length of header record

| MN098: VM/370 MONITOR TRAILER RECORD


| MN098 contains the userid of the user who has terminated current VM/370 Monitor activity.
This is the last record of the file.

0	MN098UID	
---	----------	--

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	MN098UID DS	CL8	ID of user stopping the VM/370 Monitor
	MN098LEN EQU	*-MN098	Length of trailer record

MN099: VM/370 MONITOR SUSPENSION RECORD


| MN099 contains information recorded when VM/370 Monitor activity is suspended because all
| buffers are full and are queued for output.



Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	MN099TOD	DS	XL5
5	MN099CNT	DS	XL4
		M*1	Count of suspensions
	MN099LEN	EQU	*--MN099
			Length of the suspension record

MN10X: VM/370 MONITOR RESPONSE CLASS RECORD

MN10X contains information on the number of input or output console line transmissions for a given userid.



Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	MN10XUID	DS	CL8
8	MN10XADD	DS	1H
			Userid Terminal line address
	MN10XLEN	EQU	*--MN10X
			Short record length
A	MN10YCNT	DS	1X
		M*1	Byte count for the following line
	MN10YLEN	EQU	*--MN10X
			Long record, header length
B	MN10YIO	EQU	*
			Input/output line starts here

MN20X**MN20X: VM/370 MONITOR SCHEDULER CLASS RECORD**

MN20X contains VM/370 Monitor data on CP's scheduler activity, dispatch queues, paging, and spool activity.

0	MN20XUID				
8	MN20XNPP			MN20XSWS	
10	MN20XQ1N			MN20XQ2N	
18	MN20XQ1E		MN20XQ2E		MN20XWSS M*1 M*2
20	MN20YTTI				
28	MN20YVTI				
30	MN204PRI		MN202PGR		MN202APR MN202REF
38	MN202RES		MN202PST		MN202IOC
40	MN202PNC			MN202LIN	
48	MN202CRD			M*3	

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN20XUID DS	CL8 Userid being added and/or dropped from queue
8	MN20XNPP DS	1F No. of system pageable pages
C	MN20XSWS DS	1F No. of working sets of in-queue users
10	MN20XQ1N DS	1F No. of users in Q1
14	MN20XQ2N DS	1F No. of users in Q2
18	MN20XQ1E DS	1H No. of users eligible for Q1
1A	MN20XQ2E DS	1H No. of users eligible for Q2
1C	MN20XWSS DS	1H User's projected working set size
1E	MN20XQNM DS	1X M*1 Queue wherein additions and/or deletions are being made
1F	MN20XPRC DS	1X M*2 CP TRACE table processor identification
	MN203LEN EQU	--MN20X Length of class 2 code 3 record (Add queue)
20	MN20YTTI DS	XL8 Current VMTIME (CP simulation time)
28	MN20YVTI DS	XL8 Current VMTIME (user virtual time)
30	MN204PRI DS	1F Eligible list priority
	ORG MN204PRI	
30	MN202PRI DS	1H Dispatch priority
32	MN202PGR DS	1H Pages read while in queue
	MN204LEN EQU	--MN20X Length of class 2 code 4 record (Drop queue)
34	MN202APR DS	1H Sum of pages read that are resident at each paging operation
36	MN202REF DS	1H No. of pages referenced while in queue
38	MN202RES DS	1H Current number of pages resident
3A	MN202PST DS	1H No. of pages stolen while in queue
3C	MN202IOC DS	1F Virtual nonspoiled SIO count
40	MN202PNC DS	1F Virtual cards punched
44	MN202LIN DS	1F Virtual lines printed
48	MN202CRD DS	1F Virtual cards read
4C	MN202LPR DS	1X M*3 Last processor on which execution took place
	MN202LEN EQU	--MN20X Length of class 2 code 2 record (add to the eligible list)

MN400: VM/370 MONITOR USER CLASS RECORD

MN400 provides user virtual machine statistics.


0	MN400UID														
8	MN400TTI														
10	MN400VTI														
18	MN400PGR					MN400PGW									
20	MN400IOC					MN400PNC									
28	MN400LIN					MN400CRD									
30	M*1		M*2		M*3		M*4		M*5		M*6		M*7		M*8
38	M*9		M*10		M*11		M*12		M*13		/M*14/		MN400RES		
40	MN400WSS					MN400PDR				MN400PDK				MN400INT	
48	M*15														

Hexadecimal Displacement	Field Name	DS	CL8	Field Description, Contents, Meaning
0	MN400UID	DS	CL8	Userid
8	MN400TTI	DS	XL8	Current VMTIME (in VMBLOCK); CP simulation time
10	MN400VTI	DS	XL8	Current VMVTIME (in VMBLOCK); user virtual time
18	MN400PGR	DS	1F	Total page reads for this user
1C	MN400PGW	DS	1F	Total page writes for this user
20	MN400IOC	DS	1F	Virtual nonspooled SIO count
24	MN400PNC	DS	1F	Virtual cards punched
28	MN400LIN	DS	1F	Virtual lines printed
2C	MN400CRD	DS	1F	Virtual cards read
30	MN400RST	DS	1X	M*1 User running status
31	MN400DST	DS	1X	M*2 User dispatch status
32	MN400OST	DS	1X	M*3 User operating status
33	MN400QST	DS	1X	M*4 User queuing status
34	MN400PST	DS	1X	M*5 User processing status
35	MN400EST	DS	1X	M*6 User execution status
36	MN400TST	DS	1X	M*7 User tracing control status
37	MN400MLV	DS	1X	M*8 User message level
38	MN400QLV	DS	1X	M*9 User queue level
39	MN400CLV	DS	1X	M*10 User command level
3A	MN400TLV	DS	1X	M*11 User timer level
3B	MN400PND	DS	1X	M*12 Interrupt pending status
3C	MN400UPR	DS	1X	M*13 Directory or SET priority
3D	MN400RSV1	DS	1X	M*14 Reserved for IBM use
3E	MN400RES	DS	1H	Number of pages resident
40	MN400WSS	DS	1H	Estimated working set size
42	MN400PDR	DS	1H	Drum allocated page frames
44	MN400PDK	DS	1H	Disk allocated page frames
46	MN400INT	DS	1H	Monitor sampling interval (in seconds)
48	MN400LPR	DS	1X	M*15 Last processor on which execution took place
	MN400LEN	EQU	*-MN400	Length of class 4 code 0 record

MN500

MN500: VM/370 MONITOR INSTRUCTION SIMULATION CLASS RECORD

MN500 provides data on instructions simulated by CP.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN500UID	Userid
8	MN500INS	Privileged instruction
C	MN500VAD	Virtual storage address of the instruction
10	MN500VH	Current total of CP simulation time
	MN500LEN EQU *-MN500	Length of class 4 code 0 record

| MN600: VM/370 MONITOR DASTAP I/O COUNT RECORD

| • Header Record


| MN600HDR header record provides the number of device data packages.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN600NUM DS 1H	Number of device data packages that follow length of header
	MN600HLN EQU *-MN600HDR	Length of header

| • I/O Count Record

| MN600DEV input/output count record provides information for each device in the device | data packages.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN600ADD DS 1H	Device address
2	MN600TY DS 1H	VM/370 device type and/or codes
4	MN600SER DS CL6	Volume serial number of device
A	MN600CNT DS XL4	Device accumulated I/O count
	MN600DLN EQU *-MN600DEV	Length of each data record
	MN600MAX EQU (4096-MNBHDLEN-MNHRLLEN-MN600HLN)/MN600DLN	Maximum device count

MN602

| MN602: VM/370 MONITOR DASTAP UTILIZATION RECORD

| • Header Record

| MN602HDR provides the number of samples for intervals of device packages.

| 0 |

MN602SAM |

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN602SAM DS	1H Number of samples for interval

| • Utilization Record

| MN602 provides, via CP MONITOR command, utilization data for DASD and tape devices.
| There is one record for each device.

| 0 |

MN602ADD | MN602CHB | MN602CUB | MN602DVB |


| 8 |

MN602CHQ | MN602CUQ | M*1 |

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN602ADD DS	1H Address of the device
2	MN602CHB DS	1H Number of times channel is busy
4	MN602CUB DS	1H Number of times control unit is busy
6	MN602DVB DS	1H Number of times device is busy
8	MN602CHQ DS	1H Input/output tasks queued on channel
A	MN602CUQ DS	1H Input/output tasks queued on the control unit
C	MN602DVQ DS	1C M*1 Input/output tasks queued on device
	MN602DLN EQU	*-MN602DEV Length of device portion in doublewords

MN700: VM/370 MONITOR SEEKS CLASS RECORD

MN700 provides, via CP MONITOR, the I/O tasks and cylinder seek activity of a specified DASD.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN700UID DS	CL8 Userid
8	MN700ADD DS	1H Device address
A	MN700CYL DS	1H Cylinder being sought
C	MN700CCY DS	1H Current cylinder
E	MN700QDV DS	1X M*1 I/O tasks queued on the device
F	MN700QCU DS	1X M*2 I/O tasks queued on the control unit
10	MN700QCH DS	1X M*3 I/O tasks queued on the channel
11	MN700DIR DS	1X M*4 Seek direction: 00=lower, 01=higher
	MN700LEN EQU *--MN700	Length of class 7 code 0 record

MN802

| MN802: VM/370 MONITOR SYSTEM PROFILE CLASS

| • Header Record


| MN802HDR provides the number of device block counters.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN802NUM DS that follow	Number of device block counters
2	MN802CNT DS	Device I/O count
	MN802DLN EQU *--MN802CTR	Length of the header

| • System Profile Data


MN802CTR provides, via CP MONITOR command, additional system profile data. The monitor data includes: the I/O activity for each device, the number of logged on users, number of page read/writes, and the total system I/O, page wait, and problem state times.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MN802NAU DS	No. of logged on users
4	MN802PGR DS	Total system page reads
8	MN802PGW DS	Total system page writes
C	MN802NPP DS	No. of system pageable pages
10	MN802WID DS	Total system idle wait time
18	MN802WPG DS	Total system page wait time
20	MN802WIO DS	Total system I/O wait time
28	MN802PRB DS	Total system problem time
	MN802CLN EQU *--MN802CTR	Length of each data entry

| MNDEVLST: VM/370 MONITOR CLASS 6 (DASTAP) DEVICE LIST

| MNDEVLST provides information on device activity. Pointed to by MONDEVLST, it (MNDEVLST) contains a list of RDEVBLOK addresses to be used by class 6 (DASTAP) data collection, together with bins, for each device, in which the high frequency sampler (DMKENTTI) can accumulate control unit and device busy counts during each monitor interval. Note that channel busy counts are accumulated in a separate area pointed to by MONCHPTR, 5 doublewords and 2 bytes per entry.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MNRDEBV DS 1F	Address of RDEVBLOK
4	MNCUBSY DS 1H	Control unit busy count
6	MNDVBSY DS 1H	Device busy count

| MNDEVLEN EQU *-MNDEVLST Device entry size in doublewords (X'01')

MONCOM

MONCOM: VM/370 MONITOR COMMUNICATIONS AREA

MONCOM provides the control link for CP's monitoring activity, the user, and the tape drive.

0	MONARDB	M*1 M*2 MONDVNUM
8	MONDVLIST	//////////MONRSV1//////////
10	MONAIOB	MONATRB
18	MONCLOCK	
20	MONSUSCK	
28	MONSUSCT	//////////MONRSVD1//////////
30	MONSAVE1	
.	.	.
70	MONSAVE2	
.	.	.
B0	MONUSER	
B8	MONSPLCT	MONSF8
C0	MONCURV	MONNXTV
C8	MONCURR	MONNITR
D0	MONDASA	MONDASB
D8	MONDAS	M*3 M*4 MONBUFNO
E0	MONCURBF	MONCRSLT
E8	MONIOBF	MONIOSLT
F0	MONSKLST	MONSACT
F8	MONCHPTR	MONUTRB
100	MONBUF1	
.	MONBUF1V	
.	(Variable number of buffers)	
		(Last address field)


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MONARDB DS 1F	Address of monitor tape real device block
4	MONFLAG1 DS 1X M*1	Monitor flag
	<u>Bits defined in MONFLAG1</u>	
	MONSYSVM EQU X'80'	Flag used by user class routine
	CFSTOP EQU X'20'	MONITOR STOP command has been issued
	TRUN EQU X'10'	Tape rewind-unload CCW has been scheduled
	ERROR EQU X'08'	Tape error has occurred -- stcp VM/370 mcnitor
	MONTIINT EQU X'04'	Handling timer interruption
	MONLSTBK EQU X'02'	Handling the last block
	MONIBUF EQU X'01'	Only one buffer for VM/370 monitoring
5	MONFLAG2 DS 1X M*2	Work byte
	<u>Bits defined in MONFLAG2</u>	
	SUSPEND EQU X'80'	VM/370 monitor has been suspended
6	MONDVNUM DS 1H	Number of entries in real device list
8	MONDVLST DS 1F	Address of the real device list
C	MONRSV1 DS 1F	Reserved for IBM use
10	MONAIOB DS 1F	Address of monitor tape I/C block
14	MONATRB DS 1F	Address of monitor timer request block
18	MONCLOCK DS 1D	TOD clock stamp for each record
20	MONSUSCK DS 1D	TOD clock value at last suspension
28	MONSUSCT DS 1F	Suspension count
2C	MONRSVD1 DS 1F	Reserved for IBM use
30	MONSAVE1 DS 16F	Monitor internal save area for main processor
70	MONSAVE2 DS 16F	Monitor internal save area for attached processor
B0	MONUSER DS 8C	User starting/stopping the VM/370 monitor
B8	MONSPLCT DS 1F	Number of records on spool file
BC	MONSFB DS 1F	Address of SFBLCK for spool file
C0	MONCURV DS 1F	Virtual address of first virtual buffer
C4	MONNXTV DS 1F	Virtual address of second virtual buffer
C8	MONCURR DS 1F	Real address of first virtual buffer
CC	MONNXTR DS 1F	Real address of second virtual buffer
D0	MONDASA DS 1F	Address of next DASD buffer
D4	MONDASB DS 1F	Address of previous DASD buffer
D8	MONDAS DS 1F	Address of DASD buffer for the spool file
DC	MONEX DS	M*3 Flag byte
	<u>Bits defined in MONEX</u>	
	CLCMD EQU X'80'	Spool file closed by command
DD	MONFLAG3 DS	M*4 Flag byte
	<u>Bits defined in MONFLAG3</u>	
	CLSUS EQU X'80'	Suspend during close
	EXHAUST EQU X'40'	Spool DASI slots exhausted
	CL EQU X'20'	Suspension necessary
	SPOOLED EQU X'10'	Monitor to spool active
DE	MONBUFNO DS 1H	Reserved for IBM use
E0	MONCURBF DS 1F	Address of current VM/370 monitor buffer
E4	MONCRSLT DS 1F	Corresponding slot address
E8	MONIOBF DS 1F	Address of VM/370 monitor buffer going to tape
EC	MONIOSLT DS 1F	Corresponding slot address
F0	MONSKLST DS 1F	Address for device list seeks
F4	MONSACT DS 1F	Limit count for real time monitor
F8	MONCHPTR DS 1F	Address of channel sampling data
FC	MONUTRB DS 1F	Address of I/O utilization
100	MONBUF1 DS 1F	First VM/370 monitor buffer address

MONCOM

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
104	MONBUF1V EQU MONBUF1+4	First buffer address of remaining variable number of buffers. There is one 4-byte entry for each monitor buffer. The last field contains X'FFFFFF'
	MONSIZE EQU (**-MONCOM)/8	Size of DSCT in doublewords
<u>Associated Monitor Control Flags</u>		
<u>Flags in DMKSYSAT</u>		
AUTOGO EQU X'80'		SYSMON setting for AUTODISK on
AUTOSPL EQU X'40'		Stop monitor when spool file record limit is reached
MONSLMT EQU X'20'		Sampling for real time Monitor
<u>Monitor Buffer Control Flag in Byte 3 of Buffer for Tape and in Byte 9 of Buffer for Spool</u>		
MONBUFIO EQU X'00'		Not collecting; being used for output
MONBUFAV EQU X'01'		Available for use
MONBUFAC EQU X'03'		Current active collector
<u>Monitor Buffer Control Flag in Byte 10 of Spool Buffer</u>		
TRAP EQU X'80'		Last buffer queued for I/O
UNFIN EQU X'40'		Close occurred before the buffer was full
<u>Flag in Spool File Control Block (SFBFLAG2)</u>		
SFBMON EQU X'01'		Monitor spool file identifier

| **MSSCOM: MSS COMMUNICATIONS CONTROL BLOCK**

| MSSCOM contains information necessary to request a MSS volume mount, request a MSS volume
| demount, or complete processing when a pack change interrupt is received on a MSS device.
| The MSSCOM blocks are chained from location DMKSSSMQ in module DMKSSS.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	MSSSER DS CL6	Volume serial number of the MSS volume to be mounted or demounted
6	MSSVUA DS XL2	Device address for the volume
8	MSSRSRVD DS 1F	Reserved for IBM use
C	MSSTASK1 DS 1F	Pointer to a CPEXBLOK for a pending MSS pack change interrupt
10	MSSTASK2 DS 1F	Pointer to a CPEXBLOK for a pending MSC return on mount or demount
14	MSSTASK3 DS 1F	Pointer to a CPEXBLOK for an I/C request to a volume being mounted
18	MSSNEXT DS 1F	Next entry in the chain, or zero
1C	MSSUSER DS CL8	Name of the virtual machine that requires the MSS activity
24	MSSFLAGS DS X12	Binary flags representing the status of the request
Bits defined in MSSFLAGS		
	MOUNT EQU X"8000"	Mount volume MSSSER on address MSSVUA
	DEMOUNT EQU X"2000"	Demount MSSSER from MSSVUA
	MSSERR EQU X"400"	The MSC detected an error while attempting the requested action
	RQENT EQU X"80"	This request is waiting to be passed to the MSC
	MQENT EQU X"40"	This request has been passed to the MSC, and is awaiting a pack change interrupt
	INPROC EQU X"20"	This request being processed by the MSC
	MSGPROC EQU X"10"	The MSC has completed for this request and message DMKSSS088I is being sent
	MSSSIZE EQU (*-MSSSER)/8	MSSCOM size in doublewords

NCPTBL

NCPTBL: NAMED 370X CONTROL PROGRAM TABLE

NCPTBL entries provide description information on 370x control program images saved on CP-owned volumes.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	NCPPNT DS 1F	Displacement to next entry
4	NCPSIZE DS 1F	370x storage size required for load
8	NCPNAME DS CL8	Control program reference name
10	NCPVOL DS CL6	Volume identification of DASD containing saved image
16	NCPFLAG DS 1X	N*1 CPTYPE flag byte
<u>Bits defined in NCPFLAG</u>		
	NCPTNCP EQU X'01'	Network Control Program
	NCPTCEP EQU X'02'	270x Emulation Control Program
	NCPTPEP EQU X'03'	Partitioned Emulation Program
17	NCPRSV1 DS 1X	N*2 Reserved for IBM use
18	NCPSTART DS 1F	Pointer to first page (CCPD) on NCPVOL of saved NCP
1C	NCPPAGCT DS 1F	Total number of pages saved
	NCPSIZE EQU (*-NCPSIZE)/8	NCPTBL size in doublewords (X'04')

NICBLOK: NETWORK INTERFACE CONTROL BLOCK

NICBLOK contains control information related to 3704/3705 resources, teleprocessing lines, and display screen status information. The RDEVNICL field of RDEVELOK points to NICBLOK.


0	NICNAME	NICEPAD	N*1	N*2	N*3	N*4
8	NICRCNT	NICVRID		NICTMAT		
10		NICUSER		NICQPNT		
18			NICDSP			

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	NICNAME DS	1H 370x NCP resource name
2	NICEPAD DS	1H Subchannel address when in EP mode
4	NICSTAT DS	1X N*1 Resource status flags
	<u>Bits defined in NICSTAT</u>	
	NICERLK EQU X'80'	Device error lock is set
	NICNTRL EQU X'40'	Control operation is active
	NICDISA EQU X'20'	Resource inactive (offline)
	NICSWEP EQU X'10'	Resource is switchable to EP mode
	NICEPMD EQU X'08'	Resource now in emulator mode
	NICLTRC EQU X'02'	NCP line trace active
	NICDED EQU X'01'	Resource is dedicated
	NICTRQ EQU X'80'	Graphic device - timer request pending
	NICHOLD EQU X'10'	Graphic device - screen full; in HOLD status
	NICMORE EQU X'08'	Graphic device - screen full; in MORE status
	NICRUNN EQU X'04'	Graphic device - screen in running status
	NICREAD EQU X'02'	Graphic device - read pending for screen input
	NICCPNA EQU X'01'	Graphic device - last input not accepted
5	NICFLAG DS	1X N*2 Interface control flags
	<u>Bits defined in NICFLAG</u>	
	NICSESN EQU X'80'	Session is active for this device
	NICATTN EQU X'40'	Attention handling in progress
	NICPSUP EQU X'20'	Resource has print suppress feature
	NICATOF EQU X'10'	Suppress attention signal character
	NICENAB EQU X'08'	Resource is active and enabled
	NICDISB EQU X'02'	Resource to be disabled as soon as possible
	NICMTA EQU X'01'	Multiple terminal access resource
	NICFMT EQU X'80'	Graphic device - screen formatted VM/370 online
	NICDIAG EQU X'40'	Graphic device - screen written with DIAGNOSE
	NICALRM EQU X'10'	Graphic device - screen has an alarm message
	NICCARD EQU X'04'	Graphic device - data from card reader
	NICPROCN EQU X'01'	Graphic device - process control task now
6	NICLLEN DS	1X N*3 Terminal output line length
7	NICTYPE DS	1X N*4 Resource type and/or features
	<u>Bits defined in NICTYPE</u>	
	NICCTRL EQU X'00'	Resource is the 370x
	NICLINE EQU X'80'	Resource is a teleprocessing line
	NICTERM EQU X'40'	Resource is a terminal device
	NICLGRP EQU X'20'	Resource is a logical line group

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
Bits defined in NICTYPE (cont.)			
	NICSDLC EQU X'08'		LINE - Synchronous data link control
	NICLBSC EQU X'04'		LINE - Binary synchronous line control
	NICSWCH EQU X'02'		LINE - Switched line interface
	NICMLTP EQU X'01'		LINE - Multiple-drop leased line
	NICTELE EQU X'10'		TERM - Telegraph line adapter
	NICCIBM EQU X'08'		TERM - Selectric-based terminal
	NICRCPU EQU X'04'		TERM - Bisynch remote computer
	NICRSPL EQU X'02'		TERM - Bisynch remote spool device
	NICGRAF EQU X'01'		TERM - Bisynch remote graphics
	NIC3271 EQU X'08'		Graphic device - 3271 control unit
	NIC3275 EQU X'04'		Graphic device - 3275 standalone display station
	NICOPRDR EQU X'10'		Graphic device - card reader feature
8	NICRCNT DS 1H		
A	NICVRID DS 1H		Retry count for BTU errors
C	NICTMAT DS 1F		Virtual resource ID when dedicated
10	NICUSER DS 1F		TOD clock value when attached
14	NICQPNT DS 1F		VMBLCK address of associated user
18	NICDSP DS 1D		Pointer to input BTU chain
			Remote 3270 information
ORG NICDSP			
	NICRSV1 DS 1X		Reserved for IBM use
	NICDTYPE DS 1X		Display station type
Bits define in NICDTYPE			
	NICD3277 EQU X'04'		3277 display station
	NICD3275 EQU X'02'		3275 display station
	NICMDL DS 1X		Display station model
	NICRSV2 DS 1X		Reserved for IBM use
	NICRSV3 DS 1X		Reserved for IBM use
	NICSIZE EQU (*-NICBLOK)/8		Size of block in doublewords (X'03')
Device Dependent Data - 3270 on Binary Synchronous Lines			
	ORG NICEPAD		
2	NICCORD DS 1X		Current line coordinates
3	NICTMCD DS 1X		Terminal mode
Bits defined in NICTMCD			
	NICTABF EQU X'80'		Second scan of screen's input area
	NICSIO EQU X'40'		DIAGNOSE issued to input area
	NICAPL EQU X'20'		APL cn for 3270 remote
	NICTEXT EQU X'10'		Text feature on for 3270 remote
	ORG NICRCNT		
8	NICSELT DS 1H		Remote station selection characters
A	NICPOLL DS 1H		Remote station polling characters
C	NICATRB DS 1F		Timer request block address
Equate Symbols for VM/370 Support of the 370x			
	WRITBRK EQU X'09'		Write break CCW operation code
	RDBUFLN EQU 96		Length of host read buffers
	RDBUFNO EQU 6		Number of host read buffers
Sense Bits (sense byte 0) Peculiar to the 370x			
	IPLREQ EQU X'02'		IPL required--3705 inactive
	ABORT EQU X'01'		Buffer depletion--transfer terminated

| NPRTEL: NAMED 3800 IMAGE LIBRARY TABLE

| NPRTEL lists by name all pages saved and indicates the DASD volume that contains the
| saved image.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	NPPRPT	DS 1F Chain pointer to next entry
4	NPPRSV1	DS 1F Reserved for IBM use
8	NPPRNAME	DS CL8 Reference name for image library
10	NPPRVOL	DS CL6 Volume of DASD containing the saved image
16	NPPRCNT	DS 1X N*1 Number of 3800s active on this image
17	NPPRSV2	DS 1X N*2 Reserved for IBM use
18	NPPRSTART	DS 1F CCP1 of first page on NPPRVCL
1C	NPPPAGCT	DS 1F Number of pages saved

OERRECN (Long OBR)

OERRECN: UNIT CHECK ERROR RECORD (LONG OUTBOARD RECORD)

OERRECN provides error, sense, and other statistical data needed for error recording on a specified channel-attached I/O device.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
<u>24-Byte Header Record</u>				
0	OBRKEYN DS 1H			Record type
2	OBRWSN DS 1H			Switches
<u>Bits defined in OBRWSN</u>				
Byte 0	OBRMORE EQU X'80'			More records to follow
	OBRTOD EQU X'40'			TOD clock instruction issued
<u>Bits defined in OBRWSN</u>				
Byte 1	OBREOD EQU X'80'			SDR counters dumped at ECD
	OBRTTEMP EQU X'40'			Temporary error
	OBRSHOBR EQU X'20'			Short record
	OBRDEMNT EQU X'04'			Volume demounted
4	OBRSP1 DS 1F			Reserved for IBM use
8	OBRTDTEN DS 1F			Date
C	OBRTMEN DS 1F			Time
10	OBRCPIDN DS 2F			Processor identifier and serial number
	OBRHSIZE EQU (*-OBRRECN)			Size of OER header
<u>End of 24-Byte Header Record</u>				
18	OBRPGMN DS 2F			Job identification
20	OERFCCWN DS 2F			Failing CCW
28	OERCSSWN DS 2F			Failing CSW
30	OBRDDCNT DS 1X			S*1 Number of doublewords in record
31	OBRCUAIN DS 3C			Address of failing device

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
34	OBRDEVTN	DS 1F	Device type
38	OBRSDRCT	DS 1X	S*2 Number of SIR work area bytes
39	OBRCUAPR	DS 3C	Primary unit address
3C	OBRIORTY	DS 2X	Number of retries
3E	OBRSNST	DS 2X	Number of sense bytes
	OBR1SIZE	EQU (*-OBRRECN)	Size of long OBR record base
	<u>Format of Device Dependent Data</u>		
	<u>All DASD Units</u>		
40	OBRVOLN	DS 8C	Volume identification
48	OBRLSKN	DS 8X	Last seek address
50	OBRHAN	DS 8X	Home address
	<u>2314/2319 Format</u>		
58	OBRSDRWK	DS 10X	SDR work area
62	OBRSENSN	DS 6C	Sense data
	OBR2SIZE	EQU (*-OBRRECN)	Maximum size of 2314/2319 record
	<u>3350/3340/3330/2305 Format</u>		
	ORG	OBRSDRWK	
58	OBR33SNS	DS 24C	3350/3340/3330/2305 sense data
	OBR3SIZE	EQU (*-OBRRECN)	Maximum size of 3330/3340/2305 record
	<u>Unit Record Format</u>		
	ORG	OBRVOLN	
40	OBRURST	DS 10X	SDR work area
4A	OBRURSNS	DS 1C	Unit record sense data
	<u>3505/3525 Format</u>		
	ORG	OBRVOLN	
40	OBR3505S	DS 1C	3505/3525 sense data
	<u>3203 Format</u>		
	ORG	OBRVOLN	
40	OBRCCORRL	DS 1X	Correlation number
41		DS 7X	Reserved for IBM use
48	OBRSDRO3	DS 10X	SDR work area
52	OBR3203S	DS 24C	3203 sense data
	<u>3211 Format</u>		
	ORG	OBRVOLN	
40	OBRCCORL	DS 1X	Correlation number
41		DS 7X	Reserved for IBM use
48	OBRSDR32	DS 10X	SDR work area
52	OBR3211S	DS 6C	3211 sense data
	<u>2400 Tape Format</u>		
	ORG	OBRLSKN	
48	OBRTAPST	DS 10X	SDR work area
52	OBRTAPSN	DS 24C	Tape sense data
	<u>3420/3410 Tape Format</u>		
	ORG	OBRLSKN	
48	OBRDVDEP	DS 16C	Device dependent data
58	OBR342ST	DS 20X	SDR work area
6C	OBR3420S	DS 24C	3420 sense data

OERRREC (Short OBR)

OERRREC: UNIT CHECK ERROR RECORD (SHORT OUTBOARD RECORD)


OERRRECN provides error, sense, and other statistical data needed for error recording on a specified channel-attached I/O device.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning			
<u>24-Byte Header Record</u>					
<u>Note:</u> The 24-byte Header Record for the Short OER is identical to that of the Long OER, the description of which precedes this block.					
18	OBRDEVSH	DS	1F Device type		
1C	OBRSRSH	DS	1X 0*1 Number of SIR work area bytes		
	OBRSIZE	EQU	(*-OBRRECN) Size of short OBR record base		
	OBRSIZE1	EQU	(*-OBRRECN+7)/8 Size in doublewords (X'04')		
1D	OBRCUA	DS	3X Channel and unit address		
20	OBRSRIN	DS	20X SDR work area		
20	ORG	OBRSSDRIN			
2A	OBRSSDR1	DS	10X SDR work area		
2A	OBRSSDR2	DS	10X SDR work area		
34	OBRSV1	DS	1F Reserved for IBM use		
	OBRSIZE2	EQU	(*-OBRRECN+7)/8 Size in doublewords (X'07')		

CWNDLIST: CP-OWNED VOLUMES LIST


CWNDLIST contains a list of all the system owned DASD volumes that are used for paging, spooling, and temporary disk storage activity. Each entry specifies the volume identity and its preferred use (that is, paging/spooling/T-disk space). This block is generated by the SYSOWN macro at system generation.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	OWNDVSR DS	CL6 Volume serial number
6	OWNDRDEV DS	1H Displacement of RDEVELOK for the volume
6	ORG OWNDPREF DS	1H Allocation preference

PAGTABLE: TRANSLATION PAGE TABLE

PAGTABLE is used by CP for allocating and referencing storage. It is referenced by the segment table (SEGTABLE) data area and contains a pointer to the swap table (SWPTABLE) which, in turn, is related to a DASD cylinder location. The SWPPAG field of SWPTABLE points to PAGTABLE.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
-8	8-Byte Header	
-8	PAGSTMP DS	1F Page table time stamp
-4	PAGACT DS	1H Count of active segment table entries for this segment
-2	PAGTOT DS	1H Count of total segment table entries for this segment
0	PAGSHR DS	1F Pointer to NAME table (SEGTABLE)
4	PAGSWP DS	1F Pointer to swap table (SWPTABLE)

PAGTABLE, PGBLOK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
8	PAGCORE DS 1H	Real page address (start of page table for hardware)
	<u>Bits defined in PAGCORE+1</u>	
	PAGINVAL EQU X'08'	PAGTAELE entry invalid
	PAGREF EQU X'01'	Page has been referenced
	<u>Equates Used in Attached Processor Support for Shared Segments</u>	
	PAGTSWP EQU	(PAGCORE-PAGSTMP+16*L'PAGCCRE) length of a full 16 entry page table
	PAGBMP EQU	(PAGISWP+(SWPFLAG-SWPVM)+16* (SWPCODE-SWPFLAG+1)*8) length of a contiguous page and swap table

PGBLOK: PSEUDO PAGE FAULT STACK BLOCK

PGBLOK is used by VM/VS Handshaking. The block is created and stacked when a multiprogramming or multitasking VS1 program interrupt occurs when a referenced page is not available in storage. The VMBLOK field in the VMBLOK points to PGELCK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	PGPNT DS 1F	Pointer to next page block on the stack
4	PGADDR DS 1F	Virtual page fault address
	PGBSIZE EQU (*-PGBLOK+7)/8	PGELCK size in doublewords (X'01')

PSA: PREFIX STORAGE AREA (LOW STORAGE LOCATIONS)

PSA is the primary control block for controlling CP and virtual machine activity. This control block contains the normal low core IPL, logout, and PSW information; the processor model and type and features of the processor; and save areas used by BALR and FREE. This block also contains monitor and trace data and the necessary linkages to virtual machines, real devices, and spool files.

Note: All fields reside in real PSA unless otherwise specified. Fields residing in absolute PSA are specifically identified. For uniprocessor operation, real PSA equals absolute PSA (or 0). If the system was running in AF mode when a catastrophic error occurred, the Attached Processor will no longer be running. System recovery is in uniprocessor mode and the real PSA will no longer be zero.

Page 0, Machine Usage

0	IPLPSW	!	IPLCCW1		37C	CPIID	CPABEND F*3 P*4 ASYSVM
10	IPLCCW2	!	EXOPSW		38C	ARSPPR	ARSPFU ARSPRD ARICPU
20	SVCOPSW	!	PROPSW		39C	ARIOPR	ARIORD F*5 F*6 ARSPAC
30	MCOPSW	!	IOOPSW		3AC	AVMREAL	ASYSABND ASYSLC ASYSOP
40	CSW	!	CAW QUANTUMR		3EC	ARIOCT	ARIOCH ARICCU ARICDV
50	TIMER QUANTUM	!	EXNPSW		3CC	ARIOPC	ARIOUC ARICDC ACORETEL
60	SVCNPSW	!	PRNPSW		3DC	APAGCF	CPCREG0 CECREG6 CPCREG8
70	MCNPSW	!	IONPSW		3EC	TIMEDISP	ASVCLIST AVMALIST LASTUSER
80			CPULOG		3FC	PAGECUR	MONNEXT FAGEND PAGENXT
100			FXDLOG		40C	TRACEFLG	TTSEGCNT ////////////////////////////////
160			FPRLOG				///////////////////PSARSV15//////////////////
180			GPRLOG		43C	INSTWRD1 INSTWRD2 INSTWRD3 INSTWRD4	
1C0			CRLOG		44C		Constants Fcol
200			TEMPSAVE				.
240			BALRSAVE				.
280			FREESAVE				.
2C0			FREEWORK				.
2F0	DATE	!	TODATE				.
300	STARTIME	!	CPUID				.
310	IDLEWAIT	!	PAGEWAIT				.
320	IONTWAIT	!	PROBTIME				.
330	RUNPSW	!	RUNUSER DSPLPSW				.
340	RUNCRO RUNCR1	!	CPSTAT CPRESTRT				.
350	PGREAD PGWRITE	!	PGWAITIM				.
360	////PGWAITPG//////	!	PSASVCCT P*1 P*2				.

5C0	MFASAVE		6EC	CHGREGS	RESERVED
.	.	.	6CC	UNSHRVM P*10 P*11	RESERVED
.	.	.	6DC	STACKVM UNSHRVM2 ADMKCFE RESERVED/	
600	SWTHSAVE		6EC	RESERVED (cont)	
.	.	.	6FC	ALOKUM RESERVE ALCKSF AEXTSP	
640	LOCKSAV		70C	ATMRSN RESERVED	
650	SVCREGS		71C	MCRREGS	
660	PREFIXA PREFIXB PSACPXBFI//RESVD//		750	LOCKSAVE2	
670	WAITSTRRT WAITEND		.	.	
680	PWTPAGES ACTIVTRQ EMSPEND EMSREC		.	.	
690	XCPEND P*7 P*8 P*9 APSTATUS		.	.	
6A0	AMCHARERA SHRLKCNT PROBSTRRT		.	.	

Hexadecimal Displacement	Field Name	Machine Usage	Field Description, Contents, Meaning
0	IPLPSW	DS 1D	IPL start PSW
	RSRTNPSW	ORG DS 1D	Restart new PSW
	RSRTOPSW	DS 1D	Restart old PSW
8	IPLCCW1	DS 1D	IPL CCW
10	IPLCCW2	DS 1D	IPL CCW
	PSARSV3	ORG DS 1F	Reserved for IBM use
C	TRACSTRRT	DS 1F	Address of start of trace table. Note that TRACSTRRT is in absolute PSA
10	TRACEND	DS 1F	Address of end of trace table. Note that TRACEND is in absolute PSA
14	TRACCURR	DS 1F	Address of next available trace table entry. Note that TRACCURR is in absolute PSA
18	EXOPSW	DS 1D	External old PSW
20	SVCOPSW	DS 1D	SVC cld PSW
28	PROPSW	DS 1D	Program old PSW
30	MCOPSW	DS 1D	Machine check old PSW
38	IOOPSW	DS 1D	I/O cld PSW
40	CSW	DS 1D	Channel status word
48	CAW	DS 1F	Channel address word
4C	QUANTUMR	DS 1F	Interval timer value at last interrupt
50	TIMER	DS 1F	13-microsecond interval timer
54	QUANTUM	DS 1F	Interval timer value at last dispatch
58	EXNPSW	DS 1D	External new PSW
60	SVCNPSW	DS 1D	SVC new PSW
68	PRNPSW	DS 1D	Program new PSW
70	MCNPSW	DS 1D	Machine check new PSW
78	IONPSW	DS 1D	I/O new PSW

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
80	CPULOG DS 16D	Processor and storage logout area
80	ORG CPULOG	
80	DS 1F	Reserved for IBM use
84	INTEXF DS 1F	External interrupt code (fullword)
86	<u>Bits defined in INTEXF</u> INTEX EQU INTEXF+2	External interrupt code (halfword)
88	INTSVCL DS 1H	SVC instruction length code (ILC)
8A	INTSVC DS 1H	SVC interrupt code
8C	INTPRL DS 1H	Program instruction length code (ILC)
8E	INTPR DS 1H	Program interrupt code
90	TREXADD DS 1F	Translation exception address
94	MONCLASS DS 1H	Monitor class
96	PERCODE DS 1H	PER code to be reflected
98	PERADD DS 1F	Address of instruction causing PER interrupt
9C	MONCODE DS 1F	Monitor code
A0	DS 1D	Reserved for IBM use
A8	CHANID DS 1F	Channel ID
AC	IOELPNTR DS 1F	I/O extended logout (IOEL) pointer
B0	ECSWLOG DS 1F	Limited channel logout (ECSW)
B4	DS 1F	Reserved for IBM use
B8	INTKFLIN DS 1F	I/O interrupt key, flags, and interface address
BA	<u>Bits defined in INTKFLIN</u> INTTIO EQU INTKFLIN+2	I/O interrupt device address (halfword)
BC	DS 11F	Reserved for IBM use
B8	INTMC DS 1D	Machine check interrupt code
F0	DS 1F	Reserved for IBM use
F4	INTRC DS 1X	External damage reason code
F5	DS 3X	Reserved for IBM use
F8	FAILSTAD DS 1F	Failing storage address
FC	REGNCODE DS 1F	Region code
100	FXDLOG DS 12D	Fixed logout area
160	FPRLOG DS 4D	Floating-point register logout area
180	GRLOG DS 16F	General register logout area
1C0	CRLLOG DS 16F	Control register logout area
200	CPUSAGE DS 0H	End of machine usage; start of CP usage
200	ORG CPUSAGE	
200	TEMPSAVE DS 16F	Temporary save area
200	ORG TEMPSAVE	
204	TEMPRO DS 1F	Registers 0-15
208	TEMPR1 DS 1F	
20C	TEMPR2 DS 1F	
210	TEMPR3 DS 1F	
214	TEMPR4 DS 1F	
218	TEMPR5 DS 1F	
21C	TEMPR6 DS 1F	
220	TEMPR7 DS 1F	
224	TEMPR8 DS 1F	
228	TEMPR9 DS 1F	
22C	TEMPR10 DS 1F	
230	TEMPR11 DS 1F	
234	TEMPR12 DS 1F	
238	TEMPR13 DS 1F	
23C	TEMPR14 DS 1F	
	TEMPR15 DS 1F	

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
240	BALRSAVE DS	16F	BALR linkage save area
	ORG BALRSAVE		
240	BALR0 DS	1F	Registers 0-15
244	BALR1 DS	1F	
248	BALR2 DS	1F	
24C	BALR3 DS	1F	
250	BALR4 DS	1F	
254	BALR5 DS	1F	
258	BALR6 DS	1F	
25C	BALR7 DS	1F	
260	BALR8 DS	1F	
264	BALR9 DS	1F	
268	BALR10 DS	1F	
26C	BALR11 DS	1F	
270	BALR12 DS	1F	
274	BALR13 DS	1F	
278	BALR14 DS	1F	
27C	BALR15 DS	1F	
280	FREESAVE DS	16F	DMKFRE save area
	ORG FREESAVE		
280	FREERO DS	1F	Registers 0-15
284	FREER1 DS	1F	
288	FREER2 DS	1F	
28C	FREER3 DS	1F	
290	FREER4 DS	1F	
294	FREER5 DS	1F	
298	FREER6 DS	1F	
29C	FREER7 DS	1F	
2A0	FREER8 DS	1F	
2A4	FREER9 DS	1F	
2A8	FREER10 DS	1F	
2AC	FREER11 DS	1F	
2B0	FREER12 DS	1F	
2B4	FREER13 DS	1F	
2B8	FREER14 DS	1F	
2BC	FREER15 DS	1F	
2C0	FREEWORK DS	12F	DMKFRE work area
2F0	DATE DS	CL8	Date - mm/dd/yy - edited EBCDIC
2F8	TODATE DS	1D	TOD clock at hh.mm.ss today - local time
300	STARTIME DS	1D	Date and time started - TOL clock value
308	CPUID DS	1D	Processor identification field
	ORG CPUID		
308	CPUVERSN DS	1X	Version code
309	CPUSER DS	3X	Processor serial number - packed unsigned
30C	CPUMODEL DS	2X	Processor model number
30E	CPUMCELL DS	1H	Maximum length in bytes of MCEL
310	IDLEWAIT DC	X'7FFFFFFFFFFF000'	Total system idle wait time
318	PAGEWAIT DC	X'7FFFFFFFFFFF000'	Total system page wait time
320	IONTWAIT DC	X'7FFFFFFFFFFF000'	Total system I/O wait time
328	PROBTIME DC	X'7FFFFFFFFFFF000'	Total system problem state time
330	RUNPSW DS	1D	PSW last loaded by dispatcher
338	RUNUSER DS	1F	Address of dispatched VMELOCK
33C	DSPLPSW DS	1F	Load PSW instruction used to dispatch
340	RUNCRO DS	1F	Control register 0 at dispatch
344	RUNCRI DS	1F	Control register 1 at dispatch

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
348	CPSTAT	DS	1F	CP running status
348	CPSTATUS	ORG DS	CPSTAT 1X	CP running status
			<u>Bits defined in CPSTATUS</u>	
	CPWAIT	EQU	X'80'	CP in wait state
	CPRUN	EQU	X'40'	CP running user in RUNUSER
	CPEX	EQU	X'20'	CP executing stacked request
	CPFVRUN	EQU	X'10'	Reserved for IBM use
	CPSUPER	EQU	X'08'	Processor is executing in supervisor state
349	XTNDLOCK	DC	1X	System extending free storage if it is equal to X'FF'. Note that XTNDLOCK is in absolute PSA.
34A	CPSTAT2	DC	1X	Flag byte
			<u>Bits defined in CPSTAT2</u>	
	CPMICAVL	EQU	X'80'	Virtual machine assist available on processor
	CPMICON	EQU	X'40'	Virtual machine assist is on for system
	CPSHRLK	EQU	X'20'	CP processing shared named system page
	CPASTAVL	EQU	X'08'	CP assist available on processor
	CPASTON	EQU	X'04'	CP assist is on for system
34B	CPSTAT3	DS	1X	Wait time accounting flag
			<u>Bits defined in CPSTAT3</u>	
	CPTIDLE	EQU	X'80'	Timer contains idle time
	CPTPAGE	EQU	X'40'	Timer contains page wait time
	CPTIONT	EQU	X'20'	Timer contains I/O wait time
34C	CPRESTRT	DS	1F	Restart address if external interrupt marks page invalid
350	PGREAD	DS	1F	Total number of page reads
354	PGWRITE	DS	1F	Total number of page writes
358	PGWAITIM	DS	1D	Time spent in page wait, multiplied by number of pages waiting
360	PGWAITPG	DS	1D	Reserved for IBM use
368	PSASVCCT	DS	1F	Total number of user SVCS
36C	PAGELOAD	DS	1H	P*1 Page wait percent, last measurement
36E	PAGERATE	DS	1H	P*2 Paging rate, pages per secnd Note that PAGERATE is in absolute PSA.
370	PSENDCLR	DS	0F	End of area cleared by DMKCFINT
370	CPID	DS	1F	CP running identifier. Note that CPID is in absolute PSA.
374	CPABEND	DS	1F	CP abend code
378	PSTARTSV	DS	0F	Start of save/restored code
378	SYSIPLDV	DS	1H	P*3 Device address of system IFL device
37A	PGSRATIO	DC	H'0'	P*4 Page steals/total replenished
37C	ASYSVM	DC	V(DMKSYSVM)	Address of system VMBLCK
380	ARSPPR	DC	V(DMKRSPPR)	Address of system printer file chain.
384	ARSPPU	DC	V(DMKRSPPU)	Address of system punch file chain.
388	ARSPRD	DC	V(DMKRSPRD)	Address of system reader file chain.
38C	ARIOPU	DC	V(DMKRIOPU)	Address of system punch table.
390	ARIOPR	DC	V(DMKRIOPR)	Address of system printer table.
394	ARIORD	DC	V(DMKRIORD)	Address of system reader table.
398	IPUADDR	DS	1H	P*5 Instruction processing address
39A	PSAMSS	DS	1H	P*6 Address of MSS volume
			<u>Bits defined in PSAMSS</u>	
	MSSPRES	EQU	X'80'	The MSS is online and the MSS communicator has been initialized

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
39C	ARSPAC	DC V(DMKRSPAC)
3A0	AVMREAL	DC A(0)
3A4	ASYSABND	DC A(0)
3A8	ASYSLC	DC V(DMKSYSLC)
3AC	ASYSOP	DC V(DMKSYSOP)
3B0	ARI OCT	DC V(DMKRIOCT)
3B4	ARI OCH	DC V(DMKRIOCH)
3B8	ARI OCU	DC V(DMKRIOCU)
3BC	ARI ODV	DC V(DMKRIODV)
3C0	ARI OCC	DC V(DMKRIOCC)
3C4	ARI OUC	DC V(DMKRIOUC)
3C8	ARI ODC	DC V(DMKRIODC)
3CC	ACORETBL	DC V(DMKSYSCS)
3D0	APAGCP	DC A(X'FFFFFF')
3D4	CPCREG0	DC X'808008C0'
3D8	CPCREG6	DC F'0'
3DC	CPCREG8	DC F'0'
3E0	TIMEDISP	DS 1F
3E4	ASVCLIST	DC V(DMKSVCNS)
3E8	AVMALIST	DC V(DMKPRVMA)
3EC	LASTUSER	DC V(DMKSYSVM)
3F0	PAGECUR	DS 1F
3F4	MONNEXT	DS 1F
3F8	PAGEND	DS 1F
3FC	PAGENXT	DS 1F
400	TRACEFLG	DS 1F
400	ORG TRACEFLG	
400	TRACFLG1	DS 1X
	<u>Bits defined in TRACFLG1</u>	
	TRAC01	EQU X'80'
	TRAC02	EQU X'40'
	TRAC03	EQU X'20'
	TRAC04	EQU X'10'
	TRAC05	EQU X'08'
	TRAC67	EQU X'04'
	TRAC08	EQU X'02'
	TRAC09	EQU X'01'
401	TRACFLG2	DS 1X
	<u>Bits defined in TRACFLG2</u>	
	TRAC0A	EQU X'80'
	TRAC0C	EQU X'40'
	TRAC0D	EQU X'20'
	TRACBEF	EQU X'10'
	TRAC10	EQU X'08'
	TRAC11	EQU X'04'
	TRAC12	EQU X'02'
	TRAC13	EQU X'01'
402	TRACFLG3	DS 1H
404	TTSEGCNT	DS 1F
408	PSARSV15	DS 5D
430	INSTWRD1	DC F'0'

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
434	INSTWRD2 DC	F'0'
438	INSTWRD3 DC	F'0'
43C	INSTWRD4 DC	F'0'
List of Frequently Used Constants		
440	ZEROES DC	6D'0'
470	BLANKS DC	8X'40'
478	FFS DC	8X'FF'
440	F0 EQU	ZEROES
480	F1 DC	F'1'
484	F2 DC	F'2'
488	F3 DC	F'3'
48C	F4 DC	F'4'
490	F5 DC	F'5'
494	F6 DC	F'6'
498	F7 DC	F'7'
49C	F8 DC	F'8'
4A0	F9 DC	F'9'
4A4	F10 DC	F'10'
4A8	F15 DC	F'15'
4AC	F16 DC	F'16'
4B0	F20 DC	F'20'
4B4	F24 DC	F'24'
4B8	F60 DC	F'60'
4BC	F240 DC	F'240'
4C0	F255 DC	F'255'
4C4	F256 DC	F'256'
4C8	F4095 DC	F'4095'
4CC	F4096 DC	F'4096'
		Also = X'CCCC000F'
4D0	APTRLK DC	V(DMKPTRLK)
4D4	NOADD DC	X'F000000'
4D8	X40FFS DC	X'40FFFFFF'
4DC	XRIGHT24 DC	X'00FFFFFF'
4E0	XPAGNUM DC	X'00FFF000'
4E4	XRIGHT16 DC	X'0000FFFF'
4E8	AFREE DC	V(DMKFREE)
4EC	AFRET DC	V(DMKFRET)
4F0	AQCNWT DC	V(DMKQCNWT)
4F4	ADSPCH DC	V(DMKDSPCH)
4F8	APTRAN DC	V(DMKPTRAN)
4FC	X2048BND DC	X'00FFF800'
		Entry to lock a page in storage
		Frequently used work value
		Frequently used work value
		Isolate right 24 bits
		Isolate the page number
		Isolate the right 16 bits
		Entry to allocate free storage
		Entry to release free storage
		Entry to write a terminal message
		Entry to the VM/370 dispatcher
		Entry to the paging supervisor
		Locate a half-page boundary
500	PSBCLR2 DS	0F
		Start of second area cleared by CP initialization (DMKCPI)
500	DUMPSAVE DS	16F
540	SIGSAVE DS	16F
580	LOKSAVE DS	16F
5C0	MFASAVE DS	16F
600	SWTHSAVE DS	16F
640	LOCKSAV DS	4F
650	SVCREGS DS	4F
660	PREFIXA DC	F'0'
664	PREFIXB DC	F'0'
668	PSACPXB P	A(0)
		Prefix value of this processor
		Prefix value of other processor
		Address of CPEXBLOK for switch SVC.
		Note that PSACPXB is in absolute PSA.
66C	RESVD DS	1F
670	WAITSTRT DS	D
678	WAITEND DS	D
680	PWTPAGES DC	F'0'
684	ACTIVTRQ DC	A(0)
		Pages in PGWAIT at start of wait
		Address of active transit queue


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
688	EMSPEND DC F'0'	Emergency signal pending flags
	<u>Bits defined in EMSPEND</u>	
	EMSPQUI EQU X'80'	Quiesce pending
	EMSPEXT EQU X'40'	Extend pending
	EMSPSYNC EQU X'20'	Synchronization pending
	EMSPSHD EQU X'10'	Shutdown pending
	EMSPCLKC EQU X'08'	High order TOD synchronization pending
	EMSINQSC EQU X'01'	Processor is quiesced
68C	EMSREC DC F'0'	Emergency signal received flags
	<u>Bits defined in EMSREC</u>	
	EMSRQUI EQU X'80'	Quiesce request received
	EMSREXT EQU X'40'	Extend request received
	EMSRSYNC EQU X'20'	Synchronization request received
	EMSRSHD EQU X'10'	Shutdown request received
	EMSRCLKC EQU X'08'	High order TOD synchronization received
690	XCPEND DC F'0'	External call pending flags
	<u>Bits defined in XCPEND</u>	
	XCAPR EQU X'80'	Automatic processor recovery pending
	XCRES EQU X'40'	Resume request pending
	XCWAK EQU X'20'	Wakeup request pending
	XCDISP EQU X'10'	Dispatch request pending
694	IPUADDRX DC H'0'	P*7 Processor address of other processor
696	LPUADDR DC H'0'	P*8 Logical address of this processor
698	LPUADDRX DC H'0'	P*9 Logical address of other processor
69A	APSTATUS DS 6X	Attached processor status bytes
69A	ORG APSTATUS	Attached processor status
	<u>Bits defined in APSTATUS</u>	
	APUOPER EQU X'80'	Attached processor operational
	PROCIO EQU X'40'	Processor has I/O capability
	APUNONLN EQU X'20'	System generated for attached processor mode but running in uniprocessor mode
	MPFEAT EQU X'10'	Multiprocessing feature is installed
	CPINITD EQU X'01'	System initialization complete
69B	APSTAT2 DC X'00'	Second flag byte
	<u>Bits defined in APSTAT2</u>	
	CPMCHK EQU X'10'	Machine check processing pending (for ECPS only)
	CPPTLBR EQU X'02'	PTLE required for processor
69C	CPTERMLK DC X'00'	DMKMCT system termination is in progress. Note that CPTERMLK is in absolute PSA.
69D	CPFRELK DC X'00'	Free storage extend pending. Note that CPFRELK is in absolute PSA.
69E	FRLKPROC DC X'00'	Logical processor identification for CPFRELK. Note that FRLKPROC is in absolute PSA.
69F	CPFRESW DC X'00'	DMKFRE must transfer execution to the attached processor. Note that CPFRESW is in absolute PSA.
6A0	AMCHAREA DC F'0'	Address of DMKMCH work area
6A4	SHRLKCNT DC F'0'	Count of times CPSHRLK is set (used to clear CPSHRLK)
6A8	PROBSTRT DS 1D	Virtual machine time out queue at dispatch

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
6B0	CHGREGS	DS	2F	Save area for charge synchronization
6B8	RESERVED	DS	2F	Reserved for IBM use
6C0	UNSHRVM	DC	A(0)	VMELOCK for pending DMKVMAPs call (attached processor only)
6C4	TRACPROC	DC	X'00'	P*10 Processor identifier for CP trace table entries
6C5	APSTAT	DS	3X	More attached processor status flag bytes
6C5	APSTAT3	ORG DC	APSTAT X'00'	Third attached processor status flag byte
<u>Bits defined in APSTAT3</u>		CPSYSLK EQU	X'80'	Other processor is spinning on lock
6C6	APSTAT4	ORG DC	APSTAT X'00'	P*11 Fourth attached processor status flag byte
<u>Bits defined in APSTAT4</u>		CPLOKFL EQU	X'80'	DMKLCK enabled for external interrupts
		RECMODE EQU	X'40'	Processor will record soft machine checks
		CPMCHSE EQU	X'20'	Machine check processing pending (CPMCHSE is the replacement of CPMCHK in APSTAT2)
		PROCSCHK EQU	X'10'	TOD synchronous check received
		CPAPRPND EQU	X'08'	Automatic processor recovery pending
		POFFLINE EQU	X'04'	Vary processor function in use
6C8	RESERVE	DS	2F	Reserved for IBM use
6D0	STACKVM	DC	A(0)	R11 for dispatcher unstacking
6D4	UNSHRVM2	DC	A(0)	R2 value for pending VMAPs call (attached processor only)
6D8	ADMKCPE	DC	V(DMKCPE)	Address of DMKCPE for IPCS use
6DC	RESERVED	DS	5F	Reserved for IBM use
	PSECLR2	DS	0F	End of second area cleared by CP initialization (DMKCPI)
6F0	ALOKVM	DC	V(DMKLOKVM)	Entry to lock VMBLOK
6F4	RESERVED	DC	1F	Reserved for IBM use
6F8	ALOKSP	DC	V(DMKLOKSP)	Entry to spin on lock
6FA	AEXTSP	DC	V(DMKEXTSP)	Entry to signal processor routine
700	ATMRSN	DC	V(DMKTMRSN)	Entry to charge synchronization routine
704	RESERVED	DC	3F'0'	Reserved for IBM use
710	MONREGS	DC	16F	Register save area for Monitor call
750	LOKSAVE2	DC	16F	Save area for switching to virtual machine in DMKLOK
	PSAEND	DS	0D	End of page 0 usage

PWDIBLOK

| PWDIBLOK: PASSWORD INVALID BLOCK

| The PWDIBLOK is used to retain information about invalid passwords supplied with LOGON
| and AUTOLOG commands.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	PWDUSRID DS CL8	Userid attempting LOGON or AUTOLOG
8	PWDDATE DS CL6	Date (mmddyy)
E	PWDTIME DS CL8	Time (hh:mm:ss)
14	PWDTERMA DS CL4	Terminal address
18	PWDCHAIN DS F	Address of next PWDIBLOK
1C	PWDINVCT DS 1X	P*1 Invalid password count
1D	PWDFLAGS DS 1X	P*2 Flags
<u>Bits defined in PWDFLAGS</u>		
	PWDLOG EQU X'80'	This block for LOGON
	PWDALOG EQU X'40'	This block for AUTOLOG
1E	DS XL2	Reserved for IBM use

Real I/O Control Blocks

In order to control the activity of the I/O devices of the system and schedule I/O requests upon them, I/O control uses several types of control blocks. These blocks can be separated into two basic types:

- Static blocks that describe the components of the I/O system.
- Dynamic blocks that represent active and pending requests for I/O operations.

The I/O components of the real system are described by one control block for each channel, control unit, and device available to the control program. Units present but not represented by control blocks are not available for either user-initiated or control program-initiated operations.

REAL CHANNEL CONTROL BLOCKS

For each channel attached to the system there exists a Real Channel Control Block (RCHEBLOK) which contains:

- The channel portion of the address of its attached units,
- Status flags indicating the channel's availability for scheduling.
- A two-way queue anchor pointing to the list of I/O requests waiting to use the channel.

In addition, each RCHEBLOK contains 32 halfword indexes, arranged in ascending address order, that represent the displacement into the Real Control Unit table of the control blocks for the control units attached to the channel. The 32 entries are required because the control unit address may be made up of five bits from the unit address. To locate the control block for a given unit:

1. Index into the table in the RCHEBLOK a displacement equal to twice the control unit address.
2. Load the index value.
3. Add the value to the base address of the Real Control Unit Table.

REAL CONTROL UNIT BLOCKS

The Real Control Unit Table is composed of Real Control Unit Blocks (RCUEBLOK), one for each control unit on the system. These blocks are similar to the RCHEBLOK in that they contain the control unit portion of the address and status flags, and a pointer to a queue of I/O requests. In addition, the RCUEBLOK contains a pointer to the RCHEBLOK for the channel to which it is attached. The RCUEBLOK contains a table of 16 halfword entries that represent the displacement into the Real Device Table of its attached devices. This table is referenced in the same manner as the table in the RCHEBLOK.

REAL DEVICE CONTROL BLOCKS

Each device and 3270 remote communications line in the system is represented by a Real Device Control Block (RDEVELCK), contains the device portion of the unit address and status flags similar to those in RCHELCK and RCUELCK. There is also a pointer for those operations that are waiting for the device to become available. Fields that appear in the RDEVELCK and not in the other blocks include a pointer to the I/O request that is currently active on the device, SIC counts, and a pointer to error and sense information. The RDEVELCK contains a pointer to the RCUEBLOK for the control unit to which it is attached and fields of device dependent information which do not affect the operation of I/O control.

If the RDEVBLOK is associated with 3270 remote communications line, then the RDEVELCK contains a pointer to NICBLCKs that represents the resources on that line.

INPUT/OUTPUT BLOCKS

I/O requests that are active in the system are represented by Input/Output Blocks (ICELOK). There is one ICELOK for each operation (that is, channel program) to be executed. The ICELOK is constructed by the requesting task and contains such information as:

- The identity of the requestor
- The address of the channel program to be executed

The address to which control is to be returned upon completion of the operation

In addition, the IOBLOK contains status flags that indicate the current state of the operation (such as, whether or not an error has occurred, if an errcr recovery procedure (ERP) is in control, and the condition returned from the SIO) and the CSW associated with the interrupt that signals the end of the operation. Since IOBLOKS are queued off various I/O control blocks, they also contain forward and backward queue pointers. DMKIOS builds in them the real device address of the unit on which the operation is started.

In general, the IOBLOK representing a given operation progresses through the system by being queued, in turn, from device, control unit, and channel blocks until a path is at last free to the device. A SIO is then issued. After the operation is complete, the IOBLOK is dequeued from the RDEVBLOK and stacked on a queue maintained in the dispatcher, DMKDSP. Each time the dispatcher is entered, the entries on the queue are unstacked and control is

passed to the point specified in the Interrupt Return Address (IOEIRA). After I/C contrcl stacks the ICBLCK for the given task, it attempts to restart all of the components that have been freed by the completion of the operation.


NETWORK INTERFACE CONTROL FLOCK

There is one Network Interface Cctrcl Elcck (NICBLOK) for each defined 370x and each resource attached to a 3270 bisynchronous line. The NICBLOK provides the correspondence between the line or device address and the physical resource connected to that line. This block not only defines the identity cf the terminal type, line, or control unit but it also contains flags and status information pertaining to that resource. If the defined resource is a remote 3270 component, the NICBLOK ccntains the current line coordinates, polling and selection characters information as well.

The remainder of this secticn describes the real I/O control blocks.

RCHBLOK: REAL CHANNEL BLOCK

RCHBLOK contains status and type information for the specified channel. The linkage to I/O tasks operated on by that channel and to the control units attached to that channel is also maintained. The ARIOCH field of the PSA points to the first RCHBLOK, which is generated in contiguous storage.



Hexadecimal Displacement	Field Name	DS	1H		Field Description, Contents, Meaning				
0	RCHADD	DS	1H		Channel address				
2	RCHLOCK	DS	1H		Channel lock				
4	RCHSTAT	DS	1X	R*1	Channel status				
<u>Bits defined in RCHSTAT</u>									
	RCHBUSY	EQU	X'80'		Channel busy				
	RCHSCED	EQU	X'40'		IOE scheduled on channel				
	RCHDED	EQU	X'01'		Channel dedicated				
5	RCHTYPE	DS	1X	R*2	Channel type				
<u>Bits defined in RCHTYPE</u>									
	RCHSEL	EQU	X'80'		Selector channel				
	RCHBMX	EQU	X'40'		Block multiplexer channel				
	RCHMPX	EQU	X'20'		Byte multiplexer channel				
	RCH370	EQU	X'01'		S/370 type channel (S/370 I/C instruction support)				
6	RCHQCNT	DS	1H		Number of ICBLOKS queued off channel				
8	RCHFIQB	DS	1F		Pointer to first IOBLOK queued				
C	RCHLIQB	DS	1F		Pointer to last IOBLOK queued				
10	RCHDTCK	DS	1X	R*3	Channel data check count				
11	RCHCCCK	DS	1X	R*4	Channel control check count				
12	RCHIFCC	DS	1X	R*5	Interface control check count				
13	RCHCHCK	DS	1X	R*6	Channel chaining check count				
14	RCHSTIDC	DS	1F		Result of STIDC instruction issued at CP initialization; if cc = 3, the ccnt is X'FFFFFF'				
18	RCHRSTQ	DS	1F		Address of channel to be restarted				
1C	RCHOPER	DS	1F		IOELOK operational on channel time				
20	RCHCUTBL	DS	32H		Control units attached - RCUSTART index (The index values must be multiplied by 8 and added to the beginning of the REVELOK table (ARIODV).)				
	RCHSIZE	EQU	(*-RCHBLOK)/8		RCHELOCK size in doublewords (X'0D')				

RCUBLOK

RCUBLOK: REAL CONTROL UNIT BLOCK

RCUBLOK provides control and status information on a defined real control unit. Linkages are provided to queued IOBLOKS. The ARIOCU field of the PSA points to the first RCUBLOK, which is generated in contiguous storage.

0	RCUADD		RCULOCK		R*1		R*2		RCUQCNT
8	RCUFIOB								RCULIOB
10	RCUCHA								RCUCEB
18	RCUCHC								RCUCED
20	RCURSTQ								RCUOFER
28									RCUDVTEL
.									.
.									.
.									(Variable Length)


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	RCUADD DS 1H	Control unit address
2	RCULOCK DS 1H	Control unit lock
4	RCUSTAT DS 1X R*1	Control unit status
	<u>Bits defined in RCUSTAT</u>	
	RCUBUSY EQU X'80'	Control unit busy
	RCUSCED EQU X'40'	IOB scheduled on control unit
	RCUDISA EQU X'20'	Control unit disabled
	RCUCHAOF EQU X'08'	RCUEA to RCHBLOCK path is not available
	RCUCHBOK EQU X'04'	RCUCBE to RCHBLOCK path is not available
	RCUCHCOF EQU X'02'	RCUCHC to RCHBLOCK path is not available
	RCUCHDOF EQU X'01'	RCUCHD to RCHBLOCK path is not available
5	RCUTYPE DS 1X R*2	Control unit type
	<u>Bits defined in RCUTYPE</u>	
	RCUSHRD EQU X'80'	This control unit can be attached to only one subchannel
	RCUSUB EQU X'40'	This is a subordinate control unit
	RCU2703 EQU X'03'	TCU is a 2703
	RCU2702 EQU X'02'	TCU is a 2702
	RCU2701 EQU X'01'	TCU is a 2701
6	RCUQCNT DS 1H	Number of ICBLOKS queued off control unit
8	RCUFIOB DS 1F	Pointer to first ICBLOK queued
C	RCULIOB DS 1F	Pointer to last IOBLOK queued
10	RCUCHA DS 1F	Pointer to RCHBLOCK - path A
	RCUPRIME ORG RCUCHA	
10	RCUPRIME DS 1F	Pointer to the primary control unit

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
14	RCUCHB	DS	1F	Pointer to RCHBLOK - path E
18	RCUCHC	DS	1F	Pointer to RCHBLCK - path C
1C	RCUCHD	DS	1F	Pointer to RCHBLOK - path I
20	RCURSTQ	DS	1F	Address of control unit to be restarted
24	RCUOPER	DS	1F	IOBLCK operational on control unit time
28	RCUDVTBL	DS	16H	Devices attached - RDVSTART index (The index values must be multiplied by 8 and added to the beginning of the RDEVBLOK table (ARIODV).)
	RCUSIZE	EQU	(*-RCUBLOCK)/8	RCUELOK size in doublewords (X'08')

RCWTASK

RCWTASK: TRANSLATED VIRTUAL I/O CCW

RCWTASK contains the virtual-to-real CCW translation and other data related to a virtual machine's I/O operation. A pointer is maintained to the virtual CCW operation. The first CCW-16 points to the beginning of RCWTASK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	RCWPNT DS 1F	Pointer to next RCWTASK
4	RCWVCBW DS 1F	Virtual address of CCW chain
8	RCWCNT DS 1H	Virtual CCW count
A	RCWRCCNT DS 1H	Real CCW count
C	RCWHEAD DS 1H	RCWTASK header mark X'FFFF'
E	RCWCCNT DS 1H	RCWTASK control word count
10	RCWCCW DS 1D	One or more CCWs for device I/O
	ORG RCWCCW	
10	RCWADDR DS 1F	CCW data address
14	RCWFLAG DS 1X	CCW flag bits
15	RCWCTL DS 1X	CCW CP-control bits
	Bits defined in RCWCTL	
	RCWIO EQU X'80'	I/O data page locked
	RCWGEN EQU X'40'	CP-generated CCW
	RCWHMR EQU X'20'	DMKUNIT must relocate home address/record R0
	RCWREL EQU X'10'	CCW address relocatable if CCWs moved
	RCWISAM EQU X'08'	ISAM modifying CCW
	RCW2311 EQU X'04'	TYP2311T-E pseudo 2311 on 2314
	RCWINVL EQU X'02'	CCW operation code or address is invalid
	RCWSHR EQU X'01'	Shared user page was copied
16	RCWCNT DS 1H	CCW byte count
	ORG RCWADDR	
10	RCWCOMND DS 1X	CCW command code

RDEVEBLOK: REAL DEVICE BLOCK

RDEVEBLOK is generated by the RDEV macro at system generation. There is one RDEVELOCK for each real device and one for each binary synchronous line. The block contains status and device parameters applicable to I/O instruction processing. The ARICDV field of the PSA and the VDEVREAL field of the VDEVBLOCK point to the first RDEVELOCK, which is generated in contiguous storage.

0	RDEVADD		RDEVLOCK		R*1		R*2		R*3		R*4
8	RDEVFIOB								RDEVLIOB		
10	RDEVCUA								RDEVCUB		
RDEVQUED											
20	RDEVIOCT								RDEVIAOB		
28	RDEVUSER				RDEVATT				RDEVCYL		
30	RDEVSER								RDEVLNKS		
38	RDEVTCTL (8 device dependent bytes)										
40	RDEVTMAT				R*5		R*6		R*7		R*8
48	RDEVIOER								RDEVCTRS		
50	RDEVNAME	//RDEVRSV1///							RDEVIOBL		

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	RDEVADD DS	1H Device address
2	RDEVLOCK DS	1H Device lock
4	RDEVSTAT DS	1X R*1 Device status
<u>Bits defined in RDEVSTAT</u>		
	RDEVBUSY EQU X'80'	Device busy
	RDEVSCED EQU X'40'	IOP scheduled on device
	RDEVDISA EQU X'20'	Device disabled (offline)
	RDEVRSVD EQU X'10'	Device reserved
	RDEVIRM EQU X'08'	Device in intensive error recording mode
	RDEVNRDY EQU X'04'	Device intervention required
	RDEVWAIID EQU X'02'	GRAF - IOBLOCK pending, queue requests
	RDEVDED EQU X'01'	Dedicated device (attached to a virtual machine)

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
5	RDEVFLAG DS	1X R*2 Device flags, device dependent
	Bits defined in RDEVFLAG	
	RDEVSKUP EQU X'80'	DASD - ascending order seek queuing
	RDEVPREF EQU X'40'	EASD - volume preferred for paging
	RDEVSYS EQU X'20'	EASI - volume attached to system
	RDEVOWN EQU X'10'	DASL - CP-owned volume
	RDEVMOUT EQU X'08'	DASD - volume mounted, not attached
	RDEV333V EQU X'04'	DASD - volume dedicated as 3330V
	RDEVSEL EQU X'02'	EASI - device selected for MSS mount
	RDEVPSUP EQU X'80'	Console - terminal has print suppress
	RDEVPREP EQU X'40'	Console - terminal executing PREPARE command
	RDEVACTV EQU X'20'	Console - ICBLOK pending; queue request
	RDEVIDNT EQU X'10'	Console - 2741 terminal code identified
	RDEVENAB EQU X'08'	Console - device is enabled
	RDEVHIO EQU X'04'	Console - next interrupt from a Halt I/O
	RDEVDISB EQU X'02'	Console - device is to be disabled
	RDEVEPMD EQU X'01'	Console - 370x NCP resource in EP mode
	RDEVDRAN EQU X'80'	Spooling - device output drained
	RDEVTERM EQU X'40'	Spooling - device output terminated
	RDEVACNT EQU X'20'	Spooling - device busy with accounting
	RDEVSPAC EQU X'10'	Spooling - force printer to single space
	RDEVRSTR EQU X'08'	Spooling - restart current file
	RDEVBACK EQU X'04'	Spooling - backspace the current file
	RDEVSEP EQU X'02'	Spooling - print/punch job separator
	RDEVLOAD EQU X'01'	Spooling - UCS buffer verified
	RDEVLNCP EQU X'80'	Special - network control program active
	RDEVLCEP EQU X'40'	Special - 270x Emulation program active
	RDEVSLOW EQU X'20'	Special - 370x in buffer slowdown mode
	RDEVAUTO EQU X'10'	Special - automatic dump/lcad enabled
	RDEVWAIT EQU X'08'	Special - ICBLOK pending; queue requests
	RDEVPLN EQU X'04'	Special - emulator lines in use by system
	RDEVRCVY EQU X'02'	Special - automatic dump/lcad process active
	RDEVTBTU EQU X'01'	Special - BTU trace requested
6	RDEVTPC DS	1X R*3 Device type class (see "Appendix A. CP and RSCS Equate Symbols")
7	RDEVTYPE DS	1X R*4 Device type (see "Appendix A. CP and RSCS Equate Symbols")
8	RDEVFIOB DS	1F Pointer to first ICBLOK queued
C	RDEVLIQB DS	1F Pointer to last IOBLCK queued
10	RDEVCUA DS	1F Pointer to RCUBLOK - interface A
14	RDEVCUB DS	1F Pointer to RCUBLOK - interface B
18	RDEVQUED DS	1D IOBLCK queued time - TOD clock units
20	RDEVIOCT DS	1F Device I/O count
24	RDEVAIOB DS	1F Active IOBLCK
28	RDEVUSER DS	1F Pointer to VMBLOCK of dedicated user
2C	RDEVATT DS	1H Attached virtual address
2E	RDEVCYL DS	1H EASI - current cylinder location
30	RDEVSER DS	CL6 Device volume serial number
36	RDEVLNKS DS	1H DASL - number of links to this disk
38	RDEVTCTL DS	8X 8 device-dependent terminal control bytes
40	RDEVTMAT DS	1F Device attached time - TCD clock word 0
44	RDEVQCNT DS	1X R*5 Number of queued ICBLOCKS


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
45	RDEVSTA2 DS 1X R*6	Device status (byte 2)
<u>Bits defined in RDEVSTA2</u>		
	RDEVRACT EQU X'80'	Active device is being reset
	RDEVBUCH EQU X'40'	Device is busy with the channel
	RDEVCONC EQU X'20'	Contingent connection present
	RDEVDROP EQU X'10'	Logdrop or loghold indicated
	RDEVALT EQU X'08'	Alternate path device
	RDEVSYBC EQU X'04'	Attention signal during active I/O
	RDEVPURG EQU X'02'	3800 - Purge files in error
	RETRYSW EQU X'01'	Retry count switch
46	RDEVMDL DS 1X R*7	Device model number
47	RDEVFTR DS 1X R*8	Device feature code
48	RDEVIOER DS 1F	Pointer to IOERBLCK for last CP error
4C	RDEVCTRS DS 1F	Pointer to error counter control block
50	RDEVNAME DS 1H	Real device name
52	RDEVRSV1 DS 1H	Reserved for IBM use
54	RDEVIOBL DS 1F	IOBLCK queue lock
	RDEVSIZE EQU (*-RDEVELOK)/8	RDEVELOK size in doublewords (X'0B')
<u>For CP-owned Devices</u>		
	ORG RDEVUSER	
28	RDEVALLN DS 1F	Anchor for ALOCBLCK chain for this device
2C	RDEVCODE DS 1H	Device code - SYSOWNED index
	ORG RDEVTCTL	
38	RDEVPAGE DS 1F	Anchor for RECBLCK chain for paging
3C	RDEVRECS DS 1F	Anchor for RECBLCK chain for spooling
40	RDEVPNT DS 1F	Pointer to next RDEVBLCK for allocation
<u>For Slotted 2301 Paging Drums</u>		
	ORG RDEVRECS	
3C	RDEVDCTL DS 1F	Pointer to DRUMTABL control block
<u>For Graphic Devices</u>		
	ORG RDEVCYL	
2E	RDEVCORD DS 1H	Current line coordinates
30	RDEVGRTB DS 1F	Address of table of CCWs and data streams
<u>For Spooling Unit Record Devices</u>		
	ORG RDEVQUED	
18	RDEVSPL DS 1F	Pointer to active RSPLCTL block
1C	RDEVCLAS DS 4C	Device class(es)
	ORG RDEVUSER	
28	RDEVDELP DS A	
2C	RDEVCURP DS 1X	Current page length in half inches
2D	DS 1X	Reserved for IBM use
2E	RDEVMAXP DS 1X	Maximum number of entries in delay purge queue
2F	RDEVFSEP DS 1X	Function control block for separator Page (6, 8, or 12)
30	RDEVXSEP DS CL4	Name of character arrangement table for the separator page
34	RDEVEXTN DS 1A	Pointer to the 3800 extension
38	RDEVIMAG DS CL8	Name of current image library
40	RDEVOLVY DS CL4	Name of current forms overlay
<u>For Terminal Devices</u>		
	ORG RDEVQUED	
18	RDEVCON DS 1F	Pointer to CONTASK list
1C	RDEVAIR4 DS 1F	Attention interrupt return address
	ORG RDEVTCTL	
38	RDEVRCNT DS 1H	Start/stop line retry count

RDEVBLOK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
3A	RDEVTFLG DS 1X	Additional terminal flags
	<u>Bits defined in RDEVTFLG</u>	
	RDEVLOG EQU X'80'	TERM and GRAF - Logon process has been initiated
	RDEVREST EQU X'40'	TERM - Terminal in reset process
	RDEVATOF EQU X'20'	TERM - Suppress attention signal
	RDEVLOG EQU X'80'	GRAF - Logon process has been initiated
	RDEVMORE EQU X'40'	GRAF - Screen full; more data waiting
	RDEVRUN EQU X'20'	GRAF - Screen in running status
	RDEVREAD EQU X'10'	GRAF - Read pending for screen input
	RDEVCPNA EQU X'08'	GRAF - Last input not accepted
	RDEVTRQ EQU X'04'	GRAF - Timer request pending
	RDEVCTL EQU X'02'	GRAF - Control function interrupt pending
	RDEVHOLD EQU X'01'	GRAF - Screen full; in hold status
3B	RDEVGRTY DS 1X	Display alternate screen size index
3C	RDEVLEN DS 1X	Device line length
3D	RDEVATNC DS 1X	Device attention count
3E	RDEVBASE DS 1H	370x base address for emulator line
3F	RDEVRSV3 DS 1X	Reserved for IBM use
46	ORG RDEVMDL	Terminal code
	<u>Bits defined in RDEVTMCD</u>	
	RDEVTEXT EQU X'20'	3270 Text character set
	RDEVUSC8 EQU X'10'	ASCII-8 level keyboard
	RDEVAPLC EQU X'0C'	APL Correspondence keyboard
	RDEVAPLP EQU X'08'	APL PTTC/EBCD keyboard
	RDEVCORR EQU X'04'	Correspondence keyboard
	RDEVPTTC EQU X'00'	PTTC/EBCD keyboard
47	RDEVSADN DS 1X	Terminal set-address number
	<u>For Real 3704/3705 Communications Controller</u>	
1C	ORG RDEVAIR	Start of free RDEVBLOK list for EP line
2E	RDEVEPDV DS 1F	
30	ORG RDEVCYL	
38	RDEVMAX DS 1H	Highest valid NCP resource name
3C	RDEVNCP DS CL8	Reference name of active 3704 NCP
	RDEVNICL DS 1F	Pointer to network control list
	RDEVCKPT DS 1F	Pointer to CKPBLOK for re-enable
	<u>For 3270 Remote Support</u>	
30	ORG RDEVNCP	
34	RDEVBSC DS 1F	Pointer to binary synchronous control block
	RDEVPDLY DS 1F	Poll delay timer interval

RECBLOK: DASD PAGE (SLOT) ALLOCATION BLOCK

RECBLOK maintains the correlation of DASD storage pages to a specific cylinder location. Also maintained is a bit map to indicate the page slots available for data page storage. The RDEVRECS field and the RDEVPAGE field of the RDEVELCK point to RECELCK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	RECPNT	DS 1F Pointer to next RECBLOK on chain
4	RECCYL	DS 1H Cylinder address for pages in this block
6	RECUSED	DS 1X R*1 Number of pages currently in use
7	RECMAX	DS 1X R*2 Maximum number of pages available
8	RECMAP	DS 1L Page allocation bit map (128 pages maximum)

Bits defined in RECMAP

- 0 - Page is available
- 1 - Page has been assigned


Note: Although the size of RECMAP is fixed, the maximum number of pages available on a cylinder is device dependent. Bits corresponding to pages not physically present on a cylinder are set to 1.

```
RECSIZE EQU (*-RECBLOK)/8 RECELCK size in doublewords
```

RECPAG

RECPAG: ERROR RECORDING PAGE RECORD


RECPAG retains up to 4K bytes of error recording data for eventual placement on the specified errcr recording cylinder.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	RECCCPD DS 4X	CCPD of the record
4	RECNXT DS 2X	Displacement to next error record
6	RECFLAG1 DS 1X R*1	Record usage flags
<u>Bits defined in RECFLAG1</u>		
	RECPAGIU EQU X'80'	Page contains valid data
	RECPAGFR EQU X'40'	Page is cleared
	RECPAGFL EQU X'20'	Page is full of error records
	RECPAGER EQU X'10'	Next page is unreadable (I/O error)
	RECPAGFA EQU X'08'	Page contains page frame records
7	RECFLAG2 DS 1X R*2	Record format flag
<u>Bits defined in RECFLAG2</u>		
	RECPAGFM EQU X'80'	Set in page 1 of a recording cylinder when the cylinder is being formatted. This flag bit is reset when all pages are cleared.
	RECPAGDN EQU X'00'	Cylinder formatted
8	RECDATA DS 4088C	Data area
	RECPAGSZ EQU (*-RECPAG)/8	Size of page in doublewords (X'512')

RSPLCTL: REAL SPOOLING CONTROL BLOCK


RSPLCTL is used in conjunction with SFBLOK for processing closed spcol files. The RDEVSPLOK field of RDEVBLCK points to RSPLCTL.



Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	RSPRSTRT DS	1F	Restart CAW - CCW address
4	RSPDPAGE DS	1F	DASS location (DCHR) of current page buffer
8	RSPVPAGE DS	1F	Virtual address of page buffer
C	RSPRPAGE DS	1F	Real address of page buffer
10	RSPMISC DS	1F	Use varies according to caller
14	RSPSFBLK DS	1F	Pointer to SFBLCK for file
18	RSPDPAG2 DS	1F	DASI location of second page buffer if any
1C	RSPVPAG2 DS	1F	Virtual address of second page buffer if any
20	RSPRPAG2 DS	1F	Real address of second page buffer if any
24	RSPFLAG1 DS	1X	Real spooling control flag byte
<u>Bits defined in RSPFLAG1</u>			
	RSPBF1IO EQU	X'80'	I/O pending on buffer 1
	RSPBF2IO EQU	X'40'	I/O pending on buffer 2
	RSPBF1VL EQU	X'20'	Buffer 1 is full of data to print
	RSPBF2VL EQU	X'10'	Buffer 2 is full of data to print
25	RSPRSVD DS	3X	Reserved for IBM use
	RSPSIZE EQU	(*-RSPLCTL)/8	Size in doublewords (X'05')

RSPXBLOK: REAL DEVICE EXTENSION BLOCK

RSPXBLOK is used with the RDEVBLCK to accommodate the 3800 requirements.



Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	RSPXCHR DS	CL4	Character arrangement table now in 3800
4	RSPXCRWC DS	4X	Current contents of WCGMs
8	RSPXCMOD DS	CL4	Copy module now in 3800
C	RSPXFBC DS	CL4	FCB now in 3800
	RSPXSIZE EQU	(*-RSPXBLOK)/8	RSPXBLOK size in doublewords (X'01')

SAVEAREA

SAVEAREA


SAVEAREA is used to save the registers of a module when that module has called another module. Register 13 points to SAVEAREA.

0	SAVERETN		SAVER12
8	SAVER13		SAVEWRK1
10	SAVEREGS		
.	.		
.	.		
40	SAVEWRK2		SAVEWRK3
48	SAVEWRK4		SAVEWRK5
50	SAVEWRK6		SAVEWRK7
58	SAVEWRK8		SAVEWRK9

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	SAVERETN DS	1F	Active SAVEAREA (caller's return address)
<u>Redefinition of SAVERETN To Include Processor Address</u>			
0	SAVEPROC DS	1X	Active SAVEAREA -- processor address
1	SAVERTN DS	3X	Active SAVEAREA -- return address
0	SAVENEXT DS	1F	Inactive SAVEAREA (next SAVEAREA address)
4	SAVER12 DS	1F	Caller's base (R12)
8	SAVER13 DS	1F	Caller's SAVEAREA (R13)
C	SAVEWRK1 DS	1F	Called routine's work area
10	SAVEREGS DS	12F	Caller's registers (R0 to R11)
10	ORG	SAVEREGS	
14	SAVER0 DS	1F	
18	SAVER1 DS	1F	
1C	SAVER2 DS	1F	
20	SAVER3 DS	1F	
24	SAVER4 DS	1F	
28	SAVER5 DS	1F	
2C	SAVER6 DS	1F	
30	SAVER7 DS	1F	
34	SAVER8 DS	1F	
38	SAVER9 DS	1F	
3C	SAVER10 DS	1F	
40	SAVER11 DS	1F	
44	SAVEWRK2 DS	1F	
48	SAVEWRK3 DS	1F	
4C	SAVEWRK4 DS	1F	
50	SAVEWRK5 DS	1F	
54	SAVEWRK6 DS	1F	
58	SAVEWRK7 DS	1F	
5C	SAVEWRK8 DS	1F	
	SAVEWRK9 DS	1F	
}			
Called routine's work area (8 fullwords)			
SAVESIZE EQU (*-SAVEAREA)/8 Size in doublewords (X'0C')			

SAVTABLE: FIRST PAGE ON SAVED SYSTEM DASD

SAVTABLE is used in the initial program loading of saved virtual machine named systems. It is created by the name system generation process (SAVESYS macro/SAVESYS command).




Hexadecimal Displacement	Field Name	DS	Length	Field Description, Contents, Meaning
0	SAVPSW	DS	1D	PSW of virtual machine at SAVESYS time
8	SAVGREGS	DS	16F	General registers
48	SAVFPRES	DS	4D	Floating-point registers
68	SAVCREGS	DS	16F	Control registers
A8	SAVKEYS	DS	1H	Two-byte entry for each saved page containing storage keys for each page

SDRBLOK

SDRBLOK: STATISTICAL DATA RECORDING BLOCK


Contains counters to record temporary errors on a given I/O device.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	SDRRDEV DS 1F	Address of associated RDEVELCK
4	SDRFLAGS DS 1X	S*1 SDRELOK flags
	<u>Bits defined in SDRFLAGS</u>	
	SDRSHRT EQU X'80'	Short OBRRECN to be written
	SDRRECD EQU X'40'	Long OBRRECN to be recorded on counter overflow
	SDRMAX EQU X'20'	Maximum numbers of SDR counters handled
5	SDRPRMCT DS 1X	S*2 Parameter list counter
6	SDRFLCT DS 1X	S*3 Full byte counter
7	SDROVFWK DS 1X	S*4 Statistical update work byte
8	SDRLNGTH DS 1X	S*5 Length (bytes) of SDR counters
9	SDRCUA DS 3X	Primary CUA of device being used
	SDRBSIZE EQU (*-SDRBLOK)	SDRELOK base size, in bytes
C	SDRCTRS DS 10X	SDR error counters
	SDRSIZE EQU (*-SDRELOK+7)/8	Size in doublewords (X'03')
16	SDRCTRS1 DS 10X	Additional SDR error counters for devices that use more than 10 SDR counters.
	SDRSIZE1 EQU (*-SDRBLOK)/8	Size in doublewords (X'04')

SEGTABLE: TRANSLATION SEGMENT TABLE

SEGTABLE is used in conjunction with the page table (PAGTABLE) and swap table (SWPTABLE) by the page management routines. The VMSEG field of the VMELOK points to SEGTABLE.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
0	SEGPAGE	DS	1F	Pointer to page table (PAGTABLE)
0	SEGPLEN	ORG DS	BL.4	S*1 Page table length (Total pages - 1) (in left half of byte)
<u>Bits defined in SEGPAGE+3</u>				
				SEGINV EQU X'01' Segment invalid
				SEGMIG EQU X'10' Segment migrated if pointer is equal to 0
				SEGENQ EQU X'40' Segment is enqueued if pointer is equal to 0

SFBLOK

SFBLOK: SPOOL FILE BLOCK

SFBLOK retains all the information relating to a spool file. A pointer provides a linkage to the next SFBLOK in the chain. The VSPSFBLK field of VSPLCTL and the RSPSFBLK field of RSPLCTL point to the SFBLOK.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	SFBPNT DS 1F	Pointer to next SFBLOK
4	SFBSTART DS 1F	EASD location (CCPD) of first page buffer
8	SFBUSER DS CL8	VMUSER identification of file owner
10	SFBORIG DS CL8	VMUSER identification of file origin
18	SFBRECNO DS 1F	Number of data records in file
1C	SFBRECSZ DS 1H	Logical record size - excluding CCWs
1E	SFBFILID DS 1H	Binary system file number
20	SFBFLAG DS 1X	SFELOCK control bits
Bits defined in SFBFLAG		
	SFBINUSE EQU X'80'	File being processed
	SFBRECOOK EQU X'40'	Allocation records complete
	SFBUHOLD EQU X'20'	File in user hold status
	SFBDDUMP EQU X'10'	File is a CP system dump
	SFBOPEN EQU X'08'	Input file has been opened
	SFBSHOLD EQU X'04'	File in system hold status
	SFBEOF EQU X'02'	Input file has reached EOF
	SFBRECER EQU X'01'	SFEREC chain incomplete
21	SFBTYPE DS 1X	S*2 Device type for spool output
22	SFBMISC1 DS 1H	Use varies according to caller
24	SFBRECS DS 1F	Pointer to RECBLOKS for active file
28	SFBFNAME DS CL12	Filename

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
34	SFBFTYPE	DS CL12	Filletype
40	SFBDATE	DS CL8	Creation date of spool file
48	SFBTIME	DS CL8	Creation time of spool file
50	SFBLAST	DS 1F	DASD location (CCPD) of last page buffer
54	SFBCOPY	DS 1H	Number of copies requested
56	SFBCLAS	DS 1X	Spool file class character
57	SFBFLAG2	DS 1X S*4	SFBLCK flag (byte 2)
<u>Bits defined in SFBLCK2</u>			
	SFBHOLD	EQU X'80'	Save input file, or hold output file
	SFBNOHLD	EQU X'40'	Delete input file, or do not hold output file
	SFBFLNMT	EQU X'20'	File not empty if on
<u>Note:</u> SFBHOLD and SFBNOHLD override options in VDEVBL0K.			
	SFBREQUE	EQU X'20'	Requeue spool file
	SFBRSTRT	EQU X'10'	Restart in progress
	SFBTICER	EQU X'08'	Buffer TIC error
	SFBPURGE	EQU X'04'	Purge open spool file
	SFBFIRST	EQU X'02'	Indicate first page written
	SFBMON	EQU X'01'	Monitor spool file
58	SFBDIST	DS CL8	Distribution code
60	SFBFLASH	DS CL4	Overlay name for 3800 is flashing
64	SFBSTCPY	DS 1X S*5	Current starting copy number
65	SFBRSVD	DS XL3	Reserved for IBM use
	SFBSIZE	EQU (*-SFBLCK)/8	Size in doublewords (X'0E')

SHQBLOK

SHQBLOK: SPOOL HOLD QUEUE BLOCK

SHQBLOK provides a holding function for identified spool files to prevent output to another user or to a real output device.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	SHQPNT DS 1F	Address of next SHQBLOK
4	SHQFLAGS DS 0CL4	Length
4	SHQUHOLD DS 1X	S*1 User USER HOLD flag byte
5	SHQSHOLD DS 1X	S*2 User SYSTEM HOLD flag byte
<u>Bits defined in SHQUHOLD and SHQSHOLD</u>		
TYPPRT EQU	Printer	See "Appendix A. CP and RSCS Equate Symbols"
TYPPUN EQU	Punch	See "Appendix A. CP and RSCS Equate Symbols"
6	SHQSPARE DS 2X	Reserved for IBM use
8	SHQUSER DS CL8	Virtual machine user identification of file owner
SHQBSIZE EQU $(*-SHQBLOK)/8$ Size in doublewords (X'02')		

SHRTABLE: NAMED-SHARED SEGMENT SYSTEMS TABLE

SHRTABLE contains pointers to the segment locations of named systems for both the shared and nonshared user. This block is used in paging, IPL, and virtual machine assist operations. PAGTABLE-8 points to SHRTABLE.

0	S*1		SHRFPNT		SHRFPNT
SHRNAME					
10	SHRTSIZE		SHRUSECT		SHRSEGCT
18	SHRSEGNM				SHRPAGE


Hexadecimal Displacement	Field Name	DS	Size	Field Description, Contents, Meaning	
0	SHRFPNT	DS	1F	Pointer to next SHRTABLE	
0	SHRFLAG	DS	1X	S*1	Shared segment flag byte
1	SHRFPNT	DS	3X		Pointer to next SHRTABLE
Bits defined in SHRFLAG					
	SHRNOPRT	EQU	X'40'	Nonprotected shared segments	
4	SHRBPN	DS	1F	Pointer to previous SHRTABLE	
8	SHRNAME	DS	C18	Name of saved system	
10	SHRTSIZE	DS	1H	Size of SHRTABLE in doublewords	
12	SHRUSECT	DS	1H	Number of users using this segment name	
14	SHRSEGCT	DS	1F	Number of shared segments	
18	SHRSEGNM	DS	1F	Contains shared segment numbers; up to four segment numbers per word	
1C	SHRPAGE	DS	1F	Pointers to each of the shared page tables. There is one word for each shared segment. The entry is the same as S*1 SEGPAGE in "SEGTABLE: Segment Table."	

Note: In attached processor (AP) mode, there will be two sets of page tables (PAGTABLE) for each shared segment; one for the main processor, one for the attached processor. SHRPAGE will point to the page tables for the main processor. The page tables for the attached processor will be at a fixed displacement (PAGBMP) from those of the main processor.

SPLINK

SPLINK: SPOOL PAGE BUFFER LINKAGE BLOCK

SPLINK resides in auxiliary storage and contains one page (4096 bytes) of unit record spool information consisting of data and all required CCWs. The RSPVPAGE field and the RSPRPAGE field in RSPLCTL point to SPLINK.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	SPNXTPAG DS 1F	DASD location (DCHR) of next page buffer
4	SPPREPAG DS 1F	DASD location (DCHR) of previous page buffer
8	SPRMISC DS 1F	Use varies according to caller
C	SPRECNUM DS 1F	Number of data records in buffer
	SPSIZE EQU (*-SPLINK)	Size in bytes (X'10')
	ORG SPLINK+4096-48	End of first DASD buffer
FD0	SPCHAR DS CL4	3800 character arrangement table for file
FD4	SPRSVD1 DS CL12	Reserved for IBM use
FE0	SPFBCB DS CL4	3800 function control block for file
FE4	SPCMOD DS CL4	3800 copy module for file
FE8	SPRSVD2 DS CL12	Reserved for IBM use
FF4	SPFLSHC DS 1X	S*1 3800 flash count
FF5	SPFLAG1 DS 1X	S*2 3800 flag byte
	Bits defined in SPFLAG1 SPCOPYFG EQU X'80'	If flag is set, multiple copies can be done in one transmission
FF6	SPRSVD3 DS 2X	Reserved for IBM use
FF8	SPFILID DS 1H	File identifier used for verification
FFA	SPTIME DS CL6	SFTIME -- used for verification
	SPENDSIZE EQU *-SPCHAR	End-of-buffer size in bytes

¹First DASD buffer only. All others comprise 4080 bytes.

SWPTABLE: SWAP TABLE FOR VIRTUAL MACHINE PAGING

SWPTABLE is used in conjunction with the page table (PAGTABLE) and the segment table (SEGTABLE) by the CP page management routines for relating the virtual storage to DASD slots and real storage. The PAGSWP field of the PAGTABLE points to SWPTABLE.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning			
0	SWPVM DS 1F				Pointer to VMBLK
4	SWPFLAG2 DS 1X S*7				Swap table FLAG2 bits
<u>Bits defined in SWPFLAG2</u>					
	SWPAPP EQU X'80'			Attached processor's shared page table and swap table	
4	SWPPAG ORG SWPFLAG2 DS 1F				Pointer to page table
8	SWPFLAG DS 1X S*1				Swap table flag bits
<u>Bits defined in SWPFLAG</u>					
	SWPTRANS EQU X'80'				Page in transit
	SWPRECMP EQU X'40'				Page permanently assigned
	SWPALLOC EQU X'20'				Page enqueued for allocation
	SWPSHR EQU X'10'				Page shared
	SWPREF1 EQU X'08'				First half-page referenced
	SWPCHG1 EQU X'04'				First half-page changed
	SWPREF2 EQU X'02'				Second half-page referenced
	SWPCHG2 EQU X'01'				Second half-page changed
9	SWPVPAGE DS 1X S*2				Virtual page number within the segment
A	SWPKEY1 DS 1X S*3				Virtual storage key, first 2048 bytes
B	SWPKEY2 DS 1X S*4				Virtual storage key, second 2048 bytes
C	SWPCYL DS 1H				DASD cylinder address
E	SWPDPAGE DS 1X S*5				DASD page number on cylinder
F	SWPCODE DS 1X S*6				REVELOK device code (The device code is used as an index into the list of CP-owned paging volumes pointed to by DMKSYSOW)

Note: For each SWPTABLE there is only one doubleword that consists of SWPVM and SWPPAG followed by 16 entries (one for each PAGTABLE entry) that consist of S*1, S*2, S*3, S*4, SWPCYL, S*5, and S*6. Thus, the total size of the SWPTABLE is 17 doublewords.

SYSLOCS

SYSLOCS: SYSTEM LOW STORAGE INFORMATION BLOCK


SYSLOCS contains user logon and dial statistics, time/date and log message data, TOD values, and line edit values.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DMKSYSDT DC	CL8'MM/DD/YY' Date of system log message
8	DMKSYSTEM DC	CL8'HH:MM:SS' Time of system log message
10	DMKSYSLW DC	X'00',X'00',CL10' Weekday of system log messages
1C	DMKSYSLG DC	A(0) Pointer to first log message block
20	DMKSYSNM DC	F'0' Current number of users on the system
24	DMKSYSMA DC	F'0' Maximum number of users allowed on the system
28	DMKSYSMU DC	F'0' Maximum number of users on the system
2C	DMKSYSND DC	F'0' Number of dialed users on the system
30	DMKSYSLB DC	A(0) Pointer to user directory lock block
34	DMKSYSUD DC	A(0) Pointer to start of user directory on SYSRES
38	DMKSYSPL DC	A(0) Pointer to a list of virtual page buffers
3C	DC	A(0) Reserved for IBM use
40	DMKSYSDW DC	X'00',X'00', CL10' Day of week in hexadecimal and EBCDIC
4C	DMKSYSLE DC	X'7B' S*1 Terminal line-end symbol
4D	DMKSYSLD DC	X'4A' S*2 Terminal line-delete symbol
4E	DMKSYSCD DC	X'7C' S*3 Terminal character-delete symbol
4F	DMKSYSSES DC	X'7F' S*4 Terminal escape symbol
50	DMKSYSLL DC	AL1(130,129,72,80) S*5 Default line lengths for 3210 and 3215 - 2741 and 1050 - 3270 and 3066 terminals
53	DMKSYSCK DC	XLS'0' D'0' Reserved for IBM use
58		TOD clock value last stored by accounting, DUMP, or machine check

SYSTBL: NAMED SYSTEM TABLE

SYSTBL contains the system and DASD information required to load a saved system by name. SYSTBL is built during system generation in DMKSNT using the NAMESYS macro.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	SYSPNT DS 1F	Chain pointer to next entry
4	SYSSIZE DS 1F	Minimum storage size needed to run system
8	SYSNAME DS CL8	System name
10	VSYSRES DS CL6	Volume identification number of DASD containing user's system
16	SYSVADDR DS 1H	Virtual address of VSYSRES
18	SYSVOL DS CL6	Volume identification number of DASD containing saved pages
1E	SYSCYL DS 1H	Cylinder on VSYSRES of user's system. Same as VDEVRELN
20	SYSSTART DS 1F	CCPD of first page on SYSVOL
24	SYSpagct DS 1F	Total number of pages saved
28	SYSPAGLN DS 1H	Number of entries in SYSPAGNM
2A	DS 1X S*1	Reserved for IBM use
2B	SYSFLAG DS 1X S*2	Named system flag
Bits defined in SYSFLAG		
	SYSPROT EQU X'80'	Unprotected shared segments
	SYSPAGNM DS 1F	One fullword entry for each range of pages to be saved
	SYSSEGLN DS 1H	Numbers of entries in SYSHRSEG
	SYSHRSEG DS 1X	One byte for each segment to be shared

TNSREC

TNSREC: "T" TYPE RECORD FORMAT (ENVIRONMENTAL RECORDING)


TNSREC is used by DMKIOE to record miscellaneous data records on CP's I/O error recording cylinders. The record contains sense data applicable to a specific I/O device.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>24-Byte Header Record</u>		
0	TNSKEYN DS 1H	Class source 90=T type N/S NCN TPER
2	TNSSWS1 DS 1X	T*1 Switch byte 0
3	TNSSWS2 DS 1X	T*2 Reserved for IBM use
4	TNSSWS3 DS 1X	T*3 Reserved for IBM use
5	TNSRECNT DS 1X	T*4 Reserved for IBM use
6	TNSSPE1 DS 1H	Reserved for IBM use
8	TNSDTEN DS 1F	Date
C	TNSTMEN DS 1F	Time
10	TNSCPIDN DS 2F	Processor identification and model number
<u>End of 24-Byte Header</u>		
<u>Device Dependent Data</u>		
18	TNSDEVAD DS 1H	Device address request is pending
1A	TNSVOLID DS 6X	Volume identification number
20	TNSSNS1 DS 24X	24 Sense bytes
38	TNSSNS2 DS 24X	24 Additional sense bytes
50	TNSSNS3 DS 24X	24 Additional sense bytes
68	TNSSNS4 DS 24X	24 Additional sense bytes
80	TNSSNS5 DS 24X	24 Additional sense bytes
98	TNSSNS6 DS 24X	24 Additional sense bytes
B0	TNSSNS7 DS 24X	Last 24 sense bytes

TREXT: VIRTUAL MACHINE TRACING EXTENSION TO VMBLOCK

TREXT facilitates the tracing of virtual machine program instructions and interrupts. This block is used whenever the CP TRACE command is invoked. The VMTREXT field of the VMBLOCK points to TREXT.




Hexadecimal Displacement	Field Name	Field Description, Ccontents, Meaning
0	TREXIN1 DS 1F	First address - replaced instruction
4	TREXIN2 DS 1F	Second address - replaced instruction
8	TREXSVC1 DS 1H	Displaced halfword - instruction 1
A	TREXSVC2 DS 1H	Displaced halfword - instruction 2
0	ORG TREXIN1	
0	TREXPSW DS 1D	Old PSW for pending SVC interrupt
8	TREXINTL DS 1H	Instruction length code
A	TREXINTC DS 1H	Interrupt code for pending interrupt
C	TREXFLAG DS 1X	T*1 Tracing control flags
	<u>Bits defined in TREXFLAG</u>	
	TREXRUN EQU X'80'	Prevent CFWAIT between events
	TREXVAT EQU X'40'	Call DMKVATRN to put back virtual instruction
	TREXNDSP EQU X'20'	DSP should not call TRCIT
D	TREXOUT DS 1X	T*2 Trace output controls
	<u>Bits defined in TREXOUT</u>	
	TREXPRT EQU X'80'	Output to the virtual spool printer
	TREXCON EQU X'40'	Output to user virtual machine terminal
E	TREXLOCK DS 1H	Indicates tracing when set
10	TREXPERA DS 1F	Address of instruction causing PER interrupt
10	ORG TREXPERA	Redefinition for TRACE use
		Actual next (or last) sequential instruction
14	TREXNSI DS 6X	
16	TREXPERC DS 1H	PER code to be reflected
16	TREXLCNT DS 1H	Printed output line count
18	TREXANSI DS 1A	Address of next (or last) sequential instruction

TREXT

Hexadecimal Displacement	Field Name	Field Description, Ccontents, Meaning
1C	TREXCR9 DS OF	Shadow control registers for PER trace
1C	ORG TREXCR9	Redefinition for TRACE use
1C	TREXCTL DS OH	Halfword holding tracing control bits:
	TREXCTL1 DS 1X	First byte = same as VMTRCTL in VMBLOK
1D	TREXCTL2 DS 1X	Second byte = remaining control bits
	<u>Bits defined in TREXCTL2</u>	
	TREXCCW EQU X'80'	Trace virtual and real CCWs
	TREXCSW EQU X'40'	Trace virtual and real CSWs
	TREXBRAN EQU X'20'	Trace successful branches
	TREXINST EQU X'10'	Trace all instructions
1C	TREXPER DS XL2	PER control field
1E	TREXPREG DS 1H	PER register mask field
20	TREXCR10 DS 1F	Address range starting value
1E	TREXPRNT DS 1H	Printer flag bits corresponding to TREXCTL
20	TREXTERM DS 1H	Terminal flag bits corresponding to TREXCTL
22	TREXRUNF DS 1H	Run/notrun flag bits corresponding to TREXCTL
24	TREXPNTR DS 1F	Pointer to first stacked TRACE request, if any
24	TREXCR11 DS 1F	Address range ending value
28	TREXBUFF DS 10D	Console/printer output buffer (80 bytes)
	TREXSIZEx EQU (**-TREXT)/8	TREXT size in doublewords (X'0F')

TRQBLOK: TOD CLOCK COMPARATOR REQUEST


TRQBLOK manages the timing facilities of VM/370.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TRQBVAL DS	TOD clock comparator value for interrupt
8	TRQBFPNT DS	Pointer to next TRQBLOK
C	TRQBBPNT DS	Pointer to previous TRQBLOK
10	TRQBTOD DS	TOD clock value when TRQBLCK is queued
18	TRQBUSER DS	Address of VMBLOK for user
1C	TRQBIRA DS	Interrupt return address
20	TRQBQUE DS	Time left in queue; tracking virtual processor timer
TRQBSIZE EQU (*-TRQBLOK)/8 Size in doublewords (X'05')		

| • Local Graphic Device Support

The following continuation of the TRQBLOK DSECT for local graphic device support is built, referenced, and released by DMKGRC.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
28	TRQBCRT DS	Graphic device return IRA
2C	TRQBDEV DS	Graphic device device address
2E	TRQBFLAG DS	T*1 Graphic device flags
<u>Bits defined in TRQBFLAG</u>		
	CRTFMT EQU X'80'	Screen formatted VM/370 online
	CRTDIAG EQU X'40'	Screen written with Diagnose
	CRTALRM EQU X'20'	Screen has alarm message
	CRTWNG EQU X'10'	Screen has MORE... warning
	CRTCARD EQU X'08'	Data from card reader
	CRTTAB2 EQU X'04'	Second pass flag for tab function
	CRTAPL EQU X'02'	APL read buffer allocated
	CRTSIO EQU X'01'	User issue Diagnose to input area
	CRATAIO EQU CRTSIO	Timer interrupt pending after I/O completes
2F	TRQBLINE DS	T*2 Line coordinate for input area

TRQBLOK, UDBFELOK

| • Remote Graphic Device Support

The following continuation of the TRQBLOK DSFCT for remote graphic device support is built, referenced, and released by DMKRG and DMKRGE.

28

TRQBCRT

| TRQEDEV

| TRQNAME

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
28	TRQBCRT	DS 1F	Graphic device return IRA
2C	TRQBDEV	DS 1H	Graphic device line address
2E	TRQNAME	DS 1H	Resource identification
	TRQBPOLL	EQU X'FF'	Timer interrupt for general poll

UDBFELOK: USER DIRECTORY BUFFER BLOCK

UDBFELOK is used as a buffer for user device block data in user directory access operations.

0

UDBFWORK

.

.

.

38

UDBFVADD

| UDEFDASD

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	UDBFWORK	DS 7D	Buffer work space used by the caller
38	UDBFVADD	DS 1F	Virtual address of the last directory page
3C	UDBFDASD	DS 1F	DASD address of the last directory page

UDBFSIZE EQU (*-UDBFBLOK)/8 UDBFELOK size in doublewords (X'08')

UDEVBLOK: USER DEVICE BLOCK

UDEVBLOK supplies the information about the virtual machine's virtual devices, the operational parameters for its use, such as DASD access passwords, read/write link mode, spool device, T-disk space versus dedicated device space, as well as other parameters.

0	UDEVAADD		UDEVDISP		UDEVDASD									
8	U*1		U*2		U*3		U*4		U*5		U*6		UDEVNCYL	
10	UDEVRELN													UDEVVUSER
18														UDEVPASR
20														UDEVPASW
28														UDEVPASM


Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
0	UDEVAADD DS	1H		Virtual device address
2	UDEVDISP DS	1H		Displacement of the next block
4	UDEVDASD DS	1F		DASD address of the next block
8	UDEVSTAT DS	1X	U*1	Device status information
	<u>Bits defined in UDEVSTAT</u>			
	UDEVDED EQU	X'80'		Device to be dedicated to this user
	UDEVTDISK EQU	X'40'		T-disk to be allocated
	UDEVLONG EQU	X'20'		Device block is full length (6 doublewords)
	UDEVLKDV EQU	X'10'		Device is to be linked (at logon)
	UDEVSPOO EQU	X'08'		Device is a spool device
	UDEV3158 EQU	X'04'		Device is a 3158 console
	UDEVVRR EQU	X'02'		Virtual reserve/release requested
9	UDEVMODE DS	1X	U*2	Access mode information
	<u>Bits defined in UDEVMODE</u>			
	UDEVLR EQU	X'80'		Read links allowed
	UDEVLW EQU	X'40'		Write links allowed
	UDEVLM EQU	X'20'		Multiple write links allowed
	UDEVR EQU	00		Device to be in R link mode for owner
	UDEVRR EQU	04		Device to be in RR link mode for owner
	UDEVW EQU	08		Device to be in W link mode for owner
	UDEVWR EQU	12		Device to be in WR link mode for owner
	UDEVM EQU	16		Device to be in M link mode for owner
	UDEVMR EQU	20		Device to be in MR link mode for owner
	UDEVMW EQU	24		Device to be in MW link mode for owner
A	UDEVTPC DS	1C	U*3	Virtual device class
B	UDEVTYPE DS	1C	U*4	Virtual device type
C	UDEVFTR DS	1C	U*5	Device feature codes
D	UDEVMDL DS	1C	U*6	Device model number
		ORG	UDEVMDL	User device block (short)
D	UDEVCLAS DS	1C		Spcl device output class
E	UDEVLINK DS	1H		User link to disk
10	UDEVLKID DS	1D		User link to userid
E	UDEVNCYL DS	1H		Virtual DASD size
10	UDEVRELN DS	1H		Virtual DASD cylinder relocation
12	UDEVVUSER DS	6C		Volume identification number

UDFVELOK, UDIRBLOK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
18	UDEVPASR DS	1D Password for read access
20	UDEVPASW DS	1D Password for write access
28	UDEVPASM DS	1D Password for multiple access
UDEVSIZE EQU		(*-UDEVBLOK)/8 UDFVELOK size in doublewords (X'06')

UDIRELOK: USER DIRECTORY BLOCK


UDIRELOK contains data describing the user's command privilege classes, special virtual machine options, terminal line edit values, and other values.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	UDIRRSV1 DS	1H Reserved for IBM use
2	UDIRDISP DS	1H Displacement of the user's UMACELOK
4	UDIRDASD DS	1F DASS address of the user's UMACELOK
8	UDIRUSER DS	1D Userid
10	UDIRPASS DS	1D User password
UDIRSIZE EQU		(*-UDIRBLOK)/8 UDIRELOK size in doublewords (X'03')

UMACELOK: USER MACHINE BLOCK

UMACELOK contains the logon parameters for one virtual machine user. This block provides, in addition to the linkage to the user's defined virtual machine device UDEVBLOK, the command privilege class, assigned line edit values, as well as other virtual machine options.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	UMACDVCT DS	1H Number of devices
2	UMACDISP DS	1H Displacement of the next block
4	UMACDASD DS	1F DASD address of the next block
8	UMACCLEV DS	1C U*1 Command level flags
	<u>Bits defined in UMACCLEV</u>	
	UMACCLA EQU X'80'	Privilege Class A functions
	UMACCLB EQU X'40'	Privilege Class B functions
	UMACCLC EQU X'20'	Privilege Class C functions
	UMACCLD EQU X'10'	Privilege Class D functions
	UMACCLE EQU X'08'	Privilege Class E functions
	UMACCLF EQU X'04'	Privilege Class F functions
	UMACCLG EQU X'02'	Privilege Class G functions
	UMACCLH EQU X'01'	Privilege Class H functions
9	UMACPRIR DS	1X U*2 Virtual machine priority
A	UMACOPT DS	1X U*3 Virtual machine option flags
	<u>Bits defined in UMACOPT</u>	
	UMACISAM EQU X'80'	ISAM CCW checking option
	UMACECOP EQU X'40'	Extended control mode option
	UMACRT EQU X'20'	Real timer option
	UMACVROP EQU X'10'	Virtual = Real storage option
	UMACACC EQU X'08'	Accounting card option
	UMACRSV4 EQU X'04'	Reserved for IBM use
	UMACNSVC EQU X'02'	SVCs not handled by virtual machine assist feature
	UMACBMX EQU X'01'	Virtual block multiplexer channel

UMACBLOK

Hexadecimal Displacement	Field Name		Field Description, Ccontents, Meaning
<hr/>			
B	UMACOPT2 DS	1C	U*4 Virtual machine option flags
<u>Bits defined in UMACOPT2</u>			
	UMACCPU EQU	X'80'	Processor identification number on option statement
	UMACVMSV EQU	X'10'	VMSAVE on option statement
C	UMACLEND DS	1C	U*5 Terminal line end symbol
D	UMACLDEL DS	1C	U*6 Terminal line delete symbol
E	UMACCDEL DS	1C	U*7 Terminal character delete symbol
F	UMACES DS	1C	U*8 Edit escape symbol
10	UMACCORE DS	1F	Virtual storage size in bytes
14	UMACMCOR DS	1F	Maximum virtual storage size in bytes
18	UMACACCT DS	1D	Accounting information
20	UMACDIST DS	1D	User machine distribution information
28	UMACIPL DS	1D	Name of system to be IPLED at logon
30	UMACPUID DS	XL3	Processor identification number in binary
33	UMACAFF DS	1X	U*9 Affinity and processor address
<u>Bits defined in UMACAFF</u>			
	UMACFFON EQU	X'40'	Affinity specified
	UMACFFAD DS	OBL6	Processor address for affinity
34	UMACRSVR DS	1F	Reserved for IBM use
	UMACSIZE EQU	(*-UMACBLOK)/8	UMACELOK size in doublewords (X'06')

Virtual I/O Control Blocks

The base for locating the I/O block structure is the user's Virtual Machine Control Block (VMBLOK). The VMBLOK contains a pointer to the start of three control block tables, and a table of 16 channel indexes. The control block tables contain one block for each of the virtual channels, control units, and devices that are defined for the user's virtual machine. The entries in the channel index table (VMCHTBL) contain the pointers to each channel defined for the user in the table of Virtual Channel Blocks (VCHBLOKS). Each VCHBLOK contains a table of pointers that point to the Virtual Control Unit Blocks (VCUBLOKS) for the control units attached to that virtual channel. Each VCUBLOK contains pointers to the Virtual Device Blocks (VDEVBLCK) attached to the control unit.

Thus, if given the unit address of any component in the form cuu, the appropriate control blocks representing each component in the subchannel path to the given unit is located via the indexing scheme.

VIRTUAL CHANNEL BLOCKS

There is one Virtual Channel Block (VCHBLOK) for each virtual channel connected to the user's virtual processor. Each VCHBLOK contains the channel address and flag indicating the channel type (selector, byte multiplexer, or block multiplexer). The status of the channel and its attached units are represented by several status and mask bytes.

- A status byte (VCHSTAT) indicates whether the channel is busy or has a channel class interrupt pending.
- A halfword unit address identifies the unit causing the channel-class interrupt (if it is present).
- A halfword mask (VCHCUINT) contains a bit map of the attached control units that have interrupt status pending.

Following these status flags and masks is the table of indexes pointing to the attached VCUBLOKS; index entries representing addresses at which no control unit is attached have a value of -1.

VIRTUAL CONTROL UNIT BLOCKS

There is one Virtual Control Unit Block (VCUBLOK) for each control unit in the virtual configuration. These blocks are arranged in a table, each contains: in addition to its base address, status flags similar to those in the VCHBLCK and a table of indexes to attached VDEVBLCKs. The status flags defined for the VCUBLOK differ from those for the VCHBLCK in that they can contain status for the control unit and also for a subchannel.

For example, if the VCUBLOK representing a 2803 tape control unit is attached to a virtual selector channel, both the VCHBLCK and the VCUBLOK are marked busy. However, if the VCUBLOK is attached to a virtual byte multiplexer channel and is for a control unit on a selector subchannel of the multiplexer, the busy status of the channel is reflected in the VCUBLOK only. Thus, the virtual byte multiplexer appears nonbusy to operations on other, nonshared subchannels.

VIRTUAL DEVICE BLOCKS


There is one Virtual Device Block (VDEVBLCK) in the configuration for each virtual device defined by the user. Each VDEVBLCK contains the device portion of the unit address, device status, and the virtual CSW for the last interrupt taken by the device. In addition, the VDEVBLCK contains device type specific information that allows the I/O translation and simulation routines to interpret the channel programs presented by the user.

Note: The VCHBLCK, VCUBLOK, VDEVBLCK, VFCEBLOK, and VSPXBLOK DSECTS are all contained in the VELOKS COPY file.

VCHBLOK

VCHBLOK: VIRTUAL CHANNEL BLOCK


VCHBLOK contains information providing linkage between the virtual machine and one of its virtual channels. Supplied in this block, in addition to channel status and type information, are the reflected interrupts from attached virtual control units. The VMCHSTRT field of the VMBLOK points to the first VCHBLOK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VCHADD DS 1H	Virtual channel address
2	VCHCUINT DS 1H	VCUELOK with interrupt-bit map
4	VCHCEDEV DS 1H	Virtual device address with channel class interrupt
6	VCHSTAT DS 1X	V*1 Virtual channel status
	<u>Bits defined in VCHSTAT</u>	
	VCHBUSY EQU X'80'	Virtual channel busy
	VCHCEPND EQU X'40'	Virtual channel class interrupt pending
	VCHDED EQU X'01'	Virtual channel dedicated
7	VCHTYPE DS 1X	V*2 Virtual channel type
	<u>Bits defined in VCHTYPE</u>	
	VCHSEL EQU X'80'	Virtual selector channel
	VCHBMX EQU X'40'	Virtual block multiplexer
8	VCHCUTBL DS 16H	Control units attached - VMCUSTRT index
	VCHSIZE EQU (*-VCHBLOK)/8	VCUELOK size in doublewords (X'05')

VCONCTL: VIRTUAL CONSOLE CONTROL BLOCK


VCONCTL contains CCW and data buffer information for the communications of the virtual console. The VDEVBLOK field of the VDEVBLOK points to VCONCTL.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VCONCAW DS	1F Virtual address of user CCW
4	VCONBUF DS	1F Pointer to data buffer
8	VCONCCW DS	1D Current user CCW
8	ORG VCONADDR DS	1F CCW data address
C	VCONFLAG DS	1X CCW flag bits
D	VCONDWC DS	1X Diagnose write control
E	VCONCNT DS	1H CCW byte count
8	ORG VCONCOMD DS	1X CCW command code
10	VCONRSV1 DS	1X V*1 Reserved for IBM use
11	VCONBFSZ DS	1X V*2 Data buffer size in doublewords
12	VCONRSV2 DS	1X V*3 Reserved for IBM use
13	VCONRSV3 DS	1X V*4 Reserved for IBM use
14	VCONIDAP DS	1F For indirect data addressing pointer to current IDAW
18	VCONRBUF DS	1F Address of read data buffer
1C	VCONRCNT DS	1H Data count in read buffer
1E	VCONRBSZ DS	1X V*5 Read buffer size in doublewords
1F	VCONRSV6 DS	1X V*6 Reserved for IBM use
20	VCONWBUF DS	1F Address of write data buffer
24	VCONWCNT DS	1H Data count in write buffer
26	VCONWBSZ DS	1X V*7 Write buffer size in doublewords
27	VCONRSV8 DS	1X V*8 Reserved for IBM use
VCONSIZ EQU		(*-VCONCTL)/8 VCONCTL size in doublewords (X'05')

VCUBLOK**VCUBLOK: VIRTUAL CONTROL UNIT BLOCK**

VCUBLOK contains status information relating to the virtual channel, and the status and features of the virtual control unit. The VMCUSTRRT field of the VMELCK points to the first VCUBLOK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VCUADD DS 1H	Virtual control unit address
2	VCUDVINT DS 1H	VMELCK with interrupt - bit map
4	VCUINTS DS 1H	Virtual control unit interrupt status
6	VCUSTAT DS 1X	V*1 Virtual control unit status
<u>Bits defined in VCUSTAT</u>		
	VCUCHBSY EQU X'80'	Virtual subchannel busy
	VCUCEPND EQU X'40'	Interrupt pending in subchannel
	VCUBUSY EQU X'20'	Virtual control unit busy
	VCUPEND EQU X'10'	Virtual control unit interrupt pending
	VCUCUEPN EQU X'08'	Virtual control unit end pending
	VCUACTV EQU X'04'	Virtual control unit active
7	VCUTYPE DS 1X	V*2 Virtual control unit type
<u>Bits defined in VCUTYPE</u>		
	VCUSHRD EQU X'80'	Virtual control unit on shared subchannel
	VCUCTCA EQU X'40'	Virtual control unit is a channel-to-channel adapter
8	VCUDVTBL DS 16H	Devices attached - VMDVSTRT index
	VCUSIZE EQU (*-VCUBLOK)/8	VCUELCK size in doublewords (X'05')

VDEVBLOK: VIRTUAL DEVICE BLOCK

VDEVBLOK maintains status and interrupt conditions for one virtual device. The **VMDVSTRT** field of the **VMBLOK** points to the first **VDEVBLOCK**.

0	VDEVAADD		VDEVINTS		V*1		V*2		V*3		V*4
VDEVCSW											
10	VDEVRELN		VDEVBNP								VDEVPCSN
18	VDEVQUED										VDEVOOPER
20	VDEVLINK										VDEVREAL
28	VDEVIOCT										VDEVUSER
30	VDEVIOER										VDEVICB
38	V*5		VDEVRES1								VDEVRRB

Hexadecimal Displacement	Field Name	Field Description, Ccntents, Meaning
0	VDEVAADD DS	1H Virtual device address
2	VDEVINTS DS	1H Virtual device interrupt status
4	VDEVTPC DS	1X V*1 Virtual device type class
5	VDEVTYPE DS	1X V*2 Virtual device type
6	VDEVSTAT DS	1X V*3 Virtual device status
<u>Bits defined in VDEVSTAT</u>		
	VDEVCHES EQU X'80'	Virtual subchannel busy
	VDEVCHAN EQU X'40'	Virtual channel interrupt pending
	VDEVBUSY EQU X'20'	Virtual device busy
	VDEVPEND EQU X'10'	Virtual device interrupt pending
	VDEVCUU EQU X'08'	Virtual control unit end
	VDEVNRDY EQU X'04'	Virtual device not ready
	VDEVCATF EQU X'02'	Virtual device attached by console function
	VDEVDED EQU X'01'	VDEVREAL is dedicated device RDEVBLOK
7	VDEVFLAG DS	1X V*4 Virtual device flags
<u>Bits defined in VDEVFLAG</u>		
	VDEVRDO EQU X'80'	DASD - read-only
	VDEVNAB EQU X'80'	Virtual 270x - line enabled
	VDEVTDISK EQU X'40'	DASD - T-disk space allocated by CP
	VDEVDIAL EQU X'40'	Virtual 270x - line connected
	VDEVCSPL EQU X'40'	Console - activity spooled
	VDEV231T EQU X'20'	DASD - 2311 simulated on top half of 2314
	VDEV231B EQU X'10'	DASD - 2311 simulated on bottom half of 2314
	VDEVCCW1 EQU X'10'	Console and spooling - processing first CCW
	VDEVSAS EQU X'08'	DASD - Executing standalone seek
	VDEVDLY EQU X'08'	Console - delay spooling
	VDEVDET EQU X'04'	Virtual device is being detached
	VDEVPOST EQU X'02'	Present attention with a single interrupt
	VDEVRSRL EQU X'02'	Reserve/release are valid CCW operation codes
	VDEVUC EQU X'01'	Virtual device sense bytes present

VDEVELOK


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
8	VDEVCSW DS 1D	Virtual channel status word
10	VDEVRELN DS 1H	Virtual DASD cylinder relocation
12	VDEVBND DS 1H	Virtual DASD size (in cylinders)
14	VDEVPOSN DS 1F	Virtual DASD seek position
18	VDEVQUED DS 1F	Virtual SIO to real SIO queued time
1C	VDEVOPER DS 1F	Device operational time
20	VDEVLINK DS 1F	Link to virtual shared devices
20	ORG VDEVLINK VDEVTMAT DS 1F	T-disk attached time (TOD clock word 0)
24	VDEVREAL DS 1F	Pointer to real device RDEVELOK
28	VDEVIOCT DS 1F	Virtual device I/O count
2C	VDEVUSER DS 1F	Pointer to VMBLOK of VDEVBLOCK owner
30	VDEVIOER DS 1F	Pointer to IOERELOK for last error
30	ORG VDEVIOER VDEVSNSE DS 1F	Sense bytes for spool device
34	VDEVFCBK DS 1F	Address of forms control block (VFCBBLOK)
34	VDEVIOB DS 1F	Pointer to active IOBLOK
38	VDEVFLG2 DS 1X	V*5 Virtual device flag byte 2
Bits defined in VDEVFLG2		
	VDEVRRF EQU X'80'	Process virtual RESERVE/RELEASE commands
	VDEVRES EQU X'40'	Minidisk reserved by VDEVUSER
	VDEVODE EQU X'20'	VDEVELOK to get device when minidisk is released
	VDEVCPLEX EQU X'10'	Virtual I/O waiting for release of minidisk
	VIRTUAL EQU X'01'	Virtual device is known by the virtual machine as a 3330V
39	VDEVRES1 DS 3X	Reserved for IBM use
3C	VDEVRRB DS 1F	Address of VRRELOK for RESERVE/RELEASE
	VDEVSIZE EQU (*-VDEVBLOCK)/8	VDEVELOK size in doublewords (X'07')
For Spooling/Console Devices		
10	ORG VDEVRELN	
14	VDEVEXTN DS 1F	Pointer to spool extension block
18	VDEVSPAR DS 1F	Spare pointer to spool extension block
1C	VDEVCON DS 1F	Pointer to VCONCTL console control
20	VDEVCLAS DS 1C	Pointer to VSPLCTL spool control
21	VDEVKEY DS 1X	Spool output class
22	VDEVUNIT DS 1H	Storage key in user's CAW
24	VDEVCOPY DS 1H	Spool output directed device address
26	VDEVCFLG DS 1X	Number of copies requested
		Console - virtual console flags
Bits defined in VDEVCFLG		
	VDEVATTN EQU X'80'	User pressed Attention key two or more times
	VDEVATIC EQU X'40'	Last CCW processed was a TIC
	VDEVTRAN EQU X'20'	Data transfer occurred during this channel program
	VDEVVCF EQU X'10'	Virtual console function in progress
	VDEVAUCR EQU X'08'	Automatic carriage return on first read

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
27	VDEVSFLG DS 1X	Spccl - virtual spool flags
<u>Bits defined in VDEVSFLG</u>		
	VDEVFEED EQU X'80'	Spool reader - last command was a feed
	VDEVXFER EQU X'80'	Spccl output - transferred to VDEVXUSR
	VDEVCONT EQU X'40'	Spccl device - continuous operation
	VDEVHOLD EQU X'20'	Hold output - save input
	VDEVFOR EQU X'10'	Spccl output - for user and distribution
	VDEVEOF EQU X'08'	Spccl input - set unit exception at EOF
	VDEVTERM EQU X'08'	Terminal output required for spooled console
	VDEVCFCL EQU X'04'	Device closed by console function
	VDEVPURG EQU X'02'	Spool output - purge file at close
	VDEVDIAG EQU X'02'	Spccl input - device opened by DIAGNOSE
	VDEVSVC EQU X'01'	Spccl device busy by CP

VFCBEBLOK, VMABLOK

VFCBEBLOK: VIRTUAL FORMS CONTROL BUFFER BLOCK


VFCBEBLOK is exclusively used for virtual 3211 printer carriage contrcl forms activity.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VFCBCNT DS 1H	Current pointer to carriage ccolumn
2	VFCBFLAG DS 1X	V*1 Working flag byte
<u>Bits defined in VFCBFLAG</u>		
	VFCBEOF EQU X'80'	End-of-forms passed once
	VFCBCMD EQU X'40'	Forms contrcl given
3	VFCBCHL DS 1X	V*2 Channel number or space count
4	VFCBWORK DS 1F	Work area
8	VFCBSPAR DS 2X	Spare
A	VFCBNDEX DS 1X	V*3 Index byte value
B	VFCBLOAD DS CL181	Forms contrcl buffer area
	VFCBSIZE EQU (*-VFCBEBLOK)/8	Size in doublewords (X'18')

VMABLOK: SHARED SYSTEMS CONTROL ADDITION TO VMBLOCK

VMABLOK contains the name of a shared system, a pointer to the share table (SHRTABLE), and a pointer to the next VMABLOK. The VMASSIST field in the VMAELCK points to the VMABLOK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VMAFPNT DS 1F	Forward pointer to next VMABLOK
4	VMAshrbk DS 1F	Address of share table (SHRTABLE)
8	VMANAME DS CL8	Identification of named shared system
	VMASIZE EQU (*-VMABLOK)/8	VMAELCK size in doublewords (X'02')

VMBLOK: VIRTUAL MACHINE CONTROL BLOCK

VMBLOK is used as the primary control block for almost all activities related to a single virtual machine. This block contains the following information: the dispatch and priority level of the virtual machine, the virtual machine's processor registers, preferred virtual machine option values, and other values significant to virtual machine operations. The ASYSVM field of the PSA points to the system VMELOK.

0	VMQFPNT		VMQBPNT
8	VMPNT		VMECEXT
10	VMSEG		VMSIZE
18	VMCHSTRT		VMCUSTRT
20	VMDVSTRT		VMTERM
28	VMVTERM VMTRMID	V*1 V*2 V*3 V*4	
30	VMCHCNT VMCUCNT	VMDDVCNT VMIOACTV	
38	VMCHTBL		
.	.		.
.	.		.
58	V*5 V*6 V*7 V*8 V*9 V*10 V*11 V*12		
60	V*13 V*14 V*15 V*16	VMLOCKER	
68	V*19 V*20 VMIOINT		VMTIMER
70	VMVTIME		
78	VMTMOUTQ		
80	VMTTIME		
88	VMTMINQ		
90	VMTODINQ		
98	VMINST	V*17 V*18	
A0	VMTREXT		VMADSTOP
A8	VMPSW		
B0	VMGPRS		
.	.		.
F0	VMFPRS		
.	.		.
.	.		.
110	VMUSER		
118	VMACNT		

120	VMDIST		
128	VMPGREAD		VMPGWRIT
130	VMWCNT VMSEGDSP		VMSTOR
138	VMIOCNT		VMPNCH
140	VMLINS		VMCRDS
148	VMCOMND		
150	/VMEDRAM/ /VMPDISK/ VMPAGES VMPRGIL		
158	VMDEDCH VMQPRIOR VMWSPROJ VMSTEALS		
160	VMTIMEON		VMTRQBLK
168	VMACCOUNT		VMRDINQ
170	VMGRINQ		VMEPRIOR
178	VMSTKO		VMMICRO
180	VMPFUNC		VMPXINT
188	VMDELAY		VMRPRIOR
190	VMPGPNT		VMNDCNT VMSHRSYS
198	V*21 V*22 V*26 V*27	VMASSIST	
1A0	VMCPNT		VMCPUID V*25/
1A8	VMLOCK		VMDFTPNT
1B0	VMUSER1		VMUSER2
1B8	VMUSER3		VMUSER4
1C0	VMUHS		VMPCKP
1C8	VMXPG C*1 C*2 VMSTKCNT VMPRRCT		
1DC	VMSWPMIG	C*3 C*4 V*28 V*29	
1D8	VMCPETIME		
1E0	VMAPTIME		
1E8	VMACTDEV VMFLPAG V*30 RSVD VMCONLN		
1F0	VMCONBUF	V*31 //RESERVED///	

VMBLOCK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VMQFPNT	DS 1F Pointer to next VMBLOCK in queue
4	VMQBPNT	DS 1F Pointer to previous VMBLOCK in queue
8	VMPNT	DS 1F Pointer (CYCLIC) to next VMBLOCK
C	VMECEXT	DS 1F VMBLOCK extended control pointer - ECBLOK
	VMVCR0	EQU VMECEXT Virtual control register 0 for non-EC mode virtual machine
10	VMSEG	DS 1F Pointer to VMSEG_TBL
14	VMSIZE	DS 1F Virtual temporary storage size in bytes
18	VMCHSTRT	DS 1F Pointer to VCHBLOCK table
1C	VMCUSTRT	DS 1F Pointer to VCUBLOCK table
20	VMDVSTRT	DS 1F Pointer to VDEVBLOCK table
24	VMTERM	DS 1F Pointer to RDEVELOK for user terminal
28	VMVTERM	DS 1H Displacement to virtual console VDEVBLOCK
2A	VMTRMID	DS 1H Resource ID of real terminal if 370x
2C	VTMLEND	DS 1C V*1 Terminal line end symbol
2D	VMTLDEL	DS 1C V*2 Terminal line delete symbol
2E	VMTCDDEL	DS 1C V*3 Terminal character delete symbol
2F	VMTESCP	DS 1C V*4 Terminal escape symbol
30	VMCHCNT	DS 1H Virtual channel count
32	VMCUCNT	DS 1H Virtual control unit count
34	VMDVCNT	DS 1H Virtual device count
36	VMIOACTV	DS 1H Active channel mask
38	VMCHTB1	DS 16H Channels attached - VMCHSTRT index
58	VMRSTAT	DS 1X V*5 Virtual machine running status
	<u>Bits defined in VMRSTAT</u>	
	VMCFWAIT EQU X'80'	Waiting - Executing console function
	VMPGWAIT EQU X'40'	Waiting - Paging operation(s)
	VMIOWAIT EQU X'20'	Waiting - Scheduled IOELOK start
	VMPSWAIT EQU X'10'	Waiting - Virtual PSW wait state
	VMEXWAIT EQU X'08'	Waiting - Instruction simulation
	VMLOGON EQU X'04'	User not logged on
	VMLOGOFF EQU X'02'	User logging off
	VMIDLE EQU X'01'	Virtual machine in idle wait state
	VMCPWAIT EQU	VMCFWAIT+VMPGWAIT+VMIOWAIT+VMEXWAIT+VMLOGCFF+VMLOGON
	VMNORUN EQU	VMCPWAIT+VMPSWAIT
	VMLONGWT EQU	VMCFWAIT+VMLOGON+VMLCGOFF+VMIDLE
59	VMDSTAT DS	1X V*6 Virtual machine dispatching status
	<u>Bits defined in VMDSTAT</u>	
	VMDSP EQU X'80'	Virtual machine is dispatched run user
	VMTSEND EQU X'40'	Virtual machine is compute bound
	VMQSEND EQU X'20'	Virtual machine in-queue time slice end
	VMTIO EQU X'10'	Virtual machine is in TIO busy loop
	VMRUN EQU X'08'	Virtual machine runnable
	VMINQ EQU X'04'	Virtual machine in a queue
	VMELIG EQU X'02'	Virtual machine in eligible list
	VMPAZAPL EQU X'01'	Use dispatch path DMKDSPCH

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
5A	VMOSTAT DS 1X V*7	Virtual machine operating status		
<u>Bits defined in VMOSTAT</u>				
	VMSYSOP EQU X'80'	Virtual machine is system operator		
	VMSHR EQU X'40'	Virtual machine running shared system		
	VMSLEEP EQU X'20'	Virtual machine is in SLEEP state		
	VMDISC EQU X'10'	Virtual machine console disconnected		
	VMCFRUN EQU X'08'	Virtual machine running in console function mode		
	VMVIRCF EQU X'04'	Virtual machine executing virtual console function		
	VMCF EQU X'02'	Virtual machine executing console function		
	VMKILL EQU X'01'	Virtual machine is to be logged off		
5B	VMQSTAT DS 1X V*8	Virtual machine queueing status		
<u>Bits defined in VMQSTAT</u>				
	VMPRIDSP EQU X'80'	Virtual machine eligible for queue 1		
	VMAUTLOG EQU X'40'	Autologged user is in disconnect mode		
	VMWSERNG EQU X'20'	Last working set error was negative		
	VMDLDRP EQU X'10'	Delayed queue drop flag		
	VMWSCHG EQU X'08'	Force a new working set on queue entry		
	VMINHMG EQU X'04'	Page migration switch		
	VMCFREAD EQU X'02'	Virtual machine with console function read on		
	VMPA2APL EQU X'01'	Reflects external interrupts to machine		
5C	VMPSTAT DS 1X V*9	Virtual machine processing status		
<u>Bits defined in VMPSTAT</u>				
	VMISAM EQU X'80'	Virtual machine has ISAM CCW checking		
	VMV370R EQU X'40'	Virtual machine can use extended format		
	VMRPAGE EQU X'20'	Virtual machine can reserve pages		
	VMREAL EQU X'10'	Virtual machine has virtual=real option		
	VMNOTRAN EQU X'08'	No CCW translation for virtual=real user		
	VMNSHR EQU X'04'	Running nonshared named saved system		
	VMACCOUN EQU X'02'	Virtual machine may punch account cards		
	VMPAGEX EQU X'01'	Virtual machine receiving pseudc page faults		
5D	VMESTAT DS 1X V*10	Virtual machine control status		
<u>Bits defined in VMESTAT</u>				
	VMSHADT EQU X'80'	Shadow tables are present		
	VMPERCM EQU X'40'	Virtual CP PER active		
	VMBADCR0 EQU X'20'	Virtual control register 0 is invalid		
	VMMICSV C EQU X'10'	User wants SVCs done by virtual machine assist feature		
	VMEXTCM EQU X'08'	Virtual machine in extended control mode		
	VMNEWCR0 EQU X'04'	Virtual control register 0 has changed		
	VMINVSEG EQU X'02'	All shadow tables invalid		
	VMINVPG EQU X'01'	Shadow page tables invalid		
	VMECZAP EQU 255-VMMICSV C	All bits except VMMICSV C		
5E	VMTRCTL DS 1X V*11	Virtual machine tracing control		
<u>Bits defined in VMTRCTL</u>				
	VMTRPER EQU X'80'	Virtual PER tracing active		
	VMTRSVC EQU X'40'	Trace user SVC instructions		
	VMTRPRG EQU X'20'	Trace virtual program interrupts		
	VMTRIO EQU X'10'	Trace virtual I/O interrupts		
	VMTREX EQU X'08'	Trace external interrupts		
	VMTRPRV EQU X'04'	Trace user privileged instructions		
	VMTRSIO EQU X'02'	Trace virtual I/O instructions		
	VMTRBRIN EQU X'01'	Trace successful branches or all instructions		
	VMTRINT EQU VMTRSVC+VMTRPRG+VMTRIO+VMTREX	Trace all user interrupts		

VMBLOCK

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
5F	VMLEVEL DS	1X	V*12	Message level
<u>Bits defined in VMLEVEL</u>				
	VMMSGON EQU	X'80'		Receiving messages
	VMWNGON EQU	X'40'		Receiving warnings
	VMPCODE EQU	X'20'		Receiving error message codes
	MMTEXT EQU	X'10'		Receiving texts of error messages
	VMMLINED EQU	X'08'		Line editing on
	VMMACCON EQU	X'04'		Receiving accounting information
	VMCPENV EQU	X'02'		Terminal in CP mode
	MMSTMP EQU	X'01'		Time stamp desired on console output
60	VMQLEVEL DS	1X	V*13	Queue level
<u>Bits defined in VMQLEVEL</u>				
	VMQ1 EQU	X'80'		Virtual machine is interactive
	VMCOMP EQU	X'40'		Virtual machine is compute bound
	VMHIPRI EQU	X'20'		Virtual machine is highest priority
	VMLOPRI EQU	X'10'		Virtual machine is lowest priority
	VMAEX EQU	X'08'		Virtual machine is assured execution
	VMAEXP EQU	X'04'		Virtual machine is assured percentage
	VMQ3 EQU	X'02'		Virtual machine using multiple Q2. Note that this bit is used only by the fair share scheduler.
	VMDROP1 EQU	X'02'		Virtual machine dropped from Q1. This bit is used only by the standard scheduler.
	VMFS EQU	X'01'		Using more than fair share flag
61	VMCLEVEL DS	1X	V*14	Command level
<u>Bits defined in VMCLEVEL</u>				
	VMCLASSA EQU	X'80'		Privilege Class A functions
	VMCLASSB EQU	X'40'		Privilege Class B functions
	VMCLASSC EQU	X'20'		Privilege Class C functions
	VMCLASSD EQU	X'10'		Privilege Class D functions
	VMCLASSE EQU	X'08'		Privilege Class E functions
	VMCLASSF EQU	X'04'		Privilege Class F functions
	VMCLASSG EQU	X'02'		Privilege Class G functions
	VMCLASSH EQU	X'01'		Reserved for IBM use
62	VMTLEVEL DS	1X	V*15	Timer level
<u>Bits defined in VMTLEVEL</u>				
	VMTON EQU	X'80'		Virtual timer running
	VMRON EQU	X'40'		Virtual real timer running
	VMCPUTMR EQU	X'20'		Virtual processor timer in real processor timer
	VMSTMPI EQU	X'08'		Virtual interval timer request queued
	VMSTMPT EQU	X'04'		Virtual processor timer request queued
	VMTRINT EQU	X'01'		Interrupt from processor real timer pending
<u>Bits redefined for System VMBLOCK</u>				
	VMTIDLE EQU	VMTON		Processor timer contains idle wait state time
	VMTPAGE EQU	VMRON		Processor timer contains system page wait time
	VMTIONT EQU	VMSTMPI		Processor timer contains I/O wait state time

Hexadecimal Displacement	Field Name	Field Description, Ccntents, Meaning
63	VMPEND DS 1X V*16	Interrupt pending summary flag
<u>Bits defined in VMPEND</u>		
	VMDEFSTK EQU X'80'	Deferred task wait for system lock
	VMPERPND EQU X'40'	Virtual PER interrupt pending
	VMPRGPNPND EQU X'20'	Virtual program interrupt deferred
	VMSVCPND EQU X'10'	Virtual SVC interrupt deferred
	VMPGPND EQU X'08'	Virtual pseudo page fault pending
	VMIOPND EQU X'02'	Virtual I/O interrupt pending
	VMEXTPND EQU X'01'	Virtual external interrupt pending
64	VMLOCKER DS 1F	Base address of holder of VMLOCK
68	VMFSTAT DS 1X V*19	Virtual machine feature status
<u>Bits defined in VMFSTAT</u>		
	VMFBMX EQU X'80'	Virtual block multiplexer channels
	VMFAUTO EQU X'40'	Autocall handshake option in use
	VMFVTMR EQU X'20'	User requested virtual timer assist enabled
	VMNPWDCL EQU X'04'	Virtual machine requests password suppression
69	VMMVL2 DS 1X V*20	Additional message handling information
<u>Bits defined in VMMVL2</u>		
	VMMIMSG EQU X'80'	Receiving all informational messages
6A	VMIOINT DS 1H	I/O interrupt pending flags
6C	VMTIMER DS 1F	Virtual timer value - X'50'
70	VMVTIME DS 1D	Virtual processor time used
78	VMTMOUTQ DS 1D	Time remaining in queue 1 and/or queue 2
80	VMTTIME DS 1D	Total time while in supervisor state
88	VMTMINQ DS 1D	VMTTIME value at entry to queue
	VMTSOUTQ EQU VMTMINQ	Supervisor time allowed (redefine label)
90	VMTODINQ DS 1D	TOD clock time stamp at queue entry
98	VMINST DS 3H	Virtual machine privileged or tracing instruction
9E	VMUPRIOR DS 1H V*17	User priority from directory
9F	VMPWDCT DS 1X V*18	Invalid LINK password count
A0	VMTREXT DS 1F	Address of extended trace control block
A4	VMADSTOP DS 1F	Address of address stop control block
A8	VMPSW DS 1D	Virtual machine PSW
B0	VMGPRS DS 16F	Virtual machine general purpose registers
F0	VMFPRS DS 4D	Virtual machine floating-point registers
110	VMUSER DS CL8	Virtual machine identification
118	VMACNT DS CL8	Virtual machine accounting number
120	VMDIST DS CL8	Virtual machine distribution code
128	VMPGREAD DS 1F	Total page reads
12C	VMPGWRIT DS 1F	Total page writes
130	VMWCNT DS 1H	Page wait count
132	VMSEGDSP DS 1H	Displacement of virtual machine SEGTABLE from start of block
134	VMSTOR DS 1F	Permanent storage size (in bytes)
138	VMIOCNT DS 1F	Virtual SIO count for nonspooled I/O
13C	VMPNCH DS 1F	Virtual card count - spooled punch
140	VMLINS DS 1F	Virtual line count - spooled printer
144	VMCRDS DS 1F	Virtual card count - spooled reader
148	VMCOMND DS CL8	Last CP command executed
150	VMPDRUM DS 1H	Reserved for IBM use
152	VMPDISK DS 1H	Reserved for IBM use
154	VMPAGES DS 1H	Number of real pages currently resident
156	VMPFGIL DS 1H	ILC for latest program interrupt
158	VMDEDCH DS 1H	Mask for dedicated channel
15A	VMQPRIOR DS 1H	Priority in dispatching queue
15C	VMWSPROJ DS 1H	Projected working set size

VMBLOK


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
15E	VMSTEALS DS	1H Number of waits for stolen pages
160	VMTIMEON DS	1F Logon time -- TOD clock word 0
164	VMTRQBLK DS	1F Address of TRQBLOK for real timer
168	VMACOUNT DS	1F Address of user ACCTELOK
16C	VMRDINQ DS	1F Page read total (VMPGREAD) at queue entry
170	VMPGRINQ DS	1F Sum of virtual machine pages count at each page read
174	VMEPRIOR DS	1F Eligible list priority
178	VMSTKO DS	1F Console function output stack pointer
17C	VMMICRO DS	1F Virtual machine assist - real control R6
17C	ORG VMMICRO	
17C	VMMCR6 DS	1X Control register 6 - hardware flag byte
	<u>Bits defined in VMMCR6</u>	
	VMMFE EQU	X'80' Virtual machine assist feature enabled
	VMMPROB EQU	X'40' Virtual machine in problem state
	VMMNOSK EQU	X'20' Virtual machine assist does not handle SSK, or ISK
	VMM360 EQU	X'10' S/360 operations only; no EC mode operations allowed
	VMM SVC EQU	X'08' Virtual machine assist does not handle SVCs
	VMM SHADT EQU	X'04' Shadow tables present (EC mode and translate)
	VMMCPAST EQU	X'02' CP assist feature enabled
	VMMVTMR EQU	X'01' Virtual interval timer assist feature enabled
17D	VMMADDR DS	3X Control register 6 - address of virtual machine's pointer list (MICELOK)
180	VMPFUNC DS	1F PFnn function table
184	VMPXINT DS	1F Extended external interrupt stack pointer
188	VMDELAY DS	1F TRQELOCK for delayed SLEEP or LOGOFF
18C	VMRPRIOR DS	1F Run list dispatching priority
190	VMPGPNT DS	1F Pointer to list of pages in PGBLOK
194	VMNDCT DS	1H Nondeferred page read count
196	VMSHRSYS DS	1H Number of shared named systems
198	VMRBCS DS	1X V*21 Remote display line count
199	VMCXSTAT DS	1X V*22 VMCF status byte
	<u>Bits defined in VMCXSTAT</u>	
	VMBCAUTH EQU	X'80' VMCF active
	VMOLOG EQU	X'20' I/O logout mask bit from control register 14. Referenced through VMVCR14.
	VMVCR14 EQU	VMCXSTAT V*22 Contains I/O logout mask bit from control register 14 (for both EC and PC mode). During EC mode, control register 14 data is also kept in the ECBLOK.
19A	VMAFF DS	1X V*26 Affinity request field
	<u>Bits defined in VMAFF</u>	
	VMAFFON EQU	X'40' Affinity set on
	VMAFFAD DS	0BL6 Processor address
19B	VMLSTPRC DS	1X V*27 Last processor executed in problem state
19C	VMASSIST DS	1F Pointer to list of VMAELOKs
1A0	VMCPNT DS	1F VMCELOK anchor
1A4	VMCPUID DS	3X Processor identification number in binary
1A7	VMNOECPS DS	1X V*25 Reserved for IBM use
1A8	VMILOCK DS	1F Lock word for compare and swap locking
1AC	VMDFTPNT DS	1F Deferred task pointer
1B0	VMUSER1 DS	1F Reserved for installation use
1B4	VMUSER2 DS	1F Reserved for installation use

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
1B8	VMUSER3	DS 1F	Reserved for installation use
1BC	VMUSER4	DS 1F	Reserved for installation use
1C0	VMUHS	DS 1F	Recent history of user processor utilization
1C4	VMPCKP	DS 1F	User page read checkpoint
1C8	VMXPG	DS 1H	Maximum virtual machine pages count in-queue
1CA	VMQ2CNT	DS 1X	C*1 Consecutive queue 2 count
1CB	VMQ3CNT	DS 1X	C*2 Count of consecutive Q2s allowed
1CC	VMSTKCNT	DS 1H	Count of stacked ICB plus CPEXBLOCKS
1CE	VMPPRCT	DS 1H	Processor related stacked CPEXBLOCKS
1D0	VMSWPMIG	DS 1F	Pointer to pseudo page table
1D4	VMFVRF	DS 1X	C*3 SET FAVORED percentage for user
1D5	VMCRTO	DS 1X	C*4 COMPUTE/ELAPSED ratio
1D6	VMSHRPRC	DS 1X	V*28 Processor (main or attached) whose shared segments were last used
1D7	VMGRFTAB	DS 1X	V*29 GRAF virtual console logical tab
1D8	VMCPTIME	DS 1D	Main processor supervisor time
1E0	VMAPTIME	DS 1D	Attached processor supervisor time
1E8	VMACTDEV	DS 1H	Virtual device address for last virtual SIO
1EA	VMFLPAG	DS 1H	Count of nonshared flushed pages
1EC	VMSPMFLG	DS 1X	V*30 VMCF special message flag
<u>Bits defined in VMSPMFLG</u>			
	VMSPMON	EQU X'40'	Receiving special messages
	VMSMSGON	EQU X'20'	Processing special messages
1ED	RESERVED	DS 1X	Reserved for IBM use
1EE	VMCONLN	DS 1H	Bytes left in response buffer
1F0	VMCONBUF	DS 1F	Virtual address of response buffer
1F4	VMPWDCA	DS 1X	V*31 Invalid AUTOCLOG password count
1F5	RESERVED	DS 3X	Reserved for IBM use
	VMBSIZE	EQU $(*-VMBLOK)/8$	VMELOCK size in doublewords (X'38')

VMCBLOK

VMCBLOK: VIRTUAL MACHINE COMMUNICATION BLOCK

VMCBLOK contains data transfer and status information used by the Virtual Machine Communication Facility (VMCF). The VMCPNT field of the VMBLOK points to VMCBLOK.



Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning						
0	VMCSTAT	DS	1X	V*1	VMCELOK user status					
<u>Bits defined in VMCSTAT</u>										
	VMCRESP	EQU	X'80'		Final response interrupt					
	VMCRJCT	EQU	X'40'		Message rejected					
	VMCPRTY	EQU	X'20'		Priority message					
1	VMCEFLG	DS	1X	V*2	Data transfer return code					
2	VMCFUNC	DS	1H		Subfunction code					
4	VMCMID	DS	1F		Message identifier					
8	VMCUSER	DS	1D		Source and/cr sink userid (VMUSER)					
10	VMCVADA	DS	1F		Vaddr of message buffer					
14	VMCLENA	DS	1F		Length of message					
18	VMCVADB	DS	1F		Vaddr of reply buffer (SEND/RECV only)					
1C	VMCLENB	DS	1F		Length of reply buffer (SEND/RECV only)					
20	VMCUSE	DS	1D		User-supplied doubleword					
28	VMCFPNT	DS	1F		Address of next VMCBLOK					
2C	VMCKEY	DS	1X	V*3	User PSW key					
2D	VMCCSTAT	DS	1X	V*4	VMCELOK control status					
<u>Bits defined in VMCCSTAT</u>										
	VMCCXINT	EQU	X'80'		External interrupt VMCELOK					
	VMCCRECP	EQU	X'40'		Transaction processed					
	VMCCBUSY	EQU	X'20'		VMCELOK busy					
2E	VMCASTAT	DS	1X	V*5	VMCELOK authorization status					
<u>Bits defined in VMCASTAT</u>										
	VMCAAUTS	EQU	X'80'		Authorized specific					
	VMCAPRTY	EQU	X'40'		Authorized priority					
	VMCAQIES	EQU	X'20'		User is quiescent					
2F	VMCRSB1	DS	1X	V*6	Reserved for IBM use					
30	VMCTOD	DS	1D		TOD at authorization and/or build operation					
	VMCBSIZE	EQU	(*-VMCBLOK)/8		VMCELOCK size in doublewords					
<u>Redefinition for Master VMCBLOK</u>										
	VMCACNT	EQU	VMCFUNC		Active message count					

VMCMHDR: VMCF MESSAGE HEADER

VMCMHDR provides information to identify the special VMCF external interrupts.


0	V*1		V*2		VMCMFUNC		VMCMID
VMCMUSER							
10			VMCMVADA			VMCMLENA	
18			VMCMVADB			VMCMLENE	
20					VMCMUSE		
28					VMCMBUF		
.							.
.							.
.			(Optional Message Buffer)				.

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VMCMSTAT DS 1X	V*1 Message status byte
	<u>Bits defined in VMCMSTAT</u>	
	VMCMRESP EQU X'80'	Final response interrupt
	VMCMRJCT EQU X'40'	Message rejected
	VMCMRPTY EQU X'20'	Priority message
1	VMCMFLG DS 1X	V*2 Data transfer return code
2	VMCMFUNC DS 1H	Subfunction code (original request)
4	VMCMID DS 1F	Message identifier
8	VMCMUSER DS 1D	Source and/or sink userid (VMUSER)
10	VMCMVADA DS 1F	Virtual buffer address
14	VMCMLENA DS 1F	Message length
18	VMCMVADB DS 1F	Virtual reply buffer address
1C	VMCMLENB DS 1F	Reply buffer length
20	VMCMUSE DS 1D	User supplied doubleword
28	VMCMBUF DS 0X	Optional SENDX data buffer
	VMCMLEN EQU (*-VMCMHDR)	VMCMHDR size in bytes

VMCPARM

VMCPARM: VMCF PARAMETER LIST


VMCPARM contains the user-supplied parameters when a VMCF subfunction is executed. Register 1 in the Diagnose instruction points to VMCPARM.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VMCPFLG1 DS 1X	V*1 VMCPARM flag byte
	Bits defined in VMCPFLG1	
	VMCPAUTS EQU X'80'	Authcrize specific request
	VMCPPRTY EQU X'40'	Priicity message
	VMCPMSG EQU X'20'	Receiving special messages
1	VMCPFLG2 DS 1X	V*2 Reserved for IBM use
2	VMCPFUNC DS 1H	Subfunction code
	Bits defined in VMCPFUNC	
	VMCPRJCT EQU X'000B'	REJECT
	VMCPIDEN EQU X'000A'	IDENTIFY
	VMCPRESM EQU X'0009'	RESUME
	VMCQUIE EQU X'0008'	QUIESCE
	VMCPREPL EQU X'0007'	REPLY
	VMCPANC EQU X'0006'	CANCEL
	VMCPRECV EQU X'0005'	RECEIVE
	VMCPSENX EQU X'0004'	SENDX
	VMCPSENR EQU X'0003'	SEND/RECEIVE
	VMCPSEND EQU X'0002'	SEND
	VMCPAUT EQU X'0001'	UNAUTHORIZE
	VMCPAUTH EQU X'0000'	AUTHCRIZE
4	VMCPMID DS 1F	Message identifier
8	VMCPUSER DS 1D	Target userid
10	VMCPVADA DS 1F	Virtual address of message buffer
14	VMCPLENA DS 1F	Length of message
18	VMCPVADE DS 1F	Virtual address of reply buffer (SEND/RECEIVE only)
1C	VMCPLENB DS 1F	Length of reply buffer (SEND/RECEIVE only)
20	VMCPUSE DS 1D	User supplied doubleword
	VMCPLEN EQU (*-VMCPARM)	Length of VMCPARM (bytes)

VRRBLOK: VIRTUAL RESERVE/RELEASE BLOCK


VRRBLOK is linked to the VDEVBLOK and contains information about minidisk usage. The VDEVRRB field of the VDEVBLOK points to VRRBLOK.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
0	VRRADD	DS	1H	Reserved virtual device address
2	VRRSTAT	DS	1X	V*1 Virtual RESERVE/RELEASE status flags
<u>Bits defined in VRRSTAT</u>				
2	VRRRES	EQU	X'80'	Minidisk is reserved
3	VRSSV1	DS	1X	V*2 Reserved for IBM use
4	VRRCPLEX	DS	1F	Queued request for the minidisk
8	VRRUSER	DS	1F	VMELCK of the user who has the minidisk
reserved				
C	VRSSV2	DS	1F	Reserved for IBM use
VRSSIZE EQU (*-VRRBLOK)/8 Size in doublewords (X'02')				

VSPLCTL**VSPLCTL: VIRTUAL SPOOLING CONTROL BLOCK**


VSPLCTL is linked to the VDEVBLOK and contains information for opened spool files. The VDEVSPL field of the VDEVBLOK points to VSPLCTL.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VSPCAW DS 1F	Virtual address of user CCW
4	VSPDPAGE DS 1F	DASD location (LCHR) of current page buffer
8	VSPVPAGE DS 1F	Virtual address of page buffer
C	VSPRECNO DS 1F	Records remaining in current buffer
10	VSPNEXT DS 1H	Displacement in buffer of next record start
12	VSPIDACT DS 1H	Data byte count of indirect data address CCW
14	VSPSFBLK DS 1F	Pointer to SFBLCK for file
18	VSPCCW DS 1D	Current user CCW
20	VSPBUFBK DS 1F	Address of a buffer area
24	VSPMISC DS 1F	Use varies according to caller
28	VSPIDASW DS 1X	V*1 Indirect data address work flag
29	VSPIDAL DS 3X	Address of indirect data list
2C	VSPIDAW2 DS 1F	Contains IDAW2
	VSPSIZE EQU (*-VSPLCTL)/8	Size in doublewords (X'06')
	VSPBUFSZ EQU (200)/8	Size in doublewords (X'19')

VSPXBLOK: VIRTUAL SPOOL EXTENSION BLOCK

VSPXBLOK serves as an extension to the virtual spool control block (VSPLCTL). It contains the user named destination of the file as well as RSCS tag information used by the Remote Spooling Communications Subsystem.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	VSPXLEN DS 1X	V*1 VSPXBLOK length (doublewords)
1	VSPXTGLN DS 1X	V*2 VSPXTAG data length (bytes)
2	VSPXFLSH DS 1X	V*3 3800 flash count
3	VSPXFLG1 DS 1X	V*4 3800 flag byte
<u>Bits defined in VSPXFLG1</u>		
	VSPXCPYF EQU X'80'	If this bit is set, multiple copies can be sent in one transmission
4	VSPXSPAR DS XL4	Reserved for IBM use
8	VSPXDIST DS CL8	Virtual device distribution code
10	VSPXXUSR DS CL8	Virtual machine user to whom the file is transferred
18	VSPXCHAR DS CL4	3800 character arrangement table
1C	VSPXFBC DS CL4	3800 forms control buffer
20	VSPXCMD DS CL4	3800 copy modification
24	VSPXOVLY DS CL4	Name of flash overlay to be used
	VSPXSIZ1 EQU (*-VSPXBLOK)/8	VSPXBLOK header in doublewords
28	VSPXTAG DS CL136	Tag application data area
	VSPXSIZ2 EQU (*-VSPXBLOK)/8	VSPXBLOK size in doublewords

XINTELOK

XINTELOK: EXTERNAL INTERRUPT BLOCK

XINTELOK saves the various types of external interrupts that are presented to the virtual machine. If multiple external interrupt conditions are simultaneously presented, as indicated by values presented in the block, code exists for handling the interrupts in their defined hierarchical order. The VMPXINT field of the VMBLCK points to XINTELOK.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	XINTNEXT DS 1F	Address of next external interrupt block
4	XINTSORT DS 1H	Left half of interrupt collating key
6	XINTCPUA DS 1H	Right half of interrupt collating key
8	XINTCODE DS 1H	External interrupt code
A	XINTMASK DS 1H	Control register 0 mask (bits 16-31)
C	XINTPARM DS 1F	External interrupt parameter word

XINTSIZE EQU (*-XINTELOK)/8 XINTELOK size in doublewords (X'02')

XOBR3211: EXTENDED OUTBOARD RECORDING BLOCK

XOBR3211 is appended to the IOERBLOK to contain sense data and other data associated with I/O errors and error recovery for devices that generate more than 24 bytes of sense information.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
50	XOBRCW1 DS	1D CCW used to read OBR information
58	XOBRCW2 DS	1D CCW used to read OBR information
60	XOBRCW3 DS	1D CCW used to read OBR information
68	XOBRCW4 DS	1D CCW used to read OBR information
70	XOBRFLAG DS	1X X*1 Outboard recording flag byte
		<u>Bits defined in XOBRFLAG</u>
	XOBRT1 EQU X'80'	T1 Buffer type information present
	XOBRT2 EQU X'40'	T2 Buffer type information present
	XOBRT3 EQU X'20'	T3 Buffer type information present
71	XOBRSTAT DS	1X X*2 Outboard recording status byte
		<u>Bits defined in XOBRSTAT</u>
	XOBRRT1 EQU X'80'	Perfrm routine 1 in error module
	XOBRRT2 EQU X'40'	Perfrm routine 2 in error module
	XOBRRT3 EQU X'20'	Perfrm routine 3 in error module
	XOBRRT4 EQU X'10'	Perfrm routine 4 in error module
	XOBRRT5 EQU X'08'	Perfrm routine 5 in error module
	XOBRRT6 EQU X'04'	Perfrm routine 6 in error module
	XOBRRT7 EQU X'02'	Perfrm routine 7 in error module
	XOBRRT8 EQU X'01'	Perfrm routine 8 in error module

XOBR3211

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
72	XOBRMIS1	DS 1H	Used by the error routine
74	XOBRMIS2	DS 1F	Used by the errcr routine
78	XOBR512	DS CL512	Space for USCB data
278	XOBR180	DS CL184	Space for FCB data
330	XOBR010	DS CL10	Space for first ten error characters
33A	XOBRSV1	DS CL6	Reserved for IBM use
278		ORG XOBR180	Redefinition for PLB check
	XOBR150	DS CL150	Space for PLB check data
	XOBRSIZE	EQU (*-IOERBLOK)/8	Size of IOER and XOBR in doublewords (X'67')
	XOBREXT	EQU (*-XOBRCW1)/8	Size of XOBR3211 in doublewords (X'5E')

Section 2. CMS Data Areas and Control Blocks

This section contains CMS data areas and control blocks. Figure 2 shows the relationships between the control blocks and data areas of CMS.





Figure 2. CMS Control Block Relationships

AFTAB**AFTAB: ABEND TERMINATION OPTION TABLE**


AFTAB contains one 8-byte entry for the background partition. Bytes 0-3 contain the address of the entry point of the user's abnormal termination routine. Bytes 4-7 contain the address of a 72-byte save area used by the supervisor to store the interrupt status information and the contents of the general registers. The IJBABTAB field in the SYSCOM block in the DOSCON CSECT of NUCON points to the AFTAB block.



Hexadecimal Displacement	Field Name				Field Description, Contents, Meaning
0	ABROUT	DC	F'0'		
4	ABSAVE	DC	F'0'		
	ABTAB	EQU	*-8	Abend option table	

ABWSECT: ABEND RECOVERY WORKSPACE

ABWSECT describes the fields used for saving registers and other data during abend recovery. V-constants in DMSABN, DMSDBG, DMSFRE, DMSITI, DMSITP, and DMSITS point to the ABWSECT block. ABWSECT is defined in module DMSAEW.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	ABNREGS DS 16F	Registers at time of abend
40	ABNPSW DS D	PSW at time of abend
48	ABNRR DS F	Temporary save area
4C	ABNPAS13 DS 18F	Area passed to nucleus routines
94	Space for DMSERR PLIST ORG ABNPAS13	
4C	ABNERLST DS 47X	

ADTSECT

ADTSECT: ACTIVE DISK TABLE

ADTSECT describes the attributes of virtual disks (A-G, S, Y, Z) accessed by a virtual machine via the ACCESS command. Space is allocated for the ADT when DMSNUC is assembled. In the ADT, certain fields are defined for use by both CMS and OS. For example, ADTHBCT field at displacement 1C (hexadecimal) into ADTSECT is also defined as OSADTVTA for use by OS simulation routines. ADTSECT is invoked by the ALT macro.

0	ADTID	A*1 A*2
8	ADTPTR	ADTDTA
10	ADTFDA	ADTMFDN
18	ADTMFDA	ADTHECT
20	ADTFSTC	ADTCHBA
28	ADTCFST	ADT1ST
30	ADTNUM	ADTUSEE
38	ADTLEFT	ADTLAST
40	ADTCYL	A*3 A*4 A*5 A*6
48	ADTMSK	ADTQQM
50	ADTPQM1	ADTPQM2
58	ADTPQM3	ADTLHBA
60	ADTLFST	ADTNACW ADTRES
68	ADTXNREC	ADTXAREC

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
<u>Needed for Read-Only Disks and Read/Write Disks</u>				
0	ADTID DS CL6	Disk identifier (label)		
6	ADTFLG3 DS 1X	A*1 Third flag byte		
<u>Bits defined in ADTFLG3</u>				
	ADTFUPD1 EQU X'80'	First half of DMSAUD has been called		
	ADTFXCHN EQU X'40'	Extra chain link(s) to be returned		
	ADTFRWOS EQU X'20'	Read/write CS or DOS disk		
	ADTFSORT EQU X'10'	All FST hyperblocks and FSI entries sorted		
	ADTFORCE EQU X'08'	CMS/ICS/OS disk forced to a read-only		
	ADTFNOAB EQU X'04'	For IMSAUI routine: Do not abend if it is a disk error		
7	ADTFTYP DS 1X	A*2 Filetype flag byte		
8	ADTPTR DS 1A	Pointer to next ADT block in chain		
C	ADTDTA DS 1A	Device table address in NUCON		
10	ADTFDA DS 1A	File directory (PSTAT) address		
14	ADTN DS 1F	Number of doublewords in master file directory		
18	ADTMFDA DS 1A	Master file directory address		
1C	OSADTVTA DS 0F	VTOC address of OS pack		
1C	ADTHBCT DS 1F	FST hyperblock count		

Hexadecimal Displacement	Field Name	Field Description, Ccontents, Meaning
20	ADTFSTC DS 1F	Number of FST 40-byte entries (files)
24	OSADTFST DS 0F	Address of first OS FST
24	ADTCBHA DS 1A	Pointer to current FST hyperblock
28	OSADTVTB DS 0F	Upper VTOC address of OS pack
28	ADTCFST DS 1F	Displacement of current FST entry
2C	ADT1ST DS 1F	Displacement of first word in bit mask with "hcle"
30	OSADTDISK DS 0F	OS disk address (cuu)
30	ADTNUM DS 1F	Number of records (NUMTRKS)
34	OSADTSV1 DS 0F	Save area
34	ADTUSED DS 1F	Number of records in use (CTUSEDPP)
38	ADTLEFT DS 1F	Number of records left (QTLEFTTP)
3C	ADTLAST DS 1F	Displacement of last nonzero byte in bit mask
40	ADTCYL DS 1F	Number of cylinders on disk (NUMCYLP)
44	ADTM DS 1C	A*3 Mode letter (A,B,C,...,S,Y,Z)
45	ADTMX DS 1C	A*4 Extension-of-mode letter (A,B,C,...,S,Y,Z)
46	ADTFLG1 DS 1X	A*5 First flag byte
<u>Bits defined in ADTFLG1</u>		
	ADTFSF EQU X'80'	ADT block in free storage
	ADTFRO EQU X'40'	CMS read-only disk (attached and ready)
	ADTFRW EQU X'20'	CMS read/write disk (attached and ready)
	ADTFFSTF EQU X'10'	First FST hyperblock is in free storage
	ADTFFSTV EQU X'08'	FST hyperblocks are of varying lengths
	ADTFQQF EQU X'04'	200-byte PQMSK is in free storage
	ADTROX EQU X'02'	This disk has read-only extension(s)
	ADTFMIN EQU X'01'	ADT block is minimum size
47	AFTFLG2 DS 1X	A*6 Secnd flag byte
<u>Bits defined in AFTFLG2</u>		
	ADTFMD EQU X'80'	MFD is in storage
	ADTFALNM EQU X'40'	All filenames are in storage
	ADTFALTY EQU X'20'	All filetypes are in storage
	ADTFMDRO EQU X'10'	Modes 1 through 5 are in storage
	ADTFALMD EQU ADTFMDRO+X'08'	All modes (0 through 5) are in storage
	ADTFALUF EQU ADTFMD+ADTFALNM+ADTFALTY+ADTFALMD	
	ADTPSTM EQU X'02'	All UFD is in storage
	ADTFROS EQU X'04'	ADT FSTAT chain modified
	ADTFDOS EQU X'01'	Indicates this is an OS disk
		Indicates this is a DOS disk
48	ADT2ND DS 0D	
<u>Needed for Read/Write Disks</u>		
48	ADTMASK DS 1A	800-byte (PQMSK) bit-mask address
4C	ADTQQM DS 1A	200-byte (PQQMSK) bit-mask address
50	ADTPQM1 DS 1F	PQMSIZ equals number of bytes in PQMSK is greater than 215
54	ADTPQM2 DS 1F	PQMNUN equals number of 800-byte records for PQMSK
58	ADTPQM3 DS 1F	RONUM equals number of doublewords in PQMSK
5C	ADTLHBA DS 1A	Pointer to last FST hyperblock (see Note)
60	ADTLFST DS 1F	Displacment of last FST in last hyperblkck (see Note)
64	ADTNACW DS 1H	Number of active write files -- halfword
66	ADTRRES DS 1H	Reserve count (RESRVCNT) -- halfword
<u>Note:</u> Applies to all CMS disks except for the S-disk.		
68	ADTXNREC DS 1F	Number of doublewords of extra chain link records

ADTSECT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
6C	ADTXAREC DS	1F Address of block of extra chain link records
	ADTLBM EQU	ADT2ND-ADTSECT Length of minimum ADT block (in bytes)
	ADTLDM EQU	ADTLBM/8 Length of minimum ADT block in doublewords
	ADTLB EQU	*-ADTSECT Length of full ADT block (in bytes)
	ADTLD EQU	(ADTLB+7)/8 Length of full ADT block in doublewords
	<u>Other Parameters</u>	
	ADTRL EQU	Logical record length
	ADTMXBML EQU	Maximum bit map length (number of records) for 3330
	<u>NUCON Device Table Displacements</u>	
	DTAD EQU	0 Device number
	DTADT EQU	3 Device type byte
	DTAS EQU	4 Symbolic device name

AFTSECT: ACTIVE FILE TABLE

AFTSECT is used to describe a file currently open for a read or write. The AFT is created when a file is opened. Space for up to five AFTs is available in DMSNUC; any others must reside in free storage. AFTSECT is invoked via the AFT macro.

0	AFTCLD		AFTCLN		AFTCLA		
8	AFTDBD		AFTDBN		AFTDEA		
10							
.							
.							
.							
60	A*1		AFTPFS		AFTIN		AFTID
68	AFTFCLA				AFTFCLX		AFTCLDX
70	A*2		AFTOCLDX				
78	AFTN						
80	AFTT						
88	AFTD				AFTWP		AFTRP
90	AFTM		AFTIC		AFTFCL		A*3 A*4
98	AFTIL				AFTIEC		AFTYR
A0	AFTADT				AFTPTR		


Hexadecimal Displacement	Field Name	Active File Table Block	Field Description, Contents, Meaning
<u>Active File Table Block</u>			
0	AFTSTART	DS 0D	
0		DC 41F'0'	First AFT block
A4		DC A(*+4)	
A8		DC 41F'0'	Second AFT block
14C		DC A(*+4)	
150		DC 41F'0'	Third AFT block
1F4		DC A(*+4)	
1F8		DC 41F'0'	Fourth AFT block
29C		DC A(*+4)	
2A0		DC 41F'0'	Fifth AFT block
344		DC A(0)	Address of next AFT block (in free storage)
348		DC 2F'0'	Reserved for IBM use
<u>Active File Table</u>			
0	AFTCLD	DS H	Disk address of current chain link
2	AFTCLN	DS H	Number of current chain link
4	AFTCLA	DS F	Address of chain link buffer
8	AFTDBD	DS H	Disk address of current data block
A	AFTDBN	DS H	Number of current data block
C	AFTDBA	DS F	Address of current data block
10	AFTCLB	DS XL80	Chain link buffer from first chain link

AFTSECT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
60	AFTFLG DS X A*1	Flag byte
<u>Bits defined in AFTFLG</u>		
	AFTUSED EQU X'80'	Active file table block in use
		X'40' Reserved for IBM use
	AFTICF EQU X'20'	First chain link in storage
	AFTFBAA EQU X'10'	Full buffer assigned
	AFTDBF EQU X'08'	Data block in storage
	AFTWRT EQU X'04'	Active write
	AFTRD EQU X'02'	Active read
	AFTFULD EQU X'01'	Full disk special case
61	AFTPFS T DS 3X	Pointer to (static) FST entry
64	AFTIN DS H	Current item number
66	AFTID DS H	Displacement of current item in data block
68	AFTFCLA DS F	Address of first chain link
6C	AFTFCLX DS H	Disk address of swapped FCI
6E	AFTCLDX DS H	Disk address of swapped chain link
70	AFTFLG2 DS X A*2	Secnd flag byte
<u>Bits defined in AFTFLG2</u>		
	AFTNEW EQU X'80'	New file
	AFTOLDCL EQU X'40'	Current chain link existed previously
	AFTCLX EQU X'20'	Alternate chain link assigned/implied
	SAMLEN EQU X'01'	Force same length update
71		Reserved for IBM use
72	AFTOCLDX DS 1H	Old value (if any) of AFTCLDX
74	DS F	Reserved for IBM use
<u>Copy of FST Block Embedded in AFT Block</u>		
78	AFTFST DS OD	
78	AFTN DS D	Filename
80	AFTT DS D	Filetype
88	AFTD DS F	Date/time last written
8C	AFTWP DS H	Write pointer (item no.)
8E	AFTRP DS H	Read pointer (item no.)
90	AFTM DS H	Filemode
92	AFTIC DS H	Item count
94	AFTFCL DS H	First chain link
96	AFTFV DS C	A*3 Fixed(F)/variable(V) flag
97	AFTFB DS X	A*4 FST flag byte
98	AFTIL DS F	(Maximum) item length
9C	AFTDBC DS H	800-byte data block count
9E	AFTYR DS H	Year
A0	AFTADT DS F	Pointer to active disk table
A4	AFTPTR DS F	Pointer to next AFT block in chain
<u>Bit defined in AFTPTR</u>		
	AFTFSF EQU X'40'	Indicates in free storage
A8		DS OD End of DSECT
	AFTLB EQU *-AFTSECT	Length of AFT block in bytes
	AFTLD EQU AFTLB/8	Length of AFT block in doublewords

ANCHSECT: ANCHOR TABLE

ANCHSECT defines the DOS/VS anchor table. This DSECT is used by DMSDCS when a CDLOAD (SVC 65) is issued, and the phase is not found in either the CMSVSAM or CMSAMS segment. In this case, the specified phase is loaded either from a CMS DOSLIB or a DOS core image library, and the name, load point, entry point, and the length in bytes, of the phase are saved in an available slot in the anchor table. ANCHSECT is invoked by the ANCHTAB macro.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	ANCHENDA DC A(0)	End address of anchor table
4	DC F'0'	Reserved for IBM use
8	ANCHCBS DC A(0)	Pointer to VSAM AMCB table
C	ANCHOAL DC A(0)	Pointer to VSAM OAL (OPEN ACE) table, which is followed by one or more Anchor Table entries
10	ANCHPHNM DC CL8' '	Anchor Table Entries and Their Format
18	ANCHLDPT DC A(0)	Phase name
1C	ANCHENTP DC A(0)	Load point
20	ANCHSTSW DC X'00' A*1	Entry point Status switch
		<u>Bits defined in ANCHSTSW</u>
	ANCHMLOD EQU X'00'	Phase must be loaded
	ANCHINST EQU X'7F'	Phase is already in storage
	ANCHRPJL EQU X'FF'	Requested phase just loaded by another task (only if AP=YES)
	ANCHLENG EQU 20	Length of one anchor table entry
	ANCHSIZ EQU 1024	Default size of anchor table (in bytes)
21	ANCHPHLN DC AL3(0)	Length of phase in bytes

BATLSECT 146 BBOX

BATLSECT: CMS BATCH USER JOB LIMITS

BATLSECT describes the fields in the user job limits table for CMS batch jobs. The ABATLIMT field in NUCON points to BATLSECT.

0	BATCPUL		BATCPUC		BATPRTL		BATPRTC
8	BATPUNL		BATPUNC				

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	BATCPUL DC H'32767'	Virtual processor limit (in seconds); can be reset
2	BATCPUC DC H'0'	Current processor count; dc not reset
4	BATPRTL DC H'32767'	Number printed lines limit; can be reset
6	BATPRTC DC H'0'	Current line count; do not reset
8	BATPUNL DC H'32767'	Number punched cards limit; can be reset
A	BATPUNC DC H'0'	Current card count; do not reset

BBOX: BOUNDARY BOX

BBOX contains the begin and end addresses of the virtual and real partitions, respectively. The IJBBOX field in the SYSCOM block in the DOSCCN CSFCT of NUCON points to the BBOX block.

0	REALORP		REALNRP
8	VIRTORP		VIRTENDE

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	REALORP DS XL4	Origin of real partition
4	REALNDP DS XL4	End of real partition +1
8	VIRTORP DS XL4	Origin of virtual partition
C	VIRTENDP DS XL4	End of virtual partition +1

Equates for Fields in BBOX

ALTSDAR EQU	REALORP	Address of alternate area
MINREALP EQU	REALNDP	No. page frames in minimum real partition
MPGEPOOL EQU	REALNDP+2	No. page frames in main page pool
ORIGVIRT EQU	VIRTORP	Origin of virtual storage
FINVIRT EQU	VIRTENDP	End of virtual storage +1

BGCOM: DOS/VIS PARTITION COMMUNICATION REGION

BGCOM simulates the DOS/VS Partition Communication Region (BGCOM). The AEGCOM field in NUCON points to the BGCOM block.


0	JOBDATE			
8	PPBEG		EOSSP	
10				UPSI
18	COMNAME			
20	PPEND		HIPHAS	
28	HIPROG		LAELEN	PIK
30	EOCADR		A*1	A*2 A*3 A*4
38	A*5 A*6 A*7 A*8		DALC	FCCLPT
40	PUBPT		FAVPT	JIEPT TEEPT
48	FICLPT		NICLPT	LUEPT A*9
50	MMDD		YYDDD	
58	LIOCSCOM		PIEPT	CHKPTID JCBZON
60	DIBPT	//////////	PCPTR	ITPTR
68	OCPT		PWTIMS	////////// LTK
70	SYSPAR			
78	TODCOM		PIE2PTR	PDTAEB
80	IJLQTTAD		BGCCMPT	A*10 A*11
88	COMEX		A*12 A*13 A*14	
90	PROCNAME (cont. from 8F)			
98	POVNAM			
				A*16

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	JOBDATE	DC C'00/00/00' Job date
8	PPBEG	DC S(0) Supervisor end
A	EOSSP	DC S(0) End of storage protection
C		DC 11X'00' User scratch area
17	UPSI	DC X'00' UPSI byte
18	COMNAME	DC CL8'CMS/DOS' Job name
20	PPEND	DC A(0) Highest storage address of partition

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
24	HIPHAS	DC A(0) End address of last phase loaded
28	HIPROG	DC A(0) End address of longest phase loaded
2C	LABLEN	DC H'0' Length of problem program label area
2E	PIK	DC X'0010' Program interrupt key
30	EOCADR	DC A(0) End of virtual storage address
34	CONFIG	DC B'11101000' A*1 Machine configuration byte
35	LTACT	DC B'00010000' A*2 System configuration byte
36	SOB1	DC B'11000100' A*3 Standard language translator options
37	SOB2	DC B'11011010' A*4 Standard supervisor options
38	JCSW1	DC B'11010000' A*5 Job control byte
39	JCSW2	DC B'00000000' A*6 Linkage control byte
3A	JCSW3	DC B'11000100' A*7 Nonstandard language translator options
3B	JCSW4	DC B'10000000' A*8 Job duration indicator byte
3C	DALC	DC H'0' Disk address of volume label
3E	FOCLPT	DC S(0) Address of FOCL
40	PUBPT	DC S(0) Address of PUB
42	FAVPT	DC S(0) Address of FAVP
44	JIBPT	DC S(0) Address of JIB
46	TEBPT	DC S(0) Address of TEB
48	FICLPT	DC S(0) Address of FICL
4A	NICLPT	DC S(0) Address of NICL
4C	LUBPT	DC S(0) Address of LUB
4E	SYSLINE	DC AL1(56) A*9 SYSLST line count
4F	SYSDATE	DS OCL9 System date
4F	MMDD	DC XL4'00' MMDD or DDMM
53	YYDDD	DC XL5'00' YYDD portion of date
58	LIOCSCOM	DC 2X'00' LICCS communication bytes
5A	PIBPT	DC S(0) Address of PIB
5C	CHKPTID	DC H'0' Last checkpoint number
5E	JOBZON	DC S(0) Job zone in minutes
60	DIBPT	DC S(0) Background DIB pointer
62		DC H'0' Reserved for IBM use
64	PCPTR	DC S(0) PC option table
66	ITPTR	DC S(0) IT option table
68	OCPT	DC S(0) OC option table
6A	PWTIMS	DC X'0000' Key of program with IT support
6C		DC H'0' Reserved for IBM use
6E	LTK	DC S(0) Logical transient key
70	SYSPAR	DC F'0' Address of SYSPARM
74	JAPART	DC F'0' Address of job accounting table
78	TODCOM	DC A(0) Address of TOD communications area
7C	PIB2PTR	DC S(0) Address of PIB extension
7E	PDTABB	DC S(0) Address of MICR DTF table
80	IJLQTTAD	DC A(0) Address of QTAM vector table
84	BGCOMPT	DC S(0) Address of background COMREG
86	OPTNBYTE	DC X'00' A*10 Option indicator byte
87	RMSROPEN	DC B'00000000' A*11 System configuration byte 2
88	COMEX	DC A(0) Pointer to SYSCOM option table
8C	STDOPTR	DC B'01000000' A*12 Standard job control option byte
8D	TEMOPTR	DC B'01000000' A*13 Temporary job control option byte
8E	DISKCONF	DC X'00' A*14 Disk configuration byte
8F	PROCNAM	DC CL8' ' Procedure name
97	PSWTCH	DC X'0' A*15 Interface byte for catalog procedure
98	POVNAM	DC CL7' ' Save area for statement name
9F	INSIZE	DC X'0' A*16 81-byte SYSIN indicator

CMSTAXE: TERMINAL ATTENTION EXIT ELEMENT

CMSTAXE defines the fields used in a Terminal Attention Exit Element (TAXE). The TAXE is used mainly by DMSCIT for processing attention interrupts. CMSTAXE is invoked via the TSOBLKS macro. The TAXFADDR field in NUCON points to CMSTAXE.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TAXESPSW DS	1F Left half PSW for ATTN return
4	TAXEEEXIT DS	A ATTN exit address
8	TAXESTAT DS	0X Status of exit return
	TAXEFREQ EQU X'80'	ATTN exit taken
8	TAXELNK DS	A Next TAXE on queue
C	TAXEICL DS	1F Left half of I/O old PSW
10	TAXE TSOF DS	1F TSO flags saved here
14	TAXERTNA DS	A Return address
18	TAXEEEXTS DS	18F ATTN exit routine save area
60	TAXEICWS DS	11F DMSICW save area
	<u>Also Attention Exit Parameter List</u>	
8C	TAXETAIE DS	A Address of TAIE
90		DS 1F Reserved for IBM use
94	TAXEDEF DS	0X Defer indicator
94	TAXEUSER DS	A User PLIST address
	<u>Terminal Attention Interrupt Element (TAIE)</u>	
98	TAIEMSGL DS	2X Reserved for IBM use
9A	TAIETGET DS	1X A*1 Reserved for IBM use
9B		DS 1X Reserved for IBM use
9C	TAIEIAD DS	A Right half cf I/O old PSW
A0	TAIERSAV DS	16F Registers 0-15 of interrupted program

CVTSECT

CVTSECT: COMMUNICATION VECTOR TABLE AS SUPPORTED BY CMS

CVTSECT simulates the OS Communication Vector Table. CVTSECT is invoked via the CMSCVT macro. The ACMSCVT field in NUCON points to CMSCVT.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0		Reserved for IBM use
2	CVTMDL	Processor identification and model number
4		CMS release number (latest release level)
8	CMSCVT	CVT start
8		Not supported
40	CVTDATE	Current date in packed decimal
44		Not supported
50		Not supported
54		Not supported
58	CVTEXIT	A SVC 3 instruction (exit)
5A	CVTBRET	A BCR 15,14 instruction
5C		Not supported
7C	CVTDCB	System configuration = PCP
7D		Not supported
80	CVTR13	R13 saved during OPEN
84		Not supported
88	CVTNUCB	Lowest storage address not in nucleus
8C		Not supported
AC	CVTMZ00	Highest storage address in machine
B0		Not supported
BC		Not supported
BE	CVTOPTA	Bit 7: extended precision floating point hardware in processor
C0		Not supported
C8		Not supported
D4	CVTUSER	Field available to user
D8		Not supported
108	CVTAVIB	Address of VSAM interface bootstrap

DEGSECT

DEGSECT: DEBUG WORK AREA

DEGSECT contains the files used by DEBUG for saving registers, breakpoints, PSWs, and other data. V-constants in DMSDBD, DMSDBG, and LMSITE point to the DEBUG wcrk area.



tr


DEGSECT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>ENTRY DBGSECT</u>		
0	CCWPRINT CCW	X'09',0,SILI,133 Printer CCW for DEBDUMP
8	SYMTABLE DS	32D User-defined symbol table
108	SYMTBG DC	F'0' Symbol table entries
10C	BRKPNTBL DC	16F'0,-1' Breakpoint table
18C	TBLEND DC	A(TBLEND) End address of breakpoint table
<u>Storage and Constants for NEWLIN and Control</u>		
190	DS	0D
190	ARGS DS	5D Arguments stored here
	MVCNT1 EQU	*--ARGS Number of bytes in arguments
	MVCNT EQU	MVCNT1-8 Needed for SET GPR command
	ARGMAX EQU	*
		End of argument area
1B8	JFLAGS DS	6X Flags corresponding to arguments. There is one flag for each parameter, as follows:
		00 = Numeric (0 - 9)
		F0 = Hexadecimal (A - F, 0 - 9)
		FF = Alphabetic (A - F)
1BE	ARGSCT DS	1X A*1 Number of arguments in command line
	MVCNT2 EQU	*--ARGS For initializing to zero
1C0	DS	0D
1C0	WAITRD DC	CL8'WAITRD'
1C8	DC	A(INPUT)
1CC	DC	C'U'
1CD	DC	X'00'
1CE	WTRDCNT DC	H'0'
		Byte count filled in here
1D0	ORG DC	F'0' Origin of routine being examined
<u>The Following Variables Are Used by DEBUG and DEBDUMP</u>		
1D8	DEC DS	1D Binary word
1E0	DECDEC DS	1D Decimal word
1E8	ARGSAV DS	1F Storage for argument location
1EC	RETSAV DS	1F Storage for return address
1F0	EXAMLC DS	1F First location to be examined
1F4	EXAMLG DS	1F Length of field to be examined
1F8	BEGAT DS	1F Beginning parameter being processed
1FC	STOPAT DS	1F Last parameter location
	LASTLINE EQU	DECDEC 32 bytes for last line dumped
200	SAVE1 DS	1F DEBDUMP uses this area for line count
204	SAVE2 DS	1F
208	DBGSAV1 DS	16F DEBUG BALR-call save
248	DBGSAV2 DS	16F Save area for CONWAIT/CONREAD

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
288	TSYM	DS	4F	Symbol entry
298	XPSW	DS	1D	Execution PSW
2A0	OUTPT1	DC	1C' '	A*2 Byte count
2A1	LINE	DC	CL11' '	I/O buffer
2AC	LINE1	DC	87X'40'	Filler bytes
303	LINE1B	DC	C'*'	A*3 Filler bytes
304	LINE1A	DC	32X'40'	Filler bytes
324	LINE1C	DC	C'*'	A*4 Filler bytes
325	LINE1D	DC	X'40'	A*5 Filler bytes
	DBGOUT	EQU	LINE	Output buffer
	INPUT	EQU	LINE	Input buffer
	INPUT1	EQU	LINE+60	Hexadecimal pack area
328	CONWR	DS	0D	PLIST for DMSCWR to type output line
328		DC	CL8'TYPLIN'	PLIST continued
330		DC	AL1(1), AL3(DBGOUT)	PLIST continued
334		DC	CL1'B', AL2(0)	PLIST continued
337	CONWRL	DC	AL1(0) A*6	PLIST continued
338	INPUTSIZ	DS	1H	Size of typed-in input line
33A		DS	1H	Reserved for IBM use
33C		DC	F'0'	
340	CONHCT	DC	X'FAFBFCFDFF0000'	Translate table
348	HEX	DS	1F	Binary word
34C		DC	X'FFFFFFF'	Fence
350	HEXHEX	DS	2F	Printer graphic word
358		DC	X'FF'	Extra translate byte
359	BITS	DC	X'C0C0C0C0C0C0C0C0'	Scratch word
361		ORG	*+14	Translate table
36F		DC	C'0123456789'	Translate table
379		DC	C'ABCDEF'	Translate table
	CONHXT	EQU	CONHCT-C'A'	
37F	DBGSWTCH	DC	X'00'	A*7 Internal DEBUG status flags
	<u>Bits defined in DBGSWTCH</u>			
			X'80'	Reserved for IBM use
			X'40'	Reserved for IBM use
	DBDEXIT	EQU	X'20'	Exit from DEBDUMP
	DBDDMSG	EQU	X'10'	Duplicate message in DEBDUMP
	DBGSET	EQU	X'08'	SET command
	DBGPERM	EQU	X'04'	Reserved for IBM use
	DBGCOND	EQU	X'02'	Reserved for IBM use
	<u>The Following are Reserved for IBM Use</u>			
380	YPSW	DS	D	PSW containing NSI
388	TBLINDX	DS	F	Current BRKPT table index
38C	BCR	NOPR	0	NOPR to pad DBGXWK when needed
38E		NOPR	0	Additional NOPR (if needed)
390	ILC	DS	1C	A*8 ILC cf instruction in DBGXWK
391	ILC11	DC	X'06'	A*9 3 halfword instructions (6 bytes)
392	ILC0110	DC	X'04'	A*10 2 halfword instructions (4 bytes)
393	ILC00	DC	X'02'	A*11 1 halfword instructions (2 bytes)
	BAL	EQU	X'45'	BAL operation code
	BALR	EQU	X'05'	BALR operation code
394	DBGXWK	DS	3H	Re-create instruction at BRKPT address
39A	LPSW	48		Give control to NSI

DEVSECT**DEVSECT: DEVICE TABLE DSECT**

DEVSECT describes the device information required for input/output routines. DEVSECT is a DSECT corresponding to the data in a DEVTAB entry.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DEVADDR	DS 1H Virtual device address
2	DEVFLAG	DS 1X D*1 Device flags
3	DEVTYPE	DS 1X D*2 Device type
4	DEVNAME	DS 1F Symbolic device name
8	DEVIPRA	DS 1F Interrupt processing routine address
C	DEVMISC	DS 1F Miscellaneous -- device dependent
	DEVSIZE EQU *-DEVSECT	Device table size (in bytes)

DEVTAB: DEVICE TABLE

DEVTAB contains the entries for the various devices handled by CMS (disks, tapes, reader, punch, printer, and cconsole). DEVTAB is pointed to by V-constants in DMSICW and DMSITI, and is also referenced indirectly by the ADEVTAE field in NUCON.

0	CONSOLE	B0	READER1
10	ADISK	C0	PUNCH1
20	BDISK	D0	PRINTER1
30	CDISK	E0	READER2
40	DDISK	F0	PUNCH2
50	EDISK	100	PRINTER2
60	FDISK	110	TAPE1
70	GDISK	120	TAPE2
80	SDISK	130	TAPE3
90	YDISK	140	TAPE4
A0	ZDISK	150	DUMMY

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CONSOLE	Device table entry for console
0	DS	OD
2	DC	XL2'009'
4	DC	XL2'0'
8	DC	CL4'CON1'
C	DC	VL4(CONSI)
	DC	XL4'0'
10	ADISK	Device table entry for A-disk
10	DS	OD
12	DC	XL2'191'
14	DC	XL2'0'
18	DC	CL4'DSK1'
1C	DC	AL4(0)
	DC	XL4'0'
20	BDISK	Device table entry for B-disk
20	DS	OD
22	DC	XL2'000'
24	DC	XL2'0'
28	DC	CL4'DSK2'
2C	DC	AL4(0)
	DC	XL4'0'
30	CDISK	Device table entry for C-disk
30	DS	OD
32	DC	XL2'000'
	DC	XL2'0'

DEVTAB


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning	
34	DDISK	DC	CL4'DSK3'
38		DC	AL4(0)
3C		DC	XL4'0'
40		DS	OD
40		DC	XL2'192'
42		DC	XL2'0'
44		DC	CL4'DSK4'
48		DC	AL4(0)
4C		DC	XL4'0'
50		DS	OD
50	EDISK	DC	XL2'000'
52		DC	XL2'0'
54		DC	CL4'DSK5'
58		DC	AL4(0)
5C		DC	XL4'0'
60	FDISK	DS	OD
60		DC	XL2'000'
62		DC	XL2'0'
64		DC	CL4'DSK6'
68		DC	AL4(0)
6C	GDISK	DC	XL4'0'
70		DS	OD
70		DC	XL2'000'
72		DC	XL2'0'
74		DC	CL4'DSK7'
78	SDISK	DC	AL4(0)
7C		DC	XL4'0'
80		DS	OD
80		DC	XL2'190'
82		DC	XL2'0'
84	YDISK	DC	CL4'DSK8'
88		DC	AL4(0)
8C		DC	XL4'0'
90		DS	OD
90		DC	XL2'19E'
92	ZDISK	DC	XL2'0'
94		DC	CL4'DSK9'
98		DC	AL4(0)
9C		DC	XL4'0'
A0		DS	OD
A0	READER1	DC	XL2'000'
A2		DC	XL2'0'
A4		DC	CL4'DSK0'
A8		DC	AL4(0)
AC		DC	XL4'0'
B0	PUNCH1	DS	OD
B0		DC	XL2'00C'
B2		DC	XL2'0'
B4		DC	CL4'RDR1'
B8		DC	AL4(0)
BC	PRINTER1	DC	XL4'0'
C0		DS	OD
C0		DC	XL2'00D'
C2		DC	XL2'0'
C4		DC	CL4'PCH1'
C8	PRINTER1	DC	AL4(0)
CC		DC	XL4'0'
D0		DS	OD
D0		DC	XL2'00E'
D2		DC	XL2'0'
D4	PRINTER1	DC	CL4'PRN1'
D8		DC	AL4(0)
DC		DC	XL4'0'

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
E0	READER2	Device table entry for READER2
E0	DC	XL2'012'
E2	DC	XL2'0'
E4	DC	CL4'RDR2'
E8	DC	AL4(0)
EC	DC	XL4'0'
F0	PUNCH2	Device table entry for PUNCH2
F0	DC	XL2'013'
F2	DC	XL2'0'
F4	DC	CL4'PCH2'
F8	DC	AL4(0)
FC	DC	XL4'0'
100	PRINTER2	Device table entry for PRINTER2
100	DS	OD
102	DC	XL2'010'
104	DC	XL2'0'
108	DC	CL4'PRN2'
10C	DC	AL4(0)
110	DC	XL4'0'
110	TAPE1	Device table entry for TAPE1
110	DS	OD
112	DC	XL2'181'
114	DC	XL2'0'
118	DC	CL4'TAP1'
11C	DC	AL4(0)
120	DC	XL4'0'
120	TAPE2	Device table entry for TAPE2
122	DS	OD
124	DC	XL2'182'
128	DC	XL2'0'
12C	DC	CL4'TAP2'
130	DC	AL4(0)
130	DC	XL4'0'
130	TAPE3	Device table entry for TAPE3
132	DS	OD
134	DC	XL2'183'
138	DC	XL2'0'
13C	DC	CL4'TAP3'
140	DC	AL4(0)
140	DC	XL4'0'
142	TAPE4	Device table entry for TAPE4
144	DS	OD
144	DC	XL2'184'
148	DC	XL2'0'
14C	DC	CL4'TAP4'
150	DC	AL4(0)
150	DUMMY	Device table entry for DUMMY
152	DS	OD
154	DC	XL2'000'
158	DC	XL2'0'
15C	DC	CL4'XXXX'
160	TABEND	Device table entry for TABEND
	DS	OD

DIOSECT

DIOSECT: DISK I/O WORK AREA

DIOSECT describes the fields used by DMSDIO as a work area when reading and writing actual blocks of data on CMS disks. DIOSECT is pointed to by a V-constant in DMSNUC, and referenced indirectly by ADIOSECT in NUCON.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DIOSECT	DSECT
0	IOOLD	DC 1D'0'
8	DIOCSW	DC 1D'0'
		I/O cld PSW (from interrupt routine)
		CSW (from interrupt routine)
10	<u>PLIST To Call DMSIOW</u>	
10	DS	OF
10	PWAIT	DC CL8'WAIT'
18		DC C'DSK-'
1C		DC F'0'
20		DC F'0'
24	QQDSK1	DC F'0'
		First two bytes are always 0
	QQDSK2	EQU QQDSK1+2
		Halfword copy of 16th track disk address
	<u>CCW Chain</u>	
28	CCW1	CCW X'07',SEEKADR,X'40',6
30	CCW1A	CCW X'03',0,X'40',1
38	CCW2	CCW X'31',SEEKADR+2,X'40',5
40	CCW3	CCW X'08',*-8,0,1
48	RWCCW	CCW X'00',**-,X'20',**-
		Seek
		Seek or set sector
		Search
		TIC back to search
		Read or write data
50	SEEKADR	DC XL7'00'
		Seek/search information (first 3 bytes are 0)
57	SECTNUM	DC X'00'
		Sector number
	<u>I/O Information</u>	
58	LASTCYL	DC F'0'
5C	LASTHED	DC F'0'
		Becomes last cylinder number used
		Becomes last head number used
60	DEVTYP	DC X'00'
		A*1 01=2311, 08=2314, 09=3330
61	DIOFLAG	DC X'00'
		A*2 RDTK/WRTK flag:
	<u>Bits defined in DIOFLAG</u>	
	TOOBIG	EQU X'04'
	WRTKF	EQU X'02'
	QQTRK	EQU X'01'
		Byte count is greater than 800
		Writing first chain link
		Handling first chain link
	DIAGNUM	EQU 24
		Number assigned by CP for DIAGNOSE I/O
62	SENSB	DC XL24'00'
7C		DS OF
80	SENCCW	CCW X'04',SENSB,X'20',24 READ 24 BYTES SILL
	<u>Miscellaneous Storage</u>	
88	DOUBLE	DC 1D'0'
		(Scratch area, for CVD use, etc.)
	<u>Keep the Following Three in Order</u>	
90	XRSAVE	DS 15F
CC		Registers 0-14 saved here for RDTK/WRTK
CF	ERRCODE	DC AL3(0)
		First 3 bytes of R15 error code
		Errcor code (in R15 at exit)
	<u>Keep the Following Two in Order</u>	
D0	FREERO	DC F'0'
D4	DIOFREE	DC F'0'
		No. of doublewords of free storage (if any)
		Address of free storage for buffer or CCWs
D8	SAVEADT	DC F'0'
E0	CCWX	CCW X'23',SECTNUM,X'40',1
		Set sector
E8	DIAGRET	DC X'00'
		A*3 CP's DIAGNOSE return code if nonzero
E9	IOCOMM	DC X'00'
		A*4 Set to read (06) or write (05)
EA	LASTREC	DC X'00'
		A*5 Number (1-14) of the last record processed

DMSCCB: COMMAND CONTROL BLOCK

DMSCCB describes all fields of a DOS Command Control Block (CCB). This ESELECT is used by DMSXCP to map the CCB specified by a user for an SVC 0 (EXCP) and passes the address of CCB to DMSXCP.

0	CCBCNT		A*1		A*2		A*3		A*4		A*5		A*6
8	A*7		CCBCCW				A*8		CCECSW				
10		CCBLDATB							CCBLCCWE				
18							A*9		CCEFSCCW				
20		CCBRDCCW							CCBWTCCW				
28		CCBLWCCW											
30													
38		CCBNCCB											

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
	CCBST EQU *	Start CCB
	CCBD EQU *	Command control block
0	CCBLEN DS 0CL16	Map of the DOS CCB
0	CCBCNT DS XL2	Residual count
2	CCBERMAP DS 0XL4	Four bytes used to check errors
2	CCBCOM1 DS XL1 A*1	Communications byte 1
	<u>Bits defined in CCBCOM1</u>	
	CCBWAIT EQU X'80'	Traffic bit (set at CE)
	CCBEOF EQU X'40'	End of file
	CCBIOERR EQU X'20'	Unrecoverable I/O error
	CCBERROK EQU X'10'	Accept unrecoverable error
	CCBRDC EQU X'08'	Return data checks
	CCBPDE EQU X'04'	Post at device end
	CCBDCV EQU X'02'	Return data check RD/CHK
	CCBUERR EQU X'01'	User error routine
3	CCBCOM2 DS XL1 A*2	Communications byte 2
	<u>Bits defined in CCBCOM2</u>	
	CCBDCCNT EQU X'80'	Data check in count area
	CCBTRKOV EQU X'40'	Track overrun
	CCBEOC EQU X'20'	End of cylinder
	CCBDC EQU X'10'	Data check
	CCBNOREC EQU X'08'	No record found
	CCBRETRY EQU X'04'	Retry no record found
	CCBVER EQU X'02'	Verify error
	CCBCC EQU X'01'	Command chain (retry)

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
4	CCBCSW1	DS XL1	A*3 CSW status bit 1
			<u>Bits defined in CCBCSW1</u>
	CCBATTN	EQU X'80'	Attention
	CCBSTMOD	EQU X'40'	Status modifier
	CCBCUE	EQU X'20'	Control unit end
	CCBBUSY	EQU X'10'	Busy
	CCBCE	EQU X'08'	Channel end
	CCBDE	EQU X'04'	Device end
	CCBUC	EQU X'02'	Unit check
	CCBUE	EQU X'01'	Unit exception
5	CCBCSW2	DS XL1	A*4 CSW status bit 2
			<u>Bits defined in CCBCSW2</u>
	CCBPCI	EQU X'80'	Program-controlled interrupt
	CCBILEN	EQU X'40'	Incorrect length
	CCBPROGM	EQU X'20'	Program check
	CCBPROT	EQU X'10'	Protection check
	CCBCHAND	EQU X'08'	Channel data check
	CCBCHANC	EQU X'04'	Channel control check
	CCBICTRL	EQU X'02'	Interface control check
	CCBCHAIN	EQU X'01'	Chaining check
6	CCBSYMU	DS 0XL2	Symblic unit (SYSUN)
6	CCBSUCLS	DS XL1	A*5 U - LUB class
7	CCBSUNUM	DS XL1	A*6 N - LUB number within class
8	CCBLIOBS	DS XL1	A*7 Reserved for LICBS
9	CCBCCW	DS XL3	Pointer to start of channel program
C	CCBCOM3	DS XL1	A*8 Communication byte 3
	CCBAPEND	EQU X'40'	Appendage exit at interrupt
D	CCBCSW	DS XL3	Pointer to CSW or to appendage routine
10	CCBLDATB	DS A	Address of last data block
14	CCBLCCWB	DS A	Address of last CCW block
18		F	Reserved for IBM use
1C	CCBUFLGS	DS X	A*9 I/O manager CCB flags
			<u>Bits defined in CCBUFLGS</u>
	CCBUEAIC	EQU X'80'	Error analysis in control
	CCBUEAC	EQU X'40'	Error analysis complete
	CCBURDCW	EQU X'20'	Read CCW active
	CCBRPS	EQU X'10'	RPS channel program candidate
1D	CCBFSCCW	DS XL3	Save area for first CCW address
20	CCBRDCCW	DS F	Address of first read CCW
24	CCBWTCCW	DS F	Address of first write CCW
28	CCBLWCCW	DS F	Address of the last write CCW
2C		3F	Reserved for IBM use
			<u>Note:</u> CCBLWCCW chain field must have the same displacement as does FCBCCHAIN in FCDB and also BKPFSTBK in BKPRD
38	CCBNCCB	DS A	Address of next CCB block
3C		F	Reserved for IBM use

DOSSECT

DOSSECT: DOS SIMULATION CONTROL BLOCK

DOSSECT simulates the CMS File Control Block (FCB) in the CMS/DOS environment. **DOSSECT** is invoked by the **DOSCBL** macro.

The DOS Simulation Control Blocks are chained together. The DOSFIRST field in NUCCN points to the first DOSCB in the chain, or if no chain exists, contains zero.

0	DOSNEXT		DOSCBIID
8	DOSDD		
10	DOSOP		
18	DOSDSNAM		
20	DOSDSTYP		
28	DOSDSMD	DOSITEM	DOSBUFF
30	DOSBYTE	DOSFORM	DOSCOUT
38	DOSREAD	A*1	A*2 DOSBLKSZ
40	DOSWORK		
48	A*3 A*4 A*5 A*6		DOSCSFST
50	DOSOSDSN		DOSVOLTE
58	DOSEXTTB	DOSSENSE	A*7 A*8
60	DOSBUFSP		DOSUCNAM
68	DOSUCNAM (cont.)		
	DOSSAVE		
80		A*9 A*10 ////////////////	

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DOSINIT DS 0X	DOSCE flag byte
Bits defined in DOSINIT		
	DOSOS EQU X'40'	OS user-created bit
	DOSDOS EQU X'20'	Defined for non-CMS disk
	DOSCMS EQU X'10'	Defined for CMS disk
	DOSDDCAT EQU X'08'	User catalog data set
	DOSPERM EQU X'04'	Permanent control block
	DOSJCAT EQU X'02'	Search VSAM job catalog
	DOSUCAT EQU X'01'	Search VSAM user catalog
0	DOSNEXT DS A	AL3(next DOSCB)
4	DOSCBID DS CL4	DLBL to distinguish from CMSCB
8	DOSDD DS CL8	Data definition name
10	DOSOP DS CL8	CMS operation
18	DOSTAPID DS 0X	Tape identification
18	DOSDSNAM DS CL8	Data set name
20	DOSDSTYP DS CL8	Data set type
28	DOSDSMD DS CL2	Data set mode
2A	DOSITEM DS H	Item (record) number
2C	DOSBUFF DS F	A(input/output buffer)
30	DOSBYTE DS F	Size of buffer (data count)
34	DOSFORM DS CL2	File format: fixed/variable
36	DOSCOUT DS H	Records per CMS physical block
38	DOSREAD DS F	Number of bytes actually read
3C	DOSDEV DS X	Device type code
Bits defined in DOSDEV		
	DOSDUM EQU 0	Dummy device
	DOSDSK EQU 20	Disk
3D	DOSTAPMD DS X	A*2 Tape mode set to save
3E	DOSBLKSZ DS H	Block size
40	DOSWORK DS D	Work area
48	DOSYSXXX DS 0H	Logical unit for CMS/DOS
48	DOSSYS DS 1X	A*3 SYS/PROG unit: X'00'=SYS, X'01'=PROG
49	DOSXXX DS 1X	A*4 Number from 000-255 associated with the unit
4A	DOSEXT DS 1X	A*5 Number of DCS extents left to process
4B	DOSEXTCT DS 1X	A*6 Current DOS extent
4C	DOSOSFST DS F	Pointer to CS FST
50	DOSOSDSN DS F	Pointer to CS dname block
54	DOSVOLTB DS F	A(volume ID table)--VSAM multivolume data set
58	DOSEXTTB DS F	A(extent table) for VSAM data space
5C	DOSSENSE DS H	I/O sense data
5E	DOSVOLNO DS X	A*7 No. of volumes (entries in DOSVOLTB)
5F	DOSEXTNO DS X	A*8 No. of extents (entries in DOSEXTTB)
60	DOSBUFSP DS F	Size of VSAM I/C buffer(s)
64	DOSUCNAM DS CL8	VSAM user catalog ddname
6C	DOSSAVE DS 6F	Temporary save area for re-entrant code
84	DOSEXTCX DS 1X	A*9 Current extent (used by DMSXCF)
85	DOSTYPE DS 1C	A*10 Data set type (SAM=S, VSAM=A)
86	DS H	Reserved for IBM use
88	DOSEND DS 0D	End address of this block
	DOSENSIZ EQU (*-DOSSECT)/8	Size of block in doublewords

EDCB

EDCB: EDIT CONTROL BLOCK

EDCB is used by all CMS EDIT modules to define common free storage control blocks. It is initialized by DMSEDIX, the EDIT bootstrap routine, and built dynamically from user free storage each time a user issues the EDIT command.

0	FNAME					
8	FTYPE					
10	FMODE	A*1	A*2	TRUNCOL ZONE1		
18	ZONE2	VERCOL1	VERCOL2	VERLEN		
20	SCRBUFAD			CARDINCR		
28	LMSTART	LMINCR	A*3	A*4		
.	TABS					
.	.					
48	SEQNAME	A*5	PADBUF			
50	PADBUF (cont.)					
58	PTR1					
60	PTR2		PTR3			
68	AEXTEND		CORITEM			
70	SPARES		FPTR			
78	ITEM		AFSTFNRD			
80	FREELEN		FREEAD			
88	EDRET		EDMSK			
90	MAINAD					
.	AUTOREG					
.	.					
C8	CARDNO		COUNT			
D0	LMCURR					
D8	BUFFL		BUFFA			
E0	CANSAV					
.	.					
.	.					
100	DUALNOS					

DUALNOS (cont.)

1F8	DECIMAL		HALF
200	REGSAVE		
210			
218	REGSAVX		
220	REPCNT		
	SAVEAR		
260	KYCNT		CHNGNUM
268	TIN		
270		AEDLIN	A*6
278	TOUT		
280			A*7
288	IOLIST		
290	IOID		
298			
2A0	IOMODE		IOAL
2A8	RECS		
2B0		ALILIST	
2B8	ALTLIST (cont.)		EDWORK
2C0	EDWORK (cont.)		
2C8		ALTMODE	
2D0	ALTMODE (cont.)		
.			
.			
.			
2F0			STACKAT
2F8	STACKAT (cont.)		
300	STACKATL		ATIN

308	ATTN (cont.)	
310	ATTNLEN	RENLIST
318	RENLIST (cont.)	RPLIST
320		RPLIST
328	STRTNO	INCRNO
330	AINCORE	FSIZE
338		DECLTH
340		RANGE
348	RESVD1	
350	A*8 BUFAD	A*9 A*10 WRCOUNT
358	BUFFLOC	ALINELOC
360	ANUMLOC	AFLAGLOC
368	TRNCNUM	AUTOCNT AUTOCURR
370	CHNGCNT DITCNT	EECT LINELOC
378	NUMLOC SAVCNT	TVERCOL1 TVERCCL2
380	A*11 A*12	AREA
388	AREA (cont.) A*13 A*14	CHNGMSG
3A0		CHGTRUNC
3A8		(unidentified)
3B0	CMODE	
3C0		FILEMS
	.	
	.	
	.	
		A*15 A*16
3D8	A*17	
	.	JAR
	.	
	.	
		NEWNAME
428	NEWNAME (cont.)	NEWTYPE
430	NEWTYPE (cont.)	NEWMODE A*18
438	SERSAV (cont.)	A*19

440 SERTSEQ (cont) | A*20 | A*21 |

448 .

. . .

460 A*24 | A*25 | SCLNO

468 SCLNO (ccnt.) | A*26 | A*27 | XAREA |

. . .

(Same length as ELLIN)

. . .

4F8 YAREA

. . .

580 . . . | A*28 |

588 XXXCWD

590 SAVCWD

598 INVLDHDR | MACROHDR

5A0 MACROHDR (cont) | INVLD | MACRC

5A8 . . .

5B0 EDLIN

. . .

630 LINENO | A*29 |

. . .

LINE

. . .

6D8 A*30 |

. . .

TABLIN

. . .

Hexadecimal Displacement	Field Name	DS	OF	Field Description, Contents, Meaning
	BLOC	EQU	*	
0	FNAME	DS	CL8	Filename
8	FTYPE	DS	CL8	Filetype
10	FMODE	DS	CL2	Filemode
12	FV	DS	CL1	A*1 Record format
13	CASESW	DS	CL1	A*2 Case setting
14	TRUNCOL	DS	H	Truncation column
16	ZONE1	DS	H	Beginning zone initialized to first column
18	ZONE2	DS	H	End zone
1A	VERCOL1	DS	H	Verify column 1
1C	VERCOL2	DS	H	Verify column 2
1E	VERLEN	DS	H	Verify length
20	SCRBUFAD	DS	F	Address of GETMAIN buffer
24	CARDINCR	DS	F	Increment for serialization
28	LMSTART	DS	H	Where line numbers start
2A	LMINCR	DS	H	Automatic line numbers using default increment
2C	FLAG	DS	CL1	A*3 Flags for line monitoring
2D	FLAG2	DS	CL1	A*4 Miscellaneous flags
2E	TABS	DS	26AL1	Maximum of 25 tabs is allowed
	ENDTABS	EQU	*	End of tabs
48	SEQNAME	DS	CL3	
4B	PADCHAR	DS	CL1	A*5 '0' on right, ' ' on left
	ENDBLOC	EQU	*	End of blocks
	<u>Note:</u> PADBUF must remain directly behind PADCHAR			
4C	PADBUF	DS	9C	Pad characters
	PTRCONS	EQU	*	DMSFII line pointers
58	PTR1	DS	2F	Pointer to top of file (for dummy top line)
60	PTR2	DS	F	Current line pointer
64	PTR3	DS	F	Pointer to bottom line
68	AEXTEND	DS	F	Pointer to end of used area of storage
6C	CORITEM	DS	F	Number of bytes for one line in storage
70	SPARES	DS	F	Number of spare lines
74	FPTR	DS	F	Free list pointer
78	ITEM	DS	F	Item length
7C	AFSTFNRD	DS	F	Anchor for stacked lines upon entry
80	FREELEN	DS	F	Length of free storage
84	FREEAD	DS	F	Address of free storage
88	EDRET	DS	F	CMS return address
8C	EDMSK	DS	F	DMSSCR edit mask
90	MAINAD	DS	F	LOADSYS address; 0 if LOADMCD
	EPTRCONS	EQU	*	DMSFII save areas and buffer pointers
94	AUTOREG	DS	13F	
C8	CARDNO	DS	F	Autocheck save area
CC	COUNT	DS	F	Save area for sequence number
D0	LMCURR	DS	2F	Number of characters in EDLIN
D8	BUFFL	DS	F	Prompter current line number
DC	BUFFA	DS	F	Length of string (EDC)
E0	CANSAV	DS	9F	Address of string (EDC)
104	DUALNOS	DS	CL240	Register save (EDC)
1F8		DS	OD	Temporary string buffer (EDC)
1F8	DECIMAL	DS	F	Used by DECEIN and BINDEC

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
1FC	HALF	BINDEC only edits four characters
200	REGSAV	DS 5F Register save area
214	REGSAVX	DS 3F Register save area
220	REPCNT	DS F FOR count
224	SAVEAR	DS 15F DMSSCR save area
260	XYCNT	DS F X or Y execution count
264	CHNGNUM	DS F Number of lines to change
268	TIN	DS OF WAITRD PLIST
268		DS CL8 WAITRD
270		DS X '1' for console No. 1
271	AEDLIN	DS 3X A(EDLIN)
274	CASEREAD	DS C A*6 Default to uppercase
275		DS 3X Length put here
278	TOUT	DS OF TYPLIN PLIST
278		DS CL8 TYPLIN
280		DS X '1' for console No. 1
281		DS 3X Address goes here
284		DS C 'B' for black ribbon
285	TYPFLG	DS X A*7 X'20' maximum length override
286		DS H Length goes here
	CRBIT	EQU X'80' Suppress carriage return
288	IOLIST	DS OF Initialization for state of source
288		DS CL8 STATE
290	OID	DS CL8 EDIT
298		DS CL8 CMSUT1
2A0	IOMODE	DS CL2 A1
2A2		DS H Item number for RDBUF
2A4	IOAD	DS CL4 Do not allow asterisks
2A8		DS F 133 (XINSCRIPT use LINE)
2AC		DS CL2 F/V and null record indicator
2AE	RECS	DS H 1 (XINSCRIPT one line at a time)
2B0		DS F Number of bytes read from RDBUF
2B4	ALTLIST	DS OF RENAME
2B4		DS CL8 EDIT
2BC	EDWORK	DS CL8 CMSUT1
2C4		DS CL8 A1
2CC	ALTMODE	DS CL8 New filename
2D4		DS CL8 New filetype
2DC		DS CL8 '**'
2E4		DS CL2 New filemode
2E6		DS CL6 FF fence
2EC		DS 8X PLIST to stack first in first out
2F4	STACKAT	DS OF ATTN
2F4		DS CL8 First in first out
2FC		DS CL4 Length and address of line to stack
300	STACKATL	DS F ATTN
304	ATTN	DS OF Last in first out
304		DS CL8 Length and address of line to stack
30C		DS CL4 RENLIST
310	ATTNLEN	DS F RENUM PLIST
314	RENLIST	DS OF RENUM
314		DS CL8 Fileid
31C	RPLIST	DS CL12 Starting number
328	STRTNO	DS F Increment number
32C	INCRNO	DS F In-storage copy address
330	AINCORE	DS F Record length
334	FSIZE	DS D DMSSCR work area
338	DECLTH	DS D Message data areas
340	RANGE	DS D Reserved for IBM use
348	RESVD1	DS D A*8 X'19'
350	CMDBLOK	DS X BUFAD
351		DS 3X Buffer address
354	FLG	DS X A*9 CCW flag

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
355	CTL	DS	X	A*10 Control byte
356	WRCOUNT	DS	H	Write count
358	GIOPLIST	DS	OF	DMSSCR PLIST for DMSGIO
358	BUFFLOC	DS	F	Buffer location
35C	ALINELOC	DS	F	Address of line location
360	ANUMLOC	DS	F	Address of number location
364	AFLAGLOC	DS	F	Address of flag location
368	TRNCNUM	DS	F	Number of lines truncated
36C	AUTOCNT	DS	H	Autosave parameter
36E	AUTOCURR	DS	H	Current modification count
370	CHNGCNT	DS	H	Temporary area for change
372	DITCNT	DS	H	Count of lines stacked by the REUSE (=) subroutine
374	EDCT	DS	H	Next char in EDLIN
376	LINELOC	DS	H	Display line number
378	NUMLOC	DS	H	Display count
37A	SAVCNT	DS	H	Length of last saved request not beginning with either a ? or =
37C	TVERCOL1	DS	H	Temporary area for verifying column 1
37E	TVERCOL2	DS	H	Temporary area for verifying column 2
380	ALCHAR1	DS	C	A*11 Temporary byte used by ALTER
381	ALCHAR2	DS	C	A*12 Temporary byte used by ALTER
382	AREA	DS	CL8	EDIT instruction work
38A	BYTE	DS	X	A*13 Temporary byte (used by GET)
38B	CHNGFLAG	DS	X	A*14 Flag for change
38C	CHNGMSG	DS	CL20	Lines changed message
3A0		DS	2X	'.'
3A2	CHGTRUNC	DS	13X	C'...LINE(S)'
3AF		DS	9X	C'TRUNCATED'
3B8	CMODE	DS	CL4	Filemode for MODECHK routine
3BC	FILEMS	DS	CL26	Retry message
3D6	FLAGLOC	DS	X	A*15 Flag for DMSGIO
3D7	GETFLAG	DS	X	A*16 Flag for GETFILE
3D8	HOLDFLAG	DS	X	A*17 DMSSCR SCRFLGS
3D9	JAR	DS	(ENDBLOC-BLOC) AL1	Save area for preserve
425	NEWNAME	DS	CL8	Name area for FILE and SAVE commands
42D	NEWTYPE	DS	CL8	Type area for FILE and SAVE commands
435	NEWMODE	DS	CL2	Mode area for FILE and SAVE commands
437	SERSAV	DS	CL8	A*18 Identification number for save area
43F	SERTSEQ	DS	CL3	A*19 Temporary byte identification number area
442	SERTSW	DS	X	A*20 Temporary byte used by identification number
443	SIGNAL	DS	X	A*21 Signal between routines
444	TEMPTAB	DS	(ENDTABS-TABS) AL1	Temporary spot for new tabs
45E	UTILFLAG	DS	X	A*22 DMSSCR utility flags
45F	XYFLAG	DS	X	A*23 X/Y active flag
460	SCRFLGS	DS	X	A*24 Screen function flags
461	SCRFLG2	DS	X	A*25 More screen function flags
462	SCLNO	DS	8C	Save LINEMODE sequence number
46A	TWITCH	DS	X	A*26 Location flags
46B	TYPSCR	DS	X	A*27 Display unit size index value
46C	XAREA	DS	H	X length and request buffer (Same length as EDLIN)
46E		DS	CL135	Y length and request buffer (Same length as EDLIN)
4F6	YAREA	DS	H	
4F8		DS	CL135	
57F				
580	CNOP		6,8	Alignment for XXXCWD
586		DS	X	Alignment for XXXCWD
587	BLANK1	DS	X	A*28 Blank for clearing EDIT XXXCWD
588	XXXCWD	DS	CL8	EDIT token buffer
590	SAVCWD	DS	CL8	Location at which contents of XXXCWD are saved
598	INVLDHDR	DS	CL6	?EDIT: (for invalid request message)

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
59E	MACROHDR	DS	CL4	EXEC for EDIT macro stacking
5A2	INVLD	DS	OCL6"?EDIT:"	Location to store invalid header
5A4	MACRO	ORG DS	INVLD+2 OCL4"EXEC"	Location to hold macro header (if invalid)
5A8		ORG DS	MACRO+4 C	Blank used for clearing EDLIN
5A9	EDLIN	DS	CL135	Terminal input buffer
630	LINENO	DS	CL5	Line number for typeout
635	BLANK2	DS	X	A*29 Blank for clearing line
636	LINE	DS	CL160	Current line is held here
6D6	BLANK3	DS	X	A*30 Blank for clearing TABLIN
6D7	TABLIN	DS	CL160	Output from spread
778	EDCBEND	DS	0D	
	EDCBLTH	EQU	(EDCBEND-EDCB)	Length of EDCB in doublewords

ERDSECT

ERDSECT: ERROR HANDLING ROUTINE DSECT

ERDSECT describes the fields in a work area used for giving responses and error messages via the DMSERR or LINEDIT macros. A V-constant in DMSERR points to the DMSERT CSECT in DMSNUC.

0	ERT1		
8	ERT2		
10			
18	ERSAVE		
.			
.			
.			
58	ERPAS13		
.			
.			
A0	A*1 A*2		ERPTXA
A8	ERPNUM A*3	ERPCS	
B0	ERPBFA ERPSBA		
B8	ERSBD A*4 A*5		
C0	ERSSZ		
C8	(Doubleword preceding text)		
D0	ERMESS	ERSECT	ERNUM
D8	A*6 A*7		
E0	ERTEXT		
.			
.			
160	ERTPL		
168	ERTPLA	ERTPLL	


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
<u>Work Area for DMSERR Error Handling Routine</u>				
0	ERT1 DS D	Doubleword workspace		
8	ERT2 DS 2D	Two doublewords workspace		
<u>Save Area</u>				
18	ERSAVE DS 16F			
58	ERPAS13 DS 18F	Pass this save area in R13 to BALR-ed to-routines		
<u>Reconstructed PLIST Area</u>				
A0	ERPF1 DS B	A*1	First flag byte	
<u>Bits defined in ERPF1</u>				
	ERF1TX EQU X'80'		Text address in PLIST	
	ERF1HD EQU X'40'		Header in PLIST	
	ERF1BF EQU X'20'		Buffer address in PLIST	
	ERF1SB1 EQU X'10'		One substitution	
	ERF1SBN EQU X'08'		More than one substitution	
A1	ERPF2 DS B	A*2	Second flag byte	
<u>Bits defined in ERPF2</u>				
	ERF2CM EQU X'80'		Blank compression wanted	
	ERF2DT EQU X'40'		Dot at end of line wanted	
	ERF2DI EQU X'20'		HALT=YES wanted	
<u>Last 3 Bits Indicate DISP Field</u>				
	ERF2ER EQU 0		Error message	
	ERF2TY EQU 1		Type	
	ERF2SI EQU 2		SIO	
	ERF2NO EQU 3		None	
	ERF2PR EQU 4		Print	
	ERF2CP EQU 5		CPCCOMM	
A4	ERPTXA DS A		Text address	
A8	ERPHDR DS OCL6		Error message header	
A8	ERPNUM DS H		Message number	
AA	ERPLET DS C	A*3	Message letter	
AB	ERPCS DS CL3		CSECT name	
B0	ERPBFA DS A		Buffer address (for BUFFA)	
<u>Fields for Substitutions</u>				
B4	ERPSBA DS A		Pointer to first (next) group of substitution parameter in original PLIST	
B8	ERSBD DS A		Data address and/or value of current substitution parameter	
BC	ERSBF DS B	A*4	Flag byte for current substitution parameter	
<u>Bits defined in ERSBF</u>				
	ERSFLST EQU X'80'		The last substitution parameter	
	ERSFA EQU X'40'		A-type option	
	ERSFL EQU X'20'		Length specified	

ERDSECT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
	Last 3 Bits Give Option Type	
	ERSFH EQU 0	HEX or HEXA
	ERSFD EQU 1	DEC or DECA
	ERSFC EQU 2	CHARA
	ERSFH4 EQU 3	HEX4A
	ERSFC8 EQU 4	CHAR8A
BD	ERSBL DS X	A*5 Byte length for the current substitution parameter
C0	ERSSZ DS A	Size of substitution field is number of dots minus 1
	<u>Message Construction Area</u>	
C8	DS D	Need doubleword before text
D0	ERMESS DC C'DMS'	First letters of header
D3	ERSECT DC C'MMM'	DSECT name
D6	ERNUM DC C'NNN'	Message number
D9	ERLET DC C'L'	A*6 Message level letter
DA	ERBL DC C' '	A*7 Blank
	ERTSIZE EQU 130	Maximum text size
DB	ERTEXT DS (ERTSIZE+1)C	Message text area
	<u>TYPLIN/PRINTER PLIST Construction Area</u>	
160	DS OF	
160	ERTPL DC CL8'TYPLIN '	
168	ERTPLA DS AL1(1),AL3(ERMESS)	Message text address
16C	ERTPLL DS C'R',AL3	Message length

EXTSECT: EXTERNAL INTERRUPT WORK AREA

EXTSECT describes the fields in the External Interrupt work area referenced by DMSITE. EXTSECT is pointed to by the AEXTSECT field in NUCON.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
<u>Storage for Timer Interrupt</u>				
0	EXSAVE	DS	16F	Saved external old PSW and/or contents of registers
40	TYPLIST	DC	CL8'TYPLIN'	PLISTI to type BLIP character
48	TIMCCW	DC	A(TIMCHAR)	
4C		DC	C'B',X'81',AL2(1)	
50	TIMCHAR	DC	X'FF',XL7'00'	BLIP character(s)
58	SCAW	DC	XL12'00'	Saved CSW/CAW
64	TIMINIT	DC	A(2000000/13)	Value that sets timer equal to 2 seconds
<u>Storage for External (Other than Timer) Interrupt</u>				
68	EXSAVE1	DS	16F	Saved registers
A8	EXTPSW	DC	X'80000000'	Filled-in PSW
AC		DC	A(0)	
B0	SAVEEXT	DC	F'0'	Transfer address for external interrupt
B4		DC	V(DMSDBG)	Address in DEBUG for external interrupt

EXTSECT

<u>Hexadecimal Displacement</u>	<u>Field Name</u>	<u>Field Description, Contents, Meaning</u>		
<u>Storage for External Interrupt Set Up by TRAP</u>				
B8	EXTRET DS D	Saved external old PSW		
C0	JR0 DC F'22'	22 doublewords for floating-point registers and user save area		
C4	JR1 DC A(0)	Address of free storage		
C8	STIMEXIT DC A(0)	Address of TIMER exit routine		
CC	EXTFLAG DC X'00' A*1	External flag		
	REALTIMR EQU X'80'	Real timer indicator		
CD	DC AL3(0)	Reserved for IBM use		

EXTUAREA: EXTERNAL USER AREA

EXTUAREA is a 96-byte user area generated by the CMSAVE macro. The pointer to the user area is passed to the user via register 13. The USAVEPTR field in CMSAVE also points to the user area.



Hexadecimal Displacement	Field Name	DS	OD	Field Description, Contents, Meaning
0	GRS	DS	16F	Registers at time of interrupt
40	FRS	DS	4D	Floating-point registers at interrupt
60	UEXTPSWO	DS	1D	External old PSW at interrupt
68	USERAREA	DS	18F	User save area
B0	USEREAND	DS	0F	End user area

FCBSECT

FCBSECT: SIMULATED OS CONTROL BLOCKS

FCBSECT consists of the CMS File Control Block (FCB) (used for file management under CMS), the simulated OS Job File Control Block (JFCB), Input/Output Block (IOB), and Data Extent Block (DEB). FCBSECT is invoked via the CMSCE macro. FCBSECT is dynamically allocated from CMS free storage each time the FILEDEF command is issued.

0	FCBNEXT		FCBPROC										
8	FCBDD												
10	FCBOP												
18	FCBDSNAM												
20	FCBDSTYP												
28	FCBDSMD		FCBITEM		FCEBUFF								
30	FCBBYTE		FCEFORM		FCBCOUT								
38	FCBREAD		A*1		A*2		FCBXTENT						
40	FCBRECL		A*3		A*4		FCBMEMBR						
48	FCBMEMBR (cont.)						FCBOSFST						
50	FCBOSDSN						FCBR13						
58	FCBKEYS						FCBPDS						
60	JFCBMASK												
68	JFCBCRDT		JFCBXPET		A*5		A*6						
70	A*7		A*8		JFCBUFL		A*9		A*10				A*11
78	JFCLIMCT (cont.)		JFCDSORG		A*12		A*13		JFCBLKSI				
80	JFCLRECL		A*14		A*15								
88	DEBTCBAD						SEBSAV						
90	DEBOFLGS						DEBCPATB						
98	IOBNXTAD						IOBECB						
A0	DEBDCBAD						IOBECBPT						
A8	IOBCSW												
B0	TOBSTART						TOBLCBPT						

- Format of Location X'24' for Console Device

20			FCBIOOUT		
28	FCBIOOUT (cont.)		FCBIOBUF		
30	A*16		A*17		FCBIOCNT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	FCBINIT DS 0X	Initialization flag bytes
	<u>Bits defined in FCBINIT</u>	
	FCBDOSL EQU X'20'	Concatenated DOSLIB data set
	FCBOS EQU X'10'	FCB for OS formatted disk
	FCBOPCB EQU X'08'	OPEN acquired this CMS block
	FCBPERM EQU X'04'	Permanent control block
	FCBBATCH EQU X'02'	Special batch data set
	FCBCATML EQU X'01'	Concatenated MACLIB data set
0	FCBNEXT DS A	AL3(next CMSCB)
4	FCBPROC DS A	A(special processing routine)
8	FCBDD DS CL8	Data definition name
10	FCBOP DS CL8	CMS operation
18	IHAJFCB DS OD	Job file control block
18	JFCBDSNM DS 0X	44 bytes, data set name
18	FCBTAPID DS 0X	Tape identification
18	FCBDSNAM DS CL8	Data set name
20	FCBDSTYP DS CL8	Data set type
	FCBPRPU EQU FCBYSTYP+4	Printer/punch command list
	ORG FCBYSTYP+4	
24	FCBIOOUT DS CL8	Special I/O command list
2C	FCBIOBUF DS A	A(data buffer)
30	FCBCONCR DS C	A*16 Console color code
31	FCBCONMS DS X	A*17 Console miscellaneous information
32	FCBIOCNT DS H	Length of data buffer
	FCBTBSP DS 0X	Two bytes for tape backspace count
28	FCBDSMD DS CL2	Data set mode
2A	FCBITEM DS H	Item identification number
2C	FCBBUFF DS F	A(input/output buffer)
30	FCBBYTE DS F	Data count
34	FCBFORM DS CL2	File format: fixed/variable records
36	FCBCOUT DS H	Records per CMS physical block
38	FCBREAD DS F	Number of bytes actually read
3C	FCBDEV DS X	A*1 Device type code
	<u>Bits defined in FCBDEV</u>	
	FCBCRT EQU 28	CRT
	FCBPCH EQU 24	Punch
	FCBDSK EQU 20	Disk
	FCBTAP EQU 16	Tape
	FCBCON EQU 12	Console terminal
	FCBRDR EQU 8	Reader
	FCBPTR EQU 4	Printer
	FCBDUM EQU 0	Dummy device
3D	FCBMODE DS X	A*2 Mode: 1, 2, 3, 4, and 5
3E	FCBXENT DS H	Number of items in extent
40	FCBRECL DS H	DCB LRECL at open time
42	IOBIOFLG DS X	A*3 I/O flags
43	FCBDCBCT DS X	A*4 No. of DCBs using this FCB
44	FCBMEMBR DS 2F	OS PES member name
4C	FCBOSFST DS F	Pointer to CS FST
50	FCBOSDSN DS F	Pointer to OS dsnname block
54	FCBR13 DS F	Save area vector R13
58	FCBKEYS DS A	A(DDS in-storage key table)
5C	FCBPDS DS A	A(PES in-storage directory)
60	JFCBMASK DS 8X	Various mask bits
68	JFCBCRDT DS 3C	Data set creation date (YDD)
6B	JFCBXPDT DS 3C	Data set expiration date (YDD)


FCBSECT

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
6E	JFCBIND1 DS	X	A*5 Indicator one
6F	JFCBIND2 DS	X	A*6 Indicator two
70	JFCBUENO DS	X	A*7 Number of buffers
71	JFCBFTEK DS	0X	Buffering technique
71	JFCBFALN DS	X	A*8 Buffer alignment
72	JFCBUFL DS	H	Buffer length
74	JFCEROPT DS	X	A*9 Error option
75	JFCKEYLE DS	X	A*10 Key length
76		X	Reserved for IBM use
77	JFCLIMCT DS	3X	A*11 EDAM search limit
7A	FCBDSORG DS	0X	Data set organization
7A	JFCDSORG DS	2X	Data set organization
7C	FCBRECFM DS	0X	Record format
7C	JFCRECFM DS	X	A*12 Record format
7D	JFCOPTCD DS	X	A*13 Option codes
7E	FCBBLKSZ DS	0H	Block size
7E	JFCBLKSI DS	H	Block size
80	FCBLRECL DS	0H	Logical record length
80	JFCLRECL DS	H	Logical record length
82	FCBIOSW DS	X	A*14 I/O operation indicator
	<u>Bits defined in FCBIOSW</u>		
	FCBCLOSE EQU	X'80'	Switch turned on during CLCSE operation
	FCBCLEAV EQU	X'40'	DISP=LEAVE during CLOSE operation
	FCBPROCC EQU	X'20'	GOTO FCBPROC during CLOSE operation
	FCBPROC0 EQU	X'10'	GOTO FCBPROC during OPEN operation
	FCBCASE EQU	X'08'	ON=LOWER CASE console I/C
	FCBPVMB EQU	X'04'	PUT-MOVE-VAR-BLK
	FCBIOWR EQU	X'02'	WRITE/PUT
	FCBIORD EQU	X'01'	READ/GET
83	FCBIOSW2 DS	1X	A*15 I/O operation indicators
	<u>Bits defined in FCBIOSW2</u>		
	FCBMVFILE EQU	X'08'	Move file is active
	FCBMMV EQU	X'02'	Move PDS switch for FIND
	FCBMVPDS EQU	X'01'	Switch for MOVEFILE with PDS option
84	DEBLNGTH DS	0X	Length of DFB in doublewords
84		F	Reserved for IBM use
88	IHADEB DS	0D	Data extent block
88	DEBTCBAD DS	A	A(move-mode user buffer)
8C	SEBSAV DS	F	Dynamic save for SEB return address (OS input/output simulation)
90	DEBOFLGS DS	4X	Data set status flags
94	DEBOPATB DS	4X	OPEN/CLOSE option byte
98	IOBFLG DS	0X	Start of IOEPREFIX for normal scheduling
	<u>Bits defined in IOBFLG</u>		
	IOBBFLG EQU	0	Displacement of IOB flag in ICB
	IOBOUT EQU	X'40'	WRITE,PUT in progress
	IOBIN EQU	X'20'	READ,GET in progress
	IOBUPD EQU	X'10'	QSAM PUTX in progress
98	IOBNXTAD DS	A	A(next buffer to be used)
9C	IOBECB DS	F	ECB for QSAM normal scheduling
A0	IHAIOB DS	0F	Input/output block
A0	DEBDEBID DS	0X	DEB identification
A0	DEBDCBAD DS	A	A(data control block)
A4	IOBECBCC DS	0X	ECB completion code
	<u>Bits defined in IOBECBCC</u>		
	IOBBECBC EQU	12	Displacement of ECB code in ICB
	IOBBECBP EQU	12	Displacement of ECB pointer in IOB

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
A4	IOBECBPT DS	A	A (event control block) - see IHADECB DSECT
A8	IOBFLAG3 DS	0X	I/O error flag
	IOBBCSW EQU	16	Displacement of CSW in IOB
A8	IOBCSW DS	8X	Last CCW stored (that is, residual count)
B0	IOBSTART DS	A	X'ID-NEXT BUFFER', AL3 (INITIAL BUFFER)
B4	IOBDCBPT DS	A	A (data control block)
B8	IOBEND DS	0X	End of input/output block
B8	FCBEND DS	0D	End of FCB, JFCB, DEB, and ICB blocks
	FCBENSIZ EQU	(*-FCBSECT)/8	Size of FCB entry in doublewords

FCHTAB: FETCH TABLE

FCHTAB contains a fetch/load parameter list that points to a 34-byte directory list. The fetch table is used when a DOS program issues a LOAD or FETCH request without the LIST= parameter. The IJBFTTAB field in the SYSCOM block in the DOSCON CSECT of NUCON points to the fetch table.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>8-Byte Parameter List Pointing to Directory List</u>		
0	FCHAPHNM DC A(DIRNAME)	Address of phase name
4	FCHOPT DC X'00'	A*1 Options
5	FCHALSNM DS AL3	Address of listname
<u>34-Byte Directory List</u>		
8	DIRNAME DS CL8	Phase name
10	DIRTTR DS XL3	Phase TTR
13	DIRN DS XL1	A*2 No. of halfwords in directory
14	DIRTT DS XL2	No. of text blocks in phase
16	DIRLL DS XL2	Length last text block
18	DIRC DS XL1	A*3 Flag byte
<u>Bits defined in DIRC</u>		
	SELFREL EQU X'80'	Phase self-relocatable
	RELPHSE EQU X'40'	Phase to be relocated
	SVAELIG EQU X'20'	Phase SVA eligible
	SVAPHSE EQU X'10'	Phase in SVA
	PCLPHSE EQU X'08'	Phase in private core image library
	PNOTFND EQU X'04'	Phase not found
	DACTIVE EQU X'02'	Phase directory active
	NOTEEXT EQU X'01'	TEXT=NO specified
19	DIRT DS XL1	A*4 Reserved for IBM use
1A	DIRPPP DS XL3	Phase load point
1D	DIREEE DS XL3	Phase entry point
20	DIRRR DS XL2	No. of RLD items in phase
22	DIRR DS XL1	A*5 No. of additional RLD blocks
23	DIRAAA DS XL3	Partition start address
26	DIRK DS XL1	A*6 Reserved for IBM use
27	DIRVEE DS XL3	Phase entry point in SVA
	FCHLENG EQU *-FCHTAB	Total length in bytes (X'2A')
	FCHLENDW EQU (FCHLENG+7)/8	Total length in doublewords (X'06')

FICL: FIRST IN CLASS BLOCK

FICL is a 2-byte table used in CMS/DOS to address system and programmer logical unit blocks.

Byte 0 of FICL points to the first system class logical unit in the LUB table. This is always the first entry in the LUB table. The second byte points to the first programmer class logical unit in the LUB table partition area.

The FICLPT field in the BGCOM block points to the FICL block.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
0	SYSINDX DC AL1(0)	A*1	First BG system LUB index	
1	PROGINDX DC AL1(14)	A*2	Programmer LUBs index	

FRDSECT

FRDSECT: FREE CHAIN ELEMENT HEADER BLOCKS

FRDSECT describes the fields used by DMSFRE to reference the four free chain element header blocks. FRDSECT is invoked by the macro DMSFRT. The DMSFRT DSECT is pointed to by a V-constant in DMSFREE, and also by the ADMASFRT field in NUCCN.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>The Following Are the Four Free Chain Element Header Blocks</u>		
0	FREELN DC 3F'0', AL1(FLNU+FLPA,NUCKEY,NUCCODE,0)	Low storage nucleus
10	FREELU DC 3F'0', AL1(0,USERKEY,USERCODE,0)	Low storage user chain
20	FREEHN DC 3F'0', AL1(FLNU+FLHC,NUCKFY,NUCCODE,0)	High storage nucleus
30	FREEHU DC 3F'0', AL1(FLHC,USERKEY,USERCODE,0)	High storage user chain

The Following Symbolic Equates Describe the Format of Each of the Four Free Chain Element Header Blocks

POINTER	EQU	0	Pointer to first free element
NUM	EQU	4	Number of elements in chain
MAX	EQU	8	Maximum size of an element
FLAGS	EQU	12	Flag byte

Bits defined in FLAGS

FLCLN	EQU	X'80'	Cleanup flag
FLCLB	EQU	X'40'	Overlaid chain flag
FLHC	EQU	X'20'	High storage flag
FLNU	EQU	X'10'	Nucleus flag
FLPA	EQU	X'08'	Page available on chain

SKEY	EQU	13	Storage key for this chain
------	-----	----	----------------------------


Bits defined in SKEY

USERKEY	EQU	X'E0'	User storage key
NUCKEY	EQU	X'F0'	Nucleus storage key

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
	TCODE EQU 14	FREETAB table code
	<u>Bits defined in TCODE</u>	
	USERCODE EQU 1	User free storage page
	NUCCODE EQU 2	Nucleus free storage page
	TRNCODE EQU 3	Transient area page
	USARCODE EQU 4	User area page
	SYSCODE EQU 5	System page
	MAXCODE EQU 5	Maximum possible code value
	*UNUSED EQU 15	
	BLOCKLEN EQU 16	Symbolic length of block
40	AFREETAB DC A(0)	Address of FREETAB table
44	FREELOW1 DS F	Original value of FREELOWE (set by INIT2)
48	ACALL DS A	Address of caller (for errors)
	<u>Flags Set by Examining SVC 203 Halfword Code</u>	
4C	FREEFLG1 DC BL1'0' A*1	
	<u>Bits defined in FREEFLG1</u>	
	FRF1C EQU X'80'	Conditional request
	FRF1V EQU X'40'	Variable request
	FRF1N EQU X'20'	Nucleus request
	FRF1E EQU X'10'	FREE (vs FRET) request
	FRF1L EQU X'08'	Low storage is OK
	FRF1H EQU X'04'	High storage is OK
	FRF1M EQU X'02'	Messages wanted on error
	FRF1B EQU X'01'	TYPICAL equals BALR in macro
	<u>The Following Byte Holds Flags Internal to the DMSFRE Routine</u>	
4D	FREEFLG2 DC BL1'0' A*2	
	<u>Bits defined in FREEFLG2</u>	
	FRF2CL EQU X'80'	Cleanup flag
	FRF2SVP EQU X'40'	Variable pages request flag (SCHWPGE)
	FRF2NOI EQU X'20'	Second initialization routine has not yet been called by DMSINS
	FRF2CKE EQU X'10'	Do a check each time FREE or FRET is called
	FRF2CKT EQU X'08'	Do a check this time
	FRF2CKX EQU X'04'	Executing CHECK routine now
	<u>Free Chain Element Description</u>	
	POINTER EQU 0	Pointer to next FREE element
	SIZE EQU 4	Size of this element in bytes

FSCBD**FSCBD: FILE SYSTEM CONTROL BLOCK**


FSCBD is a PLIST defined for general use by routines that use the CMS file system. FSCBD is generated when the user invokes the FSCBD macro.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning			
0	FSCBCOMM DS	CL8			File system command (RDBUF, WRBUF, etc.)
8	FSCBFN DS	CL8			Filename
10	FSCBFT DS	CL8			Filetype
18	FSCBFM DS	CL2			Filemode
1A	FSCBITNO DS	H			Relative record number to be read/written
1C	FSCBBUFF DS	F			Address of read/write buffer or of STATEFST
20	FSCBSIZE DS	F			Length of buffer
24	FSCBFV DS	CL2	F*1		RECFM -- C'F' or C'V'
25	FSCBFLG EQU	FSCBFV+1	F*2		Flag byte
26	FSCBNOIT DS	H			Number of records to be read/written
28	FSCBNORD DS	A			Number of bytes actually read

FSTD: FILE STATUS TABLE ENTRY DSECT

FSTD describes the fields in a 40-byte file status table entry as found by STATE, STATEW, DMSLFS or DMSLFSW. FSTD is functionally equivalent to the FSTSECT DSECT.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	FSTFNAME DS	1D
8	FSTFTYPE DS	1D
10	FSTDATEW DS	1H
12	FSTTIMEW DS	1H
14	FSTWRPNT DS	1H
16	FSTRDPNT DS	1H
18	FSTFMODE DS	1H
1A	FSTRECCT DS	1H
1C	FSTFCLPT DS	1H
1E	FSTRECFT DS	1C
1F	FSTFLAGS DS	1X
		F*1 Record format (F or V)
		F*2 FST flag byte
<u>Bits defined in FSTFLAGS</u>		
	FSTXWDSK EQU	X'C0'
	FSTRWDSK EQU	X'80'
	FSTXRDSK EQU	X'40'
	FSTFILEA EQU	X'07'
	FSTACTRD EQU	X'04'
	FSTACTWR EQU	X'02'
	FSTACTPT EQU	X'01'
	FSTRODSK EQU	X'00'
		Extension of read/write disk
		Read/write disk
		Extension of read-only disk
		File is active (one of the following)
		File active for reading
		File active for writing
		File active from a point
		Read-only disk
<u>Bits redefined for use in RDBUF</u>		
	FSTDIA EQU	X'40'
	FSTDRA EQU	X'01'
	FSTDNI EQU	X'00'
		Item available
		Previous record null
		Null record
20	FSTLRECL DS	1F
24	FSTBLKCT DS	1H
26	FSTYEARW DS	1H
		Logical record length
		Number of 800-byte blocks
		Year last written
	FSTDSIZE EQU	(*-FSTD)
		FST size in bytes

FSTSECT

FSTSECT: FILE STATUS TABLE

FSTSECT defines the file status table (FST) which describes the attributes of a file on a CMS virtual disk. FSTSECT is invoked by the macro FSTB.


The file status tables for all files on the disk are grouped into 800-byte disk records referred to as file status table blocks (FSTEs). Each file status table block can accommodate up to 20 file status tables.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	FSTN	DS 1D
8	FSTT	DS 1D
10	FSTD	DS 1F
14	FSTWP	DS 1H
16	FSTRP	DS 1H
18	FSTM	DS 1H
1A	FSTIC	DS 1H
1C	FSTFCL	DS 1H
1E	FSTFV	DS 1C
1F	FSTFB	DS 1C
		A*1 Fixed(F)/variable(V) flag
		A*2 Flag byte (if used)
<u>Bits defined in FSTFB (Applicable only to STATEFST copy of FST-entry after successful STATE or STATEW call)</u>		
	FSTFRWX	EQU X'C0'
		Read-only extension of read/write disk
	FSTFRW	EQU X'80'
	FSTFROX	EQU X'40'
		Read-only extension of read-only disk
	FSTFACT	EQU X'07'
	FSTFAR	EQU X'04'
	FSTFAW	EQU X'02'
	FSTFAP	EQU X'01'
	FSTFRO	EQU X'00'
		File is active (one of the following)
		File active for reading
		File active for writing
		File active from a designated point
		Read-only disk
<u>Bits redefined for use in RDEUF</u>		
	FSTITAV	EQU X'40'
		Item available
	FSTRECAV	EQU X'01'
		Previous record null
	FSTNOIT	EQU X'00'
		Null record
20	FSTIL	DS 1F
24	FSTDBC	DS 1H
26	FSTYR	DS 1H
	FSTL	EQU *--FSTSECT
		Size of FST in bytes (X'28')
<u>FST Hyperblock Parameters</u>		
	FSTFWDP	EQU 800
	FSTBKWD	EQU 804
		Forward pointer to next hyperblock in storage
		Backward pointer to previous hyperblock in storage

FVSECT: FIXED VARIABLE STORAGE WORK AREA FOR CMS FILE SYSTEM

FVSECT is used mainly by file management and I/O routines. FVS contains save areas, work areas, and commonly used constants. A typical use of FVS is when a reentrant I/O routine requires a work area or save area, since the routine cannot modify itself. FVSECT is invoked by the FVS macro.



158	VFRET		JSRC
160	JSR1		RWMFD
168	F800		
170	FVSDSKA		DSKLOC
178	RWCNT		DSKADR
180	ADTADD		
188	FINISLST	.	.
198			FFF
1A0	FFE	FFD	SIGNAL A*3 A*4
1A8	A*5 A*6 A*7		FVSERAS0
1B0	FVSERAS1		FVSERAS2
1B8	READCNT		
1C0	FVSFSTN		
1C8	FVSFSTT		
1D0	FVSFSTD	FVSFSTWP FVSFSTRP	
1D8	FVSFSTM	FVSFSTIC FVSFSTCL A*8 A*9	
1E0	FVSFSTIL	FVFSTDB FVSFSTYR	
1E8	FVSFSTAD		FVSFSTAC

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DISK\$SEG DS	15F
3C	REGSAV3 DS	15F
78	RWFSTRG DS	18F
C0	ADTFVS DC	2F'0'
<u>Save Area for Lowest Level Routines</u> (For example, READMFN, RELUFN, UPDISK, TIPSRCH, and ADTLKP)		
C8	REGSAVO DS	15F
104		AL3(00)
107	ERRCOD0 DC	AL1(***) A*1
	TRKLSAVE EQU REGSAVO	For TRKLKP/X only when called by QQTRK/X
<u>Save Area for Next-to-Lowest Level Routines</u> (For example, READFST, ERASE, ALTER, and INTSVC-LOADMOD)		
108	REGSAV1 DS	15F
144		DC AL3(00)
147	ERRCOD1 DC	AL1(***) A*2
148	F65535 DC	F'65535'
14C	FW4 DC	F'4'
	HW4 EQU FW4+2	Constant value
150	VFREE DC	V(FREE)
154	F100 DC	F'100'
158	VFRET DC	V(FRET)
15C	JSR0 DC	F'0'
160	JSR1 DC	F'0'
<u>PLIST to Read/Write MFD</u>		
164	RWMFD DC	A(***)
168	F800 DC	F'800'
16C		DC A(HW4)
170	FVSDSKA DC	A(***)
		Address of the active disk table
174	DSKLST DS	0F
174	DSKLOC DS	A(***)
178	RWCNT DC	A(***)
17C	DSKADR DC	A(***)
180	ADTADD DC	A(***)
184	FINISLST DC	CL8'FINIS'
18C		DC CL8**'
194		DC CL8**'
19C		DC CL2**'
		Halfword constants
19E	FFF DS	0H
19E	FFE DC	X'FFFF'
1A0	FFE DC	X'FFFE'
1A2	FFD DC	X'FFFD'
		Means no significant data past 215th byte 1968-era MFL still supported on input only Newest signal for 2314 handling

FVSECT

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
1A4	SIGNAL DC H'0'		SIGNAL = Scratch halfword used by READMFD or ERASE = 0000, X'FFFF', X'FFFE', or X'FFFD'
	<u>Bits defined in SIGNAL</u>		
	SWTCH EQU SIGNAL+1		00, FF, FE, or FD
1A6	UFDBUSY DC X'00'	A*3	Nonzero means UFD is being updated
	<u>Bits defined in UFDBUSY</u>		
	WRBIT EQU X'80'		WREUF
	UPBIT EQU X'40'		UPDISK - READMFD
	FNBIT EQU X'20'		FINIS
	ERBIT EQU X'10'		ERASE - ALTER - READFST
	DIOBIT EQU X'08'		RDTK/WRTK
	<u>Bits for Routines That Do Not Update the Disk, but That Cannot Be Interrupted by a HX Command</u>		
	ABNBIT EQU X'02'		DMSAEN (abend recovery routine)
	ITSBIT EQU X'01'		DMSITS (SVC handling routine)
1A7	KXFLAG DC X'00'	A*4	HX flags
	<u>Bits defined in KXFLAG</u>		
	KXWANT EQU X'80'		HX wanted as soon as possible
	KXWSVC EQU X'01'		Hold HX until any SVC activity
1A8	DC X'00'		Reserved for IBM use
1A9	FLGSAVE DC X'00'	A*5	For scratch use (for example, by RELUFD)
1AA	FVSFLAG DC X'00'	A*6	For general use (as needed)
	<u>Miscellaneous Storage Used by ERASE (or RENAME)</u>		
1AB	ERSFLAG DC X'00'	A*7	Flag for use by ERASE or RENAME
1AC	FVSERAS0 DC F'0'		R0 to/from FSTLKW (for ERASE)
1B0	FVSERAS1 DC F'0'		R1 to ACTLK0 or FSTLKW (for ERASE)
1B4	FVSERAS2 DC F'0'		Address of free storage used by ERASE
1B8	READCNT DC F'0'		Current read count (DMSBRD)
1BC	DC F'0'		Reserved for IBM use
	<u>File Status Table (FST) Copy from STATE</u>		
1C0	STATEFST DS OD		Full FST of file (STATE)
1C0	FVSFSTN DC D'0'		Filename
1C8	FVSFSTT DC D'0'		Filetype
1D0	FVSFSTDT DC 2H'0'		Date/time last written
1D4	FVSFSTWP DC H'0'		Write pointer (item ID)
1D6	FVSFSTRP DC H'0'		Read pointer (item ID)
1D8	FVSFSTM DC H'0'		Filemode
1DA	FVSFSTIC DC H'0'		Number of items in file
1DC	FVSFSTCL DC H'0'		Disk address (first chain link)
1DE	FVSFSTFW DC C' '	A*8	Fixed(F)/variable(V) indicator
1DF	FVSFSTFB DC X'00'	A*9	Flag byte
1E0	FVSFSTIL DC F'0'		Length of largest item in file
1E4	FVSFSTDB DC H'0'		Number of data blocks
1E6	FVSFSTYR DC 2C' '		Year last written
1E8	FVSFSTAD DC A(0)		A(active disk table for this file)
	STATERO EQU FVSFSTAD		
1EC	FVSFSTAC DC A(0)		A(real FST entry for this file)
	STATER1 EQU FVSFSTAC		

IHADECB: DATA EVENT CONTROL BLOCK

IHADECB, which is invoked via the CMSCB macro, is the simulated data event control block used for CMS processing of OS macros and OS access methods. The ICBECCBPT field in FCBSECT points to IHADECB.


0	DECSDECB		DECETYPE		DECLNGTH
8	DECDCBAD		DECAREA		
10	DECIOBPT		DECKYADR		
18	DECRECPT				

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DECSDECB DS F	Event control block
4	DECETYPE DS H	Type of I/O request
	<u>Bits defined in DECETYPE</u>	
	DECBRD EQU X'80'	Read SF
	DECBWR EQU X'20'	Write SF
6	DECLNGTH DS H	Length of key and data
8	DECDCBAD DS A	V(data control block)
C	DECAREA DS A	V(key and data, buffer)
10	DECIOBPT DS A	V(IOE)
	<u>B DAM Extension</u>	
14	DECKYADR DS A	V(key)
18	DECRECPT DS A	V(block reference field)
	<u>Frequently Used Equates</u>	
DDNAM	EQU FCBBDSTYP	Filetype = data set name
BLK	EQU X'10'	RECFM=blocked records
BS	EQU X'20'	MACRF=BSAM
DA	EQU X'20'	DSORG=direct access
FD	EQU X'80'	RECFM=fixed-length records
IS	EQU X'80'	DSORG=indexed sequential
LOC	EQU X'08'	MACRF=locate mode
MOV	EQU X'10'	MACRF=move mode
PS	EQU X'40'	DSORG=physical sequential
PO	EQU X'02'	DSORG=partitioned organization
PREVIOUS	EQU X'80'	OFLGS=previous I/O operation
QS	EQU X'40'	MACRF=QSAM
UND	EQU X'C0'	RECFM=undefined format records
VAR	EQU X'40'	RECFM=variable-length records

IOSECT

IOSECT: I/O INTERRUPT SAVE AREA


IOSECT describes the fields used by DMSITI for save registers, I/O old PSW, and other data when handling I/O interrupts. IOSECT is pointed to by the AIOSECT field in NUCON.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	IOSAVE	DS 16F Register save area
40	IONTABL	DC F'0' Size of user interrupt table in doublewords
44	AUSRITBL	DC A(0) Address of user interrupt table
48		DC F'28' Length of each entry
4C	AUSRILST	DC A(0) Address of last entry in table
50	OLDEST	DS 4F Oldest I/O old PSW and CSW
60	NEXTO	DS 4F Next oldest I/O old PSW and CSW
70	IOPSW	DS 2F Newest I/O old PSW
78	IOCSW	DS 2F Newest CSW
80	HOLD	DC F'0' Holds entry pointer for device
84	VSTRANGE	DC H'0' Unknown device address saved here
86		DC 1H'0' Reserved for IBM use
88		DC 2F'0' Reserved for IBM use

KEYSECT: DISK KEY TABLE DSECT FOR BDAM SIMULATION

KEYSECT defines the key table used in OS simulation of BDAM files for I/O by key. KEYSECT is built dynamically from CMS free storage.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	KEYLNGTH DS	1F Key length
4	DATAEND DS	1F Pointer to last data item in file
8	KEYOP DS	2F Start of PLIST for keys file
10	KEYNAME DS	2F Filename of keys file
18	KEYTYPE DS	2F Filetype of keys file
20	KEYMODE DS	1H FileMode of keys file
22	KEYTBLNO DS	1H Item number of key table
24	KEYTBLAD DS	1F Address of key table
28	TBLLENGTH DS	1F Byte size of key table
2C	KEYFORM DS	1X A*1 Format of keys file
2D	KEYCHNG DS	1X A*2 Indicates change in key table
2E	KEYCOUT DS	1H Blocking factor of key table
30	DS	1F Number of bytes read
34	KEYTABLE DS	0F Start of keys table (item number)

LDRST

LDRST: LOADER STORAGE AREA

LDRST describes the fields of the work area used by the loader. The work area is obtained and built by DMSLDR. LDRST is built dynamically by DMSLDR from CMS free storage.



5D8	NUMBYTE
5E0	FINIS
.	.
5F8	A*4 //////////
5FC	SYSUT1 (44 bytes)
.	.
628	TYPLIN
630	TYPREAD
638	DSKLIN
.	.
650	DSKAD
658	
660	HEXCON
	OUTPUT
670	OUTBUF
.	.
6D0	PRVCNT
6D8	SAV67
6E0	ENTNAME
6E8	ENTADR MEMBOUND
6F0	PLISTSAV
.	.
8F0	REG13SAV A*5

LDRST

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	GPRSAV	DS 3F R9 through R12
C	LOCSAV	DS F Base register contains A(DMSLDRA)
10	RETT	DS F Return register for DMSLSB
14	LOCCT	DS F (LOCNT) next load location
18	BRAD	DS F (STRTADDR) start execution address
1C	TBLREF	DS F (ALDRTBL) top of loader table
20	FLAG1	DS X A*1 Loader switches (permanent)
	<u>Bits defined in FLAG1</u>	
	ABSOLUTE	EQU X'80' Absolute loading
	FSTXTADR	EQU X'40' First text address saved
	COMMONEX	EQU X'20' Common entries exist in loader table
	PEXIST	EQU X'10' PR entries exist in loader table
	ENDCDADR	EQU X'08' Allow end card address
	NOERASE	EQU X'04' Do not erase the load map
	WORKFILE	EQU X'02' Work file (SYSUT1) exists
	NODUP	EQU X'01' Do not type message DMSLI0202W
21	FLAG2	DS X A*2 Loader switches (permanent)
	<u>Bits defined in FLAG2</u>	
	STRINITC	EQU X'80' Call STRINIT in LOADMOD
	NOMAP	EQU X'40' Do not create a load map
	APRILB	EQU X'20' REP card processing control
	NOAUTO	EQU X'10' No automatic text deck checking
	TYPE	EQU X'08' Type load map at terminal
	NOREP	EQU X'04' No REP card printing
	NOINV	EQU X'02' No invalid card typeout
	NOLIBE	EQU X'01' No automatic TXT library searching
22	TBLCT	DS H Number of entries in loader table
24	FLAG3	DS X A*3 More flags
	<u>Bits defined in FLAG3</u>	
	CMD	EQU X'80' Processing names from command list
25		DS X Reserved for IBM use
26		DS 5H Reserved for IBM use
30	RLDCONST	DS F Relocation constant
34	PARMLIST	DS F Updated parameter list pointer
38	RETREG	DS F Return register
3C	SPEC	DS 200F 10-card input buffer
35C	ESIDTB	DS 256H 256 ESD entries; object deck
55C	APSV	DS 16F Register save area for subroutine calls
59C	TEMPST	DS F Temporary RLD routine storage
5A0	TMPLOC	DS F Temporary storage
5A4	CRDPTR	DS F Input card pointer
5A8	FILE	DS D Save location for DMSLIB
5B0	READBUF	DS 2F Input read parameter list
5B8	FNAME	DS 2F Filename
5C0	FTYPE	DS 2F Filetype
5C8	FMODE	DS H FileMode
5CA	RITEM	DS H Number of items
5CC	RADD	DS F Buffer address
5D0	RLENG	DS F Buffer length
5D4	RFIX	DS H Fixed/variable flag byte
5D6	RNUM	DS H Number of items

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
5D8	NUMBYTE DS F	Number of bytes actually read
5DC	FINIS DS 7F	FINIS parameter list
5F8	FLAGS DS X	A*4 Loader switches (nonpermanent)
	START EQU X'80'	Start execution requested
	ONEDYNA EQU X'40'	One call to dynamic loading per text file
	ESD1ST EQU X'20'	First ESD data item this card
	NOSLCADR EQU X'10'	No address field in SLC card
	SETLIB EQU X'08'	Set up for library searching
	CLOSELIB EQU X'04'	Clear TXTLIB searching
	LUNDEF EQU X'02'	Undefined entries exist in loader table
	RESET EQU X"01"	Reset "entry" specified
5F9	DS 3X	Library search work area pointer
5FC	SYSUT1 DS 11F	RLD work file PLISTS
628	TYPLIN DS 2F	TYPLIN parameter list
630	TYPEAD DS 2F	TYPLIN buffer address
638	DSKLIN DS 7F	Disk parameter list for load map
654	DSKAD DS 13X	
661	HEXCON DS 14X	Hexadecimal constant
	PACK EQU HEXCON	Hexadecimal constant
	UNPACK EQU HEXCON+5	Hexadecimal constant
66F	OUTPUT DS X	
670	OUTBUF DS 100X	Output buffer for load map and terminal printing
6D4	PRVCNT DS H	Address of next PR load address
6D8	SAV67 DS 2F	Temporary save area of R6 and R7
6E0	ENTNAME DS CL8	Entry name (reset ENTRY or entry control card)
6E8	ENTADR DS F	Entry name's loader table location
6EC	MEMBOUND DS F	Low extend of free storage (FREELOWE)
6F0	PLISTSAV DS 64D	LOAD (INCLUDE) PLIST saved
8F0	REG13SAV DS F	Address of LDRST
8F4	FRSTS DID DS X	A*5 First section definition identification
8F8	ENDFREE DS 0D	
	NEED EQU (ENDFREE-LDRST)/8	

Note: The following equates refer to displacements and flags in the REFTABLE entry usually pointed to by register 12

REFNAME EQU 0	Displacement of 8-byte name field
REFLG1 EQU 8	Displacement of flag byte 1
REFPRB EQU X'7C'	PR - byte alignment
REFPRH EQU X'7D'	PR - halfword alignment
REFPRF EQU X'7E'	PR - fullword alignment
REFPRD EQU X'7F'	PR - doubleword alignment
REFUND EQU X'80'	Undefined symbol
REFCXD EQU X'81'	Resolve CXD
REFCOM EQU X'82'	Define common area
REFWEX EQU X'83'	Weak external reference
REFNOB EQU X'90'	LIVE card - nonobligatory
REFLIB EQU X'10'	Single bit for nonobligatory LIVE card
REFINFO EQU 9	Displacement of relocation factor or maximum address
REFVAL EQU 13	Displacement of absolute or assigned value
REFLG2 EQU 16	Displacement of flag byte 2
REFCMD EQU X'80'	Command line name - must resolve

LUBTAB, LUBPR

LUBTAB AND LUBPR: LOGICAL UNIT BLOCK TABLE

LUBTAB is a device table that has a 2-byte entry for each symbolic name used by CMS/DOS. The simulated LUB has 255 entries: 14 entries for the system logical units and 241 entries for programmer logical units. System devices (SYSRDR, SYSIPT, SYSPCH, SYSLST, and SYSLOG) can be assigned to alternate devices. The system and programmer tables are defined with separate DSECTS: LUBTAB and LUBPR. LUBTAB is pointed to by the LUBPT field in BGCOM. The address of the first LUB entry is in the first byte of the FICL control block.

System (LUBTAB)

0	LUBRDR		LUBIPT		LUBPCH		LUBLST	
8	LUBLOG	//LUBLNK	LUBRES		LUBSLB			
10	LUBRLB	//LUBUSE	//LUBREC		LUBCLB			
18	//LUBVIS	LUBCAT						

Programmer (LUBPR)

0	LUB000		LUB001		LUEC02		LUB003	
8					LUB004 through LUF239			
.					.			
.					.			
1E0	LUB240		LUB241					

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>System LUBs</u>		
0	LUBRDR	DS XL2 System virtual reader
2	LUBIPT	DS XL2 System virtual input device
4	LUBPCH	DS XL2 System virtual punch
6	LUBLST	DS XL2 System virtual printer
8	LUBLOG	DS XL2 Terminal
A	LUBLNK	DS XL2 Reserved for IBM use
C	LUBRES	DS XL2 System residence volume
E	LUBSLB	DS XL2 Private source statement library
10	LUBRLB	DS XL2 Private relocatable library
12	LUBUSE	DS XL2 Reserved for IBM use
14	LUBREC	DS XL2 Reserved for IBM use
16	LUBCLB	DS XL2 Private core image library
18	LUBVIS	DS XL2 Reserved for IBM use
1A	LUBCAT	DS XL2 VSAM catalog
<u>Programmer LUBs</u>		
0	LUB000	DS XL2 Programmer logical unit block
2	LUB001	DS XL2 Programmer logical unit block
4	LUB002	DS XL2 Programmer logical unit block
6	LUB003	DS XL2 Programmer logical unit block
8	.	.
	.	.
	.	.
1E0	LUB240	DS XL2 Programmer logical unit block


Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
1E2	LUB241	DS	XL2	Programmer logical unit blcck
	LUBP	EQU	0	Displacement to PUB pointer
	LUBJ	EQU	1	Displacement to JIB pointer
	LUBL	EQU	*-LUB241	LUE length

NICL

NICL: NUMBER IN CLASS

Byte 0 of the Number In Class block (NICL) contains the number of system class logical units. The second byte contains the number of programmer class logical units for the partition.

The NICLPT field in the BGCOM block points to the NICL block.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning				
0	NOSYS	DC	AL1(14)	A*1	Total number of system LUEs	
1	NOPROG	DC	AL1(242)	A*2	Total number of programmer LUEs	

NUCON: NUCLEUS CONSTANT AREA

NUCON is the nucleus constant area of CMS.

0	IPLPSW
8	IPLCCW1
10	IPLCCW2
18	EXTOPSW
20	SVCOPSW
28	PGMOPSW
30	MCKOPSW
38	IOOPSW
40	CSW
48	CAW //////////NUCRSV1/////////
50	TIMER //////////NUCRSV2/////////
58	EXTNPSW
60	SVCNPSW
68	PGMNPSW
70	MCKNPSW
78	IONPSW
80	CPULOG
88	
90	//////////NUCRSV4///////// MONCLASS PERCODE
98	PERADDR MCNCODE
A0	//////////NUCRSV5/////////
C0	LOWSAVE
.	
.	
.	
160	FPRLOG
.	
.	
.	
180	GPRLOG
.	
.	
.	

	ECRLOG				
1C0					
.					
.					
200	SYSTEMID				
.					
.					
220	INSTALID				
.					
.					
260	SYSNAME				
268	IPLADDR		SYSADDR		DEVICE
270	//////////NUCRSV6//////////				
278	FEIBM				
280	CURRDATE				
288	CURRTIME				
290	CURRVIRT		CURRCPUT		
298	LASTVIRT		LASTCPUT		
2A0	LASTCMND				
2A8	PREVCMND				
2B0	LASTEXEC				
2B8	PREVEEXEC				
2C0	LASTLMOD				
2C8	LASTTMOD				
2D0	DATIPCMS				
2D8	CLKVALMD				
2E0	MACDIRC				
.					
.					
300	MACLIBL				
.					
.					
348	TXLIBSV		MACLBSV		
350	TOTLIBS		TXTDIRC		

358	TXTLIES		
.	.	.	.
3A0	GRS015		LOC0176
3A8	FIRSTDMP		LASTDMP
3B0	FRS06		DMPTIT
3B8			
.	DMPTITLE		
.	.	.	.
440	GLBLTABL		SVC\$202
448	ERR\$202		
450	A*1 A*2		ABATPROC
458	ABATABND		ABATLIMT
460	AUSERST		
468			DOSLBSV
470	DOSDIRC		
.	.	.	.
490	DOSLIBL		
.	.	.	.
4D8	A*3 A*4		ALTASAVE
4E0	ABGCOM		ASYSCOM
4E8	ADOSDCSS		SVC12SAV
4F0	DOSFIRST		DOSNUM
4F8	APPSAVE		DOSTRANS
500	MAINLIST		MAINSTRT
508	FREELIST		FREENUM
510	MAINHIGH		FREELOWE
518	FREELOWR		FREEUPPR
520	ANUCEND		AUSRAREA

528	CURRSAVE		CODE203		PCTCMSFS
530	ADMSFRT		VCADTLKP		
538	VCADTNXT		VCADTLKW		
540	CURRIOOP		PENDREAD		
548	PENDWRIT		FSIFINRD		
550	LSTFINRD		AINTRTBL		
558	AOUTRTBL		NUMFINRD		NUMPNDWR
560	VMSIZE		ALERTBLS		
568	STRTADDR		FRSTLOC		
570	LASTLOC		LOCCNT		
578	LDRADDR		LDRRTCD		
580		PSW			
588	LDRFLAGS		PRHOLD		
590	TBENT	A*5	A*6		GET1
598		DSYM			
5A0	JSYM		A*7		
5A8			ALIASENT		
5B0	DYNAEND				
5B8					
5C0	FCBFIRST		FCENUM		A*8
5C8					LINKLAST
5D0	LINKSTRT		TAXEADDR		
5D8	ATSOCPPL		DCBSAV		
5E0	A*9	A*10	A*11	A*12	/ / / / / A*13 A*14
5E8	A*15	A*16	A*17	/ / / / /	ASYSNAMS
5F0	ACMSSEG		ADMSLIO		
5F8	VCFSTLK		VCFSTLK		
600	AFVS		AOPSECT		
608	ADEVTAB		AFSTLK		
610	AGETCLK		AFSTLK		

618	APIE		AIADT
620	AUSER		ARDTK
628	ASCANN		ASSTAT
630	ATABEND		ASUBSECT
638	AOSMODL		AWRTK
640	ASTRINIT		IAIT
648	AFREE		AFRET
650	ADMSPIOC		APGMSECT
658	AIOSECT		ADMPEXEC
660	ADIOSECT		AABNSVC
668	ADMSERL		ADMSCRD
670	ADMSFREB		ASVCSECT
678	AADTLKP		AUPUFD
680	ASTATEXT		AOSRET
688	ACMSRET		ASCANO
690	AEXEC		ASTART
698	AADTLKW		AUSABRV
6A0	AEXTSECT		ASCBPTR
6A8	ADMSROS		LDMSROS CDMSROS
6B0	AACTLKP		AACTNXT
6B8	AACTFREE		AACTFRET
6C0	AADTNXT		ATRKLKP
6C8	ATRKLKPX		AQQTRK
6D0	AQQTRKX		AERASE
6D8	ATYPSRCH		AUPDISK
6E0	AKILLEX		ATFINIS
6E8	ARDBUF		AWRBUF
6F0	AFINIS		ASTATE
6F8	ASTATEW		APCINT

Hexadecimal Displacement	Field Name	Machine Usage	Field Description, Contents, Meaning
0	IPLPSW	DS 1D	Initial program load of PSW
8	IPLCCW1	DS 1D	Initial program load of CCW1
10	IPLCCW2	DS 1D	Initial program load of CCW2
		ORG	IPLPSW
0	RSTNPSW	DS 1D	PSW restart new PSW
8	RSTOPSW	DS 1D	PSW restart old PSW
10	ACMSCVT	DS 1F	Address of simulated OS CVT
14	ASYSREF	DS 1F	Address of nucleus address table
18	EXTOPSW	DS 1D	External old PSW
20	SVCOPSW	DS 1D	Supervisor call old PSW
28	PGMOPSW	DS 1D	Program old PSW
30	MCKOPSW	DS 1D	Machine-check old PSW
38	IOOPSW	DS 1D	Input/output old PSW
40	CSW	DS 1D	Channel status word
48	CAW	DS 1F	Channel address word
4C	NUCRSV1	DS 1F	Reserved for IBM use
50	TIMER	DS 1F	Interval timer
54	NUCRSV2	DS 1F	Reserved for IBM use
58	EXTNPSW	DS 1D	External new PSW
60	SVCNPSW	DS 1D	Supervisor call new PSW
68	PGMNPSW	DS 1D	Program new PSW
70	MCKNPSW	DS 1D	Machine-check new PSW
78	IONPSW	DS 1D	Input/output new PSW
80	CPULOG	DS 48D	Processor logout area
		ORG	CPULOG
80	NUCRSV3	DS 2D	Reserved for IBM use
90	NUCRSV4	DS 1F	Reserved for IBM use
94	MONCLASS	DS 1H	Monitor call class number
96	PERCODE	DS 1H	Program event recorder code
98	PERADDR	DS 1F	Program event recorder address
9C	MONCODE	DS 1F	MONITOR CALL code
A0	NUCRSV5	DS 4D	Reserved for IBM use
C0	LOWSAVE	DS XL160	Save area for first 160 bytes of storage
160	FPRLOG	DS 4D	Floating-point register logout area
180	GPRLOG	DS 16F	General-purpose register logout area
1C0	ECRLOG	DS 16F	Extended control register logout area
		System Usage	
200	SYSTEMID	DS CL32	System name and date
220	INSTALID	DS CL64	Installation identification
260	SYSNAME	DS CL8	Name of saved system loaded (via IPL)
268	IPLADDR	DS 1H	Address of device loaded (via IFL)
26A	SYSADDR	DS 1H	Address of system disk
26C	DEVICE	DS 1F	Name of device causing last I/O interrupt
270	NUCRSV6	DS 1F	Reserved for IBM use
274	FEIBM	DC CL12'FEIBM154067'	FE service number
280	DIAGTIME	DS CL24	Buffer for DIAGNOSE timer
		ORG	DIAGTIME
280	CURRDATE	DS CL8	Current date - mm/dd/yy
288	CURRTIME	DS CL8	Current time - hh.mm.ss
290	CURRVIRT	DS 1F	Current elapsed virtual time used
294	CURRCPUT	DS 1F	Current elapsed processor time used
298	LASTVIRT	DS 1F	Previous elapsed virtual time used
29C	LASTCPUT	DS 1F	Previous elapsed processor time used
2A0	LASTCMND	DC CL8' '	Last command issued
2A8	PREVCMND	DC CL8' '	Next to last command
2B0	LASTEEXEC	DC CL8' '	Last EXEC procedure
2B8	PREVEEXEC	DC CL8' '	Next to last EXEC procedure

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
2C0	LASTLMOD DC CL8' '	Last module LOADMOD into main storage
2C8	LASTTMOD DC CL8'ACCESS'	Last module LOADMOD into transient area
2D0	DATIPCMS DC D'0'	Date (mm/dd/yy) at last IPL CMS
2D8	CLKVALMD DC D'0'	Time (STCK form) at midnight (0000 hours)
		<u>Macro and Text Library Pointers</u>
2E0	MACDIRC DC 8A(0)	Address of macro library directories
300	MACLIBL DC 18F'-1'	Current macro library names
348	TXLIBSV DC F'0'	Library save area for TXTLIBS
34C	MACLBSV DC F'0'	Library save area for MACLIPS
350	TOTLIBS DC F'0'	Total global chains (in bytes)
354	TXTDIRC DC A(0)	Address of TEXT library directories
358	TXTLIBS DC 18F'-1'	Current TXFT library names
		<u>Debug Dump Parameters</u>
3A0	DUMPLIST DS 0D	DEBUG DUMP PLIST
3A0	GRS015 DC A(GPRLOG)	Address of GPR save area
3A4	LOC0176 DC A(LOWSAVE)	Address of low storage save area
3A8	FIRSTDMP DC A(0)	Address of first location to dump
3AC	LASTDMP DC A(0)	Address of last location to dump
3B0	FRS06 DC A(FPRLOG)	Address of FPR save area
3B4	DMPTIT DC A(DMPTITLE)	Address of dump title line
3B8	DC 4X'FF'	Reserved for IBM use
3BC	DMPTITLE DC CL132' '	Dump title line
440	GLBLTABL DC F'0'	Reserved for IBM use
444	DC H'0'	Used for alignment
446	SVC\$202 SVC 202	Common SVC for reentrant code
448	ERR\$202 DC A(**+4)	User will fill if necessary
44C	BR 14	Return to caller
44E	DC H'0'	Reserved for IBM use
		<u>Batch Monitor Information</u>
450	BATFLAGS DC 1X'00' A*1	Batch flags
		<u>Bits defined in BATFLAGS</u>
	BATRUN EQU X'80'	Batch monitor running
	BATLOAD EQU X'40'	Loading batch processor
	BATNOEX EQU X'20'	Suppress user job execution
	BATRERR EQU X'10'	Batch reader error
	BATCPEX EQU X'08'	CP command executing
	BATUSEX EQU X'04'	User job executing
	BATMOVE EQU X'02'	MOVEFILE executing from terminal
	BATTERM EQU X'01'	User job being flushed
451	BATFLAG2 DC 1X'00' A*2	More batch flags
		<u>Bits defined in BATFLAG2</u>
	BATXLIM EQU X'80'	User job limit exceeded
	BATXCPU EQU X'40'	Processor time exceeded
	BATXPRT EQU X'20'	No. of printed lines exceeded
	BATXPUN EQU X'10'	No. of punched cards exceeded
	BATDCMS EQU X'08'	Disabled CMS command called
	BATIPLSS EQU X'04'	Batch loading (via IPL) saved system
	BATSTOP EQU X'02'	Batch stopping after current job
	BATSYSAB EQU X'01'	System abnormal termination in process
452	DC 2X'00'	Reserved for IBM use
		<u>Batch Processor Entry Points</u>
454	ABATPROC DC A(0)	Main entry
458	ABATABND DC A(0)	User job abend entry
45C	ABATLIMT DC A(0)	User job limits table
460	AUSERST DC A(0)	Virtual machine restart entry point
464	DC 2F'0'	Reserved for IBM use

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>DOS Library Pointers</u>		
46C	DOSLBSV DC F'0'	Library save area for DOSLIBS
470	DOSDIRC DC 8A(0)	Address of DOS library directories
490	DOSLIBL DC 18F'-1'	Current DOS library names
4D8	DOSFLAGS DC X'00'	A*3 DOS simulation flags
<u>Bits defined in DOSFLAGS</u>		
	DOSMODE EQU X'80'	DOS environment flag
	DOSSVC EQU X'40'	DOS SVC simulation flag
	DOSVSAM EQU X'20'	DOS VSAM running flag
	DOSCOMP EQU X'10'	DOS compiler running flag
	DOSPIO EQU X'08'	DOS printer indicator
	VSMINSTL EQU X'04'	VSAM installation flag to relocate DCSS table
4D9	DOSRC DC X'00'	A*4 DOS return code to user
4DA	DC 2X'00'	Reserved for IBM use
4DC	ALTASAVE DC V(LTASAVE)	Address of LTA save area
4E0	ABGCOM DC V(BGCOM)	Address of partition communication region
4E4	ASYSCOM DC V(SYSCOM)	Address of system communication region
4E8	ADOSDCSS DC A(0)	Address of DOS DCSS
4EC	SVC12SAV DC F'0'	Work area for SVC 12
4F0	DOSFIRST DC A(0)	Address of first DOSCB in chain
4F0	DOSNUM DC H'0'	Number of DOSCBs in chain
4F6	DOSKPART DS H'0'	Number of K-bytes in DOS partition
4F8	APPSAVE DC V(PPSAVE)	Address of problem program save area
4FC	DOSTRANS DC A(0)	Address of DOS transient area
<u>Free Storage Pointers</u>		
500	MAINLIST DC A(0)	Address of first block of user free storage
504	MAINSTRT DC V(USERAREA)	Address of the start of user free storage
508	FREELIST DC V(NUCEND)	Address of first block of system storage
50C	FREENUM DC F'1'	Number of blocks of system storage
510	MAINHIGH DC V(USERAREA)	High extend of user free storage
514	FREELOWE DC V(NUCEND)	Low extend of system free storage
518	FREELOWR DC V(TRANSAR)	Lower limit of system free storage
51C	FREEUPPR DC A(0)	Upper limit of system free storage
520	ANUCEND DC V(NUCEND)	Address of end of nucleus storage area
524	AUSRAREA DC V(INITSUB)	Address of beginning of user area
528	CURRSAVE DC A(0)	Address of current save area
52C	CODE203 DC H'0'	Code number of last SVC 203
52E	FRERESPG DS H'2'	Amount of user storage to reserve for CMS free storage (pages: >=2)
530	ADMSFRT DC V(DMSFRT)	DMSFRE work area
534	VCADTLKP DS A(DMSLAD)	BALR equivalent of ADTLKP
538	VCADTNXT DC A(DMSLADN)	BALR equivalent of ADTNXT
53C	VCADTLKW DC A(DMSLADW)	BALR equivalent of ADTLKW
<u>Console I/O Pointers</u>		
540	CURRIOOP DC A(0)	Address of current I/O buffer
544	PENDREAD DC A(0)	Address of pending read operation
548	PENDWRIT DC A(CONSTACK)	Address of pending write operation
54C	FSTFINRD DC A(0)	Address of finished read buffer
550	LSTFINRD DC A(0)	Address of last finished read buffer
554	AINTRTBL DC A(0)	Address of user input translate table
558	AOUTRTBL DC A(0)	Address of user output translate table
55C	NUMFINRD DC H'0'	Number of finished read buffers
55E	NUMPNDWR DC H'0'	Number of pending write operations

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>Loader Information</u>		
560	VMSIZE DS	1F Virtual storage size
564	ALDRTBLS DC	1F'0' Address of loader tables
568	STRTADDR DC	1F'0' Module starting address
56C	FRSTLOC DC	1F'0' Module beginning address
570	LASTLOC DC	1F'0' Module ending address
574	LOCNT DC	1F'0' Loader location counter
578	LDRADDR DC	1F'0' Loader return address
57C	LDRRTCD DC	1F'0' Loader return code
580	PSW DC	1D'0' User's starting PSW
588	LDRFLAGS DC	1F'0' Loader flags
58C	PRHOLD DC	1F'0' Pseudo register counter
590	TBENT DC	H'0' Initialize table entries to zeros
592	UNRES DC	X'00' Unresolved reference bit for CMS loader
593	MODFLGS DC	1X'00' A*6 Flags
<u>Bits defined in MODFLGS</u>		
	NOMAPFLG EQU	X'80' NOMAP flag
	CLEAROP EQU	X'40' CLEAR option flag
	MODGNDOS EQU	X'20' Module generated with DOS option
	MODGNALL EQU	X'10' Module generated with ALL option
	SYSLOAD EQU	X'08' Allow load greater than FREELCWE or less than transient
	MDPCALL EQU	X'04' Indicate module called by DMSMDF
	MOD6 EQU	X'02' Reserved for IBM use
	MOD7 EQU	X'01' Reserved for IBM use
594	GET1 DC	1F'0' DMSLSY R1 save location
598	DSYM DC	2F'0' DMSLSY work space
5A0	JSYM DC	F'0' DMSLSY unique identifier base
5A4	NXTSYM DC	C'Z' A*7 First character of unique identifier
5A5	DC	XL7'0' Rest of unique identifier
5AC	ALIASENT DC	1F'0' Alias entry point (dynamic load)
5B0	DYNAEND DC	1F'0' Maximum load location (dynamic load)
5B4	DS	3F Reserved for IBM use
<u>OS Simulation Pointers</u>		
5C0	FCBTAB DS	0D FCB chain anchor
5C0	FCBFIRST DC	A(0) Address of first FCB
5C4	FCBNUM DC	H'0' Number of FCBs in chain
5C6	DC	X'00' Reserved for IBM use
5C7	OSSFLAGS DC	X'00' A*8 OS simulation flags
<u>Bits defined in OSSFLAGS</u>		
	COMPWT EQU	X'80' Compiler switch
	OSSMNU EQU	X'40' DMSSMN unconditional flag
	OSRESET EQU	X'20' Reset for OS
	OSWAIT EQU	X'10' Wait for OS
	DYLD EQU	X'08' Dynamic loading in process
	DYLIBO EQU	X'04' Omit dynamic library scan
	DYLIBNOW EQU	X'02' Dynamic library scan
	DYMBRNM EQU	X'01' Linked via member name
5C8	DC	A(0) Reserved for IBM use
5CC	LINKLAST DC	A(0) Address of last OS linkage block
5D0	LINKSTRT DC	A(0) Address of entry point of last module
5D4	TAXEADDR DC	A(0) Terminal attention exit element address
5D8	ATSOCPPPL DC	V(CPP) Address of TMP PLIST for TSO programs
5DC	DCBSAV DC	1F'0' DCB restoration address

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
5E0	OPTFLAGS DC	1X'00'	A*9	Option flags
				<u>Bits defined in OPTFLAGS</u>
	NOIMPEX EQU	X'80'		No implied EXEC commands
	NOIMPCP EQU	X'40'		No implied CP commands
	NOSTDSYN EQU	X'20'		No standard synonyms
	NOABBREV EQU	X'10'		No command abbreviations
	NOPAGREL EQU	X'08'		No automatic page release
	NOREAD EQU	X'04'		No automatic VM/370 console read
5E1	MISFLAGS DC	1X'00'	A*10	Miscellaneous flags
				<u>Bits defined in MISFLAGS</u>
	KXSWITCH EQU	X'80'		Halt execution switch
	KOSWITCH EQU	X'40'		Halt tracing switch
	RELPAGES EQU	X'20'		Release pages switch
	GRAFDEV EQU	X'10'		Graphics console
	QSWITCH EQU	X'08'		Quiet switch for console read
	NODDSK EQU	X'04'		Do not access D-disk
	NEGITS EQU	X'02'		Negative return code from DMSITS
	ATTNHIT EQU	X'01'		Attention posted
5E2	MSGFLAGS DC	1X'00'	A*11	Message flags
				<u>Bits defined in MSGFLAGS</u>
	NOTYPOUT EQU	X'80'		No typing - set by EXEC
	NOTYPING EQU	X'40'		No typing - set by HT
	NORDYMSG EQU	X'20'		No ready message to be typed
	NORDYTIM EQU	X'10'		No time on ready message
	REDERRID EQU	X'08'		Error code to be typed in red
	NOERRMSG EQU	X'04'		No error messages to be typed
	NOERRRTXT EQU	X'02'		No text on error messages
	SPECLF EQU	X'01'		Linefeed for typewriter CCW
5E3	DBGFLAGS DC	1X'00'	A*12	DEBUG flags
				<u>Bits defined in DBGFLAGS</u>
	DBGEXEC EQU	X'80'		DEBUG routine executing
	DBGPGMCK EQU	X'40'		DEBUG entered by a program check
	DBGEXIT EQU	X'20'		DEBUG entered by an external interrupt
	DBGABN EQU	X'10'		DEBUG entered from DMSABN
	DBGNSHR EQU	X'08'		No shared segment present
	DBGSHR EQU	X'04'		Shared segment present
	DBGRECUR EQU	X'02'		Recursion flag
5E4	DC	2X'00'		Reserved for IBM use
5E6	EXECFLAG DC	1X'00'	A*13	EXEC flags
				<u>Bit defined in EXECFLAG</u>
	EXECRUN EQU	X'80'		EXEC command running
5E7	PROTFLAG DC	1X'00'	A*14	Storage protection flags
				<u>Bits defined by PROTFLAG</u>
	PRFPOFF EQU	X'80'		Storage protection is shut off
	PRFTSYS EQU	X'40'		System routine in transient area
	PRFUSYS EQU	X'20'		System routine in user area
5E8	TSOFLAGS DC	1X'00'	A*15	TSO flag byte
				<u>Bit defined in TSOFLAGS</u>
	TSOATCNL EQU	X'80'		Read canceled by attention

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
5E9	SUBFLAG DC X'00' A*16	CMS subset flag byte		
	Bits defined in SUBFLAG			
	SUBREJ EQU X'08'	Subset command reject		
	SUBRTN EQU X'04'	Subset return		
	SUBINIT EQU X'02'	Subset initialization		
	SUBACT EQU X'01'	Subset active		
5EA	DCSSFLAG DC X'00' A*17	DCSS indicators		
	Bits defined in DCSSFLAG			
	DCSSAVAL EQU X'80'	CMSSEG segment exists		
	DCSSLDED EQU X'40'	CMSSEG loaded		
	DCSSCPNV EQU X'20'	CP or invalid command issued		
	DCSSLDSO EQU X'10'	Loading S-disk		
	DCSSVTNA EQU X'08'	DMSSVT not available		
	DCSSVTLD EQU X'04'	DMSSVT is loaded		
	DCSSOVL P EQU X'02'	Virtual machine storage overlaid by DCSS		
	DCSSJLNS EQU X'01'	CMSSEG just loaded nonshared		
5EB	DC X'00'	Reserved for IBM use		
5EC	ASYSNAMS DC V(SYSNAMES)			
5F0	ACMSSEG DC F'0'	Address of CMS saved segment		
5F4	ADMSLIO DC V(DMSLIO)			
5F8	VCFSTLK P DC V(DMSLFS)	EALR equivalent of FSTLK P		
5FC	VCFSTLK W DC V(DMSLFSW)	EALR equivalent of FSTLK W		
	<u>Nucleus Address Table</u>			
600	SYSREF DS OD			
600	AFVS DC V(FVS)			
604	AOPSECT DC V(OPSECT)			
608	ADEVTAB DC V(DEVTAB)			
60C	AFSTLK P DC V(FSTLK P)			
610	AGETCLK DC V(DMSINNM)			
614	AFSTLK W DC V(FSTLK W)			
618	APIE DC V(PIE)			
61C	AIADT DC V(IADT)			
620	AUSER DC V(USERSECT)			
624	ARDTK DC V(DMSDIOR)			
628	ASCANN DC V(DMSSCNN)			
62C	ASSTAT DC A(0)			
630	ATABEND DC V(TABEND)			
634	ASUBSECT DC V(SUBSECT)			
638	AOSMODL DC A(0)			
63C	AWRTK DC V(DMSDIOW)			
640	ASTRINIT DC V(DMSSTGST)			
644	IADT DC V(ADTSECT)			
648	AFREE DC V(FREE)			
64C	AFRET DC V(FRET)			
650	ADMSPIOC DC V(DMSPIOCC)			
654	APGMSECT DC V(PGMSECT)			
658	AIOSECT DC V(IOSECT)			
65C	ADMPEXEC DC V(DMSDBD)			
660	ADIOSECT DC V(DIOSECT)			
664	AABNSVC DC V(DMSABNUA)			
668	ADMSERL DC V(DMSERL)			
66C	ADMSCRD DC V(DMSCRD)			
670	ADMSFREB DC V(DMSFREB)			
674	ASVCSECT DC V(SVCSECT)			
678	AADTLKP DC V(ADTLKP)			
67C	AUPUF D DC V(DMSAUDUP)			
680	ASTATEXT DC A(0)			
684	AOSRET DC V(OSRET)			
688	ACMSRET DC V(CMSRET)			

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
68C	ASCANO	DC V(DMSSCNO)
690	AEXEC	DC V(DMSEXC)
694	ASTART	DC V(DMSLDRA)
698	AADTLKW	DC V(ADTLKW)
69C	AUSABRV	DC V(USABRV)
6A0	AEXTSECT	DC V(EXTSECT)
6A4	ASCBPTR	DC V(SCB PTR)
6A8	ADMSROS	DC A(0)
6AC	LDMSROS	DC H'0'
6AE	CDMSROS	DC H'0'
6B0	AACTLKP	DC V(DMSLAF)
6B4	AACTNXT	DC V(DMSLAFNX)
6B8	AACTFREE	DC V(DMSLAFFE)
6BC	AACTFRET	DC V(DMSLAFFT)
6C0	AADTNXT	DC V(ADTNXT)
6C4	ATRKLKP	DC V(DMSTRK)
6C8	ATRKLKPX	DC V(DMSTRKX)
6CC	AQQTTRK	DC V(DMSTQQ)
6D0	AQQTTRKX	DC V(DMSTQQX)
6D4	AERASE	DC V(DMSERS)
6D8	ATYPSRCH	DC V(TYPSRCH)
6DC	AUPDISK	DC V(DMSAUD)
6E0	AKILLEX	DC V(KILLEX)
6E4	ATFINIS	DC V(DMSFNST)
6E8	ARDBUF	DC V(DMSBRD)
6EC	AWRBUF	DC V(DMSBWR)
6F0	AFINIS	DC V(DMSFNS)
6F4	ASTATE	DC V(DMSSTTE)
6F8	ASTATEW	DC V(DMSSTTW)
6FC	APOINT	DC V(POINT)
<u>Terminal Buffers</u>		
700	CONCCWS	DS OD
700	CONCCWS	CCW 0,0,X'60',0
708		CCW 3,0,X'20',1
710	CONINBLK	DC A(0)
714		DC XL1'0A'
715		DC AL1(134)
716	CONINBUF	DS CL134
7A0		DS OD
7A0	CMNDLINE	DS CL160
840		DS OD
840		DC CL8'EXEC'
848	CMNDLIST	DS CL536
A60		DS OD
A60	CONSTACK	DS CL320
<u>Save Areas</u>		
B40	FREESAVE	DS 16F
B40	BALRSAVE	DS 16F
C20	WAITSAVE	DS 16F
<u>VSAM and AMSERV Control Words</u>		
C60		DS OD
<u>Percent of Available User Storage To Reserve for GETVIS/FREEVIS Use When Running VSAM</u>		
C60	PCTVSAM	DC H'50'
C62		DS 1H
C64		DS 1F
		50 percent for CMS/VSAM use
		Reserved for IBM use
		Reserved for IBM use

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>Beginning and End of IKQLAB (when in storage)</u>		
C68	ADIKQLAB DC	A(X'FFFFFF')
C6C	NDIKQLAB DC	A(0)
C70	ARURTBL DC	V(RURTBL)
C74	ADMSVIB DC	V(DMSVIB)
C78	AVIPWORK DC	A(0)
C7C	VSAMFLG1 DC	X'00' A*18 VSAM information flag
<u>Bits defined in VSAMFLG1</u>		
	VSAMRUN EQU	X'80'
	VSJOBCAT EQU	X'40'
	VIPINIT EQU	X'20'
	VSAMSERV EQU	X'10'
	VIPSOP EQU	X'08'
	VIPTCLOS EQU	X'04'
	VSAMSOS EQU	X'02'
		VSAM system loaded
		VSAM job catalog active
		DMSVIP has been initialized
		CMSAMS system loaded (AMSERV running)
		OS interface SVC 2 call
		OS TCLOSE call
		OS AMSERV running
C7D	DS	3X
C80	AVSAMSYS DC	A(0)
C84	AAMSSYS DC	A(0)
C88	AVSREOJ DC	V(\$\$BEOJ4)
C8C	AVSRWORK DC	A(0)
C90	ACBLIST DC	A(0)
C94	DS	3F
CA0	DS	0D
		Reserved for IBM use
		Address of VSAM saved system
		Address of CMSAMS saved system
		DMSVSR entry point from VSAM \$\$EACLOS
		Address of IMSVSR work area
		ACE list built by OPEN/CLOSE
		Reserved for IBM use

OPSECT: MAJOR CSECT FOR ALL I/O OPERATION LISTS

OPSECT describes the fields used by several programs as parameter lists for reading and writing on disks and other devices. The OPSECT CSECT is pointed to by the AOPSECT field in NUCON.

0	CMSOP		
8	FILENAME		
10	FILETYPE		
18	FILEMODE	FILEITEM	FILEBUFF
20	FILEBYTE	FILEFORM	FILECOUT
28	FILEREAD		SAVER14
30	SAVER15		SAVER0
38	SAVER1		CMSNAME
40	CMSNAME (cont.)		CONREAD
48	CONREAD (cont.)		CONRDBUF
50	A*1	CONRDCNT	
58	WAITLIST		
60	CONWRITE		
68	CONWRBUF	A*2	CONWRCNT
70	WAITLST		
78	WAITDEV		
80			REALLST
88	READLST (cont.)		RDBUFF
90	RDCCW	RDCOUNT	PUNCHLST
98	PUNCHLST (cont.)		PUNBUFF
A0	PUNCOUNT		PRINTLST
A8	PRINTLST (cont.)		PRBUF
B0	PRCNT		TAPELIST
B8	TAPELIST (cont.)		TAPEOPER
C0	TAPEOPER (cont.)		TAPEDEV
C8	A*3	TAPEBUFF	TAPESIZE

D0	TAPECOUT		CLOSIO
D8	CLOSIO (cont.)		CLOSIODV
E0	CLOSIODV (cont.)		
E8			
118	EXLEVEL		EXF1
120	EXNUM		EXAID
128			
130	FCBIO	A*4	


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning	
<u>Main I/O Operation List</u>			
0	PLIST	DS	OD
0	CMSOP	DS	CL8
8	FILENAME	DS	CL8
10	FILETYPE	DS	CL8
18	FILEMODE	DS	CL2
1A	FILEITEM	DS	H
1C	FILEBUFF	DS	F
20	FILEBYTE	DS	F
24	FILEFORM	DS	CL2
26	FILECOUT	DS	H
28	FILEREAD	DS	F
	POINTERS	EQU	FILEITEM
	AFST	EQU	FILEBUFF
	IOAREA	EQU	FILEBUFF
	IOLENGTH	EQU	FILEBYTE
			Buffer area location
			Buffer length
<u>Immediate Register Save Area</u>			
2C	SAVER14	DC	F'0'
30	SAVER15	DC	F'0'
34	SAVER0	DC	F'0'
38	SAVER1	DC	F'0'
3C	CMSNAME	DC	CL8'FILE'
<u>Console Parameter Lists</u>			
44		DS	OF
<u>Read Console</u>			
44	CONREAD	DC	CL8'WAITRD'
4C	CONRDBUF	DC	V(CMNDLINE)
50	CONRDCOD	DC	C'U' A*1
51		DC	X'0'
52	CONRDCNT	DC	AL2(0)
54		DC	F'0'
			Reserved for IBM use
<u>Console Wait List</u>			
58	WAITLIST	DS	OF
58		DC	CL8'CONWAIT'

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>Write Console</u>		
60	CONWRITE DS	OF
60	DC	CL8'TYPLIN'
68	CONWRBUF DC	A(0)
6C	CONWRCOD DC	C'B' A*2 Color code
6D	DC	X'00'
6E	CONWRCNT DC	AL2(0) Length of message text
<u>Wait Parameter List</u>		
70	WAITLST DS	OF
70	DC	CL8'WAIT'
78	WAITDEV DC	CL4'CON1' Address of IMSCWT
7C	DC	F'0'
80	DC	F'0'
<u>Reader Parameter List</u>		
84	READLST DS	OF
84	DC	CL8'CARDRD'
8C	RDBUFF DC	A(0) Buffer address
90	RDCCW DC	H'0' CCW byte count
92	RDCOUNT DC	H'0' Bytes actually read
<u>Card Punch Parameter List</u>		
94	PUNCHLST DS	OF
94	DC	CL8'CARDPH'
9C	PUNBUFF DC	A(0) Punch buffer address
A0	PUNCOUNT DC	A(0) Punch CCW count
<u>Printer Parameter List</u>		
A4	PRINTLST DS	OF
A4	DC	CL8'PRINTR'
AC	PRBUF DC	A(0) Printer buffer address
B0	PRCNT DC	A(0) Printer data count
<u>Tape Parameter List</u>		
B4	TAPELIST DS	OF
B4	DC	CL8'TAPEIO'
BC	TAPEOPER DC	CL8' ' Tape operation command
C4	TAPEDEV DC	CL4'TAP1' Tape symbolic device
C8	TAPEMASK DC	X'00' A*3 Set mode
C9	TAPEBUFF DC	AL3(0) Buffer location
CC	TAPESIZE DC	F'0'
D0	TAPECOUT DC	F'0' Tape counter
<u>Close Out Device Dependent Data Set on Unit Record Equipment</u>		
D4	CLOSIO DS	OF
D4	DC	CL8'CLOSIO' Operation
DC	CLOSIODV DC	CL8' ' Device type
E4	DC	4X'FF'
E8	DC	6D'0' Reserved for IBM use
<u>Storage for EXEC Bootstrap</u>		
118	EXLEVEL DC	F'0' EXEC level
11C	EXF1 DC	F'1' Follows EXEC level
120	EXNUM DC	F'0' Number of doublewords of free storage
124	EXADD DC	F'0' Address of EXECUTOR in storage
128	DC	2F'0' Reserved for IBM use
<u>Storage for OS Macro Simulation Routines</u>		
130	FCBIO DC	A(0) Address of last FCB used during I/O
134	OSIOTYPE DC	X'DD' A*4 OS access method type

OSFST

OSFST: OS FILE STATUS TABLE

OSFST describes the fields of an OS file status table. When an OS disk is accessed, DMSROS obtains storage from CMS free storage, builds and fills in an OSFST block, which is comparable to a CMS FST block. This block is released by DMSALU.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	OSFSTFM DS	1H Disk mode
2	DS	1H Reserved for IBM use
4	OSFSTBLK DS	1H Block size
6	OSFSTFVF DS	1H Fixed/variable flag
8	OSFSTLRL DS	1F Logical record size
C	OSFSTRFM DS	1X A*1 OS record format
D	DS	1X Reserved for IBM use
E	OSFSTFLG DS	1X A*2 Flag byte
<u>Bits defined in OSFSTFLG</u>		
	OSFSTALT EQU X'80'	Alternate track indicator
	OSFSTDBK EQU X'40'	Block size not specified in DSCE
	OSFSTMVL EQU X'08'	Multiple volume data set
	OSFSTUMV EQU X'02'	Unmoveable data set
	OSFSTRSW EQU X'01'	Indicates point+1 just issued
F	OSFSTXNO DS	1X A*3 Number of data extents on disk
10	OSFSTNXT DS	1F Next OS FST
14	OSFSTCHR DS	5X CCHHR of last I/O operation

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
19	OSFSTEND DS	5X	Current extent end
1E	OSFSTDSDN DS	44C	Data set name
4A	OSFSTXTN DS	170X	Data extents description
			<u>Bits defined in OSFSTXTN</u>
	OSFSTEX4 EQU	OSFSTXTN*30	Location of fourth extent from DSCB3
F4	OSFSTDSDK DS	1H	Disk address (0cuu)
F6	OSFSTTYP DS	1H	Disk device type (see OSADT for type flags)
F8	OSFSTNTE DS	5X	Used to save CCPHR for NCTE macro
FD	DS	3X	Reserved for IBM use
100	OSFSTTRK DS	1F	No. of tracks per cylinder
104	DS	2F	Reserved for IBM use
10C	OSFSTMEM DS	CL8	Partitioned data set member name
114	DS	1F	Reserved for IBM use
118	DS	0D	
	OSFSTLTH EQU	(*-OSFST)/8	OS FST length in doublewords (X'35')

OVSECT, PCTAB

OVSECT: DESCRIBES THE FIRST FEW LOCATIONS OF DMSOVS

OVSECT is used by module DMSOVS to provide trace information requested by SVCTRACE.

0	OVSGO		AERR
8	AWAIT		LENOVS

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	OVSGO	B	**
4	AERR	DC	A(0)
8	AWAIT	DC	A(0)
C	LENOVS	DC	A(0)

PCTAB: PROGRAM CHECK OPTION TABLE

PCTAB is used by DOS/VS routines in the event of a program check. The address of PCTAB is in bytes X'64' and X'65' of the partition communication region (BGCCM).

0	PCROUT		PCSAVE
---	--------	--	--------

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
	PCTAB	EQU	*-8
0	PCROUT	DC	F'0'
4	PCSAVE	DC	F'0'

PDSSECT: DIRECTORY TABLE FOR BPAM SIMULATION

PDSSECT describes the fields of the in-storage directory that is used in CS simulation of BPAM. The in-storage directory is built dynamically by DMSSVT from CMS free storage.

0	DIRNAME			DIRPTR
8	A*1	A*2	CORESIZE	PDSBLKSI A*3 ///////////////


Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DIRNAME DS	3H MACLIB identifier
6	DIRPTR DS	1H Item pointer to start of directory
8	TEMPBYTE DS	1X A*1 If byte has dollar sign (\$), then PDS is in \$PDSTEMP file
9	NEWBLKS DS	1X A*2 No. of new blocks added to PDS by STOW
A	CORESIZE DS	1H Size of dictionary in bytes
C	PDSBLKSI DS	1H Block size of dictionary
E	CHNGBYTE DS	1X A*3 Indicates updates to dictionary
F	DS	1X Reserved for IBM use
10	PDSDIR DS	0F Start of in-storage dictionary

PGMSECT

PGMSECT: PROGRAM INTERRUPT WORK AREA

PGMSECT describes the fields used by DMSITP for saving registers, old PSW, and other data for handling program interrupts.

The PGMSECT CSECT is pointed to by the APGMSECT field in NUCON.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning	
0	Storage for Program Interrupt Routine (DMSITP)	DEBPSW	DC F'0', V(DMSDBG) Point to debug
4			DC 1F Reserved for IBM use
8	PIE	DS OD	Program interrupt element
8	PICADDR	DC F'0'	PICA address from recent SPIE
C	OPSW	DC 2F'0'	Old PSW after program interrupt
14		DC 5F'0'	Registers are: R14, R15, R0, R1, and R2
	*EPIE		End program interrupt element
28	TEMPOLD	DC 8X'00'	Work area
30	TEMPNEW	DC 8X'00'	Work area
38	R13AREA	DC F'0'	Saved R13
3C	PSAVE	DC 16F'0'	Registers saved at interrupt time
7C	SCBPTR	DC F'0'	Pointer to first STAE control block
	Bits defined in SCBPTR		
	STAEBIT	EQU X'80'	
	STAIBIT	EQU X'40'	
	RETRYBIT	EQU X'20'	
80	SCBWORK	DC A(0)	Address of work area for STAE exit routine
84	SCBSAV12	DC A(0)	Address of R12 save area for DMSSAB
88	SCBSAV13	DC A(0)	Address of R13 save area for DMSSAB
8C	SCBSAV14	DC A(0)	Address of R14 save area for DMSSAB
90	AUPIE	DS A	Address of user's PIE, in SPIE exit

PIBADR: PROGRAM INFORMATION BLOCK

PIBADR contains a save area address and interrupt information. PIBADR is invoked by the PIBTAB macro and is often referred to by this macro name. The PIBPT field in the EGCCM block points to the PIBTAB CSECT.

0	A*1		A*2		PIBLOGID		PIESAVE					
8	PIBSAV2					A*3		A*4		A*5		A*6

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	PIBFLG DS X	A*1 Flags
1	PIBCNCL DS X	A*2 Cancel code
2	PIBLOGID DS XL2	SYSLOG ID
4	PIBSAVE DS XL4	Address of save area
<u>Bits defined in PIERSAVE</u>		
	ARFLG EQU PIBADR+8	Save area address
8	PIBSAV2 DS XL4	Address of system save area
C	PIBPUBAS DS X	A*3 PUP assign flags
D	PIBLUBID DS X	A*4 LUE number of first problem program LUB
E	PIBLUBNO DS C	A*5 Number of LUBs
F	PIBFLG2 DS C	A*6 More flags
<u>ORG PIBADR</u>		
0	PIBCOMRA DS XL2	PIE extension DSECT
2	SYSLUBX DS XL2	Communications region address
4	INTINFO DS XL4	System class LUB address
	Interrupt information	
<u>Bits defined in INTINFO</u>		
	SVCIC EQU INTINFO+3	SVC interruption code
8	PIBECB DS XL4	ECE address
C	PIBPIK DS XL2	Program interrupt key
E	DS XL2	Reserved for IBM use

PIB2TAB

PIB2TAB: PROGRAM INFORMATION BLOCK EXTENSION

PIB2TAB describes the entries in the PIB2TAB block, which is an extension of the PIETAB block. For each PIB table entry, an entry exists in the PIB table extension block (PIB2TAB).

The PIB2PTR field in the BGCOM block points to the PIB2TAB block.

0	PIBCOMR1		SYSLUBX		INTINFO	
8			PIBECB		PIEPIK	/\/\/\/\/\/\/\/\/\

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	PIBCOMR1	DS XL2	Address of communications region
2	SYSLUBX	DS XL2	System LUP index
4	INTINFO	DS XL4	Used for interruption code
	SVCIC	EQU INTINFO+3	SVC interrupt code
8	PIBECB	DS XL4	Address of termination ECB, if any
C	PIBPIK	DS XL2	Program interrupt key
E		DS XL2	Reserved for IBM use

| PUBADR: PHYSICAL UNIT BLOCK TABLE

| PUBADR defines the fields of a physical unit block table as used by CMS and/or DOS routines. Both DSECTS define the same storage.

| • For Use by CMS Routines (MAPPUB macro)

| The simulated PUBADR DSECT has eighteen 8-byte entries, one for each device supported by CMS. The simulated PUBADR DSECT is invoked by the MAPPUB macro.

0	PUBCUU		A*1	A*2	A*3	A*4	A*5
---	--------	--	-----	-----	-----	-----	-----

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning					
0	PUBCUU DS	XL2					
2		X					
3	PUBDSKM DS	X	A*1	Disk mode if assigned DASD			
4	PUBDEVT DS	X	A*2	Device type code			
5	PUBTAPM1 DS	X	A*3	CMS tape set mode attributes			
6	PUBTAPM2 DS	X	A*4	DOS tape set mode attributes			
7	PUBTAP7 DS	X	A*5	7-track indicator			

| • For Use by DOS/VS Routines (PUBTAB macro)

| The PUBADR DSECT is invoked by the PUBTAB macro. The address of PUBTAB is at displacement X'40' of BGCOM.


0	PUBCHANN	!/A*1//	A*2	A*3	A*4	A*5	A*6
		A*7					

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning					
0	PUBCHANN DS	XL2					
2	PUBCHQPT DS	X	A*1	Reserved for IBM use			
3	PUBERR DS	X	A*2	Error retry counter or TEB point			
4	PUBDEVTY DS	X	A*3	Device type code			
5	PUBOPTN DS	X	A*4	Set mode command or other options			
6	PUBCSFLG DS	X	A*5	Channel scheduler flags			
7	PUBJCFLG DS	X	A*6	Job control flags			
8	NEXTPUB DS	X	A*7	First byte of next PUB entry			
	PUBWIT EQU	*-PUBADR					
	PUBPTR EQU	NEXTPUB					
				Length of PUB table			
				Pointer to original PUB			

PUBOWNER

PUBOWNER: PHYSICAL UNIT BLOCK OWNERSHIP TABLE

PUBOWNER contains a 2-byte entry for each entry in the PUB table. For CMS/DOS, there are eighteen 2-byte entries. The address of the PUBOWNER table is in the SYSCOM block in the DOSCON CSECT of NUCON.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	PUBOWNER DS	PUB ownership table
0	DC 18X'0001'	PUB owner

PUBOWNER entries have the following meanings:

Byte	Value	Meaning
0	X'00'	The physical unit is reserved
	X'40'	CMS is waiting for the volume to be mounted
1	X'01'	Background partition owns the physical unit

SSAVE: SYSTEM SAVE AREA

SSAVE is used by DMSITS to save the value of the SVC old PSW, the caller's registers, and other necessary control information required to process the SVC and return to the caller. Since SVC calls can be nested, several of these save areas can exist at one time. The system save area is dynamically allocated in protected free storage. SSAVE is invoked via the CMSAVE macro.

0	A*1 A*2	CODE		CALLER
CALLEE				
OLDPSW				
18	NRMRET		FRRET	
20	EGPRO		EGPR1	
28	EGPR2		EGPR3	
30	EGPR4		EGPR5	
38	EGPR6		EGPR7	
40	EGPR8		EGPR9	
48	EGPR10		EGPR11	
50	EGPR12		EGPR13	
58	EGPR14		EGPR15	
EFPRO				
68	EFPR2			
70	EFPR4			
78	EFPR6			
80	CHKWRD1		SSAVENXT	
88	SSAVEPRV		USAVERPTR	
90	OSTEMP	A*3	KEYS	
98	KEYS (cont.)		XGPRO	
A0	XGPR1		XGPR15	
A8	XCOUNT		CHKWRD2	


SSAVE

Hexadecimal Displacement	Field Name			Field Description, Contents, Meaning
0	OVIND	DS	X	A*1 Override indicator: 0, 1, 2, and 3
	TYPFLAG	DS	BL1	A*2 SVC-type flag byte
<u>Bits defined in TYPFLAG</u>				
	TPFERT	EQU	X'80'	Error return desired
	TPFNS	EQU	X'40'	No save area allocated
	TPFR01	EQU	X'20'	Return callee's R0-R1 to caller
	TPFUSR	EQU	X'10'	User SVC call
	TPFACB	EQU	X'08'	OS VSAM SVC request
	TPFSV3	EQU	X'02'	SVC 203
	TPFSVO	EQU	X'01'	OS simulation SVC
2	CODE	DS	H	SVC 203 code value
4	CALLER	DS	A	Address of SVC caller
8	CALLEE	DS	D	Name of routine being called
10	OLDPSW	DS	D	SVC old PSW of caller
18	NRMRET	DS	A	Address for normal return
1C	ERRRET	DS	A	Address for error return
20	EGPRS	DS	OF	General-purpose registers at entry to SVC
20	EGPRO	DS	F	R0
24	EGPR1	DS	F	R1
28	EGPR2	DS	F	R2
2C	EGPR3	DS	F	R3
30	EGPR4	DS	F	R4
34	EGPR5	DS	F	R5
38	EGPR6	DS	F	R6
3C	EGPR7	DS	F	R7
40	EGPR8	DS	F	R8
44	EGPR9	DS	F	R9
48	EGPR10	DS	F	R10
4C	EGPR11	DS	F	R11
50	EGPR12	DS	F	R12
54	EGPR13	DS	F	R13
58	EGPR14	DS	F	R14
5C	EGPR15	DS	F	R15
60	EFFRS	DS	OD	Floating-point registers at entry
60	EFPRO	DS	D	FPR0
68	EFPR2	DS	D	FPR2
70	EFPR4	DS	D	FPR4
78	EFPR6	DS	D	FPR6
80	CHKWRD1	DC	C'ABCD'	Check word one
84	SSAVENXT	DS	A	Address of next SSAVE area
88	SSAVEPRV	DS	A	Address of previous SSAVE area
8C	USAVERPTR	DS	A	Address of corresponding user save area - see USAVER DSECT
90	OSTEMP	DS	F	Temporary work area for OS simulation routines
<u>DMSKEY Key Stack</u>				
	KEYMAX	EQU	7	Maximum number of keys in stack
94	KEYP	DC	X'00'	A*3 Number of keys in stack
95	KEYS	DS	(KEYMAX) X	Key stack
<u>The Following Fields Are Filled in Only by DMSOVS, the SVCTRACE Subroutine</u>				
9C	XGPRO	DS	F	Extra copy of EGPRO
A0	XGPR1	DS	F	Extra copy of EGPR1
A4	XGPR15	DS	F	Extra copy of EGPR15
A8	XCOUNT	DS	F	Extra copy of SVCOUNT
AC	CHKWRD2	DC	C'EFGH'	Check word two
	SSAVESZ	EQU	(--SSAVE+7)/8	Size of system save area in doublewords (X'15')

SUBSECT: SUBSET WORK AREA

SUBSECT defines the fields in the SUBSET work area which is used by CMS SUBSET command processing and abend recovery.

The SUBSECT block is pointed to by the ASUBSECT field in NUCON.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	RMSGBUF	DS 10F Buffer area for formatting time message
28	CMSTIM	DS 0F PLIST to obtain time from DMSINM
28		DC CL8'CMSTIME'
30		DS F Virtual machine time used
34		DS F Total processor time used (CP+CMS)
38		DS A Address of time buffer
3C		DS F Message length (filled in by CMSTIME)
40		DS 0F PLIST for ACTLKP (used by SUBSET)
40	STARS	DC CL8"**"
48		DC CL8"**"
50		DC CL2"**"
54		DS 0F Subset address for storage areas
54	ASUBRET	DS F Return address to caller
58	STAESAV	DS F STAEE save area
5C	SPIESAV	DS F SPIEE save area
60	SWTCHSAV	DS F
64	ASUBFST	DS F
68	ASUBSTAT	DS F
70	ERRNUM	DS D Work area for error return code
78	TIMBUF	DS 4D Work area for DMSINM to store date and time

SVCSECT

SVCSECT: SVC INTERRUPT STORAGE

SVCSECT describes the fields used by DMSITS in handling SVC interrupts. An SVCSECT block is built dynamically when an SVC is issued. The first SVCSECT is pointed to by the ASVCSECT field in NUCON; if SVCS are nested, the chain of SVCSECT blocks is processed using the CURRALOC and LASTALOC fields.

0	JNUMB		JFIRST	
8	JF4		JLAST	
10	A*1	SVCAB		CURRALOC
18	LASTALOC		DEPTH	
20	ADMOSVS		OVEPF	OVBTF
28	OVAPF	OVATF	A*2	
30	SVCSAVE	.	.	
78	NRMSAV	.	.	
158		SVCOUNT	.	
160	SVCSTOP		SVLAD	
168	SVLADW		SVLFS	
170	LOADLIST	.	.	
178	LOADNAME	.	.	
180	(Literals are loaded into this area)	.	.	
188	(The literals here are from the origin)	.	.	
190	LOADSTRT	.	.	
198	(Hexadecimals are entered in this area)	.	.	
1A0		.	.	
1A8	MODLIST	.	.	
1B0	DUMCOM	.	.	
1B8	A*3 ZERO3		TRANSRT	
1C0	TRANSRT (cont.)	A*4	AETRANS	
1C8	TEMP02	.	.	
1D0		.	.	
1D8		.	.	
1E0	RGPRO		RGPR1	

1E8	RGPR2		RGPR3
1F0	RGPR4		RGPR5
1F8	RGPR6		RGPR7
200	RGPR8		RGPR9
208	RGPR10		RGPR11
210	RGPR12		RGPR13
218	RGPR14		RGPR15
220	RFPR0		
228	RFPR2		
230	RFPR4		
238	RFPR6		
240	NRMUSAV		
.			
.			
.			

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning		
0	USVCTBL DS OF	User SVC table		
0	Keep Next Four in Order			
0	JNUMB DC F'0'	No. of doublewords in SVC number table		
4	JFIRST DC A(***)	Address of first item (if any) in table		
8	JF4 DC F'4'	Loop increment for BXLE		
C	JLAST DC A(***)	Address of last item in table		
10	Start-up Flags -- Indicate System Parameter Flag for the Called Routine			
	SFLAG DC BL1'0' A*1 Flag byte			
	Bits defined in SFLAG			
	SFSYS EQU X'80'	System flag -- SVC protect key is zero		
	SFTRN EQU X'40'	Transient area routine -- system mask is off		
	SFNUC EQU X'20'	Nucleus routine -- system mask is off		
	SFREN EQU X'01'	Invalid reentry flag		
11	DC X'00'	Reserved for IBM use		
12	SVCAB DC H'0'	SVC abend code if any		
14	CURRALOC DC A(0)	Current allocated save area		
18	LASTALOC DC A(0)	Last allocated save area		
1C	DEPTH DC F'0'	Nested SVC depth		
	Information for SVCTRACE			
20	ADMSOVS DC A(0)	Address of DMSOVS		
24	OVBPFF DC BL2"0"	"Before print" flags		
26	OVBTFF DC BL2"0"	"Before type" flags		
28	OVAPFF DC BL2"0"	"After print" flags		
2A	OVATFF DC BL2"0"	"After type" flags		

SVCSECT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>The Following Equate Symbols Are Associated with the First Byte of the OVBF and OVAF Flag Fields Defined Above</u>		
	OVF1ON EQU X'80'	Current option is set on
	OVF1GB EQU X'40'	GPRs before call wanted
	OVF1GA EQU X'20'	GPRs after call wanted
	OVF1GS EQU X'10'	GPRs returned from SVC callee
	OVF1PA EQU X'08'	PLISTI wanted
	OVF1F EQU X'04'	Floating-point registers wanted
	OVF1FS EQU X'01'	Floating-point registers returned from SVC callee
<u>The Following Equate Symbols Are Associated with the Second Byte in the OVBF and OVAF Flag Fields</u>		
	OVF2ST EQU X'80'	STOP wanted
	OVF2CM EQU X'40'	CMS SVC TRACE wanted
	OVF2NR EQU X'20'	Normal return CMS SVCS wanted
	OVF2OS EQU X'10'	OS SVCS wanted
	OVF2WA EQU X'08'	WAIT CMS SVCS wanted
2C	OVSTAT DC B'0'	A*2 Current status of SVCTRACE
	<u>Bits defined in OVSTAT</u>	
	OVSON EQU X'80'	Override options are on
	OVSPPREV EQU X'40'	SVCTRACE SAME is valid
	OVSAAFT EQU X'20'	After bit; set by DMSITS
	OVSNO EQU X'10'	HALT override flag
	OVSZO EQU X'08'	SUSPEND override flag
2D	DC XL3'0'	Reserved for IBM use
30	SVCSAVE DC 18F'0'	INTSVC work area
78	NRMSAV DC 28D'0'	Normal standard information
158	DC F'0'	Reserved for IBM use
15C	SVCOUNT DC F'0'	Current SVC count
160	SVCSTOP DC F'0'	For DMSITS debugging
164	SVLAD DS F	Save R14 for DMSLAD
168	SVLADW DS F	Save R14 for DMSLADW
16C	SVLFS DS F	Save R14 for DMSLFS
170	LOADLIST DC CL8'LOAD'	
178	LOADNAME DC CL8' '	
180	DC CL8')'	
188	DC CL8'ORIGIN'	
190	LOADSTRT DC CL8'0'	
198	DC 8X'FF'	
1A0	DC 2F'0'	Reserved for IBM use
<u>PLIST for Calling DMSLDR (Keep next five in strict sequence)</u>		
1A8	DS OF	
1A8	MODLIST DC CL8'LOADMOD '	Routine name
1B0	DUMCOM DC CL8' '	Module filename filled in here
1B8	SSMON DC X'FF'	A*3 Fence; allows all interrupts
1B9	ZERO3 DC AL3(0)	Address is 3-bytes long and set to zeros
1BC	TRANSRT DC CL8'	' Holds filename of transient routine

Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
1C4	TRANMSK	DC	AL1(X'FF') A*4
1C5	ADTRANS	DC	VL3(TRANSAR)
1C8	TEMP02	DC	D'0'
1D0		DC	4F'0'
1E0		DS	OD
1E0	RGPRS	DS	OF
1E0	RGPRO	DS	F
1E4	RGPR1	DS	F
1E8	RGPR2	DS	F
1EC	RGPR3	DS	F
1F0	RGPR4	DS	F
1F4	RGPF5	DS	F
1F8	RGPR6	DS	F
1FC	RGPR7	DS	F
200	RGPR8	DS	F
204	RGPR9	DS	F
208	RGPR10	DS	F
20C	RGPR11	DS	F
210	RGPR12	DS	F
214	RGPR13	DS	F
218	RGPR14	DS	F
21C	RGPR15	DS	F
220	RFPRS	DS	OD
220	RFPRO	DS	D
228	RFPR2	DS	D
230	RFPR4	DS	D
238	RFPR6	DS	D
240	NRMUSAV	DS	12D
			NRMUSAV user save area

SVEARA**SVEARA: LTA AND PP SAVE AREA DSECT**

SVEARA describes the fields in a DOS/VIS Logical Transient Area (LTA) and Problem Program (PP) save area. SVEARA is invoked via the DOSAVE macro. These areas are used by DOS/VIS routines to save the value of the PSW and registers for purposes such as linkage to and from transient routines.

0			
8	SVEPSW		SVEPSW2
10	SVER09		SVER0A
18	SVER0B		SVER0C
20	SVER0D		SVER0E
28	SVER0F		SVER00
30	SVER01		SVER02
38	SVER03		SVER04
40	SVER05		SVER06
48	SVER07		SVER08

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0		Reserved for IBM use
8	SVEPSW	DS F First half PSW
C	SVEPSW2	DS F Second half PSW
10	SVER09	DS F Save area for register 9
14	SVER0A	DS F Save area for register 10
18	SVER0B	DS F Save area for register 11
1C	SVER0C	DS F Save area for register 12
20	SVER0D	DS F Save area for register 13
24	SVER0E	DS F Save area for register 14
28	SVER0F	DS F Save area for register 15
2C	SVER00	DS F Save area for register 0
30	SVER01	DS F Save area for register 1
34	SVER02	DS F Save area for register 2
38	SVER03	DS F Save area for register 3
3C	SVER04	DS F Save area for register 4
40	SVER05	DS F Save area for register 5
44	SVER06	DS F Save area for register 6
48	SVER07	DS F Save area for register 7
4C	SVER08	DS F Save area for register 8

SYSCOM: SYSTEM COMMUNICATION REGION

SYSCOM describes the fields in the SYSCOM block which is the CMS/DOS equivalent of the DOS/V System Communication Region (SYSCOM). The ASYSCOM field in NUCN points to the SYSCOM block in DMSNUC.

0	IJBBERBLC		IJEAREX			
8	IJBERR19	IJBERR24	IJEPUBRS			
10	IJBFETCH		IJEINTRT			
18	IJBEXTRT		IJELTA			
20	IJBPPBEG		IJECHANQ			
28	IJBQSIZE	IJBQLNG	IJENPART ////////////////			
30	IJBRSAVE		IJECCNSP			
38	IJBSSAB		IJECENTB			
40	A*1	A*2	A*3	A*4	IJESTID	IJBEXIT
48	IJBPDADR		IJETKHLD			
50	IJBTIMER		IJEACTAB			
58	IJBLIK	IJBTIK	IJEPWR			
60	IJBTCAVT		IJERFTAB			
68	IJBEEUECB		IJEOLTEP			
70	IJBRAISLN		IJETRTAB			
78	IJBPBOWN		IJEJATAB			
80	IJBPMGR		IJECCWT			
88	IJBSSAVSD		IJELNSTB			
90	IJBAMCOM		IJEAPTA			
98	IJBSSBLK0		IJESBLKX			
A0	A*5	A*6	A*7	A*8	A*9	A*10 ////////////////
A8	////////////////////	////////////////////	////////////////////	////////////////////	////////////////////	////////////////////
B0	////////////////////	////////////////////	////////////////////	////////////////////	////////////////////	IJEMVCAD
B8	////////////////////	////////////////////	////////////////////	////////////////////	////////////////////	////////////////////
C0	IJBMFcer					
C8	A*11		IJEPUBLN		IJBAPNO	


Hexadecimal Displacement	Field Name		Field Description, Contents, Meaning
0	IJBERRBLC DC	A(0)	Address of error block
4	IJBAREX DC	A(0)	Exit address for attention
8	IJBERR19 DC	H'0'	Cancel exit for attention
A	IJBERR24 DC	H'0'	Cancel exit for attention
C	IJBPUFRS DC	F'0'	SYSRES PUE address
10	IJBFETCH DC	A(0)	Address of fetch routine
14	IJBINTRT DC	A(0)	Address of I/O interrupt routine
18	IJBEXTRT DC	A(0)	Address of external interrupt routine
1C	IJBLTA DC	A(0)	Pointer to logical transient area
20	IJBPPBEG DC	A(0)	Pointer to problem program area
	IJBFLPTR EQU	*	Free list pointer
24	IJBCHANQ DC	F'0'	Pointer to channel queue
28	IJBQSIZE DC	H'0'	Number of channel queue entries
2A	IJBQLNG DC	H'0'	Length of one error queue entry
2C	IJBNPART DC	H'1'	Number of partitions
2E	DC	H'0'	Reserved for IBM use
30	IJBRSAVE DC	A(0)	Pointer to channel buckets
34	IJBCONSP DC	A(0)	Address of CRT table
38	IJBSSAB DC	A(0)	Address of SAB table
3C	IJBCHNTB DC	A(0)	Address of channel control table
40	IJBFLG01 DC	X'00'	A*1 Flags and switches
41	IJBFLG02 DC	X'00'	
42	IJBFLG03 DC	X'00'	
43	IJBFLG04 DC	X'00'	
44	IJBSTID DC	H'0'	System task selection control field
	IJBSELCT EQU	*-1	System task selection byte
46	IJBEXIT DC	H'0'	Pointer to task selection
48	IJBPDADDR DC	A(0)	Pointer to PDAREA
	IJBTHPTR EQU	*-1	Track hold FLPTR
4C	IJBTKHLD DC	F'0'	Address of track hold table

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
50	IJB TIMER DC	A(0)
54	IJB AB TAB DC	A(0)
58	IJB LIK DC	H'0'
5A	IJB TIK DC	X'0010'
5C	IJB PWR DC	A(0)
60	IJB TCAVT DC	A(0)
64	IJB RFTAB DC	A(0)
68	IJB EUECB DC	A(0)
6C	IJB OLTEP DC	A(0)
70	IJB RASLN DC	A(0)
74	IJB TRTAB DC	A(0)
78	IJB PBOWN DC	A(0)
7C	IJB JATAB DC	A(0)
80	IJB PMGR DC	A(0)
84	IJB CCWT DC	A(0)
88	IJB SAVSD DC	A(0)
8C	IJB LNSTB DC	A(0)
90	IJB AMCOM DC	A(0)
94	IJB APFTA DC	A(0)
98	IJB SBLKO DC	A(0)
9C	IJB SBLKX DC	F'0'
A0	IJB SYSPT DC	X'00'
A1	IJB RASPT DC	AL1(0)
A2	IJB PMRPT DC	AL1(0)
A3	IJB SUPPT DC	AL1(0)
A4	IJB CRTPT DC	AL1(0)
A5	IJB ERPPT DC	AL1(0)
A6	DC	10X'00'
B0	DC	F'0'
B4	IJB MVCAD DC	A(0)
B8	DC	F'0'
BC	DC	H'0'
BE	DC	H'0'
C0	IJB MF CER DS	11X'00'
CB	IJB NERQ DC	AL1(0)
CC	IJB PUBLN DC	S(0)
CE	IJB APNO DC	H'1'
D0	IJB SEGT DC	A(0)
D4	IJB PFT DC	A(0)
D8	IJB PFTX DC	A(0)
DC	IJB BOX DC	A(0)
E0	IJB DPDTB DC	A(0)
E4	DC	F'0'
E8	IJB VIRAD DC	A(0)
EC	IJB EOR DC	F'0'
F0	IJB FTTAB DC	A(0)
F4	IJB SVA DC	A(0)
F8	IJB SVIS DC	A(0)
FC	ARPSL DC	A(0)
100	ARPSR DC	A(0)
104	IJB DLAB DC	A(SYS\$CODE)
108	SYS\$CODE DC	CL13'CMS/VSAM'
		System code name

SYSNAMES

SYSNAMES: SAVED SYSTEMS NAMES

SYSNAMES defines the names of any saved systems which may be loaded by CMS routines. SYSNAMES describes the entries in the SYSNAMES table which is pointed to by the ASYSNAMES field in NUCON.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CMSSEG	DC CL8'CMSSEG'
8	CMSVSAM	DC CL8'CMSVSAM'
10	CMSAMS	DC CL8'CMSAMS'
18	CMSDOS	DC CL8'CMSDOS'
20	SYSNEND	DS OD
	SYSNCNT	EQU (SYSNEND-SYSNAMES)/8 Size in doublewords (X'04')

TSOBLKS: TSO CONTROL BLOCKS

TSOBLKS DSECT describes the entries in the TSOBLKS block which contains OS control information used by CMS, that is, the command program parameters list (CPPL), user profile table (UPT), protected step control block (PSCB), and the environment control table (ECT). The ATSOCPP field in NUCON points to TSOBLKS block.

0	CPPLOBUF		CPPLUPT
8	CPPLPSCB		CPPLECT
10		UPTUSER	
18	UPTUSER (cont.)	A*1 A*2 A*3	
20		PSCEUSER	A*4
28		PSCBGPNM	
30	A*5 A*6		
48			PSCBTCOL
50	PSCBRLGB		PSCBUPT
58	PSCBUPTL		PSCBRSZ
60		PSCBU	
68	A*7 ECTR TCD		ECTIOWA
70	A*8 ECTS MSG		ECTPCMD
78	ECTPCMD (cont.)		ECTSCMD
80	ECTSCMD (cont.)	A*9	ECTDDNUM
88	ECTUSER		

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	CPPLL DS OF	Temporary PLIST to CP programs
0	CPPLOBUF DC AL4(0)	Address of command line
4	CPPLUPT DC AL4(UPT)	Address of dummy UPT
8	CPPLPSCB DC AL4(PSCB)	Address of dummy PSCB
C	CPPLECT DC AL4(ECT)	Address of dummy ECT
<u>User Profile Table (UPT)</u>		
10	UPT DS OF	Reserved for IBM use
10		Reserved for installation use
12	UPTUSER DS CL10	
1C	UPTSWS DC X'00'	A*1 User's environment switch
<u>Bits Defined in UPTSWS</u>		
	EQU X'80'	Reserved for IBM use
	EQU X'40'	No prompting is to be done
	EQU X'20'	Print message identifiers
	EQU X'10'	No user communication allowed via SEND

TSOBLKS

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>Bits Defined in UPTSWs (cont.)</u>		
	UPTPAUS EQU X'08'	Pause for "?" when in noninterface mode
	UPTALD EQU X'04'	ATTN has been specified as line delete
1D	UPTCDEL DC X'00'	A*2 Character delete character
1E	UPTDEL DC X'00'	A*3 Line delete character
1F	DS CL1	Reserved for IBM use
<u>Protected Step Control Block (PSCB)</u>		
20	PSCB DS OF	
20	PSCBUSER DC CL7' '	User ID padded with blanks
27	PSCBUSRL DC X'00'	A*4 Length of user ID
28	PSCBGPNM DS CL8	Esoteric group name initialized by logon
30	PSCBATR1 DS X	A*5 16-bit string of user attributes; bits 3-15 reserved for IBM use
<u>ORG PSCBATR1</u>		
	PSCBCTRL EQU X'80'	Operator command user
	PSCBACCT EQU X'40'	Account command user
	PSCBJCL EQU X'20'	Submit command user
32	PSCBATR2 DS X	A*6 Reserved for IBM use
33	DS X	16-bit string reserved for installation use
34	DC 6F'0'	Six fullwords used for TSC accounting; initialized to 0
4C	PSCBTCOL DS 1F	
50	PSCBRLGB DS AL4(0)	
54	PSCBUPT DC AL4(UPT)	Pointer to the user profile table
58	PSCBUPTL DC AL2(16)	Length of the user profile table
5A	DS BL.16	Reserved for IBM use
5C	PSCBRSZ DS A	Region size requested in 2K units
60	PSCBU DS CL8	Reserved for installation use
<u>Environment Control Table (ECT)</u>		
68	ECT DS OF	
68	ECTRCDF DC AL1(0)	A*7 High-order bit indicates CF abended
69	ECTRTCD DC AL3(0)	Return code from last control routine
6C	ECTIOWA DC AL4(0)	Address of I/O service routine work area
70	ECTMSGF DC X'00'	A*8 High-order bit means delete second level messages (Must be initialized by user at start of user's program)
71	ECTSMMSG DS AL3	Address of second level message chain
74	ECTPCMD DC CL8' '	Primary command name
7C	ECTSCCMD DS CL8	Subcommand name
84	ECTSWS DC X'00'	A*9 ECT switch
<u>Bits defined in ECTSWS</u>		
	ECTNOPD EQU X'80'	If 0 bit is on, no operands exist in command buffer
	ECTATRM EQU X'20'	CP terminated by TMP DETACH with STAE
*	EQU X'40'	Reserved for IBM use
	ECTLOGF EQU X'10'	Logon/off requested TMP to log off
	ECTNMAL EQU X'08'	No user messages received at logon
	ECTNNOT EQU X'04'	No broadcast notices to be received
85	ECTDDNUM DC AL3(0)	Counter for generated temporary DDNAMS
88	ECTUSER DS A	Reserved for installation use
8C	DS A	Reserved for IBM use

| Note: For terminal attention exit element (TAXE), see the CMSTAXE DSECT.

USAVE: USER SAVE AREA


USAVE is used by DMSITS to allocate and free save areas for other routines during SVC processing; it is pointed to by the USAVEPTR field in SSAVE. USAVE is invoked via the SVCSAVE macro.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DS 12D	Scratch area passed to user via a pointer in R13
	USAVESZ EQU (*-USAVE)/8	Size of user save area in doublewords (X'0C')

USERSECT: USER WORK AREA

USERSECT describes the USERSECT block which is a general scratch storage area provided for user-defined purposes. It may be redefined to suit installation requirements. USERSECT is pointed to by the AUSER field in NUCON.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	USCRTCH DC 18F'0'	User scratch area; may be redefined per installation requirements

Section 3. RSCS Data Areas and Control Blocks

This section describes in detail each of the data areas used by RSCS. Unlike the CP and CMS format blocks in this publication, the RSCS format blocks are on fullword boundaries.


This section of the publication contains only DSECTs. Appendixes B and C contain other control areas used by RSCS.

ASYNE

ASYNE: ASYNCHRONOUS EXIT ELEMENT

ASYNE defines symbolic addresses for elements on an asynchronous exit queue. An asynchronous exit queue element contains information by which a task requests that it handle asynchronous interrupts.

IOEXITQ, EXTQ, and ALERTQ in SVECTORS are the heads of three asynchronous exit queues. Each of these queues is comprised of supervisor elements defined by the ASYNE DSECT. IOEXITQ points to requests for I/O exits, EXTQ points to requests for external exit requests, and ALERTQ points to requests for ALERT exits.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	ASYNNEXT DS 1F	Address of the next asynchronous interrupt exit request element
4	ASYNTASK DS 1F	Address of task element describing the task that requested the asynchronous interrupt
8	ASYNEXIT DS 1F	Address of the requested asynchronous exit routine
C	ASYNCODE DS AL2	Address of the device for which asynchronous I/O interrupts are requested or interrupt bit code
E	ASYNSPAR DS 1X	Reserved for IBM use
F	ASYNID DS 1X	1-byte identification of the task owning the asynchronous exit routine

BUFDSECT: SML TELECOMMUNICATIONS BUFFER

BUFDSECT is used to transmit buffer control information and buffer data to and from programmable remote stations.

The buffer sent across the TP line starts at EUFSTART; the first 7 bytes of BUFDECT are used by the DMTSML line driver but are not transmitted.

\$BUFPPOOL in DMTSML points to a queue of available TF buffers; \$INBUF in module DMTSML points to a queue of TP buffers that have been received from a remote station and are waiting to be deblocked. \$OUTBUF in DMTSML points to a queue of TF buffers that are ready for transmission to remote stations.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	BUFBEGIN DS OF	Beginning of the buffer
0	BUFCHAIN DC A(0)	Buffer chain field
4	BUFCOUNT DS 1H	Count of bytes to transmit
6	BUFSTAT DS 1C	Buffer status byte
 <u>Bits defined in BUFSTAT</u>		
	BUFAKE EQU X'01'	Dummy buffer indicator
	BUFRESP EQU X'02'	Response only in buffer
	BUFNAK EQU X'04'	NAK response being sent
	BUFTEXT EQU X'08'	Buffer contains text information
	BUFUCHEK EQU X'10'	Unit check expected
7	BUFSTART DS CL2	Bisynchronous transmission control bytes
9	BUFBCB DS 1C	Block control byte
A	BUFFCS DS CL2	Function control sequence
C	BUFDATA DS OF	Data portion of TP buffer

COMDSECT

COMDSECT: ADDRESS CONSTANTS AS POINTERS


COMDSECT defines address constants used as pointers to subroutines common to all RSCS modules. These subroutines are contained in module DMTCOM. COMDSECT is pointed to by TCOM in SVECTORS.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	GLINKREQ DS 1A	Get link table entry routine
4	GPAGEREQ DS 1A	Get page of main storage
8	FPAGEREQ DS 1A	Free page of main storage
C	PMSGREQ DS 1A	Put message element into message stack
10	GMSGREQ DS 1A	Remove message element from message stack
14	GTODEBCD DS 1A	Convert S/370 TOD to EBCDIC

DEVTABLE: NPT DEVICE TABLE

DEVTABLE defines virtual device information for an I/O operation. This DSECT corresponds to the IOTABLE DSECT.




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	DEVLOCK DC F'0'	I/O request sync lock
4	DEVADDR DC AL2(0)	CUU address of I/O device
6	DEVSNREQ DC AL1(0)	Requested sense bytes
7	DEVTYPE DC X'00'	VM/370 device type code
8	DEVSTART DC F'0'	Address start channel program for I/O handling
C	DEVSIOCC DC 0X'00'	Right-justified SIO condition code
C	DEVCSW DC 2F'0'	Ending CSW from last I/O operation
14	DEVSENSE DC X'00'	Sense information on unit check
15	DEVFLAGS DC 3X'00'	Device status flags
18	DEVNAME DC CL8' '	EBCDIC device address and name

FREEE

FREEE: A FREE ELEMENT ON THE SUPERVISOR ELEMENT QUEUE

FREEE defines an element in the chain of elements that comprise the free element queue.


FREQ in SVECTORS points to the chain of free elements, each of which is defined by the FREEE DSECT.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	FREENEXT DS 1F	Address of next element in free queue
4	FREESPAR DS CL11	Spare field
C	FREEID DS 1X	Standard taskid displacement, which is: ID=X'00'=> free element

GIVE REQUEST TABLE

The format of a GIVE Request Table is:



When a task requests the services of another task via a GIVE request, the second field of the table above contains the task name of the task to which the task is to be sent. When DMTGIV builds a GIVE element for the request, it overlays this task name with the address of the GIVE element.


The task performing the requested service builds a table called the TAKE request table, which corresponds to the GIVE request table.

GIVEE: A GIVE ELEMENT

GIVEE defines symbolic addresses for items used in processing a GIVE request.

GIVEQ in SVECTORS points to the queue of GIVE elements used in task-to-task communications.

The GIVEADDR field of this DSECT is the address of a GIVE request table, which, in turn, contains addresses of buffers for elements describing requests and responses to requests. These tables are described below; the elements that fill the buffers are described in "Appendix C: RSCS Request Elements."




Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	GIVENEXT DS 1F	Address of next GIVE element
4	GIVEADDR DS 1F	Address of GIVE request table in sending task's storage
8	GIVENAME DS CL4	Task name of receiving task
C	GIVESPAR DS AL2	Reserved for IBM use
E	GIVENID DS 1X	1-byte identification of receiving task after the TAKE request has been processed
F	GIVERID DS 1X	1-byte identification of sending task

IOE: AN I/O ELEMENT

IOE defines symbolic addresses of elements and other information associated with an I/O operation requested by a task.

MPXIOQ and SELIOQ in SVECTORS point to queues of I/C elements for the multiplexer and selector channels, respectively.


The IOTABLEA field points to the address of an I/O table defined by ICTABLE, which is described in this section.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	IONEXT	DS 1F Address of next active I/O element
4	IOSUBQ	DS 1F Address of first inactive I/O element for a given subchannel
8	IOSTAT EQU *	Status flags for current I/O operation (first byte of IOTABLEA)
	Bits defined in IOSTAT	
	SENSING EQU X'80'	Flag set to 1 while automatic sense is active
	CHANDONE EQU X'40'	Flag set to 1 when subchannel terminates
8	IOTABLEA DS 1F	Address of I/O request table in task storage
C	IOADDR DS AL2	Address (cuu) of the device requesting current I/O operation
E	IOSBCHAN DS 1X	Subchannel address; 1-byte; assigned by MSUP
F	OID DS 1X	ID of task associated with this I/O operation is 1-byte and assigned by MSUP

IOTABLE: AN I/O TABLE

IOTABLE defines symbolic addresses for items used in processing an I/O interrupt request. The first five fields are filled in by the task to convey information about the I/O request to the supervisor. The last three fields are filled in by the supervisor to convey status information about the I/O operation to the task.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	IOSYNCH DS 1F	Synchronization lock for I/O operation
4	DEVCUU DS AL2	Address (cuu) of device associated with this I/O operation
6	SENSREQ DS AL1	Number of sense bytes requested on unit check
7	DEVCODE DS AL1	1-byte VM/370 device type code (not used by I/O manager)
8	PROGADDR DS 1F	Address of channel program for the I/O operation
<u>Bits defined in PROGADDR</u>		
C	SIOCOND EQU *	1-byte SIO condition code return information
D	ENDCSW DS 2F	
14	ENDSENSE DS AL1	SIO condition code Ending CSW with composite status return information Requested return sense information on unit check CSW status
<u>Bits defined in ENDSENSE</u>		
	TYPPUN EQU X'80'	VM/370 type code for the punch
	TYPPRT EQU X'40'	VM/370 type code for the printer

LINKTABL

LINKTABL: LINK TABLE

LINKTABL describes the status of a single link in the RSCS network; collectively, all the links defined for the system are referred to as the link table.

An 8-byte header precedes the first entry in the link table (that is, the first link defined by the LINKTABL DSECT). The TLINKS field in SVECTORS points to this header, which has the following format:

0	4	6
total links	maximum links	current links

where:

total links is the total number of links defined for an RSCS installation via the GENLINK macro during system generation. (For information on the GENLINK macro, see the VM/370 System Programmer's Guide.)

maximum links is the maximum number of concurrently active links allowable.

current links is the number of links active in RSCS at a given time.

0	LINKID						
4							
8	LDEFTNME						
C	LACTTNME						
10	LDEFDRVVR						
14							
18	LACTDRVVR						
1C							
20	LDEFLINE		LACTLINE				
24	LDRVVRVAR						
28	LDEFCLS1		LDEFCLS2		LDEFCLS3		LDEFCLS4
2C	LACTCLS1		LACTCLS2		LACTCLS3		LACTCLS4
30	LTIMEZON		LFLAG		LRESRVD		
34	LPENDING				LTAKEN		
38	LPOINTER						
3C	LMSGQ						
40	LTRNSCNT				LERRCNT		
44	LTOCNT				LSPARE		
48	LNKCLOCK						
4C							

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	LINKID DS CL8	EBCDIC link identification
8	LDEFTNME DS CL4	Default task name
C	LACTTNME DS CL4	Active task name
10	LDEFDRVR DS CL8	Default driver identification
18	LACTDRVR DS CL8	Active driver identification
20	LDEFILINE DS 2X	Default virtual line address
22	LACTLINE DS 2X	Active virtual line address
24	LDRVRRVAR DS 1F	Line driver variable information
28	LDEFCLS1 DS CL1	Default spool file Class 1
29	LDEFCLS2 DS CL1	Default spool file Class 2
2A	LDEFCLS3 DS CL1	Default spool file Class 3
2B	LDEFCLS4 DS CL1	Default spool file Class 4
2C	LACTCLS1 DS CL1	Active spool file Class 1
2D	LACTCLS2 DS CL1	Active spool file Class 2
2E	LACTCLS3 DS CL1	Active spool file Class 3
2F	LACTCLS4 DS CL1	Active spool file Class 4
30	LTIMEZON DS 1X	Displacement of two complete time zones from Greenwich Mean Time
31	LFLAG DS 1X	Link flag byte
<u>Bits defined in LFLAG</u>		
	LACTIVE EQU X'80'	Link active
	LALERT EQU X'40'	AXS ALERT exit set
	LHOLD EQU X'20'	Link hold set
	LDRAIN EQU X'10'	Link drain in progress
	LTRALL EQU X'08'	Link transaction tracing (all)
	LTRERR EQU X'04'	Link transaction tracing (error)
	LHALT EQU X'01'	Link to be forced inactive
	LINKLEN EQU *-LINKTABL	Length of link table entry
32	LRESERVD DS 1H	Count of tag elements reserved
34	LPENDING DS 1H	Count of unaccepted tags
36	LTAKEN DS 1H	Count of tag slots in use
38	LPOINTER DS 1F	Address of start of the TAG queue for this RSCS link
3C	LMSGQ DS 1F	MSG queue pointer
40	LTRNSCNT DS 1H	Link transaction count
42	LERRCNT DS 1H	Error count
44	LTOCNT DS 1H	Timeout count
46	LSPARE DS 1H	Spare halfword
48	LNKCLOCK DS 8X	Clock comparator value for this link


REQBLOCK

REQBLOCK: NPT REQUEST BLOCK


REQBLOCK defines data and information for a request for file processing by the DMTMFT line driver.

The first four fields of this DSECT form a GIVE request table, which is described in "GIVEEE: A GIVE Element", in this section.

The next seven fields of this DSECT for a GIVE request buffer in the format of a File Request Element, which is described in "Appendix C: RS/SCS Request Elements."



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
<u>Hexadecimal Locations 0 through F Comprise the NPT GIVE Request Table</u>		
0	RDEVSNC DC F'0'	Synchronous lock
4	RDEVREQN DC CL4'AXS'	File access task
8	RDEVREQ DC A(0)	Request buffer address
C	RDEVRESP DC AL1(0),AL3(0)	Response buffer address
<u>Hexadecimal Locations 0 through 1F Comprise the NPI GIVE Request Buffer in the Format of a File Request Element (as shown in Appendix C)</u>		
10	RDEVRLEN DC AL1(0)	Request length
11	RDEVFUN DC AL1(0)	Request function
12	RDEVRESV DC AL1(0)	Reserved for IBM use
13	RDEVSOPT DC AL1(0)	Subordinate option byte
14	RDEVTAG DC A(0)	Tag address
18	RDEVFIOA DC A(0)	File I/O area address
1C	RDEVLINK DC CL8' '	Link name
24	RDEVNAME DC C' '	Device name
27	RDEVSTYL DC C' '	Device style
2C	RDEVFLAGS DC AL1(0,0,0,0)	Device flags

ROUTE: ROUTING TABLE ENTRY

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	ROUTDEST DS CL8	Final destination ID
8	ROUTNEXT DS CL8	LINKID for indirect routing
	ROUTSIZE EQU *-ROUTDEST	Length of a routing table entry



SVECTORS

SVECTORS: LOW STORAGE DEFINITIONS

SVECTORS defines low storage for the RSCS virtual machine. It includes two types of storage: machine-defined and RSCS-defined.

• MACHINE-DEFINED LOW STORAGE

The SVECTORS machine-defined low storage defines machine status data referenced during program execution and required by System/370 architecture.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	IPLPSW	DS D X'00040000', V(DMIIINI)
8	IPLCCW1	DS D
10	IPLCCW2	DS D
18	OLDEXT	DS D External interrupt old PSW
20	OLDSVC	DS D Supervisor call old PSW
28	OLDPROG	DS D Program check old PSW
30	OLDMACH	DS D Machine check old PSW
38	OLDIO	DS D Input/output old PSW
40	CSW	DS D Channel status word
48	CAW	DS F Channel address word
4C		DS F Reserved for IBM use
50	TIMER	DS F 4X' FF' TOD clock
54		DS F Reserved for IBM use
58	NEWEXT	DS D X'00040000', V(DMTEXT)
60	NEWSVC	DS D X'00040000', V(DMTSVC)
68	NEWMACH	DS D X'00040000', A(REXOUCH)
70	NEWMACH	DS D X'00020000', A(OLDMACH)
78	NEWIO	DS D X'00040000', V(DMTIOMIN)

- RSCS-DEFINED LOW STORAGE

RSCS-defined low storage begins at hexadecimal location 200 and is defined specifically for the RSCS virtual machine. It contains pointers to modules that comprise the supervisor, supervisor control queues, and queues of requests for supervisor services.

200	NEWPSW
204	
208	SSAVE
20C	
210	ACTIVE
214	MAINMAP
218	MAINSIZE
21C	QUEUE
220	QUEUEND
224	FREEQ
228	TASKQ
22C	MPXIOQ
230	SELIOQ
234	IOEXITQ
238	EXTQ
23C	ALERTQ
240	GIVEQ
244	QREQ

248	DISPATCH
24C	WAITREQ
250	POSTREQ
254	IOREQ
258	TASKREQ
25C	MAINREQ
260	ASYNREQ
264	ALERTREQ
268	GIVEREQ
26C	TAKEREQ
270	TVECTCR0
274	TVECTCR1
278	TVECTCR2
27C	TVECTCR3
280	TVECTCR4
284	TVECTCR5
288	TVECTCR6
28C	TVECTCR7

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
200	NEWPSW	ORG SVECTORS+X'200' Leave room for machine extensions
208	SSAVE	Dispatched PSW for last dispatcher
210	ACTIVE	General-purpose low storage save area
214	MAINMAP	Identifier of currently active task DS AL3 AL3(0) Address of task element for last dispatchee
218	MAINSIZE	DS V(DMTMAPMS) Address of start of main storage allocation map Total number of pages in main storage

SVECTORS

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
21C	QUEUE	DS V(SQUEUE)
220	QUEUEEND	DS V(SQUEUEEND)
224	FREEQ	DS A(0)
228	TASKQ	DS A(0)
22C	MPXIOQ	DS A(0)
230	SELIOQ	DS A(0)
234	IOEXITQ	DS A(0)
238	EXTQ	DS A(0)
23C	ALERTQ	DS A(0)
240	GIVEQ	DS A(0)
244	QREQ	DS V(DMTQRQ)
248	DISPATCH	DS V(DMTDSP)
24C	WAITREQ	DS V(DMTWAT)
250	POSTREQ	DS V(DMTPST)
254	IOREQ	DS V(DMTIOMRQ)
258	TASKREQ	DS V(DMTASK)
25C	MAINREQ	DS V(DMTSTO)
260	SYNREQ	DS V(DMTASY)
264	ALERTREQ	DS A(DMTSIG) A(ALERT) entry address
268	GIVEREQ	DS V(DMTGIV)
26C	TAKEREQ	DS V(DMTAKE)
270	TVECTOR0	DS A(0)
274	TVECTOR1	DS A(0)
278	TVECTOR2	DS A(0)
27C	TVECTOR3	DS A(0)
280	TVECTOR4	DS A(0)
284	TVECTOR5	DS A(0)
288	TVECTOR6	DS A(0)
28C	TVECTOR7	DS A(0)
	TLINKS	EQU TVECTOR0
	TROUTE	EQU TVECTOR1
	TPORTS	EQU TVECTOR2
	TTAGQ	EQU TVECTOR3
	TCOM	EQU TVECTOR4
		Link table address Reserved for IBM use Switchable port table address Tag slot queue Common routine chain

TAG: RSCS FILE DESCRIPTOR


TAG describes a file enqueued for processing by RSCS. The data in this area is built from the TAG record associated with a file via the CP tag command and from the CP spccl file block (SFB) that describes the file.

0	TAGNEXT		
4	TAGBLOCK		
8	TAGINLOC		
C			
10	TAGLINK		
14			
18	TAGINTOD		
1C			
20	TAGINVM		
24			
28	TAGRECNM		
2C	TAGRECLN		TAGINDEV TAGCLASS
30	TAGID		TAGCOPY
34	TAGFLAG TAGFLAG2		//////////RESERVED//////////
38	TAGNAME		
3C			
40			
44	TAGTYPE		
48			
4C			
50	TAGDIST		
54			
58	TAGTOLOC		
5C			
60	TAGTOVM		
64			
68	TAGPRIOR		TAGDEV

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TAGNEXT DS 1F	Address of next active queue entry
4	TAGBLOCK DS 1F	Address of associated I/O area
8	TAGINLOC DS CL8	Originating location
10	TAGLINK DS CL8	Next location for transmission
18	TAGINTOD DS CL8	Time of file origin
20	TAGINVVM DS CL8	Originating virtual machine
28	TAGRECNM DS 1F	Number of records in file
2C	TAGRECLN DS 1H	Maximum file data record length
2E	TAGINDEV DS 1X	Device code of originating device
2F	TAGCLASS DS CL1	File output class
30	TAGID DS 1H	File number at origin location
32	TAGCOPY DS 1H	Number of copies required
34	TAGFLAG DS 1X	VM/370 SFELCK control flags (SFBFLAG)
35	TAGFLAG2 DS 1X	VM/370 SFELCK control flags (SFFFLAG)
36	DS 1H	Reserved for IBM use
38	TAGNAME DS CL12	Filename
44	TAGTYPE DS CL12	Filetype
50	TAGDIST DS CL8	File distribution code
58	TAGTOLOC DS CL8	Destination location ID
60	TAGTOVM DS CL8	Destination virtual machine ID
68	TAGPRIOR DS CL2	Transmission priority
6A	TAGDEV DS 2X	Active file's virtual device address
	TAGLEN EQU *--TAGNEXT	Length (in bytes) of the file TAG (X'0D')

TAGAREA


TAGAREA in DMTAXS module contains tag queue pointers and other tag control information. It is pointed to by TTAGQ in SVECTORS.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TAGAFREE	DC A(0) Address of queue of free TAG slots (or elements)
4	TAGACIN	DC A(0) Pointer to queue of active input TAGs
8	TAGACOUT	DC A(0) Pointer to queue of active output TAGs
C	TAGAGOT	DC H'0' Number free slots left
E	TAGAHOLD	DC H'0' Number slots to be held

TAKE REQUEST TABLE


The format of a TAKE request table is:



| The TAKE request table corresponds to the GIVE request table. It is built by the task | performing the requested service (via a GIVE request by another task).

TANKDSEC**TANKDSEC: SML UNIT RECORD TANK**

TANKDSEC is used to reference buffer data and control information contained in tanks, which are unit buffers used to deblock the larger TP buffers. (TP buffers are defined by the needs of an individual remote station and their size varies from station to station.) \$TANKPOL in module DMTSML points to a queue of available tanks.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TANKCHN	DC A(0) Tank chain field
4	TANKRCB	DC 1C Tank record control byte
5	TANKSRCB	DS 1C Tank subrecord control byte
6	TANKCNT	DS 1H Count of data bytes in tank
8	TANKDATA	DS CL200 Data area in tank
D0	TANKEND	DS 0F Force next to word boundary

TAREA: A TASK SAVE AREA

TAREA an area associated with each task. This area is used to save the contents of the task's PSW and general registers and to flag whether or not a task has information ready to pass. TAREA comprises the first 78 bytes of the storage area defined in each task's storage.

0	TPSW
4	
8	TGREG0
C	TGREG1
10	TGREG2
14	TGREG3
18	TGREG4
1C	TGREG5
20	TGREG6
24	TGREG7
28	TGREG8
2C	TGREG9
30	TGREG10
34	TGREG11
38	TGREG12
3C	TGREG13
40	TGREG14
44	TGREG15
48	TREQLOCK


TAREA

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TPSW	PSW with which a temporarily interrupted task resumes execution
8	TGREG0	Save area for general register 0
C	TGREG1	Save area for general register 1
10	TGREG2	Save area for general register 2
14	TGREG3	Save area for general register 3
18	TGREG4	Save area for general register 4
1C	TGREG5	Save area for general register 5
20	TGREG6	Save area for general register 6
24	TGREG7	Save area for general register 7
28	TGREG8	Save area for general register 8
2C	TGREG9	Save area for general register 9
30	TGREG10	Save area for general register 10
34	TGREG11	Save area for general register 11
38	TGREG12	Save area for general register 12
3C	TGREG13	Save area for general register 13
40	TGREG14	Save area for general register 14
44	TGREG15	Save area for general register 15
48	TREQLOCK	Synchronization lock used to signal whether or not a task has information

TASKE: A TASK ELEMENT

TASKE defines symbolic names of status information pertaining to an active task.

The TASKQ field of SVECTORS points to a queue of task elements, each of which is defined by this DSECT. The queue consists of one task element (TASKE) for each active task.



Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TASKNEXT DS 1F	Address of the next element on the task element queue
4	TASKSAVE DS 1F	Address of this task's Task Save Area (TAREA)
8	TASKNAME DS CL4	Task name specified by the task; 4 bytes long
C	TASKSPAR DS AL2	Reserved for IBM use
E	TASKSTAT DS 1X	Status flags associated with the task
<u>Bits defined in TASKSTAT</u>		
	WAITING EQU X'80'	Flag set to 1 when task is nondispatchable
	LOCKLIST EQU X'40'	Flag set to 1 while task is waiting for the synchronous lock list
	LIMBO EQU X'01'	Flag set to 1 when a task is being terminated.
F	TASKID DS 1X	Number ID for the task; 1 byte is assigned by the supervisor when task is made active

TCTDSECT

TCTDSECT: TASK CONTROL TABLE

TCTDSECT defines the format of six tables used by module DMTSML that are at labels \$CCOM1, \$WCOM1, \$PCOM1, \$RCOM1, \$UCOM1, and \$JCOM1. Each table corresponds to a DMTSML input/output processor and is used by that processor to perform its I/O function.

The GIVE request table and the GIVE request buffer used by DMTSML are embedded in the task control table at locations X'24' through X'30' and X'34' through X'40', respectively.

0	TCTSTRT		TCTENTY
4	TCTRTRN		
8	TCTCCW		TCTDATA
C	TCTFLAG	TCTOPCOD	TCTCCWCT
10	TCTECB	TCTSTAT	TCTWFE
14	TCTSARV1		
18	TCTNEXT		
1C	TCTFCS		TCTRRCER TCTRRCBT
20	TCTCOM		
24	TDEVSYNC		
28	TDEVREQN		
2C	TDEVREQ		
30	TDEVRESP		
34	TDEVRLEN	TDEVFUN	!///TDEVRESV/// TDEVSOPT
38	TDEVTAG		
3C	TDEVFIOA		
40	TDEVLINK		
44			
48	TSW1	TSW2	TSW3 TSW4
4C	TCTTOVM		
50			
54	TCTTANK		
58	TCTBUFER		
5C	TCTTNKLM	TCTTNKCT	TCTBUFLM TCTBUFCT

Hexadecimal Displacement	Field Name	Field Description, Contents, Meaning
0	TTCT DS OH	
0	TCTSTRT DS CL2	Branch to proper processor entry
2	TCTENTY DS CL2	Address portion modified by processor
4	TCTRPN DS CL4	Branch to next processor via commutator
8	TCTCCW DS CL1	CCW for device operation code
9	TCTDATA DS AL3	Address of data transferred
C	TCTFLAG DS CL1	Flags on CCW
D	TCTOPCOD DS CL1	Save area for CCW operation code
E	TCTCCWCT DS AL2	CCW count of data transferred
10	TCTECB DS CL1	Event control block
<u>Bits defined in TCTECB</u>		
	TCTBUSY EQU X'10'	Device busy bit
11	TCTSTAT DS CL1	Status flags
<u>Bits defined in TCTSTAT</u>		
	TCT1052 EQU X'10'	TCT status flags for 1052
	TCTREL EQU X'04'	Interlock release request for console
	TCTOPEN EQU X'80'	TCT open bit
	TCTACT EQU X'40'	Action required on this TCT
12	TCTWFB DS AL1	Waiting for buffers
14	TCTS A V1 DS 1F	Save area for processor routine
18	TCTNEXT DS 1F	Next TCT in chain
1C	TCTFCS DS AL2	Function control sequence mask
1E	TCTR CBR DS CL1	RECV record control block
1F	TCTR CBT DS CL1	Trans record control block
20	TCTCOM DS 1F	Pointer back to commutator
<u>Hexadecimal Locations 24 through 30 Comprise the SML Give Request Table</u>		
24	TDEVSYNC DS 1F	Synch lock
28	TDEVREQN DS CL4	File access name
2C	TDEVREQ DS 1A	Request buffer address
30	TDEVRESP DS 1A	Response buffer
<u>Hexadecimal Locations 34 through 40 Comprise the Give Request Buffer in the Form of a File Request Element (as shown in Appendix C)</u>		
34	TDEVRLEN DS AL1	Request length
35	TDEVFUN DS AL1	Request function
36	TDEVRESV DS AL1	Reserved for IBM use
37	TDEVSOPT DS AL1	Subordinate option byte
38	TDEVTAG DS 1A	Tag address
3C	TDEVFIOA DS 1A	File I/O area
40	TDEVLINK DS CL8	Link name
48	TSW1 DS AL1	Device switch 1
49	TSW2 DS AL1	Device switch 2
4A	TSW3 DS AL1	Device switch 3
4B	TSW4 DS AL1	Device switch 4
4C	TCTTOVM DS CL8	Virtual machine output destination
54	TCTTANK DS 1F	Next tank to generate output
58	TCTBUFER DS 1F	Address of current buffer
5C	TCTTNKLM DS CL1	Maximum number of tanks assignable
5D	TCTTNKCT DS CL1	Current number assigned
5E	TCTBUFLM DS CL1	Maximum number of buffers assignable
5F	TCTBUFCT DS CL1	Current number assigned

Appendices

Information in the following appendices supplements the text in Sections 1 through 3 of this publication:

- "Appendix A. CP and RSCS Equate Symbols" contains assembler language equate symbols used in CP and RSCS to reference data.
- "Appendix B. RSCS Control Areas" shows those constants and variables used during execution of RSCS tasks.
- "Appendix C. RSCS Request Elements" contains information on and formats of tables used during RSCS task-to-task communication.
- "Appendix D. CMS Equate Symbols" contains Assembler language equate symbols used in CMS to reference data.
- "Appendix E. Data Areas and Control Block References" lists the names of CP, CMS, and RSCS control blocks. This appendix (1) shows module references to data areas and/or control blocks and (2) gives information on how certain data areas or control blocks are created and released.

Appendix A. CP and RSCS Equate Symbols

This Appendix contains Assembler language equate symbols used to reference CP and RSCS data for:

- VM/370 Device Classes, Types, Models, and Features
- VM/370 Machine Usage
- VM/370 Extended Control Registers
- VM/370 CP Usage
- VM/370 Registers

VM/370 DEVICE CLASSES, TYPES, MODELS, AND FEATURES

Field Name			Field Description, Contents, Meaning
<hr/>			
CLASTERM	EQU	X'80'	Terminal device class
TYP2700	EQU	X'40'	2700 bisynchronous line
TYP2955	EQU	TYP2700	2955 communications line
TYPTELE2	EQU	X'20'	Telegraph terminal control type II
TYPTTY	EQU	X'20'	Teletype terminal
TYPIBM1	EQU	X'10'	IBM terminal contrcl type I
TYP2741	EQU	X'18'	2741 communications terminal
TYP1050	EQU	X'14'	1050 communications terminal
TYPUNDEF	EQU	X'1C'	Terminal device type is undefined
TYPBSC	EQU	X'80'	Bisynchronous line for 3270 remote stations
TYP3210	EQU	X'00'	3210 console
TYP3215	EQU	TYP3210	3215 console
TYP2150	EQU	TYP3210	2150 console
TYP1052	EQU	TYP3210	1052 console
FTRDIAL	EQU	X'01'	Dial feature
CLASGRAF	EQU	X'40'	Graphics device class
TYP2250	EQU	X'80'	2250 display unit
TYP2260	EQU	X'40'	2260 display statinc
TYP2265	EQU	X'20'	2265 display statinc
TYP3066	EQU	X'10'	3066 console
TYP1053	EQU	X'08'	1053 printer
TYP3277	EQU	X'04'	3277 display statinc
TYP3278	EQU	X'01'	3278 Model 2A system console
TYP3284	EQU	X'02'	3284 printer
TYP3286	EQU	TYP3284	3286 printer
TYP3287	EQU	TYP3284	3287 printer
TYP3288	EQU	TYP3284	3288 printer
TYP3138	EQU	TYP3277	3138 system console
TYP3148	EQU	TYP3277	3148 system console
TYP3158	EQU	TYP3277	3158 system console
FTROPRDR	EQU	X'80'	Operator identification card reader
CLASUR1	EQU	X'20'	Unit record input device class
TYPRDR	EQU	X'80'	Card reader device
TYP2501	EQU	X'81'	2501 card reader
TYP2540R	EQU	X'82'	2540 card reader
TYP3505	EQU	X'84'	3505 card reader
TYP1442R	EQU	X'88'	1442 card reader/punch
TYP2520R	EQU	X'90'	2520 card reader/punch
TYPTIMER	EQU	X'40'	Timer device
TYPTR	EQU	X'20'	Tape reader device
TYP2495	EQU	X'21'	2495 magnetic tape cartridge reader
TYP2671	EQU	X'22'	2671 paper tape reader
TYP1017	EQU	X'24'	1017 paper tape reader
CLASURO	EQU	X'10'	Unit record output device class
TYPPUN	EQU	X'80'	Card punch device
TYP2540P	EQU	X'82'	2540 card punch
TYP3525	EQU	X'84'	3525 card punch
TYP1442P	EQU	X'88'	1442 card punch
TYP2520P	EQU	X'90'	2520 card punch
TYPPRT	EQU	X'40'	Printer type device
TYP1403	EQU	X'41'	1403 printer
TYP3211	EQU	X'42'	3211 printer
TYP3203	EQU	X'43'	3203 printer (3211 and 1403)
TYP1443	EQU	X'44'	1443 printer

Field Name			Field Description, Contents, Meaning
TYP3800 EQU X'45'			3800 Printing subsystem
TYPTP EQU X'20'			Tape punch device
TYP1018 EQU X'24'			1018 paper tape punch
FTRUCS EQU X'01'			UCS feature
FTR4WCGM EQU X'80'			3800 has four WCGM available. Note that FTREXTSN (X'40') is also used for a 3800 printer.
CLASTAPE EQU X'08'			Magnetic tape device class
TYP2401 EQU X'80'			2401 tape drive
TYP2415 EQU X'40'			2415 tape drive
TYP2420 EQU X'20'			2420 tape drive
TYP3420 EQU X'10'			3420 tape drive
TYP3410 EQU X'08'			3410 tape drive
TYP3411 EQU TYP3410			3411 tape drive
FTR7TRK EQU X'80'			7-track feature
FTRDLDNS EQU X'40'			Dual density feature
FTRTRANS EQU X'20'			Translate feature
FTRDCONV EQU X'10'			Data conversion feature
CLASDASD EQU X'04'			Direct access storage device class
TYP2311 EQU X'80'			2311 disk storage drive
TYP2314 EQU X'40'			2314 disk storage facility
TYP2319 EQU TYP2314			2319 disk storage facility
TYP2321 EQU TYP2311			2321 data cell drive
TYP3330 EQU X'10'			3330 disk storage facility
TYP3333 EQU TYP3330			3333 disk storage facility
TYP3350 EQU X'08'			3350 disk storage facility
TYP2301 EQU TYP2311			2301 parallel drum
TYP2303 EQU TYP2311			2303 serial drum
TYP2305 EQU X'02'			2305 fixed head storage device
TYP3340 EQU X'01'			3340 disk storage facility
FTRRPS EQU X'80'			Rotational positional sensing (RPS) installed (3340)
FTREXTSN EQU X'40'			Extended sense bytes (24 bytes)
FTR2311T EQU X'20'	(= VDEV231T)		Top half of 2314 used as 2311
FTR2311B EQU X'10'	(= VDEV231B)		Bottom half of 2314 used as 2311
FTR35MB EQU X'08'			35 multibyte data module mounted (3340)
FTR70MB EQU X'04'			70 multibyte data module mounted (3340)
FTRRSRL EQU X'02'			Reserve/release are valid CCW operation codes
VIRTUAL EQU X'01'			Device is a 3330V virtual machine
SYSVIRT EQU X'20'			Device is a 3330V system virtual machine
FTRVIRT EQU X'01'			3330 virtual (MSS) volume
CLASSSPEC EQU X'02'			Special device class
TYPCTCA EQU X'80'			Channel-to-channel adapter
TYP3704 EQU X'40'			3704 programmable communication control unit
TYP3705 EQU TYP3704			3705 programmable communication control unit
TYP3851 EQU X'20'			3851 Mass Storage Controller
TYPSRF EQU X'04'			SRF device (#7443)
TYPUNSUP EQU X'01'			Device not supported by VM/370
FTRTYP1 EQU X'10'			Type 1 channel adapter (370x)
FTRTYP2 EQU X'20'			Type 2 channel adapter (370x)
FTRTYP3 EQU FTRTYP2			Treat as type 2 channel adapter (370x)
FTRTYP4 EQU FTRTYP1			Treat as type 1 channel adapter (370x)

VM/370 EQUATE SYMBOLS -- MACHINE USAGE

Field Name	Field Description, Contents, Meaning
<u>Bits defined in Standard/Extended PSW</u>	
EXTMODE EQU X'08'	Bit 12 - extended mode
MCHEK EQU X'04'	Bit 13 - machine check enabled
WAIT EQU X'02'	Bit 14 - wait state
PROBMODE EQU X'01'	Bit 15 - problem state
<u>Bits defined in Extended PSW</u>	
PERMODE EQU X'40'	Bit 01 - PER enabled
TRANMODE EQU X'04'	Bit 05 - translate mode
IOMASK EQU X'02'	Bit 06 - summary I/O mask
EXTMASK EQU X'01'	Bit 07 - summary external mask
<u>Bits defined in Channel Status Word (CSW)</u>	
ATTN EQU X'80'	Bit 32 - attention
SM EQU X'40'	Bit 33 - status modifier
CUE EQU X'20'	Bit 34 - control unit end
BUSY EQU X'10'	Bit 35 - busy
CE EQU X'08'	Bit 36 - channel end
DE EQU X'04'	Bit 37 - device end
UC EQU X'02'	Bit 38 - unit check
UE EQU X'01'	Bit 39 - unit exception
PCI EQU X'80'	Bit 40 - program-control interrupt
IL EQU X'40'	Bit 41 - incorrect length
PRGC EQU X'20'	Bit 42 - program check
PRTC EQU X'10'	Bit 43 - protection check
CDC EQU X'08'	Bit 44 - channel data check
CCC EQU X'04'	Bit 45 - channel control check
IFCC EQU X'02'	Bit 46 - interface control check
CHC EQU X'01'	Bit 47 - chaining check
<u>Bits defined in Channel Command Word (CCW)</u>	
CD EQU X'80'	Bit 32 - chain data
CC EQU X'40'	Bit 33 - command chain
SILI EQU X'20'	Bit 34 - suppress incorrect length indicator
SKIP EQU X'10'	Bit 35 - suppress data transfer
PCIF EQU X'08'	Bit 36 - program-control interrupt FETCH
IDA EQU X'04'	Bit 37 - indirect data address
<u>Bits defined in Sense Byte 0 (common to most devices)</u>	
CMDREJ EQU X'80'	Bit 0 - command reject
INTREQ EQU X'40'	Bit 1 - intervention required
EUSOUT EQU X'20'	Bit 2 - bus out
EQCHK EQU X'10'	Bit 3 - equipment check
DATACHK EQU X'08'	Bit 4 - data check

VM/370 EQUATE SYMBOLS -- EXTENDED CONTROL REGISTERS

Field Name	Field Description, Contents, Meaning	
Bits defined in CREG0		
• BYTE 0		
BLKMPX EQU X'80'	Bit 00 - enable block multiplexing	
SSMSUPP EQU X'40'	Bit 01 - enable SSM suppression	
TODSYNC EQU X'20'	TOD synchronous control	
• BYTE 1		
PAGE4K EQU X'80'	Bit 08 - use 4K pages	
PAGE2K EQU X'40'	Bit 09 - use 2K pages	
SEG1M EQU X'10'	Bit 11 - use 1M segments	
• BYTE 2		
MFAMASK EQU X'80'	Bit 16 - malfunction alert mask	
EMSMASK EQU X'40'	Bit 17 - emergency signal mask	
XCMASK EQU X'20'	Bit 18 - external call mask	
SYNCMASK EQU X'10'	Bit 19 - TOD synchronous check mask	
CKCMASK EQU X'08'	Bit 20 - mask on clock comparator interrupt	
CPTMASK EQU X'04'	Bit 21 - mask on processor timer interrupt	
• BYTE 3		
INTMASK EQU X'80'	Bit 24 - mask on interval timer interrupt	
KEYMASK EQU X'40'	Bit 25 - mask on operator key interrupt	
SIGMASK EQU X'20'	Bit 26 - mask on external signals 2 through 7	
Bits defined in CREG8		
• BYTE 3		
PERFCL EQU X'80'	Sample hardware/software utilizations	
RESPCL EQU X'40'	Trace response class	
SCHEDCL EQU X'20'	Trace scheduler activity class	
TIMECL EQU X'10'	Execution timing class	
USERCL EQU X'08'	Sample user resource usage class	
PRIVCL EQU X'04'	Privileged operands class	
DASDCL EQU X'02'	Sample DASDs; utilizations class	
SEEKCL EQU X'01'	Trace DASD seek activity	
• BYTE 4		
SPROFCL EQU X'80'	Trace system profile class	
Bits defined in CREG9		
• BYTE 0		
PERSUBR EQU X'80'	Bit 00 - monitor successful branches	
PERIFET EQU X'40'	Bit 01 - monitor instruction fetches	
PERSALT EQU X'20'	Bit 02 - monitor storage alteration	
PERGPRS EQU X'10'	Bit 03 - monitor register alteration	
Bits defined in CREG14		
• BYTE 0		
HARDSTOP EQU X'80'	Bit 00 - check stop control	
SYNCLOG EQU X'40'	Bit 01 - synchronous logout control	
IOLOG EQU X'20'	Bit 02 - I/O logout control	
RECOVRPT EQU X'08'	Bit 04 - recovery report mask	
CONFGRPT EQU X'04'	Bit 05 - configuration report mask	
DAMAGRPT EQU X'02'	Bit 06 - external damage report mask	
WARNRPT EQU X'01'	Bit 07 - warning condition report mask	
• BYTE 1		
ASYNELOG EQU X'80'	Bit 08 - asynchronous extended logout control	
ASYNFLOG EQU X'40'	Bit 09 - asynchronous fixed logout control	

VM/370 EQUATE SYMBOLS -- CP USAGE

Field Name	Field Description, Contents, Meaning
<u>Bits defined for TRANS macro</u>	
BRING EQU X'80'	Bring requested page
DEFER EQU X'40'	Defer execution until page in core
LOCK EQU X'20'	Lock page for I/O operation
IOERETN EQU X'10'	Return I/O errors to caller
SYSTEM EQU X'08'	Call to DMKPTRAN for system virtual machine space
VFAULT EQU X'04'	DMKPTRAN call for virtual page. Caller will not utilize real address
<u>Equates for Parameter Field for Calls to DMKELDRT/DMKELIRL</u>	
DELSEGS EQU X'80'	Release the segment tables
DELPAGES EQU X'40'	Release the page/swap tables
VRALOC EQU X'20'	Attempt allocation of Virtual=Real area
PAGONLY EQU X'10'	Only one page table and return
NEWPAGES EQU X'08'	Build new page/swap table
NEWSEGS EQU X'04'	Build new segment table
KEEPSEGS EQU X'02'	Retain information in old segment table
OLDVMSSEG EQU X'01'	VMSEG pointer in VMELOK valid
<u>Bits defined for Terminal I/O via DMKQCN</u>	
NOTRESP EQU X'4000'	Output - Message not a command response
ERRMSG EQU X'0800'	Output - control program error message
NORET EQU X'0400'	Output - return immediately after call
DFRET EQU X'0200'	Output - FRET buffer after queueing
OPERATOR EQU X'0100'	Output - message for system operator
LOGDROP EQU X'80'	Output - logoff and drop line after message
LOGHOLD EQU X'40'	Output - logoff and hold line after message
PRIORITY EQU X'20'	Output - write this message immediately
VMGENIO EQU X'10'	I/O request generated by virtual machine
NOAUTO EQU X'04'	Output - suppress automatic carriage return
ALARM EQU X'02'	Output - sound the audible alarm
NOTIME EQU X'01'	Output - suppress time stamp on message
INHIBIT EQU X'08'	Input - prevent display of this data
EDIT EQU X'04'	Input - edit input data for corrections
UCASE EQU X'02'	Input - translate data to uppercase
<u>Equates for Spool File Recovery Routine - DMKCKS</u>	
CHGSHQ EQU X'0200'	Checkpoint a SHQBLOK
CHGRDV EQU X'0100'	Change attributes of real device
ACTSFB EQU X'80'	File being printed or punched
OPNSFB EQU X'40'	An open print-punch file
DELSFB EQU X'20'	Delete SFBLOK from checkpoint
CHGSFB EQU X'10'	Change existing SFELOK
ADDSFB EQU X'08'	Add new SFBLOK to recovery cylinder
PRTCHN EQU X'04'	SFBLOK goes on print chain
PCHCHN EQU X'02'	SFBLOK goes on punch chain
RIRCHN EQU X'01'	SFBLOK goes on reader chain
<u>Equates for SWTCVHM macro</u>	
SVMUNLOK EQU X'04'	Unlock only the current virtual machine
SVMNOUPD EQU X'02'	Lock virtual machine with NOUPDT option
SVMSTAY EQU X'01'	Stack CPEXBLOK for current processor

Field Name	Field Description, Contents, Meaning	
Monitor Class and Code Definitions		
MNCLPERF EQU	X'00'	Monitor perform class
MNCOSYS EQU	X'0000'	Perform class, system performance
MNCOTH EQU	X'0061'	Monitor tape header record
MNCOTT EQU	X'0062'	Monitor tape trailer record
MNCOSUS EQU	X'0063'	Monitor collection suspension record
MNCLRESP EQU	X'01'	Monitor response class
MNCOBRD EQU	X'0000'	Response class, begin read code
MNCOWRIT EQU	X'0001'	Response class, write code
MNCOERD EQU	X'0002'	Response class, end read code
MNCLSCH EQU	X'02'	Monitor schedule class
MNCODQ EQU	X'0002'	Schedule class, drop queue code
MNCOAQ EQU	X'0003'	Schedule class, add to queue code
MNCOAEL EQU	X'0004'	Schedule class, add to eligible list code
MNCLUSER EQU	X'04'	Monitor user class
MNCOUSER EQU	X'0000'	User class, user data
MNCLINST EQU	X'05'	Monitor instruction simulation class
MNCOSIM EQU	X'0000'	Instruction class; instruction simulation code
MNCLDAST EQU	X'06'	Monitor DASD/tape class
MNCODASH EQU	X'0000'	DASTAP class, first record
MNCODAS EQU	X'0001'	DASTAP class, data records
MNCLSEEK EQU	X'07'	Monitor DASD class
MNCOCYL EQU	X'0000'	DASD class, seeks code
MNCLSYS EQU	X'08'	Monitor system profile class
MNCODA EQU	X'0002'	SYS class, DASD data

Field Name	Field Description, Contents, Meaning
<hr/>	
<u>Equates for SIGNAL Macro</u>	
SIGSENSE EQU X'01'	Sense order code
SIGXC EQU X'02'	External call order code
SIGEMS EQU X'03'	Emergency signal order code
SIGSTART EQU X'04'	Start order code
SIGSTOP EQU X'05'	Stop order code
SIGREST EQU X'06'	Restart order code
SIGIPR EQU X'07'	Initial program reset order code
SIGPR EQU X'08'	Program reset order code
SIGSSS EQU X'09'	Stop and store status order code
SIGIML EQU X'0A'	Initial microprogram load order code
SIGICR EQU X'0B'	Initial processor reset order code
SIGCR EQU X'0C'	Processor reset order code emergency signals
SIGQUI EQU X'800'	Quiesce emergency signal
SIGEXT EQU X'400'	Extend emergency signal
SIGSYNC EQU X'200'	Clock synchronization emergency signal
SIGSHD EQU X'100'	Shutdown emergency signal
SIGCLK EQU X'080'	Clock check signal (external call signals)
SIGAPR EQU X'800'	Automatic processor recovery (external call signal)
SIGRES EQU X'400'	Resume external call signal
SIGWAKE EQU X'200'	Wakeup external call signal
SIGDISP EQU X'100'	Dispatch external call signal

VM/370 REGISTERS

Field Name	Field Description, Contents, Meaning	
<u>Symbolic Register Equates</u>		
R0	EQU	0
R1	EQU	1
R2	EQU	2
R3	EQU	3
R4	EQU	4
R5	EQU	5
R6	EQU	6
R7	EQU	7
R8	EQU	8
R9	EQU	9
R10	EQU	10
R11	EQU	11
R12	EQU	12
R13	EQU	13
R14	EQU	14
R15	EQU	15
Y0	EQU	0
Y2	EQU	2
Y4	EQU	4
Y6	EQU	6
C0	EQU	0
C1	EQU	1
C2	EQU	2
C3	EQU	3
C4	EQU	4
C5	EQU	5
C6	EQU	6
C7	EQU	7
C8	EQU	8
C9	EQU	9
C10	EQU	10
C11	EQU	11
C12	EQU	12
C13	EQU	13
C14	EQU	14
C15	EQU	15

General register definitions

Floating-point register definitions

Control register definitions

Appendix B. RSCS Control Areas

This appendix lists the control areas used during task processing. Information such as lists of synchronous locks, channel programs, TAKE request tables and buffers, and various work constants are included in these areas.

AXS MONITOR CONTROL AREA

The AXS Monitor Control Area is a data area used by DMTAXS to set up synch locks, a TAKE request table, a TAKE request and response buffer, and an input buffer.

<u>Field Name</u>	<u>Field Description, Contents, Meaning</u>	
AXSNAME	DC OF'0',CL4'AXS'	Task name for AXS routine
REXNAME	DC OF'0',CL4'REX'	Task name for control monitor
AXSLOCKS	DC A(ARRLOCK) DC A(REQLOCK) DC X'80',AL3(CMDLOCK)	File tag arrival synchronous lock address Request arrival synchronous lock address Command synchronous lock address
ARRLOCK	DC F'0'	File tag arrival synchronous lock
CMDLOCK	DC F'0'	Command synchronous lock
AXSTAKE	DC OF'0' DC CL4' ' DC AL1(L'AXSREQ) AL3(AXSREQ) DC A(AXSRESP)	TAKE request table Giver's task name Pointer to request buffer (input) Pointer to response buffer (output)
AXSREQ	DC XL140'00'	TAKE request buffer
AXSRESP	DC XL136'00'	TAKE response buffer
CMDIN	DC CL122' '	Input buffer for command element
CMDINPGS	DC X'00'	Command in progress switch
AXSCSAVE	DC 18F'0'	Common routine save area

REX MONITOR CONTROL AREA

The REX Monitor Control Area is a data area used by DMIREX to initialize the DMTAXS and DMTLAX modules, point to queues of system data (such as the link table chain and the chain of tag elements), set up a series of synch locks for REX processing function, set up a console element, read and write channel programs, a console table buffer, a message buffer, a TAKE request table, and various work constants.

<u>Field Name</u>		<u>Field Description, Contents, Meaning</u>
RFXREX	DC OF'0',CL4'REX'	Task name
REXAXS	DC OF'0',CL8'DMTAXS'	AXSname
REXLAX	DC OF'0',CL8'DMTLAX'	LAXname
REXTVECT	DC OF'0' DC V(DMTSYSLK) DC V(DMTSYSRT) DC V(DMTSYSPT) DC V(DMTSYSTQ) DC V(DMTCOMVC) DC V(DMTSYSND)	Link table chain Route table chain Switchable port chain Tag slot queue Common routine vector End of REX initial load
REXLOCKS	DC OF'0' DC X'00',AL3(REQLOCK) DC X'00',AL3(ATTNLOCK) DC X'40',AL3(REXCONSL) DC X'80',AL3(PROGLOCK) DC OF'0',X'00',AL3(0)	Main REX wait list Request arrival synchronous lock address Console attention synchronous lock address Console I/O synchronous lock address Program check synchronous lock address Console attention lock
ATTNLOCK		
REXCONSL	DC F'0' DC AL2(CONSADDR) DC AL1(1) DC AL1(TYP3210) DC A(0) DC 2F'0' DC X'00'	Synchronous lock for I/O operation CUU console device address One byte requested on unit check Console device type code Channel program address to be filled in SIO condition code and ending CSW return information Sense return information on unit check Reserved for IBM use External name
DMTREXCN	DC 3X'00' EQU REXCONSL	
CONSADDR	EQU X'009'	Default console cuu
REXREAD	CCW X'0A',REXIN ,SILI,L'REXIN	Reader operator response
RFXWRITE	CCW X'09',REXOUT+2,SILI,0	Type a console message
REXIN	DC CL130' '	Console input buffer
REXMSG	DC CL11'M OP'	MSG command start
DMTREXID	EQU REXMSG+2	Transfer user identification
REXOUT	DC CL130' '	Output buffer
REXTAKE	DC OF'0' DC CL4' ' DC AL1(L'REXREQ),AL3(REXREQ) DC A(REXRESP)	Request TAKE table Sending task name filled in by TAKE manager Address and length of request buffer Address of response buffer
RFXREQ	DC XL140'00'	TAKE request buffer
RFXRESP	DC AL1(0)	Never any response messages

SML MONITOR CONTROL AREA

The SML Monitor Control Area is used to define various constants, save areas, BSC control sequences, channel command words, and bit settings used during SML processing.

<u>Field Name</u>			<u>Field Description, Contents, Meaning</u>
CBUFFER	DC	A(0)	Active communications buffer
CFCSSOUT	DC	X'8FCF'	Last FCS transmitted to HASP
CFCSSSTD	DC	X'88C1'	Standard FCS
FCSCTEMP	DC	AL2(0)	FCS compare area
CTEMP	DC	H'0'	Temporary storage
CMAXDUP	DC	H'3'	Maximum repeated blocks
	DC	AL1(0)	First byte of halfword
CBCBCNTO	DC	AL1(X'80')	Block check count out
	DC	AL1(0)	Spacer
CBCBCNTI	DC	AL1(X'80')	Block count character expected
	DC	H'0'	
CEUFLAST	DC	10X'00'	Save of start of last buffer
CRESP	DC	AL1(0)	Response character received
CREGS	DS	3F	Register save area
CRETREGS	DS	3F	Save area
\$COMSEXIT	DC	A(\$START)	COMSUD initial entry point
 CBCB	DC	X'00'	 Last ECB sent for reset
CSETBCB	DC	X'00'	
 CCSW	DS	OF	 Force fullword alignment
COLDRCB	DC	XL8'00'	Temporary storage for CSW
CUNITCMD	DC	X'00'	Last RCB sent
	DC	X'00'	Command code storage
 CLASTCAW	DC	F'0'	 CCW address save
 BUFSYNNSW	DC	X'00'	 Buffer synchronization switch
 <u>Bits defined in BUFSYNNSW</u>			
\$TPPNONE	EQU	X'80'	Stop all buffering
OFLSW	EQU	X'40'	Flush buffer
GDQBUFS	EQU	X'20'	Stop dequeuing buffers
\$COMBUSY	EQU	X'10'	Communications inactive
CUWFAKE	EQU	X'08'	Dummy read on for unit exception recovery
CACKSW	EQU	X'04'	ACK received
 AAEACB	DC	F'0'	 Synchronous lock
AAACUU	DC	X'0000', AL1(1), AL1(TYP2700)	Adapter CCW addr
AECCWA	DC	A(CCTCCW)	
 AAASIOCC	EQU	*	 SIO condition code
 AAACSW	DC	2F'0'	 Adapter ending CSW
AAASENSE	DC	F'10'	Adapter sense byte
AESAV	DC	8F'0'	\$SIO register save area
 <u>Control Sequences</u>			
XSTXSEQ	DC	AL1(XLDR,XSTX)	Start-of-text sequence
XFTBSEQ	DC	AL1(XTRL,XETB)	End-of-text-block sequence
XACKSEQ	DC	AL1(XDLE,XACK0)	Positive acknowledgement sequence
XNAKSEQ	DC	AL1(XSYN,XNAK)	Negative acknowledgement sequence
XSYNSEQ	DC	AL1(XSYN,XSYN,XSYN,XSYN)	Synchronization sequence

<u>Field Name</u>	<u>Field Description, Contents, Meaning</u>	
	<u>Channel Command Words</u>	
	<u>Normal Data Write with Return Data Read</u>	
CCWS	CCW 1,XSYNSEQ,CD+SILI,4	Synchronization sequence
CCWA	CCW 1,0,CC+SILI,0	Write buffer
CCWB	CCW 1,XETBSEQ,CC+SILI,2	Write ending sequence
CCWC	CCW 2,0,SILI,0	Read return data
	<u>Dummy Read To Turn Off Lost Data Sense</u>	
CCWD	CCW 2,0,SILI+SKIP,65000	
	<u>DISABLE command</u>	
CCWOFF	CCW X'2F',0,SILI,1	Disable
WRITE	EQU X'01'	Adapter write command ccde
READ	EQU X'02'	Adapter read command ccde
NOP	EQU X'03'	Adapter NOP command code
SENSE	EQU X'04'	Adapter sense command code
SENSE	EQU X'04'	Adapter sense command code
DISABLE	EQU X'2F'	Adapter disable command ccde

Appendix C. RSCS Request Elements

This appendix provides information on the format and use of RSCS request elements. These elements are used by RSCS tasks in task-to-task communication.

The information provided includes:

- The name of the module that builds the element
- The function performed by the element
- A brief description of the element's usage
- The format of the element
- Any operational notes that might be useful in understanding how the element is used

COMMAND ALERT ELEMENT FORMAT A1

BUILT BY: DMTCMX

FUNCTION: Execute an AXS command

DESCRIPTION: This ALERT element is passed via ALERT to the AXS task (DMTAXS) to request second-level processing of ORDER and PURGE commands.

0	Length (n-1)	Function Code: X'10', X'11'	Response Code	Modifiers
4		linkid		.
.		.	.	.
C	spoolid count (n-X'E')/2		spoolid	.
10				.
.		.	.	.
.		.	.	.
	spoolid		spoolid	

OPERATIONAL NOTES

The linkid field specifies the affected link. The spoolid fields are binary halfwords and specify the files enqueued on the specified link which are to be reordered or purged. The spoolid count field is a binary halfword and specifies the total number of spoolid fields present. The meanings of the other fields follow.

ORDER Command

Function Code: X'10'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:

X'80' Response messages go to local RSCS operator
X'00' Response messages go to specified link.

PURGE Command

Function Code: X'11'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:

X'80' Response messages go to local RSCS operator
X'40' Purge all files enqueued on the specified link
X'00' Purge only specified files, response messages go to specified link

COMMAND ALERT ELEMENT FORMAT A2

BUILT BY: DMTCMX

FUNCTION: Execute AXS command

DESCRIPTION: This ALERT element is passed via ALERT to the AXS task (DMTAXS) to request second-level processing of CHANGE commands.

0	Length (X'33')	Function Code: X'20'	Response Code	Modifiers				
linkid								
.								
.								
C	spoolid		priority					
10	HOLD	CLASS	COPY					
14	Distribution Code							
1C	filename/filetype, dsname							
.								
.								
.								

OPERATIONAL NOTES

The linkid field specifies the link on which the object inactive file is enqueued. The spoolid field is a binary halfword and specifies the object file's VM/370 RSCS identifier.

The following fields are specified only when the corresponding file attribute is to be changed. If the field is not specified, it is set to all 1 bits (X'FF...').

- Priority halfword contains binary priority 0-99
- HOLD has the following:
 X'7F' -- set hold status (HCLD)
 X'3F' -- reset hold status (NOHOLD)
- CLASS 1-byte EBCDIC class, A-Z, 0-9
- COPY halfword binary copy count, 1-99
- Distribution code 8-byte EBCDIC spool file distribution code
- Filename/filetype, dsname, 24-byte EBCDIC spool file filename or filetype or dsname

The meanings of the other fields follow.

CHANGE Command

Function Code: X'20'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:


X'80' Response messages go to local RSCS operator
X'00' Response messages go to specified link

COMMAND ALERT ELEMENT FORMAT LO

BUILT BY: DMTCMX

FUNCTION: Execute a line driver command

DESCRIPTION: This ALERT element is passed via ALERT to a line driver task (DMTNPT, DMTSML) to request second-level processing of START, DRAIN, FREE, HOLD, and TRACE commands.



OPERATIONAL NOTES

The locid specifies the location that is to receive response messages. The meanings of the other fields follow.

START Command

Function Code: X'80'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:

X'80' Start updated classes
X'00' Reset DRAIN status

DRAIN Command

Function Code: X'81'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers: Unused

FREE Command

Function Code: X'82'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers: Unused

HOLD Command

Function Code: X'83'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:

X'80' HOLD Immediate
X'00' HOLD after file processing

TRACE Command

Function Code: X'84'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:


X'C0' TRACE end
X'80' TRACE errors
X'00' TRACE all

COMMAND ALERT ELEMENT FORMAT L1

BUILT BY: DMTCMX

FUNCTION: Execute a line driver command

DESCRIPTION: This ALERT element is passed via ALERT to a line driver task (DMTNPT, DMTSML) to request second-level processing of BACKSPAC and FWDSpace commands.



OPERATIONAL NOTES

The locid specifies the location that is to receive response messages. The count field is a binary fullword, and specifies the number of units to be backspaced or forwardspaced. The meanings of the other fields follow.

BACKSPAC Command

Function Code: X'90'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:

X'80' Backspace count
X'00' Backspace file (restart)

FWDSPACE Command

Function Code: X'91'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy


Modifiers: Unused

COMMAND ALERT ELEMENT FORMAT L2

BUILT BY: DMTCMX

FUNCTION: Execute a line driver command

DESCRIPTION: This ALERT element is passed via ALERT to a line driver task (DMTPT, DMTSML) to request second-level processing of FLUSH commands.



OPERATIONAL NOTES

The locid specifies the location that is to receive response messages. The spoolid field is a binary halfword, and specifies the VM/370 RSCS identifier of the active file to be flushed. The meanings of the other fields follow.

FLUSH Command

Function Code: X'A0'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers:


X'80' Flush all copies, purge file
X'40' Flush hold, keep file, do not decrement copy count
X'00' Flush, decrement copy count, purge file if nc copy count remains

COMMAND ALERT ELEMENT FORMAT L3 (ALSO MESSAGE ALERT ELEMENT)

BUILT BY: DMTCMX, DMTMGX

FUNCTION: Execute a line driver command

DESCRIPTION: This ALERT element is passed via ALERT to a line driver task (DMTNPT, DMTSML) to forward messages, and to request second-level processing of CMD commands.



OPERATIONAL NOTES

The locid specifies the location that is to receive the message or command text. The meanings of the other fields follow.

CMD Command

Function Code: X'B0'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy

Modifiers: None

MSG Command

Function Code: X'B1'

Response Codes:

X'00' Element accepted for processing
X'10' Element rejected, busy


Modifiers: One-byte binary RSCS severity code

COMMAND REQUEST ELEMENT

BUILT BY: DMTNPT, DMTSML

FUNCTION: Execute an RSCS operator command

DESCRIPTION: This request element is passed by a line driver via GIVE/TAKE to the REX task in response to a command entry at a remote station.



OPERATIONAL NOTES


No response text is returned. Command responses are distributed via DMTMGX.

FILE REQUEST ELEMENT

BUILT BY: DMTNPT, DMTSML

FUNCTION: Initiates or terminates processing of an input or output file.

DESCRIPTION: This request element is passed via GIVE/TAKE to the AXS task by line drivers to effect local spool file access during communications with a remote station.



OPERATIONAL NOTES

The use and meaning of the various fields depends on the requested function, as described below. Certain fields may be updated during request processing. The (updated) file request element is returned to the requestor as a GIVE response. The meanings of the other fields follow.

Open Input

Function Code: X'01'

Modifiers: Unused

Tag Address: Response field that points to the opened file's active TAG in DMTSYS

I/O Area Address: Response field that points to a virtual page buffer containing the opened file's first VM/370 spool data buffer.

linkid: Request field that specifies the requesting line driver's linkid.

Response Post Codes:

- X'08' Terminal system error
- X'04' No file available
- X'02' Undefined linkid
- X'01' Previously open file returned

Open Output

Function Code: X'11'

Modifiers: X'80' Do not return possible previously opened file

Tag Address: Request field which points to a prototype file TAG for the output file, constructed by the calling line driver.

I/O Area Address: Response field which points to a virtual page buffer containing an I/O table, a write CCW, and a buffer for processing the output file.

linkid: Request field which specifies the requesting line driver's linkid.

Response Post Codes:

X'04' Error, file not opened

X'02' Undefined linkid

X'01' Previously open file returned

Close Input

Function Code: X'02'

Modifiers:

X'80' Do not purge copy or file

X'40' Purge all copies, and purge file

Tag Address: Request field which points to the file's active TAG in DMTSYS, as supplied by open input.

I/O Area Address: Unused

linkid: Unused

Response Post Codes:

X'04' TAG not found, close failed

Close Output

Function Code: X'12'

Modifiers: Unused

Tag Address: Request field which points to a prototype file TAG for the output file, constructed by the calling line driver. This TAG is used to update the parameters to be set for the output file.

I/O Area Address: Request field which points to the file's I/O area, as supplied by open output.

linkid: Unused

Response Post Codes:


X'04' I/O area not found, close failed

LINE ALERT ELEMENT

BUILT BY: DMTCMX

FUNCTION: Request line port allocation

DESCRIPTION: This ALERT element is passed via ALERT to the LAX task (DMTLAX) to verify and reserve line ports for links being activated in response to a START command.



OPERATIONAL NOTES

Certain fields are updated during processing. The meanings of the fields follow.

Response Codes:

- X'08' Specified line address not attached (CC=3)
- X'04' Specified line address not BSC port device type
- X'02' Line not available

Line Address: Request field specifying requested line address. Zero specification implies request for allocation of a switchable line from the port table. If successful, the port's line address is returned in this field as a response.

linkid: Response field specifying the ID of the link that has reserved the particular requested line address (with response code X'02').

MESSAGE REQUEST ELEMENT

BUILT BY: DMTREX, DMTCMX, DMTAXS, DMTNPT, DMISML

FUNCTION: Issue an RSCS message

DESCRIPTION: This request element is passed via GIVE/TAKE to the REX task, to specify the construction and distribution of an RSCS message (by DMTMSGX).

0	Length (n-1)	Function Code: X'02'	Routing Code	Severity Code
4 Receiver locid				
C Receiver userid				
14 Issuing Module Code Action Code				
18	Binary Message Number	Unused		
1C	8-byte Variable Substitution Values for Message Text			
.	.			
.	.			

OPERATIONAL NOTES

The routing code and severity code from the message definition (in DMTMSG) are used when not supplied in the message request element. If the message is not defined in DMTMSG, it is constructed using the specifications in the message request element, and the "variable substitution values" become the message text, unmodified.

Routing codes:
X'80' Local RSCS console
X'40' Remote addressee
X'20' Local user
X'10' Local VM/370 operator


No response text is returned.

PORT TABLE

BUILT BY: Assembly of DMTSYS at RSCS generation

FUNCTION: Record allocation status of switchable line ports available to RSCS

DESCRIPTION: The first doubleword of the table is reserved for control information. Each following halfword contains the virtual device address of a line port which may be dialed, and which is available to RSCS.



OPERATIONAL NOTES

The line port entries are marked "in use" by setting the high-order four bits of the entries to 1's.

TERMINATE REQUEST ELEMENT

BUILT BY: DMTNPT, DMTSML

FUNCTION: Terminate line driver task

DESCRIPTION: This request element is passed via GIVE/TAKE to the REX task, to terminate line driver operation in response to a DRAIN command.

0	Length (1)	Function Code: X'03'	
---	---------------	-------------------------	--

OPERATIONAL NOTES

There are no error conditions for the terminate function, so no response is made. However, line driver tasks must issue a WAIT request following a call to GIVE for terminate, because REX may not execute the request immediately.

Appendix D. CMS Equate Symbols

This Appendix contains Assembler language equate symbols used in CMS to reference data for:

- CMS usage
- CMS registers

CMS USAGE EQUATES

Field Name	Field Description, Contents, Meaning	
<u>Bits defined in the Program Status Word (PSW)</u>		
CHAN0	EQU X'80'	Bit 00 - channel 0 mask
CHAN1	EQU X'40'	Bit 01 - channel 1 mask
CHAN2	EQU X'20'	Bit 02 - channel 2 mask
CHAN3	EQU X'10'	Bit 03 - channel 3 mask
CHAN4	EQU X'08'	Bit 04 - channel 4 mask
CHAN5	EQU X'04'	Bit 05 - channel 5 mask
CHANM	EQU X'02'	Bit 06 - input/output mask
EXTM	EQU X'01'	Bit 07 - external mask
ECMM	EQU X'08'	Bit 12 - extended control mode mask
MCKM	EQU X'04'	Bit 13 - machine check mask
WAIT	EQU X'02'	Bit 14 - wait state mask
PROB	EQU X'01'	Bit 15 - problem state mask
FOFM	EQU X'08'	Bit 36 - fixed-point overflow mask
DOFM	EQU X'04'	Bit 37 - decimal overflow mask
EUFM	EQU X'02'	Bit 38 - exponent underflow mask
SIGM	EQU X'01'	Bit 39 - significance mask
<u>Bits defined in the Channel Status Word (CSW)</u>		
ATTN	EQU X'80'	Bit 32 - attention
SM	EQU X'40'	Bit 33 - status modifier
CUE	EQU X'20'	Bit 34 - control unit end
BUSY	EQU X'10'	Bit 35 - busy
CF	EQU X'08'	Bit 36 - channel end
DE	EQU X'04'	Bit 37 - device end
UC	EQU X'02'	Bit 38 - unit check
UE	EQU X'01'	Bit 39 - unit exception
PCI	EQU X'80'	Bit 40 - program-controlled interrupt
ICL	EQU X'40'	Bit 41 - incorrect length
PGC	EQU X'20'	Bit 42 - program check
PTC	EQU X'10'	Bit 43 - protection check
CDC	EQU X'08'	Bit 44 - channel data check
CCC	EQU X'04'	Bit 45 - channel control check
ICC	EQU X'02'	Bit 46 - interface control check
CBC	EQU X'01'	Bit 47 - chaining check
<u>Common Channel Command Codes</u>		
WRITE	EQU X'01'	Write
READ	EQU X'02'	Read
NOP	EQU X'03'	No operation
SENSE	EQU X'04'	Sense
WRDATA	EQU X'05'	Write data
RDATA	EQU X'06'	Read data
SEEK	EQU X'07'	Seek
TIC	EQU X'08'	Transfer in channel
WRITE1	EQU X'09'	Write and space 1
RDCONS	EQU X'0A'	Read from console
SFTSEC	EQU X'23'	Set sector
SEARCH	EQU X'31'	Search ID equal
<u>Bits defined in a Channel Command Word (CCW)</u>		
CD	EQU X'80'	Bit 32 - chain data
CC	EQU X'40'	Bit 33 - command chain
SILI	EQU X'20'	Bit 34 - suppress incorrect length
SKIP	EQU X'10'	Bit 35 - suppress data transfer
PCIF	EQU X'08'	Bit 36 - cause program control interrupt
IDA	EQU X'04'	Bit 37 - indirect data address

CMS REGISTER EQUATES

Field Name	Field Description, Contents, Meaning	
<u>General purpose registers</u>		
R0	EQU	0
R1	EQU	1
R2	EQU	2
R3	EQU	3
R4	EQU	4
R5	EQU	5
R6	EQU	6
R7	EQU	7
R8	EQU	8
R9	EQU	9
R10	EQU	10
R11	EQU	11
R12	EQU	12
R13	EQU	13
R14	EQU	14
R15	EQU	15
<u>Floating-point registers</u>		
F0	EQU	0
F2	EQU	2
F4	EQU	4
F6	EQU	6
<u>Extended control registers</u>		
C0	EQU	0
C1	EQU	1
C2	EQU	2
C3	EQU	3
C4	EQU	4
C5	EQU	5
C6	EQU	6
C7	EQU	7
C8	EQU	8
C9	EQU	9
C10	EQU	10
C11	EQU	11
C12	EQU	12
C13	EQU	13
C14	EQU	14
C15	EQU	15

Appendix E. Data Areas and Control Block References

This appendix -- a listing of CP, CMS, and RSCS control blocks -- contains the following:

- Module references to data areas and control blocks.
- Information on how certain data areas or control blocks are created and released.

CP CONTROL BLOCK REFERENCES

ACCTBLOK

Built by: DMKHVD
Released by: DMKHVD, DMKUSO
Referenced by: DMKACO, DMKCKP, DMKHVD,
DMKSPL

CCHREC

Built by: DMKCCH
Released by: DMKCCH, DMKIOE, DMKIOF
Referenced by: DMKCCH, DMKEIG, DMKSEV,
DMKSIX

ACNTBLOK

Built by: DMKACO, DMKHVD, DMKWRM
Released by: DMKACO
Referenced by: DMKACO, DMKCKP, DMKHVD,
DMKJRL, DMKRSE, DMKWRM

CCPARM

Built by: DMKNLD, DMKSNC
Released by: DMKNLD, DMKSNC
Referenced by: DMKNLD, DMKSNC

ALOCBLOK

Built by: DMKCPI, DMKVDC
Released by: DMKCPI, DMKVDC
Referenced by: DMKCPI, DMKMON, DMKPGT,
DMKTDK, DMKVDC

CHXBLOK

Built by: DMKDIA
Released by: DMKVCA
Referenced by: DMKCFP, DMKCQG, DMKDIA,
DMKVCA, DMKVSI

BSCBLOK

Built by: DMKRGB
Released by: DMKRGD
Referenced by: DMKBSC, DMKRGD, DMKRGB

CHYBLOK

Built by: DMKDIA
Released by: DMKVCA
Referenced by: DMKDIA, DMKVCA

BUFFER

Built by: DMKCFM, DMKCPI, DMKERM,
DMKGDF, DMKLNK, DMKLOG, DMKRGD, DMKRSP
Released by: DMKCFM, DMKCPI, DMKGDF,
DMKLNK, DMKRGD, DMKRSP
Referenced by: DMKALG, DMKCDM, DMKCFG,
DMKCFM, DMKCFO, DMKCFS, DMKCPI, DMKCP,
DMKCSB, DMKCSO, DMKCSQ, DMKCST,
DMKCSU, DMKCSV, DMKEMA, DMKERM, DMKGDF,
DMKGRT, DMKLNK, DMKMSG, DMKNMT, DMKRGD,
DMKRND, DMKRSP, DMKSCN, DMKUDU, DMKVDC,
DMKWRM

CKPBLOK

Built by: DMKRNH
Released by: DMKRNH
Referenced by: DMKRNH, DMKWRM

CONTASK

Built by: DMKCNS, DMKGDF, DMKQCN,
DMKRGD, DMKRGB, DMKRNH
Released by: N/A
Referenced by: DMKCNS, DMKGDF, DMKMON,
DMKNES, DMKQCN, DMKRGD, DMKRGB, DMKRNH

CORTABLE

Assembled in DMKSYS.

Released by: N/A

Referenced by: DMKACO, DMKATS, DMKBLD,
DMKCCW, DMKCDS, DMKCF0, DMKCF1, DMKCPU,
DMKCPV, DMKDGD, DMKDMP, DMKFRE, DMKMCC,
DMKMCH, DMKMNI, DMKPAG, DMKPGS, DMKPSA,
DMKPTR, DMKRPA, DMKUDR, DMKU DU, DMKUNT,
DMKVMA

DMPKYREC

Built by: DMKDMP

Released by: DMKDMP

Referenced by: DMKDMP

DMPTBREC

Built by: DMKDMP

Released by: DMKDMP

Referenced by: DMKDMP

CPEXBLOK

Built by:

DMKACO, DMKCDS, DMKCFM, DMKCPS, DMKCPV,
DMKDIA, DMKGRC, DMKIOE, DMKIOF, DMKIOG,
DMKIOS, DMKLOC, DMKMCC, DMKMCH, DMKMON,
DMKPGT, DMKPTR, DMKQCN, DMKRGA, DMKRGB,
DMKRNH, DMKRPA, DMKRSP, DMKSPL, DMKSVC,
DMKUSO, DMKVCA, DMKVDC, DMKVDE, DMKVMA,
DMKVMC

Released by: DMKCPS, DMKDSP, DMKIOF,
DMKMON, DMKPTR

Referenced by: DMKACO, DMKALG, DMKCCW,
DMKCDS, DMKCFM, DMKCF0, DMKCFP, DMK CNS,
DMKCPB, DMKCP S, DMKCPU, DMKCPV, DMKDGD,
DMKDIA, DMKDSB, DMKDSP, DMKEXT, DMKFRE,
DMKGIO, DMKGRC, DMKIOE, DMKIOF, DMKIOS,
DMKLNK, DMKLOC, DMKMCC, DMKMCD, DMKMCH,
DMKMCT, DMKMIA, DMKMID, DMKMNI, DMKMON,
DMKPAG, DMKPGS, DMKPGT, DMKPRG, DMKPRV,
DMKPSA, DMKPTR, DMKQCN, DMKRGA, DMKRGB,
DMKRNH, DMKRPA, DMKRSP, DMKSPL, DMKSSS,
DMKSTK, DMKSVC, DMKTAP, DMKTMR, DMKTRD,
DMKUNT, DMKUSO, DMKVAT, DMKVCA, DMKVDA,
DMKVDC, DMKVDE, DMKVMA, DMKVMC, DMKVSI,
DMKVSP

ECBLOK

Built by: DMKBLD

Released by: DMKCF0, DMKCFS, DMKUSO

Referenced by: DMKBLD, DMKCDB, DMKCDM,
DMKCDS, DMKCFG, DMKCFH, DMKCFP, DMKCFS,
DMKDSP, DMKEXT, DMKPRG, DMKPRV, DMKSCH,
DMKSVC, DMKTMR, DMKTRC, DMKTRD, DMKUSO,
DMKVAT, DMKVMC

ERRBLOK

Built by: DMKIOE

Released by: DMKIOF

Referenced by: DMKIOE, DMKIOF

DDRREC

Built by: DMKVER

Released by: DMKVER

Referenced by: DMKVER

DMPINREC

Built by: DMKDMP

Released by: DMKDMP

Referenced by: DMKDMP

Built by: DMKACO, DMKCCW, DMKCFP,
DMKCNS, DMKCPB, DMKCFI, DMKCP S, DMKCSO,
DMKCS P, DMKCSU, DMKDGD, DMKDIA, DMKGIO,
DMKGRC, DMKHVC, DMKIOS, DMKNLD, DMKRGA,
DMKRGB, DMKSPL, DMKTDR, DMKVCA, DMKVDC,
DMKVDD, DMKVDE, DMKVDR, DMKVIO

Released by: DMKCFP, DMKCNS, DMKCPB,
DMKCFI, DMKCP S, DMKCSO, DMKDAS, DMKDGD,
DMKDIA, DMKGIO, DMKGRC, DMKHVC, DMKIOS,
DMKMON, DMKNLD, DMKPAG, DMKRGA, DMKRGB,
DMKRNH, DMKRSP, DMKSEP, DMKTDR, DMKVCA,
DMKVDC, DMKVDD, DMKVDE, DMKVIO

Referenced by: DMKACO, DMKBSC, DMKCCH,
DMKCCW, DMKCFP, DMKCNS, DMKCPB, DMKCFI,
DMKCP S, DMKCSB, DMKCS C, DMKCS P, DMKCSU,
DMKCSV, DMKDAS, DMKDGD, DMKDIA, DMKDIB,
DMKDSD, DMKDSP, DMKGIO, DMKGRC, DMKHVC,
DMKIOE, DMKIOG, DMKIOS, DMKISM, DMKLOG,
DMKMCC, DMKMNI, DMKMON, DMKMSW, DMKNLD,
DMKNLE, DMKPAG, DMKPGT, DMKRGA, DMKRGB,

DMKRNH, DMKRSE, DMKRSP, DMKSSS, DMKSTK, DMKTAP, DMKTRC, DMKTRD, DMKTRK, DMKUSO, DMKVCA, DMKVDC, DMKVDR, DMKVIO, DMKVSI	DMKSEP, DMKSPL, MCRECORD DMKTCS, DMKTDK, DMKUDR, DMKUNT, DMKVDD, DMKVDE,	<u>Built by:</u> DMKMCH <u>Released by:</u> N/A <u>Referenced by:</u> DMKMCH
--	---	--

IOERBLOK

<u>Built by:</u> DMKBSC, DMKCCH, DMKDAS, DMKDIA, DMKDIB, DMKIOE, DMKIOS, DMKRSE, DMKTAP, DMKVCA	MDRREC
<u>Released by:</u> DMKBSC, DMKCCH, DMKCCW, DMKCFP, DMKCNS, DMKCPs, DMKDAS, DMKDGD, DMKDIA, DMKDIB, DMKGIO, DMKGRF, DMKIOE, DMKIOS, DMKMON, DMKNLD, DMKRGA, DMRGB, DMKRNH, DMKRSE, DMKRSR, DMKTAP, DMKVIO	<u>Built by:</u> DMKVER <u>Released by:</u> DMKVER <u>Referenced by:</u> DMKIOF, DMKVER
<u>Referenced by:</u> DMKBSC, DMKCCH, DMKCCW, DMKCFP, DMKCNS, DMKCPs, DMKDAS, DMKDGD, DMKDIA, DMKDIB, DMKDSB, DMKEIG, DMKGIO, DMKGRF, DMKIOE, DMKIOF, DMKIOS, DMKMSW, DMKNLD, DMKNLE, DMKRGA, DMRGB, DMKRNH, DMKRSE, DMKRSP, DMKSEV, DMKSIX, DMKTAP, DMKTRK, DMKUNT, DMKVCA, DMKVDC, DMKVDE, DMKVIO, DMKVSI	MICBLOK <u>Built by:</u> DMKCFS, DMKLOG <u>Released by:</u> DMKCFS, DMKLOG, DMKUSO <u>Referenced by:</u> DMKELD, DMKCFS, DMKDSP, DMKLOG, DMKMCH, DMKPTR, DMKRPA, DMKTRA

IRMBLOK

<u>Built by:</u> DMKCFO, DMKCFS	<u>Built by:</u> DMKVER
<u>Released by:</u> DMKCFS, DMKIOE	<u>Released by:</u> DMKVER
<u>Referenced by:</u> DMKCFO, DMKIOE	<u>Referenced by:</u> DMKVER

JPSCBLOK

Assembled as part of DMKSYS	<u>Built by:</u> DMKENT
<u>Referenced by:</u> DMKALG, DMKJRL, DMKLNK, DMKLOG	<u>Released by:</u> DMKENT <u>Referenced by:</u> DMKENT

LOCKBLOK

<u>Built by:</u> DMKLOC	<u>MNHDR</u>
<u>Released by:</u> DMKLOC	<u>Built by:</u> DMKMON
<u>Referenced by:</u> DMKLOC	<u>Released by:</u> DMKMON <u>Referenced by:</u> DMKMON

MCHAREA

<u>Built by:</u> DMKIOG	<u>MN000</u>
<u>Released by:</u> N/A	<u>Built by:</u> DMKMON
<u>Referenced by:</u> DMKCCH, DMKCFO, DMKCPU, DMKLOG, DMKMCH, DMKMCT	<u>Released by:</u> DMKMON <u>Referenced by:</u> DMKMON

MN001

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

MN500

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

MN097

Built by: DMKMNI
Released by: DMKMON
Referenced by: DMKMNI

MN600

Built by: DMKMON, DMKMNI
Released by: DMKMON
Referenced by: DMKMNI, DMKMON

MN098

Built by: DMKMNI
Released by: DMKMON
Referenced by: DMKMNI

MN602

Built by: DMKENT
Released by: DMKENT
Referenced by: DMKENT

MN099

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

MN700

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

MN10X

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

MN802

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

MONCOM

Built by: DMKMCC
Released by: DMKMON
Referenced by: DMKCP\$, DMKDMP\$, DMKENT\$,
DMKMCC\$, DMKMCD\$, DMKMIA\$, DMKMNI\$, DMKMON\$

MN20X

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

MSSCOM

MN400

Built by: DMKMON
Released by: DMKMON
Referenced by: DMKMON

Built by: DMKSSS
Released by: DMKLNA\$, DMKLOG\$, DMKSSS\$,
DMKVDA\$
Referenced by: DMKCPB\$, DMKDGD\$, DMKDSB\$,
DMKLNA\$, DMKLOG\$, DMKMSS\$, DMKSSS\$, DMKVDA\$,
DMKVSI\$

NCPTBLBuilt by: DMKSNTReleased by: N/AReferenced by: DMKNLD, DMKSNC**PAGTABLE**Built by: DMKBLDReleased by: DMKBLD, DMKPGSReferenced by: DMKATS, DMKBLD, DMKCFG,
DMKCPU, DMKPGS, DMKPTR, DMKVAT, DMKVMA**NICBLOK**Built by: DMKNLDReleased by: DMKNLDReferenced by: DMKACO, DMKBLD, DMKCFT,
DMKCKP, DMKCPI, DMKCQR, DMKDIA, DMKHVD,
DMKLOG, DMKNES, DMKNET, DMKNLD, DMKPSA,
DMKQCN, DMKRGA, DMKRGB, DMKRNH, DMKWRM**PGBLOK**Built by: DMKVATReleased by: DMKCFP, DMKDSPReferenced by: DMKCFP, DMKDSP, DMKVAT**NPRTBL**Built by: DMKSNTReleased by: N/AReferenced by: DMKCKS, DMKCSO, DMKHVD,
DMKTCS, DMKWRM**PSA**
Assembled as part of DMKSYS; part of CP
nucleus.**OBRRECN (Long OBR)**Built by: DMKIOFReleased by: DMKIOFReferenced by: DMKIOC, DMKIOF, DMKVER**OBRREC (Short OBR)**Built by: DMKIOFReleased by: DMKIOFReferenced by: DMKIOF**OWNDLIST**Assembled into DMKSYSReferenced by: DMKATS, DMKCKP, DMKCKS,
DMKCPI, DMKCPU, DMKDRD, DMKPAG, DMKPGS,
DMKPGT, DMKPTR, DMKSPL, DMKUDR, DMKVDA,
DMKVDC, DMKWRM**PWDIBLOK**Built by: DMKJRLReleased by: DMKJRLReferenced by: DMKJRL

RCHBLOK

Assembled into CP nucleus module DMKRIO

Released by: N/A

Referenced by: DMKCCH, DMKCFO, DMKCP,
DMKCPB, DMKCP, DMKCP, DMKCPV, DMKCP,
DMKDIA, DMKDSB, DMKENT, DMKIOP, DMKIOS,
DMKMNI, DMKMON, DMKNES, DMKPRV, DMKSCN,
DMKSSP, DMKSSS, DMKVCH, DMKVMT

RECBLOK

Built by: DMKCKS, DMKCPI, DMKPGT,
DMKRSP, DMKVSP, DMKWRM

Released by: DMKPGT, DMKSPL, DMKUSO

Referenced by: DMKCP, DMKCKS, DMKCPI,
DMKDMP, DMKPGT, DMKRSP, DMKSPL, DMKVSP,
DMKWRM

RCUBLOK

Assembled into CP nucleus module DMKRIO.

Released by: N/A

Referenced by: DMKCCH, DMKCCW, DMKCFO,
DMKCKP, DMKCPB, DMKCP, DMKCP, DMKCPV,
DMKCP, DMKDIA, DMKDSB, DMKENT, DMKGRF,
DMKIOP, DMKIOS, DMKMNI, DMKMON, DMKNES,
DMKNLD, DMKPRV, DMKSCN, DMKSSP, DMKSSS,
DMKVCH

RECPAG

Built by: DMKIOF, DMKIOP

Released by: DMKIOF, DMKIOP

Referenced by: DMKIOF, DMKIOP

RSPLCTL

Built by: DMKRSP

Released by: DMKRSP

Referenced by: DMKCKP, DMKCP, DMKCSO,
DMKRSP, DMKSPL, DMKTCS

RCWTASK

Built by: DMKCCW

Released by: DMKCCW, DMKUNT

Referenced by: DMKCCW, DMKCFP, DMKCPB,
DMKHVC, DMKIOS, DMKISM, DMKTRD, DMKTRK,
DMKUNT, DMKVDR

SAVEAREA

Built by: DMKCI, DMKSVC

Released by: DMKSVC

RDEVBLOK

Built by: Assembled into CP nucleus
module DMKRIO

Released by: N/A

Referenced by: DMKACO, DMKATS, DMKBLD,
DMKBSC, DMKCCH, DMKCCW, DMKCF, DMKCFG,
DMKCFH, DMKCFM, DMKCF, DMKCFP, DMKCF,
DMKCKP, DMKCKS, DMKCN, DMKCPB, DMKCI,
DMKCP, DMKCPU, DMKCPV, DMKCG, DMKCP,
DMKCQR, DMKCQY, DMKCSB, DMKCSO, DMKDAS,
DMKDEF, DMKDGD, DMKDIA, DMKDMP, DMKDRD,
DMKDSB, DMKDSP, DMKENT, DMKG, DMKGRT,
DMKHVD, DMKIOP, DMKIOE, DMKIOP, DMKIOP,
DMKIOS, DMKLNK, DMKLOG, DMKLOH, DMKCC,
DMKMNI, DMKMON, DMKMSW, DMKNET,
DMKNLD, DMKNLE, DMKOPR, DMKPAG, DMKPGS,
DMKPGT, DMKPRV, DMKPSA, DMKPTR, DMKQC,
DMKRGB, DMKRNH, DMKRSE, DMKRSP,
DMKSCN, DMKSEP, DMKSNC, DMKSPL, DMKSSP,
DMKSSS, DMKTAP, DMKTCS, DMKTDK, DMKTRK,
DMKTRM, DMKUNT, DMKUSO, DMKVCH, DMKVCN,
DMKVDA, DMKVDC, DMKVDD, DMKVDE, DMKVDR,
DMKVDS, DMKVER, DMKVSI, DMKWRM

Referenced by: DMKACO, DMKALG, DMKAPI,
DMKATS, DMKBLD, DMKBSC, DMKCCH, DMKCCW,
DMKCD, DMKCDM, DMKCD, DMKCF, DMKCFD,
DMKCF, DMKCFH, DMKCFM, DMKCF, DMKCFP,
DMKCF, DMKCF, DMKCKS, DMKCLK, DMKCS,
DMKCPB, DMKCP, DMKCPU, DMKCPV, DMKCG,
DMKCQH, DMKCQP, DMKCSR, DMKCQY, DMKCSB,
DMKCSO, DMKCS, DMKCSQ, DMKCS, DMKCSU,
DMKCSV, DMKDAS, DMKDDR, DMKDEF, DMKDGD,
DMKDIA, DMKDIB, DMKDIR, DMKDRD, DMKDSB,
DMKEIG, DMKENT, DMKERM, DMKFMT, DMKGIO,
DMKGRF, DMKGRT, DMKHVD, DMKIOP, DMKIOE,
DMKIOP, DMKIOP, DMKIOS, DMKISM, DMKJRL,
DMKLNK, DMKLOG, DMKLOH, DMKCC, DMKMC,
DMKMCH, DMKMA, DMKMD, DMKMNI, DMKMON,
DMKMSG, DMKMSW, DMKNEM, DMKNES, DMKNET,
DMKNLD, DMKNLE, DMKPGS, DMKPTR, DMKQC,
DMKRGB, DMKRNH, DMKRPA, DMKRSE,
DMKRSP, DMKSET, DMKSEV, DMKSIX, DMKSNC,
DMKSPL, DMKSSP, DMKSS, DMKSVC, DMKTAP,
DMKTCS, DMKTDK, DMKTHI, DMKTRA, DMKTRC,
DMKTRD, DMKTRK, DMKTRM, DMKUDR, DMKUDU,
DMKUNT, DMKUSO, DMKVAT, DMKVCA, DMKVCH,
DMKVDA, DMKVDC, DMKVDD, DMKVDE, DMKVDR,
DMKVDS, DMKVER, DMKVMA, DMKVSP, DMKWRM

SAVTABLE

Assembled into CP pageable module DMKSNT

Released by: N/A

Referenced by: DMKCFG, DMKCFH,

SPLINK

Built By: N/A

Released by: N/A

Referenced by: DMKCKS, DMKCQH, DMKCSU,
DMKDRD, DMKMIA, DMKRSP, DMKSPL, DMKTCS,
DMKVSP, DMKVSQ

SDRBLOK

Built by: DMKIOF

Released by: DMKIOE

Referenced by: DMKIOE, DMKIOF

SWPTABLE

Built by: DMKBLD, DMKVMA

Released by: DMKBLD

Referenced by: DMKATS, DMKBLD, DMKCFG,
DMKCPU, DMKPGS, DMKPTR, DMKVAT, DMKVMA

SEGTABLE

Built by: DMKBLD

Released by: DMKBLD

Referenced by: DMKATS, DMKBLD, DMKPGS,
DMKVMA

SYSLOCS

Assembled into CP nucleus module DMKSYS.

Referenced by: DMKACO, DMKBLD, DMKCF0,
DMKCF7, DMKCKP, DMKLOC, DMKLOG, DMKLOH,
DMKUDR, DMKUDU, DMKUSO

SFBLOK

Built by: DMKCKS, DMKNLD, DMKSPL, DMKWRM

Released by: DMKCKS, DMKRSP, DMKSPL,
DMKUSO

Referenced by: DMKCKP, DMKCKS, DMKCFI,
DMKCQG, DMKCQR, DMKCSO, DMKCSQ, DMKCSQ,
DMKCST, DMKCSU, DMKCSV, DMKDMP, DMKDRD,
DMKMIA, DMKMNI, DMKNLE, DMKRSE, DMKRSP,
DMKSEP, DMKSPL, DMKTCS, DMKUSO, DMKVSP,
DMKVSQ, DMKWRM

SYSTBL

Assembled into DMKSNT.

Referenced by: DMKATS, DMKCFG, DMKCFH,
DMKCPU

TNSREC

Built by: DMKIOF

Released by: DMKIOF

Referenced by: DMKIOF

TREXT

Built by: DMKTRA

Released by: DMKTRA, DMKTRC, DMKUSO

Referenced by: DMKCFM, DMKDSP, DMKPGS,
DMKPGR, DMKPRV, DMKSVC, DMKTMR, DMKTRA,
DMKTRC, DMKTRD, DMKVIO

SHRTABLE

Built by: DMKCFG

Released by: DMKPGS, DMKVMA

Referenced by: DMKATS, DMKCFG, DMKCFH,
DMKCPU, DMKPGS, DMKPTR, DMKVMA

TRQBLOK

Built by: DMKBLD, DMKCFC, DMKCFS,
DMKCPI, DMKGRC, DMKLOG, DMKMCC, DMKQCN,
DMKRGA

Released by: DMKCFM, DMKCFS, DMKDIA,
DMKMCC, DMKLOG, DMKMON, DMKQCN, DMKRGA,
DMKUSO

Referenced by: DMKBLD, DMKCDS, DMKCFC,
DMKCFCM, DMKCFP, DMKCFS, DMKCPI, DMKCPU,
DMKDIA, DMKDSP, DMKENT, DMKGRC, DMKLOG,
DMKMCC, DMKMID, DMKMNI, DMKMON, DMKPSA,
DMKQCN, DMKRGA, DMKRGB, DMKSCH, DMKSSS,
DMKTMR, DMKUSO

VCHBLOK

Built by: DMKVDS

Released by: DMKUSO

Referenced by: DMKCFM, DMKCFCM, DMKCKP,
DMKCPB, DMKCPV, DMKCQG, DMKCSP, DMKCSU,
DMKDEF, DMKDIA, DMKDSP, DMKCSV, DMKLNK,
DMKLOG, DMKPVR, DMKSCN, DMKSPL, DMKSSS,
DMKUSO, DMKVCH, DMKVCN, DMKVDA, DMKVDC,
DMKVDD, DMKVDS, DMKVIC, DMKVSI, DMKVSP

VCONCTL

Built by: DMKVDS

Released by: DMKVDR

Referenced by: DMKALG, DMKCFP, DMKGRC,
DMKRGA, DMKVCN, DMKVDR

UDBFBLOK

Built by: DMKDEF, DMKHVD, DMKSPL

Released by: DMKDEF, DMKHVD, DMKSPL

Referenced by: DMKCFS, DMKDEF, DMKHVD,
DMKLNK, DMKLOG, DMKSPL, DMKSSS, DMKUDR,
DMKUDU

VCUBLOK

Built by: DMKVDS

Released by: DMKUSO

Referenced by: DMKCFM, DMKCFCM, DMKCKP,
DMKCPB, DMKCPV, DMKCQG, DMKCSP, DMKCSU,
DMKCSV, DMKDEF, DMKDIA, DMKDSP, DMKLOG,
DMKNLD, DMKPVR, DMKSCN, DMKSPL, DMKSSS,
DMKUSO, DMKVCH, DMKVCN, DMKVDA, DMKVDC,
DMKVDD, DMKVDS, DMKVIC, DMKVSI, DMKVSP

UDEVBLOK

Built by: DMKCSP, DMKUDR

Released by: DMKCSP, DMKUDR

Referenced by: DMKDEF, DMKDIR, DMKLNK,
DMKLOG, DMKSCN, DMKUDR, DMKVDS

VDEVBLOK

Built by: DMKLOG, DMKVDS

Released by: DMKUSO

Referenced by: DMKACO, DMKALG, DMKCCH,
DMKCCW, DMKCFG, DMKCFH, DMKCFM, DMKCFP,
DMKCP, DMKCPB, DMKCPV, DMKCQG, DMKCSQ,
DMKCSU, DMKCSV, DMKDAS, DMKDEF, DMKDGD,
DMKDIA, DMKDIB, DMKDRD, DMKDSP, DMKGIO,
DMKGRC, DMKHVC, DMKHVD, DMKIOS, DMKLNK,
DMKLOG, DMKNLD, DMKPVR, DMKQCN, DMKRGA,
DMKSCN, DMKSPL, DMKSSS, DMKTHI, DMKTRC,
DMKTRD, DMKTRK, DMKUNT, DMKUSO, DMKVCA,
DMKVCH, DMKVCN, DMKVDA, DMKVDC, DMKVDD,
DMKVDR, DMKVDS, DMKVER, DMKVIO, DMKVSI,
DMKVSP, DMKVSQ

UMACBLOK

Built by: DMKDIR

Released by: DMKDIR

Referenced by: DMKCFS, DMKDEF, DMKDIR,
DMKHVD, DMKLOG, DMKSPL, DMKUDR, DMKUDU

VFCBBLOK

Built by: DMKCFG, DMKCSO

Released by: DMKVDR

Referenced by: DMKCSB, DMKVSP

VMABLOKBuilt by: DMKBLD, DMKCFGReleased by: DMKBLD, DMKPGS, DMKVMAReferenced by: DMKATS, DMKCFG, DMKPGS,
DMKVMA**VMCPARM**Built by: Virtual machine userReleased by: Virtual machine userReferenced by: DMKVMC**VMBLOK**Built by: DMKBLDReleased by: DMKBLD, DMKDIA, DMKLOG,
DMKUSOReferenced by: DMKACO, DMKALG, DMKAPI,
DMKATS, DMKBLD, DMKCCH, DMKCCW, DMKCDB,
DMKCDM, DMKCD\$, DMKCF, DMKCFD, DMKCFG,
DMKCFH, DMKCFM, DMKCF0, DMKCFP, DMKCF\$,
DMKCF\$, DMKCKP, DMKCKS, DMKCN\$, DMKCPB,
DMKCP\$, DMKCPU, DMKCPV, DMKCQG,
DMKCQH, DMKCQ\$, DMKCQR, DMKCQY, DMKCSB,
DMKCSO, DMKCS\$, DMKCSQ, DMKCS\$, DMKCSU,
DMKCSV, DMKDAS, DMKDEF, DMKDGD, DMKDIA,
DMKDIB, DMKDRD, DMKDSP, DMKENT, DMKERM,
DMKEXT, DMKFRE, DMKGIO, DMKGRT, DMKGRT,
DMKHVC, DMKHVD, DMKIOE, DMKIOF, DMKIOG,
DMKIOS, DMKISM, DMKJRL, DMKLNK, DMKLOG,
DMKLOH, DMKLOK, DMKMCC, DMKMCD, DMKMCH,
DMKMCT, DMKMIN, DMKMIN, DMKMON, DMKMON,
DMKMSG, DMKMSW, DMKNES, DMKNET, DMKNLD,
DMKNLE, DMKPAG, DMKPER, DMKPGS, DMKPGT,
DMKPRG, DMKPRV, DMKPSA, DMKPTR, DMKQCN,
DMKRGA, DMKRGB, DMKRNH, DMKRPA, DMKRSE,
DMKRSP, DMKSCH, DMKSCN, DMKSEP, DMKSNC,
DMKSPL, DMKSSS, DMKSTK, DMKSVC, DMKTCS,
DMKTHI, DMKTMR, DMKTRA, DMKTRC, DMKTRD,
DMKTRK, DMKUDR, DMKUDU, DMKUNT, DMKUSO,
DMKVAT, DMKVCA, DMKVCH, DMKVCN, DMKVDA,
DMKVDC, DMKVDD, DMKVDR, DMKVDS, DMKVER,
DMKVIO, DMKVMA, DMKVMC, DMKVSI, DMKVSP,
DMKVSQ, DMKWRM**VRRBLOK**Built by: DMKVDSReleased by: DMKVDRReferenced by: DMKCCW, DMKCFP, DMKDGD,
DMKGIO, DMKUNT, DMKVDS, DMKVSI**VSPLCTL**Built by: DMKDRD, DMKVSPReleased by: DMKVSPReferenced by: DMKCKP, DMKCS\$, DMKCSQ,
DMKDRD, DMKSPL, DMKVSP, DMKVSQ**VSPXBLOK**Built by: DMKCSTReleased by: DMKCSTReferenced by: DMKCKP, DMKCQG, DMKCS\$,
DMKCST, DMKSPL, DMKVDR, DMKVDS**XINTBLOK**Built by: DMKCFP, DMKCPB, DMKDSP,
DMKGRT, DMKRGA, DMKSCH, DMKTMRReleased by: DMKCFP, DMKDSP, DMKSCH,
DMKTMRReferenced by: DMKCFP, DMKCPB, DMKDSP,
DMKGRT, DMKRGA, DMKSCH, DMKTMR, DMKVMC**VMCBLOK**Built by: DMKVMCReleased by: DMKVMCReferenced by: DMKDSP, DMKVMC**XOBR3211**Built by: DMKRSEReleased by: DMKIOEReferenced by: DMKIOF, DMKRSE**VMCMHDR**Built by: N/AReleased by: N/AReferenced by: DMKMSG

CMS CONTROL BLOCK REFERENCES

ABTAB

Assembled as part of DMSNUC.

Referenced by: DMSBAB, DMSDOS, DMSITP

BBOX

Assembled as part of DMSNUC.

Referenced by: No CMS references. This block is used by the DOS supervisor.

ABWSECT

Assembled as part of DMSNUC

Referenced by: DMSABN, DMSDBG, DMSFRE, DMSITI, DMSITP, DMSITS

BGCOM

Assembled as part of DMSNUC.

Referenced by: DMSAMS, DMSASN, DMSBAB, DMSBCP, DMSCLS, DMSDLE, DMSDLK, DMSDMP, DMSDOS, DMSDSV, DMSFCH, DMSFET, DMSINS, DMSITP, DMSSLU, DMSOPL, DMSOPT, DMSPRV, DMSQRY, DMSSRV, DMSSET, DMSSMN, DMSSRV, DMSSTG, DMSVSR, DMSXCP

ADTSECT

Assembled as part of DMSNUC.

Referenced by: DMSABN, DMSACC, DMSACF, DMSACM, DMSALU, DMSAMS, DMSARE, DMSARN, DMSARX, DMSASM, DMSASN, DMSAUD, DMSBOP, DMSBWR, DMSCMP, DMSCPY, DMSDIO, DMSDLB, DMSDLK, DMSDSK, DMSDSL, DMSEDX, DMSERS, DMSEX, DMSEXT, DMSFNS, DMSFOR, DMSIFC, DMSINS, DMSLAD, DMSLAF, DMSLBM, DMSLB, DMSLDS, DMSLFS, DMSLK, DMSLLU, DMSLST, DMSMVE, DMSPUN, DMSQRY, DMSRNM, DMSROS, DMSSET, DMSSOP, DMSSTT, DMSTPE, DMSTQQ, DMSTRK, DMSUPD, DMSXCP

CMSTAXE

Built by: DMSSVT

Released by: DMSSVT

Referenced by: DMSCIT, DMSITE, DMSITI, DMSSVT

AFTSECT

Assembled as part of DMSNUC; also created and released dynamically by DMSLAF.

Referenced by: DMSBRD, DMSBWR, DMSCPY, DMSERS, DMSFNS, DMSINT, DMSLAF, DMSPNT, DMSRNM, DMSSOP, DMSSTT, DMSTPE

CVTSECT

Assembled as part of DMSNUC.

Referenced by: DMSINS

DBGSECT

Assembled as part of DMSNUC.

Referenced by: DMSDBD, DMSDBG, DMSITE.

ANCHSECT

Built by: DMSSTG

Released by: Not released

Referenced by: DMSDOS, DMSSTG

DEVSECT

Assembled as part of DMSNUC.

Referenced by: DMSTIO, DMSTPE

BATLSECT

Assembled as part of DMSBTP.

Referenced by: DMSCIO, DMSITE, DMSPIO

DEVTAB

Assembled as part of DMSNUC.

Referenced by: DMSASN, DMSDBD, DMSEDI, DMSEDX, DMSINI, DMSSLU, DMSSVT

DIOSECT

FCBSECT

Assembled as part of DMSNUC.

Referenced by: DMSACM, DMSDIO, DMSFNS,
DMSITI

DMSCCB

Built by: N/A

Released by: N/A

Referenced by: DMSXCP

DOSSECT

Built by: DMSDLB

Released by: DMSDLB, DMSABN

Referenced by: DMSAMS, DMSBOP, DMSCLS,
DMSDLB, DMSDLK, DMSDSV, DMSOPL, DMSQRY,
DMSSRV, DMSSRV, DMSSVT, DMSVIP, DMSXCP

EDCB

Built by: DMSEDX

Released by: DMSEDI

Referenced by: DMSEDC, DMSEDI, DMSEDX,
DMSGIO, DMSSCR

ERDSECT

Assembled as part of DMSNUC.

Referenced by: DMSERR

EXTSECT

Assembled as part of DMSNUC.

Referenced by: DMSINS, DMSINT, DMSIOW,
DMSITE, DMSQRY, DMSSET, DMSSTG, DMSSVN,
DMSSVT

EXTUAREA

Assembled as part of DMSNUC.

Released by: N/A

No CMS references.

Built by: DMSFLD

Released by: DMSFLD, DMSABN

Referenced by: DMSALU, DMSARN, DMSARX,
DMSASM, DMSDSL, DMSFCH, DMSFLD, DMSLDS,
DMSMVE, DMSQRY, DMSROS, DMSSAB, DMSSBD,
DMSSBS, DMSSCT, DMSSEE, DMSSOP, DMSSQS,
DMSSVN, DMSSVT,

FCHTAB

Assembled as part of DMSNUC.

Referenced by: DMSDOS, DMSFET

FICL

Assembled as part of DMSNUC.

Referenced by: No CMS references. This
block is used by the DOS supervisor.

FRDSECT

Assembled as part of DMSNUC.

Referenced by: DMSFRE, DMSSET

FSCBD

Built by: N/A

Released by: N/A

Referenced by: DMSBRD, DMSDLK, DMSIFC,
DMSZAP, and user programs that access
the CMS file system

FSTD

Built by: N/A

Released by: N/A

Referenced by: DMSCPY, DMSEDX, DMSEXC,
DMSFNS, DMSGND, DMSNCP, DMSSOP, DMSTPE

FSTSECT

Built by: DMSACFReleased by: DMSALU

Referenced by: DMSACF, DMSAMS, DMSARN,
 DMSARX, DMSASM, DMSBOP, DMSBRD, DMSBWR,
 DMSCPY, DMSDLK, DMSDSK, DMSDSL, DMSERS,
 DMSFNS, DMSGND, DMSIFC, DMSLAF, DMSLBM,
 DMSLKD, DMSMVE, DMSRNM, DMSSTT, DMSTPE,
 DMSUPD, DMSXCP, DMSZAP

LUBPR

Assembled as part of DMSNUC

Referenced by: DMSDLK, DMSDSV

LUBTAB

Assembled as part of DMSNUC.

Referenced by: DMSAMS, DMSBOP, DMSCLS,
 DMSDLB, DMSFCH, DMSLLU, DMSOPL, DMSPRV,
 DMSRRV, DMSSET, DMSSRV, DMSXCP

FVSECT

Assembled as part of DMSNUC.

Referenced by: DMSABN, DMSACC, DMSACF,
 DMSACM, DMSALU, DMSAUD, DMSBRD, DMSBTB,
 DMSBTB, DMSBWR, DMSCIT, DMSCRD, DMSCWR,
 DMSCWT, DMSDIO, DMSDOS, DMSDSK, DMSERS,
 DMSFNS, DMSINT, DMSITE, DMSITI, DMSITP,
 DMSITS, DMSLAD, DMSLFS, DMSMOD, DMSPNT,
 DMSQRY, DMSRNM, DMSSLN, DMSSOP, DMSSTT,
 DMSTPE, DMSTQQ

NICL

Assembled as part of DMSNUC.

Referenced by: DMSBOP, DMSCLS, DMSDLB,
 DMSLLU, DMSXCP

NUCON

Assembled as part of DMSNUC.

IHADECB

Built by: N/AReleased by: N/A

Referenced by: DMSSBD, DMSSBS, DMSSCT,
 DMSSEB, DMSSVT

Referenced by: DMSABN, DMSACC, DMSACF,
 DMSACM, DMSALU, DMSAMS, DMSARE, DMSARN,
 DMSARX, DMSASM, DMSASN, DMSAUD, DMSBAB,
 DMSBOP, DMSBRD, DMSBTE, DMSBTP, DMSBWR,
 DMSCAT, DMSCIO, DMSCIT, DMSCLS, DMSCMP,
 DMSCP, DMSCPY, DMSCRD, DMSCWR, DMSCWT,
 DMSDBD, DMSDBG, DMSDIO, DMSDLB, DMSDLK,
 DMSDMP, DMSDOS, DMSDSK, DMSDSL, DMSDSV,
 DMSEDI, DMSEDX, DMSEERR, DMSERS, DMSEX,
 DMSEXT, DMSFCH, DMSEFT, DMSFLD, DMSFNS,
 DMSFOR, DMSFRE, DMSGIO, DMSGLB, DMSGND,
 DMSHDI, DMSHDS, DMSIFC, DMSINA, DMSINI,
 DMSINM, DMSINS, DMSINT, DMSIOW, DMSITE,
 DMSITI, DMSITP, DMSITS, DMSLAD, DMSLAF,
 DMSLBM, DMSLBT, DMSLDR, DMSLDS, DMSLFS,
 DMSLGT, DMSLIB, DMSLIC, DMSLKD, DMSLLU,
 DMSLOA, DMSLSB, DMSLST, DMSLSY, DMSMDP,
 DMSMOD, DMSMVE, DMSNCP, DMSOLD, DMSOPL,
 DMSOPT, DMSOR1, DMSOVR, DMSOVS, DMSPIO,
 DMSPNT, DMSPRT, DMSPRV, DMSPUN, DMSQRY,
 DMSRDC, DMSRNE, DMSRNM, DMSROS, DMSRRV,
 DMSSAB, DMSSBS, DMSSCN, DMSSCT, DMSSEB,
 DMSSET, DMSSLN, DMSSMN, DMSSOP, DMSSQS,
 DMSSRT, DMSSRV, DMSSSK, DMSSTG, DMSSTT,
 DMSSVN, DMSSVT, DMSSYN, DMSTIO, DMSTPD,
 DMSTPE, DMSTQQ, DMSTYP, DMSUPD, DMSVIB,
 DMSVIP, DMSVSR, DMSXCP, DMSZAP

IOSECT

Assembled as part of DMSNUC.

Referenced by: DMSABN, DMSHDI, DMSINT,
 DMSITI

KEYSECT

Built by: DMSSVTReleased by: DMSSVT

Referenced by: DMSSBD, DMSSVT

OPSECT

LDRST

Built by: DMSLDRReleased by: DMSLDR

Referenced by: DMSLDR, DMSLGT, DMSLIB,
 DMSLIO, DMSLSB, DMSOLD

Assembled as part of DMSNUC.

Referenced by: DMSABN, DMSARX, DMSASM,
 DMSCPY, DMSCRD, DMSCWR, DMSCWT, DMSDBG,
 DMSEX, DMSEXT, DMSINS, DMSINT, DMSROS,
 DMSSBD, DMSSBS, DMSSCT, DMSSEB, DMSSOP,
 DMSSQS, DMSSVN, DMSSVT

OSFST

PUBADR

Built by: DMSROS

Assembled as part of DMSNUC.

Released by: DMSALU

Referenced by: DMSBOP, DMSCLS, DMSDLK,
DMSDSV, DMSLLU, DMSPRV, DMSXCP

Referenced by: DMSABN, DMSALU, DMSBOP,
DMSDLK, DMSFCH, DMSMVE, DMSROS, DMSRRV,
DMSSOP, DMSSRV, DMSSTT

PUBOWNER

OVSECT

Built by: N/A

Assembled as part of DMSNUC

Released by: N/A

Referenced by: DMSBOP, DMSCLS, DMSDLK,
DMSLLU, DMSXCP

Referenced by: DMSITS, DMSOVR

SSAVE

PCTAB

Assembled as part of DMSNUC.

Built by: DMSITS

Referenced by: DMSBAB, DMSDOS, DMSITP

Released by: DMSITS

Referenced by: DMSABN, DMSACC, DMSBAB,
DMSDBG, DMSDLB, DMSDOS, DMSERR, DMSFLD,
DMSFRE, DMSIFC, DMSITP, DMSITS, DMSLDR,
DMSOVS, DMSSAB, DMSSLN, DMSSMN, DMSSOP,
DMSSTG, DMSSVN, DMSSVT, DMSVIP, DMSXCP

PDSSECT

Built by: DMSSVT

SUBSECT

Released by: DMSSVT

Assembled as part of DMSNUC.

Referenced by: DMSSTG, DMSSVT

Referenced By: DMSABN, DMSINM, DMSINT

PGMSECT

SVCSECT

Assembled as part of DMSNUC.

Assembled as part of DMSNUC.

Referenced by: DMSITP, DMSSAB, DMSSLN,
DMSSTG, DMSSVT

Referenced by: DMSCIT, DMSFRE, DMSHDS,
DMSINT, DMSITE, DMSITS, DMSLAD, DMSLFS,
DMSOVR, DMSOVS, DMSSLN

PIBADR

SVEARA

Assembled as part of DMSNUC.

Assembled as part of DMSNUC.

Referenced by: DMSBAB, DMSDOS, DMSITP

Referenced by: DMSBAB, DMSDOS, DMSITP

PIB2TAB

SYSCOM

Assembled as part of DMSNUC.

Assembled as part of DMSNUC.

Referenced by: DMSBAB, DMSDOS, DMSVSR

Referenced by: DMSBAB, DMSBOP, DMSDOS,
DMSFET, DMSITP, DMSQRY, DMSSTG, DMSSYN

SYSNAMES

Assembled as part of DMSNUC.

Referenced by: DMSAMS, DMSBOP, DMSBPT,
DMSDOS, DMSEDIX, DMSEX, DMSINS, DMSINT,
DMSITS, DMSQRY, DMSSET, DMSVIB, DMSVSR

USAVE

Built by: N/A

Released by: N/A

Referenced by: DMSITS

TSOBLKS

Assembled as part of DMSNUC.

Referenced by: DMSSET

USERSECT

Assembled as part of DMSNUC.

No CMS references.

RSCS CONTROL BLOCK REFERENCES

ASYNE

Built by: DMTASY

Released by: DMTASY, DMTASK

Referenced by: DMTASY, DMTEXT, DMTIOM,
DMTSIG

GIVEE

Built by: DMTGIV

Released by: DMTAKE, DMTASK

Referenced by: DMTAKE, DMTASK, DMTGIV

BUFDSECT

Built by: DMTSML

Released by: DMTSML

Referenced by: DMTSML

IOE

Built by: DMTIOM

Released by: DMTIOM

Referenced by: DMTASK, DMTIOM, DMTREX

COMDSECT

Built by: DMTCOM

Released by: N/A

Referenced by: DMTAXS, DMTCMX, DMTMGX,
DMTNPT, DMTREX, DMTSML

IOTABLE

Built by: DMTIOM, DMTCRE, DMTNPT,
DMTREX, DMTSML

Released by: DMTNPT, DMTSML

Referenced by: DMTAXS, DMTCMX, DMTCRE,
DMTINI, DMTIOM, DMTREX, DMTSML

DEVTABLE

Built by: DMTNPT

Released by: DMTNPT

Referenced by: DMTNPT

LINKTABL

Assembled into DMTSYS at system
generation; also built by DMTCMX.

Released by: DMTCMX

Referenced by: DMTASY, DMTAXS, DMTCMX,
DMTCOM, DMTCRE, DMTEXT, DMTLAX, DMTMGX,
DMTNPT, DMTREX, DMTSML

FREEE

Built by: DMTQRQ

Released by: DMTQRQ

Referenced by: DMTASK, DMTINI, DMTQRQ

REQBLOCK

Built by: DMTNPT

Released by: DMTNPT

Referenced by: DMTNPT

GIVE

Built by: DMTSML, DMTNPT, DMTAXS, DMTREX

Released by: N/A

Referenced by: DMTSML, DMTNPT, DMTAXS,
DMTREX

ROUTE

Assembled in DMTSYS

Released by:

Referenced by: DMTAXS

TAKE

Built by: DMTSML, DMTNPT, DMTAXS, DMTREX

Released by: N/A

Referenced by: DMTSML, DMTNPT, DMTAXS, DMTREX

SVECTORS

Assembled into DMTVEC at system generation; resides in the RSCS nucleus.

Referenced by: DMTAKE, DMTASK, DMTASY, DMTAXS, DMTCMX, DMTCOM, DMTCRE, DMTDSP, DMTEXT, DMTGIV, DMTINI, DMTIOM, DMTLAX, DMTMGX, DMTNPT, DMTQRQ, DMTREX, DMTSIG, DMTSML, DMTSTO, DMTSVC, DMTWAT

TANKDSEC

Built by: DMTSML

Released by: DMTSML

Referenced by: DMTSML

TAG

Built by: DMTAXS

Released by: DMTAXS

Referenced by: DMTAXS, DMTCMX, DMTNPT, DMTSML

TAREA

Assembled into each task module.

Released by: DMTASK

Referenced by: DMTAKE, DMTASK, DMTASY, DMTCOM, DMTCRE, DMTDSP, DMTEXT, DMTGIV, DMTIOM, DMTREX, DMTSIG, DMTSTO, DMTSVC

TAGAREA

Built by: DMTAXS

Released by: N/A

Referenced by: DMTAXS

TASKE

Built by: DMTASK

Released by: DMTASK

Referenced by: DMTAKE, DMTASK, DMTASY, DMTAXS, DMTCOM, DMTDSP, DMTEXT, DMTGIV, DMTINI, DMTIOM, DMTNPT, DMTPST, DMTREX, DMTSIG, DMTSML, DMTSTC, DMTSVC, DMTWAT

TCTDSECT

Built by: DMTSML

Released by: DMTSML

Referenced by: DMTSML

**Reader's
Comment
Form**

Title: IBM Virtual Machine
Facility/370:
Data Areas and Control
Block Logic

Order No. SY20-0884-3

Please check or fill in the items; adding explanations/comments in the space provided.

Which of the following terms best describes your job?

- | | | | |
|--|--|---|--|
| <input type="checkbox"/> Customer Engineer | <input type="checkbox"/> Manager | <input type="checkbox"/> Programmer | <input type="checkbox"/> Systems Analyst |
| <input type="checkbox"/> Engineer | <input type="checkbox"/> Mathematician | <input type="checkbox"/> Sales Representative | <input type="checkbox"/> Systems Engineer |
| <input type="checkbox"/> Instructor | <input type="checkbox"/> Operator | <input type="checkbox"/> Student/Trainee | <input type="checkbox"/> Other (explain below) |

How did you use this publication?

- Introductory text Reference manual Student/ Instructor text
 Other (explain) _____

Did you find the material easy to read and understand? Yes No (explain below)

Did you find the material organized for convenient use? Yes No (explain below)

Specific criticisms (explain below)

- Clarifications on pages _____
Additions on pages _____
Deletions on pages _____
Errors on pages _____

Explanations and other comments:

Trim Along This Line

Cut or Fold Along Line

Reader's Comment Form

Fold and tape

Please Do Not Staple

Fold and tape

NO POSTAGE
NECESSARY
IF MAILED
IN THE
UNITED STATES



BUSINESS REPLY MAIL
FIRST CLASS PERMIT 40 ARMONK, NEW YORK



POSTAGE WILL BE PAID BY ADDRESSEE:

International Business Machines Corporation
Department D58, Building 706-2
PO Box 390
Poughkeepsie, New York 12602

Attn: VM/370 Publications

Fold and tape

Please Do Not Staple

Fold and tape

IBM VM/370 Data Areas and Code Block Logic

Printed in U.S.A.

SY20-0884-3



International Business Machines Corporation
Data Processing Division
1133 Westchester Avenue, White Plains, N.Y. 10604

IBM World Trade Americas/Far East Corporation
Town of Mount Pleasant, Route 9, North Tarrytown, N.Y., U.S.A. 10591

IBM World Trade Europe/Middle East/Africa Corporation
360 Hamilton Avenue, White Plains, N.Y., U.S.A. 10601