

Nokia XML Gateway User Guide

Release: 3.4.0

Date: January 29, 2008

Contents

CONTENTS	2
REFERENCES	4
GLOSSARY	4
PREFACE	5
ABOUT THIS GUIDE	5
CONVENTIONS	5
1. OVERVIEW	6
1.1 THE GATEWAY FRAMEWORK	6
1.2 NOKIA XML OVERVIEW	6
1.2.1 <i>Nokia XML</i>	6
1.2.2 <i>Network Details</i>	7
1.2.3 <i>Data Types</i>	7
1.2.4 <i>Data/File Formats</i>	7
1.2.5 <i>Performance Data Layout</i>	7
1.2.6 <i>File naming specification</i>	8
1.2.7 <i>Architectural extensions</i>	8
1.2.8 <i>DTD Validation</i>	9
2. ENGINE RULES AND CONFIGURATION	9
2.1 NOKIA_XML	9
2.1.1 <i>Processing Sequence</i>	9
2.1.2 <i>Rule Configuration</i>	9
2.2 NOKIA_XML_CONFIGURATION	13
2.2.1 <i>Rule Configuration</i>	13
3. POST PARSER RULES AND CONFIGURATION	14
3.1 COUNTER_JOIN	14
3.1.1 <i>Rule Configuration</i>	15
3.2 COPY_HEADER_N_BODY_COUNTERS	16
3.2.1 <i>Rule Configuration</i>	16
4. TECH PACK SUPPORT	17
5. INSTALLATION SPECIFIC INFORMATION	18

6. APPENDIX A – SAMPLE NOKIA XML _____ 19

References

Name	Description
Gateway Framework User Guide	This use guide describes in detail the functionality of the Gateway Framework, and the standard suite of tools available.
Nokia OSS 4.0 Measurement Data Export Interface	<p>This document explains how the Measurement Data Export from Nokia NetAct to an external system works in principle.</p> <p>The Measurement Data Export interface is a solution for publishing measurement data in Open Measurement Standard (OMeS) format.</p>

Glossary

OMeS	Open Measurement Standard
FTP	File Transfer Protocol
GSM	Global System for Mobile communications
GPRS	General Packet Radio Service
NE	Network Element
NM	Network Manager
NRM	Network Resource Models.
OA&M	Operation, Administration and Maintenance
TS	Technical Specification
UMTS	Universal Mobile Telecommunications System
UTRAN	Universal Terrestrial Radio Access Network
XML	eXtended Markup Language

Preface

About this Guide

This guide details the vendor specific information on the Nokia XML Gateway. It contains the following information:

- *Chapter 1. Overview.* This chapter gives a brief description of the Nokia XML Gateway and the raw data format it parses.
- *Chapter 2: Engine Rules and Configuration.* This chapter details the vendor specific rules for parsing the raw data and their configuration.
- *Chapter 3: Post Parser Rules and Configuration.* This chapter describes any vendor specific Post Parser rules and their configuration.
- *Chapter 4: Tech Pack Support.* This chapter describes any standard support for Tech Packs included with the Gateway.
- *Chapter 5: Installation specific information.* This chapter contains the customer installation specific information.

Conventions

The following conventions are used in this guide:

Fixed width Highlights a block of example code, a configuration entry, or a command line instruction

1. Overview

1.1 The Gateway Framework

The Nokia XML uses the Gateway Framework as a container for the execution of its engine and post parser stages. The Gateway Framework and Nokia XML Gateway are decoupled into two separate installations. The Gateway Framework consists of a library of Perl modules that provide functionality such as:

- a container for the execution of the Nokia XML Engine and Post Parser rules for data transformation
- Intermediate (PIF) and output data (LIF) storage and management
- logging utilities
- cleanup and crash recovery
- statistics gathering

The Nokia XML Gateway plugs into the Gateway Framework and extends this functionality to provide the final Gateway that parses the Nokia XML data. More information on the standard Gateway configuration is contained in the [Gateway Framework User Guide].

The Nokia XML Gateway supports the parsing of performance measurements data from Nokia 3G networks. The configuration of this interface is designed to be highly configurable and extensible into the future.

Only Nokia XML Gateway specific configuration details will be described in this document.

1.2 Nokia XML Overview

1.2.1 Nokia XML

Nokia uses a standard known as the Open Measurement Standard (OMeS) for transferring measurement data between Nokia NetAct™ and external systems. The OMeS file format is a proprietary standard defined by Nokia using Extensible Markup Language (XML). The OMeS XML will be referred to as Nokia XML throughout this document interchangeably.

Nokia NetAct™ is a complete solution for managing mobile networks and end-user services, ranging from control-room software for 24/7/365 monitoring of the network to software for graphical optimization. The release of this vendor gateway is to include the parsing of data output from Nokia NetAct™ OSS4.0 for OMeS versions 1.0 and 2.0 XML files.

1.2.2 Network Details

The XML performance measurement data derives from GPRS or UMTS network elements, typically via the OA&M management collection point for the network. The periodic measurement files, which can be sizeable, are delivered by the Network OA&M system for collection by northbound OSS applications. This delivery mechanism simplifies the Gateway interface with the network to that of a synchronous file transfer at predefined intervals.

1.2.3 Data Types

Measurement data is collected from the NEs to NetAct. These measurements include several areas of performance evaluation including user and signalling traffic, verification of the network configuration, resource access measurements, Quality of Service (e.g. delays during call set-up, packet throughput, etc) and resource availability.

The Nokia XML Gateway processes two basic data types, the performance data and configuration data.

1.2.4 Data/File Formats

The following outlines the data and filename formats processed by the Nokia XML Gateway.

1.2.5 Performance Data Layout

The generated performance measurement data shall be in ASCII format and in a OMeS XML structure.

The OMeS data model consists of three basic elements that identify and describe the measurements and the measurement results:

1. *Setup* identifies and describes the time stamp of the measurement and the measurement interval. The OMeS 1.0 setup also describes the network element (NE) that usually controls the measurement.

2. *Target* identifies the measured object (MO). Measurement Data Export interface supports distinguished names (DN) only.
3. *Performance Indicator* identifies the performance indicator (PI) that is measured.

OMeS XML files contain information about the measured object, the starting time and the measurement period, the duration of the period and the actual counter data.

A sample Nokia XML file is shown in Appendix A.

1.2.6 File naming specification

The naming convention for the export files are as shown below:

etlexpmx_<firstMeasuredObjectClass>_<timeStamp>_<uniqueID>.xml

For example: **etlexpmx_MMSC_20050208174900_100.xml**

- <firstMeasuredObjectClass> refers to the measured object class of the first record found from the OMeS file received from the Network Element.
- <timeStamp> is the date and time when the granularity period begins or the first granularity period of the measurement result comes to availability. It takes the format of YYYYMMDDHHmmss, where
 - YYYY - 4 digits year.
 - MM - 2 digits month (01-12).
 - DD - 2 digits day (01-31).
 - HH - 2 digits hour (00-23)
 - mm - 2 digits minute (00-59)
 - ss - 2 digits second (00-59)
- <uniqueID> is the name of the NE, EM or domain. This field is optional.

Example of Nokia XML performance data files are as follows:

etlexpmx_AXC_20050915084650_159.xml

etlexpmx_RNC_20050915165840_194.xml

etlexpmx_WCEL_20050914155329_111.xml

1.2.7 Architectural extensions

The Nokia XML Gateway parses OMeS XML data file to the Gateway PIF format. The interface uses the XML::Parser parser library to facilitate XML parsing. XML DTD and Schema validation is not currently

supported. The core 3rd party tools are the XML::Parser Perl modules which interfaces to the Expat C based XML parser.

The XML::Parser XML parser complies with SAX 1.0 and 2.0 specifications. The Nokia_XML gateway uses SAX callback routines to handle XML elements and attributes, etc.

1.2.8 DTD Validation

No DTD validation is supported in the Gateway. Deployments requiring such validation should seek to have this process completed by the equipment vendor element management systems supplying the XML.

2. Engine Rules and Configuration

2.1 Nokia_XML

The essential task of the Nokia_XML engine is to parse the XML data into output PIF files. This gateway uses its configuration to extract the data required for the performance tool.

2.1.1 Processing Sequence

The Nokia_XML processes the performance data by parsing the XML file for header counters and data counters.

Header counters are parsed based on the object elements and attributes defined within the **XML_PIF_HEADER_ELEMENT_NAMES** and **XML_UNIQUE_PIF_BLOCK_HEADER_ATTRIBUTE_NAMES** entries.

Unique PIF files are created for each PIF mapping defined within **XML_HEADER_INFO_FOR_PIF_FILENAME**.

All the data counters are parsed for each data block defined within the entry **XML_UNIQUE_PIF_BLOCK_ELEMENT_NAMES**. Counter names and counter values are mapped to a single row in the PIF file.

2.1.2 Rule Configuration

The following details the vendor specific rule entries for the Nokia XML engine rule.

- **XML_HEADER_DATE_TIME_DESCRIPTION**: This entry consists of tokens of the measurements results attribute name and the corresponding Perl Regular Expressions that matches the

attribute name token. Each token will be validated and recorded as the header counter.

```
XML_HEADER_DATE_TIME_DESCRIPTION => {
    StartDate => '^(\d{4}-\d{2}-\d{2}).*$',
    StartTime => '^.+T(\d{2}:\d{2}).*$',
}
```

- XML_PIF_HEADER_ELEMENT_NAMES: This scalar or array entry facilitates the inclusion of XML element data in the output PIF header block. This data is common to all PIF output files.

For OMeS 2.0, where DN is an element instead of an attribute:

```
XML_PIF_HEADER_ELEMENT_NAMES => [ 'DN' ],
```

- XML_UNIQUE_PIF_BLOCK_ELEMENT_NAMES: These elements contain the data blocks to be parsed into a unique PIF file.

For OMeS 1.0:

```
XML_UNIQUE_PIF_BLOCK_ELEMENT_NAMES => [ 'BG_Nokia_BG',
    'GNS_Nokia_GNS',
    'FW_Nokia_FW',
],
```

For OMeS 2.0:

```
XML_UNIQUE_PIF_BLOCK_ELEMENT_NAMES => [ 'PMMOResult' ],
```

Note: OMeS 2.0 uses PMMOResult as the standard element name for data blocks within the XML files. Therefore PMMOResult is used exclusively for OMeS2.0 XML data file as the unique PIF block element name.

- XML_UNIQUE_PIF_BLOCK_HEADER_ATTRIBUTE_NAMES: This scalar or array entry facilitates the inclusion of attribute within each XML element data in the output PIF header block. This data is common to all PIF output files.

For OMeS 1.0:

```
XML_UNIQUE_PIF_BLOCK_HEADER_ATTRIBUTE_NAMES => [ 'DN',
    'measurementType',
    'startTime',
    'interval',
],
```

For OMeS 2.0:

```
XML_UNIQUE_PIF_BLOCK_HEADER_ATTRIBUTE_NAMES => [
    'measurementType',
```

```

        'startTime',
        'interval',
    ],

```

- **XML_OUTPUT_BLOCK_NAME:** This scalar entry allows for setting the default initial output block name.

```
XML_OUTPUT_BLOCK_NAME => 'Nokia',
```

- **XML_OUTPUT_BLOCK_DESCRIPTION:** This entry configures the element name to be included to the output block name.

```
XML_OUTPUT_BLOCK_DESCRIPTION => '^(.*)_Nokia.*',
```

Note: The expression will return the argument matched with the object element name obtained from XML_UNIQUE_PIF_BLOCK_ELEMENT_NAMES.

- **XML_HEADER_INFO_FOR_PIF_FILENAME:** Values of PIF header entries can be included in the output PIF filename by including their element names in this array. It is critical that enough header counters are included here, so as to ensure a unique PIF file.

```
XML_HEADER_INFO_FOR_PIF_FILENAME=>[ 'Prefix',
                                     'StartDate',
                                     'StartTime',
    ],
```

There will typically be a one-to-many relationship between one XML file, which will probably map to several PIF files. The PIF filenames will have a prefix of the PIF data block name in addition to the unique combination of elements defined within the entry:

XML_HEADER_INFO_FOR_PIF_FILENAME

These elements represent the header data for a particular network abstraction for a particular measurement period.

A key goal of a successful configuration is to ensure that all the XML data is outputted in PIF files, and that no PIF duplication occurs. This duplication may occur if the configurations such as the PIF filename tokens do not give a unique filename for that particular measurement.

- **XML_ENABLE_PIF_COUNTER_IN_FILENAME:** This scalar entry enables the inclusion of a PIF counter in the PIF filename. This is required when all other PIF tokens used to make up a PIF

filename are identical over two or more PIF files to prevent PIF files from being overwritten.

```
XML_ENABLE_PIF_COUNTER_IN_FILENAME => 'True',
```

or

```
XML_ENABLE_PIF_COUNTER_IN_FILENAME => 0,
```

- **HEADER_DATA_RECORD_PROCESSING**: This is an optional entry whose value points to a configured Perl subroutine. The purpose of this entry is to add custom processing for a deployment, such as add a new counter. But it could be any processing on the header and data record. This entry deals with counter name/value pairs in the current header record and is invoked for each header record encountered.

The Nokia_XML default rule configuration for OMeS 2.0 uses the **HEADER_DATA_RECORD_PROCESSING** to perform the following tasks:

- Round down StartTime to the nearest interval, and
- Extract element ID from DN.

```
HEADER_DATA_RECORD_PROCESSING => sub {
    my ($parent_ref, $rec_ref, $op_hash_ref) = @_;

    # Rounding down StartTime to the nearest interval
    my ($hour, $minute) = split(":", $op_hash_ref->{StartTime});
    $minute = $minute - ($minute % $op_hash_ref->{interval});
    $op_hash_ref->{StartTime} =
        sprintf("%02d:%02d", $hour, $minute);

    # Extract element ID from DN
    if ( $header_ref->{'measurementType'} =~ /.*/ ) {
        for ($data_ref->{DN}) {
            !$_ && last; # skip processing if not exists
            /(GPBB)\-(\d+)/ && do {$data_ref->{"$1_ID"}="$1-$2"};
            /(GPST)\-(\d+)/ && do {$data_ref->{"$1_ID"}="$1-$2"};
            /(GGSN)\-(\d+)/ && do {$data_ref->{"$1_ID"}="$1-$2"};
        }
    }
    return 0;
}
```

2.2 Nokia_XML_CONFIGURATION

The processing steps of Nokia_XML_CONFIGURATION are similar to Nokia_XML. The only difference is that it is dealing with bulk configuration data that is coming from the network.

This gateway supports the parsing of network configuration data from Nokia UMTS networks. The configuration of this gateway is designed to be highly configurable and extensible into the future.

The gateway is designed to convert from Nokia UMTS XML configuration data to the Gateway PIF format.

2.2.1 Rule Configuration

- **IGNORE_ELEMENTS:** This array entry contains the list of elements that should be ignored by the rule. All sub-elements within the element will also be ignored.

`IGNORE_ELEMENTS => [],`

- **COMMON_HEADER_DATA_OBJECTS:** This array entry lists the atomic element names, which should be included in the PIF header as counters. These entries are outside the OBJECT_MAPPING XML.
- **OBJECT_MAPPING:** This mandatory hash entry contains the basic object mapping of the XML to PIF. Each OBJECT_MAPPING hash key contains the name of the XML element that commences a new PIF output for the contents of that element. The id attribute for this element is placed in the header of the PIF. Each OBJECT_MAPPING key entry in turn references a hash containing configuration entries, which determine certain mappings for the element in question. These configuration entries are:
 - **PIF_FILENAME_KEYS:** This array entry lists the counter names in either the header or record data that should be used in formulating the PIF filename.
 - **CHILD_ELEMENTS:** This hash entry contains the PIF record mapping details. Each key contains an element name that maps to the point in the XML when a new PIF record commences. Each key references another hash entry that contains configuration information relevant to the PIF record. These configuration entries are:

- NON_UNIQUE_CLASS_BLOCKS: This array entry contains the names of elements within the child element, which appear more than once. Because of the potential for overwriting on these element counters, these counter entries in the PIF filename are pre-pended with a tag. This tag is made up of the NON_UNIQUE_CLASS_BLOCKS element name and its "id" attribute. NON_UNIQUE_CLASS_BLOCKS entries must have an "id" attribute in order to ensure uniqueness.
- ENABLE_UNIQUE_PIF: Setting the ENABLE_UNIQUE_PIF to "TRUE" facilitate the placing of each PIF record in a unique PIF file.
- OUTPUT_BLOCK_NAME: This scalar entry allows for setting the name of the output block name for a particular CHILD_ELEMENTS entry.
- DUPLICATE_COUNTERS: An atomic element name, appearing as an actual counter in the PIF file should be included in this array list, if the name of the counter appears more than once in the XML block for the PIF record. This facilitates the placing of a unique incrementing numeric value on these values (vsDataType_1, vsDataType_2 etc.).

A sample OBJECT_MAPPING entry is as follows:

```

OBJECT_MAPPING => {
  'WBTS_1.5' => {
    PIF_FILENAME_KEYS => [qw( WCEL_1.5_id)],
    CHILD_ELEMENTS => {
      'WCEL_1.5' => {
        NON_UNIQUE_CLASS_BLOCKS => [qw(ADJS_1.5)],
        ENABLE_UNIQUE_PIF => 0,
      },
    },
  },
},

```

3. Post Parser Rules and Configuration

3.1 COUNTER_JOIN

This rule creates new header and data counters based on the joining of a number of counter values to create new composite keys. For

example for 2 counters PLMN_NAME -> 2 and RNC_NAME -> 3 a new counter could be created called PLMN_RNC value 2/3. The non standard configuration options for this rule are:

The non-standard configuration entries with this rule are listed below.

3.1.1 Rule Configuration

- **HEADER_COUNTERS_TO_JOIN**: An array of anonymous hashes detailing the header counters to join together to create new counters.

Each entry contains 3 configuration entries:

- **COUNTERS_TO_JOIN**: This array lists the header counters to join together
- **NEW_COUNTER_NAME**: The name to assign to the new counter created.
- **COUNTER_SEPARATORS**: The characters to use to separate the counters in the newly created value. Typically they will be separated by a "-" but any string can be configured to allow "-" and "/" to be mixed etc.

Note: If there are N counters to join then N-1 separators need to be configured.

```
{
  COUNTERS_TO_JOIN => [
    qw (PLMN_NAME RNC_NAME)
  ],
  NEW_COUNTER_NAME => 'PLMN_RNC',
  COUNTER_SEPARATORS => ['-'],
},
```

- **DATA_COUNTERS_TO_JOIN**: This array of anonymous hashes is configured in an identical way to the **HEADER_COUNTERS_TO_JOIN** except it specifies the list of data counters to join.

See above for the configuration entries.

- **DEFAULT_NULL_VALUE:** The value to use for the new counter if the counters specified to create the new counter don't exist in the input.

A full configuration of the rule is below:

```
{
  RULE_TYPE => 'COUNTER_JOIN',
  RULE_DESC => 'Join counter values to create
composite key',
  INPUT_FILE_DESCRIPTION => '.*RNC.*CE\.pif',
  OUTPUT_FORMAT => 'LIF_Writer',
  HEADER_COUNTERS_TO_JOIN => [
    {
      COUNTERS_TO_JOIN => [qw(PLMN_NAME RNC_NAME)],
      NEW_COUNTER_NAME => 'PLMN_RNC',
      COUNTER_SEPARATORS => ['-'],
    },
  ],
  DATA_COUNTERS_TO_JOIN => [
    {
      COUNTERS_TO_JOIN => [
        qw(WCEL_NAME WBTS_NAME WBTS_ID)
      ],
      NEW_COUNTER_NAME => 'WCEL_WBTS',
      COUNTER_SEPARATORS => [ qw(- /) ],
    },
  ],
  DEFAULT_NULL_VALUE => 'NULL'
}
```

3.2 COPY_HEADER_N_BODY_COUNTERS

This post parser rule allows counters to be copied from header to body, and vice versa. The counters that are going to be copied shall be listed out in the specific array.

The non-standard configuration entries with this rule are listed below:

3.2.1 Rule Configuration

- **COPY_HEADER_COUNTERS_2_BODY:** A mandatory field that consists of an array of header counters. These counters shall be copied to the PIF body.

```
COPY_HEADER_COUNTERS_2_BODY => [ 'RNC_RNCName',
                                  'RNC_RNCIdentifier', ],
```

- **COPY_BODY_COUNTERS_2_HEADER**: A mandatory field that consists of an array of PIF body record counters. These counters shall be copied to the PIF header.

```
COPY_BODY_COUNTERS_2_HEADER => [ 'NODEB_NODEBIPAddress',
                                  'RNCCELL_RncNodeBIdentifier' ],
```

- **REDUNDANT_HEADER_COUNTERS**: An optional field that consists of an array of header counters. These counters shall be removed.

```
REDUNDANT_HEADER_COUNTERS => [ 'RNC_RNCName',
                                 'RNC_RNCIdentifier', ],
```

- **REDUNDANT_BODY_COUNTERS**: An optional field that consists of an array of body record counters. These counters shall be removed.

```
REDUNDANT_BODY_COUNTERS => [ 'NODEB_NODEBIPAddress',
                              'RNCCELL_RncNodeBIdentifier', ],
```

A full sample configuration is included below:

```
{
  'RULE_TYPE' => 'COPY_HEADER_N_BODY_COUNTERS',
  'RULE_DESC' => 'Copy Header information to the Data records',
  'INPUT_FILE_DESCRIPTION' => ['PLMN.*NE_Specific.*-#-CE\.pif',
                              'PLMN.*GGSN_AP.*-#-CE\.pif',
                              'PLMN.*Interface.*-#-CE\.pif'],
  'COPY_HEADER_COUNTERS_2_BODY' => ['INTERFACE_ID'],
  'COPY_BODY_COUNTERS_2_HEADER' => [ ],
  'REDUNDANT_HEADER_COUNTERS' => ['INTERFACE_ID'],
  'REDUNDANT_BODY_COUNTERS' => [ ],
  'PRODUCE_PIF' => 'True',
},
```

4. Tech Pack Support

Tech pack support is included in the Nokia XML Gateway for the following Performance Manager solutions.

- Nokia OMeS1.0 GPRS Backbone
- Nokia OMeS2.0 Network Elements, e.g. UTRAN 3.0, GGSN5.0

The EngineConfig.pm and UserConfig.pm configuration files for these Tech Packs are located in the tech_pack_support kit sub directory.

5. Installation Specific Information

<This can consist of items that relate to the particular customer site.

Examples are:

- any hierarchy/3rd party data and it's extraction - which is not being derived or arriving on the server using a standard method (ftp/scp/cp)
- Post Parser rules implemented for the customer
- details on the directory and transfer configuration
- Any specific changes made for performance/efficiency improvements

The format of this section is left open, but should follow the conventions in the rest of this document>

6. Appendix A – Sample Nokia XML

```

<?xml version='1.0'?>
<OMeS xmlns='pm/cnf_rnc_nokia_2.xsd'>

  <PMSetup DN = 'PLMN-PLMN/RNC1'
    startTime='2001-02-17T15:00:00.000+02:00:00' interval='60'>

    <RNC_Nokia_1.2 localMoid='DN:unit_type-2/unit_index-0'
      measurementType='Unit_Load_Measurement'
      MOName='RNC-1_DN:unit_type-2/unit_index-0'

      <M250C0>3</M250C0>
      <M250C1>14</M250C1>
      <M250C2>20</M250C2>
      <M250C3>15</M250C3>
    </RNC_Nokia_1.2>

  </PMSetup>

  <PMSetup DN = 'RNC-2'
    startTime='2001-02-17T16:00:00.000+02:00:00' interval='60'
    realStartTime='2001-02-17T16:01:23.000+02:00:00'
    realStopTime='2001-02-17T17:01:12.000+02:00:00'>

    <RNC_Nokia_1.2 localMoid='DN:unit_type-2/unit_index-1'
      measurementType='Unit_Load_Measurement'
      MOName='RNC-1_DN:unit_type-2/unit_index-1'

      <M250C0>10</M250C0>
      <M250C1>12</M250C1>
      <M250C2>8</M250C2>
      <M250C3>17</M250C3>
    </RNC_Nokia_1.2>

  </PMSetup>
</OMeS>

```

Table 1 – Sample OMeS 1.0 XML performance data file contents.

```
<?xml version="1.0"?>
<OMeS>
  <PMSetup startTime="2005-03-08T00:00:00.000+01:00:00" interval="60">
    <PMMOResult>
      <MO>
        <DN>PLMN-PLMN/ADAP-NOKGPRSTRA/NGSG-123456/NGCP-100/NGMS-24407</DN>
      </MO>
      <PMTarget measurementType="madgtrIMSI">
        <total>4</total>
        <success>4</success>
        <ecgr1>0</ecgr1>
        <ecgr2>0</ecgr2>
        <ecgr3>0</ecgr3>
        <ecgr4>0</ecgr4>
        <ecgr5>0</ecgr5>
        <ecgr6>0</ecgr6>
        <ecgr7>0</ecgr7>
        <ecgr8>0</ecgr8>
        <ecgr9>0</ecgr9>
        <ecgr10>0</ecgr10>
        <ecgr11>0</ecgr11>
        <ecgr12>0</ecgr12>
        <ecgr13>0</ecgr13>
        <ecgr14>0</ecgr14>
        <ecgr15>0</ecgr15>
        <ecgr16>0</ecgr16>
      </PMTarget>
    </PMMOResult>
  </PMSetup>
</OMeS>
```

Table 2 – Sample OMeS 2.0 XML performance data file contents.