

IBM WebSphere Application Server Network Deployment
for IBM i, Version 8.0

Setting up intermediary services



Note

Before using this information, be sure to read the general information under “Notices” on page 273.

Compilation date: July 12, 2011

© Copyright IBM Corporation 2011.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

How to send your comments	vii
Changes to serve you more quickly	ix
Chapter 1. How do I...Setting up intermediary services	1
Chapter 2. Implementing a web server plug-in	3
Setting up a remote web server.	5
Installing IBM HTTP Server	8
Editing web server configuration files.	9
Configuring Apache HTTP Server V2.2	9
Configuring Lotus Domino	11
Configuring IBM HTTP Server powered by Apache 2.x.	13
Configuring IBM HTTP Server Version 6.x	14
Configuring IBM HTTP Server Version 7.0	15
Configuring IBM HTTP Server Version 8.0	16
Creating web server templates	17
Allowing web servers to access the administrative console	18
Administering web servers from the administrative console	20
Web server definition	20
Web server configuration.	21
Web server collection	23
Editing the web server type.	30
Web server plug-ins	30
Selecting a front end for your WebSphere Application Server topology	32
Web server plug-in connections	35
Web server plug-in remote user information processing	36
Private headers	36
Gskit install images files	37
Plug-ins: Resources for learning	37
Installing and configuring web server plug-ins	38
Selecting a web server topology diagram and roadmap	40
Installing and uninstalling the Web Server Plug-ins on IBM i operating systems.	49
Web server configuration.	54
Creating or updating a global web server plug-in configuration file	56
Creating or updating a global web server plug-in configuration file	58
Update the global web server plug-in configuration setting	59
Directory conventions	60
Administering web server plug-ins	61
Using the same HTTP server to handle HTTP and HTTPS requests for multiple cells	61
Web server plug-in properties	63
Web server plug-in configuration service property.	71
Application Server property settings for a web server plug-in	71
plugin-cfg.xml file	74
Web server plug-in custom properties	88
Web server plug-in configuration properties	90
Web server plug-in tuning tips	93
Chapter 3. Using the DataPower appliance manager	97
WebSphere DataPower appliance manager overview	98
Adding DataPower appliances to the DataPower appliance manager	102
Modifying DataPower appliance settings	103
Removing a DataPower appliance	104

Appliance collection	105
New appliance settings for the DataPower appliance	107
Appliance settings	107
Replacing a DataPower appliance	111
Adding new firmware versions to the DataPower appliance manager	112
Modifying settings for firmware versions	113
Deleting firmware versions	113
Firmware collection	113
Firmware settings	114
Managed set firmware settings	115
New firmware version settings	116
Adding a new managed set	116
Modifying a managed set	117
Removing a managed set from the DataPower appliance manager	118
Managed set collection for a DataPower appliance	119
Managed set settings	120
Edit membership for a managed set	123
Modifying DataPower appliance manager settings	124
Appliance manager settings	124
Importing an exported DataPower appliance manager configuration	125
Exporting the DataPower appliance manager configuration	126
Monitoring tasks that DataPower appliance manager is handling	126
DataPower appliance manager tasks collection	127
Administering managed domain versions	128
Domain history collection	128
Domain history detailed information	129
Managing versions of sharable appliance settings	129
Settings history collection for a DataPower appliance manager	130
Settings version Collection	130
Administering DataPower appliance domains	131
Managed domain settings	132
Secure Socket Layer communication with DataPower	133
Adding the DataPower signer certificate to the WebSphere Application Server default truststore to enable an SSL connection	134
Chapter 4. Setting up the proxy server	135
Creating a proxy server	136
Proxy server collection	137
Proxy server configuration	139
Proxy server settings	140
Generic server clusters collection	146
Generic server clusters configuration	146
Generic server cluster ports collection	147
Generic server cluster members	147
URI groups	148
URI group configuration	148
Routing rules	148
Routing rules configuration	149
Rewriting rules collection	150
Rewriting rules configuration	150
HTTP proxy inbound channel settings	151
Starting a proxy server	152
Stopping a proxy server	153
HTTP proxy server custom properties	154
SIP proxy server custom properties	160
SIP container custom properties	169

Creating a proxy server cluster	181
Proxy server cluster collection	182
Proxy server cluster settings	183
Proxy server cluster member collection	183
Proxy cluster member settings	184
Proxy cluster member templates collection	185
Proxy cluster member template settings	186
Creating a proxy cluster: Basic proxy cluster settings	187
Creating a proxy cluster: Create first proxy cluster member	187
Creating a proxy cluster: Create additional proxy cluster members	188
Creating a proxy cluster: Summary settings	189
Managing a proxy server cluster	189
Migrating profiles for the proxy server	190
Customizing routing to applications	191
Web module proxy server configuration settings	191
Routing requests to ODC-compliant application servers in other cells	192
Configuring rules to route requests to web servers	193
Modifying the HTTP endpoints that the proxy server listens on	193
Adding a new HTTP endpoint for the proxy server	193
Setting up caching in the proxy server	194
Static cache rules collection	195
Static cache rule settings	195
Routing requests from a plug-in to a proxy server	196
Creating a proxy server cluster using the wsadmin command	197
Monitoring the proxy server with PMI	199
Monitoring traffic through the proxy server	199
Overview of the custom error page policy	199
Request mapping	200
Session failover in the proxy server	203
Installing a Session Initiation Protocol proxy server.	203
Trusting SIP messages from external domains	204
Tracing a Session Initiation Protocol proxy server	205
High availability and workload management with Session Initiation Protocol proxy server.	206
Load balancing with the Session Initiation Protocol proxy server	206
SIP proxy settings	208
SIP external domains collection	211
SIP external domains	212
SIP routing rules collection	213
SIP routing rules set order.	214
SIP routing rules detail	214
SIP rule condition collection	215
SIP rule condition detail.	215
SIP proxy inbound channel detail	216
Troubleshooting the proxy server	217
Troubleshooting request routing and workload management through the proxy server	220
Session Initiation Protocol overload protection	221
Configuring SIP quorum support using the default core group	223
Configuring the SIP proxy for network outage detection	225
Administering proxy actions	225
Proxy server actions	229
Proxy actions collection	230
Caching action settings	232
HTTP compression action settings	232
HTTP header action settings	233
Rewrite action settings	234
Route action settings.	236

Generic server cluster route action settings	237
Time mapping settings	239
Administering custom advisors for the proxy server	240
Custom advisor policies.	240
Custom advisors collection	241
Custom advisor policy settings	241
Configuring stand-alone application server mappings	242
Configuring application server cluster mappings	243
Configuring generic server cluster mappings	245
Creating custom advisors for the proxy server	246
Administering proxy virtual hosts	247
Proxy virtual hosts.	249
Proxy virtual hosts collection	250
Proxy virtual host settings	250
Proxy virtual host settings details	251
Administering proxy rule expressions	252
Proxy rule expressions	253
Proxy rule expressions collection	254
Proxy rule expression settings	255
Creating a custom filter and deploying it to a proxy server	256
Configuring denial of service protection for the proxy server	257
Denial of Service Protection	258
Tuning the security properties for the DMZ Secure Proxy Server for IBM WebSphere Application Server	259
DMZ Secure Proxy Server for IBM WebSphere Application Server start up user permissions	260
DMZ Secure Proxy Server for IBM WebSphere Application Server routing considerations	261
DMZ Secure Proxy Server for IBM WebSphere Application Server administration options	261
Error handling security considerations for the DMZ Secure Proxy Server for IBM WebSphere Application Server	262
Proxy security level properties	262
Configuring a DMZ Secure Proxy Server for IBM WebSphere Application Server using the administrative console	264
Configure secure routing for a DMZ Secure Proxy Server for IBM WebSphere Application Server	265
WebSphere DMZ Secure Proxy Server for IBM WebSphere Application Server	267
Appendix. Directory conventions	271
Notices	273
Trademarks and service marks	275
Index	277

How to send your comments

Your feedback is important in helping to provide the most accurate and highest quality information.

- To send comments on articles in the WebSphere Application Server Information Center
 1. Display the article in your Web browser and scroll to the end of the article.
 2. Click on the **Feedback** link at the bottom of the article, and a separate window containing an e-mail form appears.
 3. Fill out the e-mail form as instructed, and click on **Submit feedback** .
- To send comments on PDF books, you can e-mail your comments to: **wasdoc@us.ibm.com** or fax them to 919-254-5250.

Be sure to include the document name and number, the WebSphere Application Server version you are using, and, if applicable, the specific page, table, or figure number on which you are commenting.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

Changes to serve you more quickly

Print sections directly from the information center navigation

PDF books are provided as a convenience format for easy printing, reading, and offline use. The information center is the official delivery format for IBM WebSphere Application Server documentation. If you use the PDF books primarily for convenient printing, it is now easier to print various parts of the information center as needed, quickly and directly from the information center navigation tree.

To print a section of the information center navigation:

1. Hover your cursor over an entry in the information center navigation until the **Open Quick Menu** icon is displayed beside the entry.
2. Right-click the icon to display a menu for printing or searching your selected section of the navigation tree.
3. If you select **Print this topic and subtopics** from the menu, the selected section is launched in a separate browser window as one HTML file. The HTML file includes each of the topics in the section, with a table of contents at the top.
4. Print the HTML file.

For performance reasons, the number of topics you can print at one time is limited. You are notified if your selection contains too many topics. If the current limit is too restrictive, use the feedback link to suggest a preferable limit. The feedback link is available at the end of most information center pages.

Under construction!

The Information Development Team for IBM WebSphere Application Server is changing its PDF book delivery strategy to respond better to user needs. The intention is to deliver the content to you in PDF format more frequently. During a temporary transition phase, you might experience broken links. During the transition phase, expect the following link behavior:

- Links to Web addresses beginning with `http://` work
- Links that refer to specific page numbers within the same PDF book work
- The remaining links will *not* work. You receive an error message when you click them

Thanks for your patience, in the short term, to facilitate the transition to more frequent PDF book updates.

Chapter 1. How do I...Setting up intermediary services

Follow these shortcuts to get started quickly with popular tasks.

When you visit a task in the information center, look for the **IBM Suggests** feature at the bottom of the page. Use it to find available tutorials, demonstrations, presentations, developerWorks articles, IBM Redbooks, support documents, and more.

Setup the proxy server.

Setting up DataPower appliance manager

Use the administrative console to establish communication with local and remote web servers.

Use scripting to establish communication with local and remote web servers.

Configure transport chains.

Configure additional nodes.

Customize the File Synchronization Service.

Provide access to relational databases (JDBC resources) with scripting

Choosing a messaging provider

Provide access to messaging resources (default messaging provider) with scripting

Chapter 2. Implementing a web server plug-in

This topic describes how to implement a web server plug-in. The product works with a web server to route requests for dynamic content, such as servlets, from web applications. The web servers are necessary for directing traffic from browsers to the applications that run on an application server. The web server plug-in uses the XML configuration file to determine whether a request is for an application server.

Before you begin

- See the information about choosing a front end for your WebSphere® Application Server topology." This topic helps you determine whether to set up a web server plug-in, a proxy server, or a secure proxy server to provide session affinity, failover support, and workload balancing for your WebSphere Application Server topology. Install your web server if it is not already installed.

gotcha: The web server that is provided with IBM® i, is already installed under product 5761-DG1 for IBM i V6R1 or 5770-DG1 for IBM i V7R1. The IBM i web server is referred to as the IBM HTTP Server for IBM i. This web server is different from the IBM HTTP Server that is provided with WebSphere Application Server, which does not run on IBM i.

If you want to use the IBM HTTP Server that is provided with the product, see the *Installing your application serving environment* PDF. Otherwise, see the installation information that is provided with your web server.

- Verify that your web server is configured to run the operations that are required by web applications, such as GET and POST. Typically, configuring your web server to run these operations involves setting a directive in the web server configuration file. Refer to the web server documentation for instructions.

If you are making a series of simultaneous changes, such as installing numerous applications, you might want the configuration service disabled until after you make the last change. The web server plug-in configuration service is enabled by default. To disable this service, in the administrative console click **Servers > Server Types > WebSphere application servers > server_name > administration services > web server plug-in configuration service**, and then clear the **Enable automated web server configuration processing** option.

gotcha: If your installation uses a firewall, make sure that you configure the web server plug-in to use a port that has been opened. See your security administrator for information about how to obtain an open port.

About this task

The appropriate plug-in file is installed. In addition, an http profile is created (/QIBM/UserData/WebSphere/Plugins/V8/websvr/profiles/http). The http profile can be used to facilitate the creation of web server definitions. See the topic about selecting a web server topology diagram and road map for instructions on how to configure IBM HTTP Server for IBM i to communicate with an application server.

The following procedure describes the steps for updating the plug-in configuration file, including configuring for SSL and web server tuning.

Procedure

1. Use the administrative console to change the settings in the plug-in configuration file.

When setting up your web server plug-in, you must decide whether to have the configuration automatically generated in response to a configuration change. When the web server plug-in configuration service is enabled and any of the following conditions occur, the plug-in configuration file is automatically generated:

- When the web server is created or saved
- When an application is installed

- When an application is uninstalled
- When the virtual host definition is updated

You can either use the administrative console, or issue the GenPluginCfg command to regenerate your plugin-cfg.xml file.

Complete the following steps to regenerate your plugin-cfg.xml file by using the administrative console:

- Select **Servers > Server Types > web Servers > web_server_name > plug-in properties**.
- Select **Automatically generate plug-in configuration file**, or click one or more of the following topics to manually configure the plugin-cfg.xml file:

Note: You must delete the plugin-cfg.xml file in the *profile_root/config/cells* directory before you complete this task. Otherwise, configuration changes do not persist to the plugin-cfg.xml file.

- Caching
- Request and response
- Request routing
- Custom Properties

See the topic about web server plug-in configuration properties for information about how to map each property to one of these topics.

gotcha: Do not manually update the plugin-cfg.xml file. Any manual updates you make for a web server are overridden whenever the plugin-cfg.xml file for that web server is regenerated.

- Click **OK**.
- Propagate the plug-in configuration. To propagate the plug-in configuration from the administrative console, click **Servers > Server Types > web Servers > web_server_name Propagate plug-in**.

Another method to propagate the plug-in configuration is to run the GenPluginCfg command. For more information, see the GenPluginCfg command documentation.

You do not need to propagate the plug-in configuration if the web server is on the same machine as the associated stand-alone version of the product. If the propagation of the plug-in configuration fails due to an unknown cause, you must manually copy the plugin-cfg.xml file to the location for the remote web server installation.

gotcha: If you use the FTP function to perform the copy, and the configuration reload fails, check the file authorities on the plugin-cfg.xml file and make sure that users QTMHHTTP, QNOTES and QEJBSVR have RWX authority. If the authorities are not correct, the web server cannot access the new version of the file, which causes the configuration reload to fail. To check the authorities, run the following IBM i command:

```
wrklnk 'plug_in_folder_location/plugin-cfg.xml'
```

Then select option 9 to view the authorities that are assigned to the users (QTMHHTTP, QNOTES, and QEJBSVR).

If the authorities are incorrect, issue the following IBM i command to change the file authorities to the appropriate settings:

```
CHGAUT USER(QEJBSVR QTMHHTTP QNOTES) OBJ('plug_in_folder_location/plugin-cfg.xml') DTAUT(*RWX)
```

The *plug_in_folder_location* is the location you specified when you transferred the plugin-cfg.xml file.

- You might have to stop the application server and then start the application server for the web server to locate the plugin-cfg.xml file.
- Tune your web server. See the *Tuning guide* PDF for more information.

Results

The configuration is complete. To activate the configuration, stop and restart the web server. If you encounter problems restarting your web server, check the `http_plugin.log` file for information about what portion of the `plugin-cfg.xml` file contains an error. The log file states the line number on which the error occurred, along with other details that might help you diagnose why the web server did not start. You can then use the administrative console to update the `plugin-cfg.xml` file.

If applications are infrequently installed or uninstalled, which is usually the situation in a production environment, or if you can tolerate the performance impact of generating and distributing the plug-in configuration file each time any of the previously listed actions occur, consider enabling the configuration service.

Setting up a remote web server

You can create a web server definition in the administrative console when the web server and the web server plug-in for WebSphere Application Server are on the same machine and the application server is on a different machine. This allows you to run an application server on one platform and a web server on another platform.

Before you begin

With a remote web server installation, WebSphere Application Server can facilitate plug-in administration functions and generation and propagation of the `plugin-cfg.xml` file for IBM HTTP Server for WebSphere Application Server, but not for other web servers.

Web servers that are not IBM HTTP Server for WebSphere Application Server must reside on the same machine as the WebSphere Application Server (as a managed node) to facilitate plug-in administration functions and generation and propagation of the `plugin-cfg.xml` file.

About this task

You can choose a remote web server installation if you want the web server on the outside of a firewall and WebSphere Application Server on the inside of a firewall. You can create a remote web server on an unmanaged node. Unmanaged nodes are nodes without node agents. Because there is no WebSphere Application Server or node agent on the machine that the node represents, there is no way to administer a web server on that unmanaged node unless the web server is IBM HTTP Server for WebSphere Application Server. With IBM HTTP Server, there is an administration server that will facilitate administrative requests such as start and stop, view logs, and view and edit the `httpd.conf` file.

Important: The administration server is not provided with IBM HTTP Server for WebSphere Application Server which runs on z/OS® platforms. So, administration using the administrative console is not supported for IBM HTTP Server for z/OS on an unmanaged node.

The following steps will create a web server definition in the default profile. This procedure does not apply when setting up a remote web server for an i5/OS® web server. For information about setting up an i5/OS web server, see the topic entitled *Selecting a web server topology diagram and roadmap*.

Procedure

1. Install IBM Installation Manager.
2. Install your WebSphere Application Server product.
3. Install IBM HTTP Server or another supported web server.
4. Install the web server plug-ins.
5. Configure the web server plug-in.

6. Complete the setup by creating the web server definition.

You can use the WebSphere Application Server administrative console or run the plug-in configuration script:

- **Using the administrative console:**

- a. Click **System Administration > Nodes > Add Node** to create an unmanaged node in which to define a web server in the topology.
- b. Click **Servers > Server Types > Web servers > New** to launch the **Create new web server definition** tool. You will create the new web server definition using this tool. The values are as follows:
 - 1) Select appropriate node
 - 2) Enter web server properties:
 - **Type:** The web server vendor type.
 - **Port:** The existing web server port. The default is 80.
 - **Installation Path:** The web server installation path. This field is required field for IBM HTTP Server only.
 - **WINDOWS Service Name:** The Windows operating system service name of the web server. The default is IBMHTTPServer7.0.
 - **Use secure protocol:** Use the HTTPS protocol to communicate with the web server. The default is HTTP.
 - **Plug-in installation location:** The directory path where the plug-in is installed.
 - **Application mapping to the web server:** Whether you want to create a mapping to existing applications that are currently deployed to the web server. Select ALL if you want the mapping created; select None if you do not want the mapping created.

CAUTION:

If you have enterprise applications in different security domains when you create a web server, the Key Database (KDB) files for your security configuration might not be created if you have Application mapping to the web server set to All. To resolve this problem, create the web server with Application mapping to the web server set to None. Then map the applications to the web server. All the KDB files for the web server are then created.

- 3) Enter the remote web server properties. The properties for the IBM HTTP Server administration server follow:
 - **Port:** The administration server port. The default is 8008.
 - **User ID:** The user ID that is created using the htpasswd script.
 - **Password:** The password that corresponds to the user ID created with the htpasswd script.
 - **Use secure protocol:** Use the HTTPS protocol to communicate with the administration server. The default is HTTP.
- 4) Select a web server template. Select a system template or a user-defined template for the web server you want to create.
- 5) Confirmation of web server creation.

- **Run the plug-in configuration script.**

7. **For AIX®, HP-UX, Linux or Solaris operating system:** On the remote web server, run the setupadm script. The administration server requires read and write access to configuration files and authentication files to perform web server configuration data administration. You can find the setupadm script in the `<IHS_install_root>/bin` directory. The administration server has to execute `adminctl restart` as root to perform successful restarts of IBM HTTP Server. In addition to the web server files, you must manually change the permissions to the targeted plug-in configuration files.

The setupadm script prompts you for the following input:

- User ID - The user ID that you use to log on to the administration server. The script creates this user ID.
- Group name - The administration server accesses the configuration files and authentication files through group file permissions. The script creates the specified group through this script.
- Directory - The directory where you can find configuration files and authentication files.
- File name - The following file groups and file permissions change:
 - Single file name
 - File name with wildcard
 - All (default) - All of the files in the specific directory
- Processing - The `setupadm` script changes the group and file permissions of the configuration files and authentication files.

In addition to the web server files, you must change the permissions to the targeted plug-in configuration files. See the topic on setting permissions manually for instructions.

8. **For AIX, HP-UX, Linux, Solaris, or Windows operating system:** On the remote web server, run the `htpasswd` script. The administration server is installed with authentication enabled and a blank `admin.passwd` password file. The administration server will not accept a connection without a valid user ID and password. This is done to protect the IBM HTTP Server configuration file from unauthorized access.

Launch the **htpasswd** utility that is shipped with the administration server. This utility creates and updates the files used to store user names and password for basic authentication. Locate **htpasswd** in the `bin` directory.

- On Windows operating systems: `htpasswd -cm <install_dir>\conf\admin.passwd [login name]`
- On AIX, HP-UX, Linux, and Solaris platforms: `./htpasswd -cm <install_dir>/conf/admin.passwd [login name]`

where `<install_dir>` is the IBM HTTP Server installation directory and `[login name]` is the user ID that you use to log into the administration server. The `[login name]` is the user ID that you entered in the user ID field for the remote web server properties in the administrative console.

9. Start IBM HTTP Server. Refer to the topic on starting and stopping the IBM HTTP Server Administration server for instructions.

What to do next

For a non-IBM HTTP Server web server on an unmanaged node, you can generate a plug-in configuration, based on WebSphere Application server repository changes. However, the following functions are not supported on an unmanaged node for a non-IBM HTTP Server web server:

- Starting and stopping the web server.
- Viewing and editing the web server configuration file.
- Viewing the web server logs.
- Propagation of the web server `plugin-cfg.xml` file.

You can configure non-IBM HTTP Server web servers as a local web server on a managed node. For a non-IBM HTTP Server web server on a managed node, the following functions are supported:

- Generation of the plug-in configuration, based on WebSphere Application Server repository changes.
- Propagation of the `plugin-cfg.xml` file, based on using node synchronization with the WebSphere Application Server node. Node synchronization is necessary in order to propagate configuration changes to the affected node or nodes.

Note: When WebSphere Application Server is installed using a stand-alone profile on one machine and IBM HTTP Server is installed on a different machine as root user using the administrative server, to ensure that propagation functions correctly, the root user must manually change the permissions of the `plugin-cfg.xml` file to the nonroot user running IBM HTTP Server from the

administrative server. The username and group needed to start the administrative server are located in the HTTPServer/config/admin.conf file.

The plugin-cfg.xml file is propagated to the application server node repository tree from the deployment manager repository.

Important: The plugin-cfg.xml file is propagated to the application server node repository tree. This is not the default plugin-cfg.xml file installation location. Changes may have to be made to non-IBM HTTP Server web server configuration files to update the location of the plugin-cfg.xml file that is read by the plug-in module.

For example, Internet Information Services (IIS) has a file name called plugin-cfg.loc, which is read by the IIS plug-in modules to determine the location of the plugin-cfg.xml file. The plugin-cfg.loc file has to be updated to reflect the plugin-cfg.xml file location in the application server node repository.

Other non-IBM HTTP Server web servers have different methods to specify the location of the plugin-cfg.xml file for the plug-in module. However, in order for propagation to work, update the location to reflect the location in the application server node repository.

For a non-IBM HTTP Server Web server that is configured as a local web server on a managed node, the following functions are not supported:

- Starting and stopping the web server.
- Viewing and editing the configuration file.
- Viewing the web server logs.

Installing IBM HTTP Server

This topic describes how to install IBM HTTP Server.

Before you begin

The IBM HTTP Server product is included in the media package when you order any of the WebSphere Application Server for IBM i products. It is not a required product. To install the product on a non-IBM i server, use the following instructions.

To use a web server other than IBM HTTP Server, install and configure the web server before or after installing the WebSphere Application Server product but before installing the Web Server Plug-ins for IBM WebSphere Application Server.

About this task

Refer to the information center for IBM HTTP Server for detailed information on installation steps, configuring the web server for SSL, the Fast Response Cache Accelerator, or Apache directives.

What to do next

After installing the web server and the application server, install and configure the appropriate web server plug-in for a supported, installed web server. No further configuration is required for most web servers.

You can manually configure supported Web servers for WebSphere Application Server as described in “Editing web server configuration files” on page 9.

The Global Security Kit (GSKit) installation image files for the WebSphere Web server plug-ins are packaged on the CD with the web server plug-in files. If you want to use GSKIT, you can download the appropriate GSKIT file to the workstation on which your web server is running.

Editing web server configuration files

Edit web server configuration files to configure a Web server.

Before you begin

Use the IBM Web Administration for IBM i to configure IBM i Web servers to communicate with a WebSphere Application Server. Doing so automatically updates the web server configuration files as needed. See the *Installing your application serving environment* PDF for more information.

If you must change a configuration for some reason, you can use the IBM Web Administration for IBM i to re-configure the web server, or you can edit the files. The recommended approach is to always use the IBM Web Administration for IBM i to configure the web server configuration file. However, sometimes you must edit the files.

You must determine whether your web server application uses a 32-bit or 64-bit architecture. If your machine supports a 64-bit architecture, you can use either a 32-bit or a 64-bit web server application. The following examples show how to determine which the architecture for your web server application:

- For Apache-based web servers, including IBM HTTP Server, you can determine the architecture using the following techniques:
- For other, non-Apache based web servers, use the following techniques. These techniques also work for Apache-based web servers.

If the web server application uses a 64-bit architecture, the plug-in library should be loaded from the `plugin_root/bin/64bit` directory. If the web server application uses a 32-bit architecture, the plug-in library should be loaded from the `plugin_root/bin/32bits` directory. If the `plugin_root/bin/64bits` directory does not exist, you must use the 32-bit architecture.

About this task

This task points you to information on editing web server configuration files. Select a link appropriate for your web server.

Procedure

- See the *Installing your application serving environment* PDF for information about configuring your web server.
- Configure IBM HTTP Server powered by Apache 2.x. See “Configuring IBM HTTP Server powered by Apache 2.x” on page 13.
- Configure IBM HTTP Server Version 6.x. See “Configuring IBM HTTP Server Version 6.x” on page 14.
- Configure IBM HTTP Server Version 7.0. See “Configuring IBM HTTP Server Version 7.0” on page 15.
- Configure IBM HTTP Server Version 78.0. See “Configuring IBM HTTP Server Version 8.0” on page 16.

Results

You can use the IBM Web Administration for IBM i to configure IBM i Web servers. You can also configure a web servers by editing its configuration.

Configuring Apache HTTP Server V2.2

This topic describes how to change configuration settings for Apache HTTP Server Version 2.2.

Before you begin

gotcha: If you are running IBM HTTP Server (powered by Apache) on IBM i, you can use the manual configuration steps outlined below. However, it is recommended that you use the IBM Web Administration for IBM i GUI.

Apache HTTP Server v2.2 is different from IBM HTTP Server (powered by Apache). Apache HTTP Server is not supported on IBM i.

This topic describes how to configure the Apache HTTP Server Version 2.2 Web server. Other procedures in "Editing web server configuration files" on page 9 describe configuring other supported web servers.

About this task

Perform the step that configures Apache 2.2 for your operating system.

Examples and messages are shown on more than one line for clarity. Place each directive in a web server configuration file on one line.

Local file path means a file path to the `plugin-cfg.xml` file on an application server that is on the same machine as the web server. Remote file path means the file path to the `plugin-cfg.xml` file when the application server is on a remote machine.

The name of the web server definition in the following steps is `webserver1`.

Procedure

Configure entries in the `httpd.conf` file. It is recommended that you use the IBM Web Administration for IBM i GUI to configure the `httpd.conf` file.

Use the following examples of the `LoadModule` and the `WebSpherePluginConfig` directives as models for configuring your file for IBM i:

```
LoadModule was_ap20_module  
    /QSYS.LIB/product_library.LIB/QSVTAP22.SRVPGM
```

where *product_library* is the name of the WebSphere Application Server product library, such as QWAS8A or QWAS8B. See the "Directory conventions" article for information about how to determine the product library name.

Local distributed example (Network Deployment only - the web server is configured in a managed node):

```
WebSpherePluginConfig /QIBM/UserData/WebSphere/AppServer/V8/  
    ND/profiles/profile1/config/cells/my_cell/nodes/  
    my_managednode/servers/webserver1/plugin-cfg.xml
```

Local standalone example:

```
WebSpherePluginConfig /QIBM/UserData/WebSphere/AppServer/V8/  
    ND/profiles/profile1/config/cells/my_cell/nodes/  
    webserver1_node/servers/webserver1/plugin-cfg.xml
```

Remote example:

```
WebSpherePluginConfig /QIBM/UserData/WebSphere/AppServer/V8/  
    ND/profiles/httpprofile1/config/webserver1/plugin-cfg.xml
```

Results

The Apache 2.2 Web Server is re-configured.

What to do next

After configuring a web server, you can install applications on it. See the Applications section of the information center for more information.

Tip: To unconfigure a web server, reverse the manual steps and remove what was manually added in this procedure.

Configuring Lotus Domino

This task describes how to change configuration settings for Lotus® Domino®.

Before you begin

If you are running Domino Web Server on IBM i, use the IBM Web Administration for IBM i GUI.

Other procedures in “Editing web server configuration files” on page 9 describe configuring other supported web servers.

About this task

Use the following procedure to enable the web server plug-in to work with Lotus Domino. Ensure that you install the plug-in as root. Domino can only be installed as root, and the configuration files belong to root.

: If you install the plug-in as local and the WebSphere Application Server as nonroot, then web server management on WebSphere Application Server, such as generation, propagation, deletion of web server definitions and more, is unavailable because the `plugin-cfg.xml` file must be installed as root.

Procedure

1. Start the Domino server.
2. Access the `names.nsf` file using your web browser (for example, `http://tarheels2.raleigh.ibm.com/names.nsf`). The browser prompts you for a password.
3. Give the administrator name and password.
4. Click **Configuration** on the left side of the page.
5. Click **Servers** on the left side of the page.
6. Click **All Server Documents** on the left side of the page.
7. Click the server that you intend to have work with the product.
8. Click **Edit Server** on the top-left of the center window.
9. Click **Internet Protocols** in the middle of the page.
10. Add the path to the Domino plug-in under the DSAPI Section in the middle-right of the page.
The DSAPI filter location on IBM i is `/QSYS.LIB/QWAS8.LIB/LIBDOMINOH.SRVPGM`. The plug-in is installed in the `bin` directory of the Web Server Plug-ins.
If specifications for filter files for the Domino Server Application Programming Interface (DSAPI) exist, use a space to delimit the web server plug-in for WebSphere Application Server.
11. Click **Save and Close** in the upper left of the center window.
12. Define the location of the `plugin-cfg.xml` configuration file.
The location varies depending on how you have configured your system. If the web server and the application server are on separate machines, you have a remote installation.
If the two servers are on the same machine, you have a local installation.
If the two servers are on the same machine and the application server node or the custom node is federated, you have a local distributed installation.
In the following examples, `webserver1` is the web server definition name.

Setting the path to the plug-in configuration file

Edit your notes.ini file.

- a. From a CL command prompt, enter the Work with Domino Servers (WRKDOMSVR) command.
- b. Type **13** next to the applicable Domino server, then press **Enter**.
- c. Add or edit the WebSphereInit property. (See the following table.)
To add a new line, type "i" next to the wanted insertion line, then press **Enter**.
- d. Press **F3** to save and exit.

Table 1. Editing the notes.ini file. Use this table when editing you notes.ini file.

If the type of installation is:	Then use this command to set the environment variable:
Remote	WebSpherePluginConfig <i>profile_root</i> /config/webserver1/plugin-cfg.xml
Local standalone	WebSpherePluginConfig <i>profile_root</i> /config/cells/my_cell/nodes/webserver1_node/servers/webserver1/plugin-cfg.xml
Local distributed	WebSpherePluginConfig <i>profile_root</i> /config/cells/my_cell/nodes/my_managednode/servers/webserver1/plugin-cfg.xml

The setupPluginCfg.sh file is created in two places:

- The *plugins_root*/bin directory
- The *lotus_root*/notesdata directory

You can run the script from either location to set the WAS_PLUGIN_CONFIG_FILE environment variable. However, if you are re-configuring the web server, you might want to set the path yourself by setting the value of the environment variable with a path from the preceding table.

13. If you are configuring a 64-bit version of the Domino Version 7 or higher web server, modify the notes.ini file to point to the *plugin_root*\bin\64bit\domino5.dll file.
14. Restart the Domino server. When the server starts, information like the following example is displayed:

```
01/21/2005 01:21:51 PM JVM: Java virtual machine initialized
WebSphere Application Server DSAPI filter loaded
01/21/2005 01:21:52 PM HTTP Web Server started
```

Results

This procedure results in reconfiguring Version 6.x of Lotus Domino.

What to do next

After configuring a web server, you can install applications on it. See the Applications section of the information center for more information.

For more information about configuring Lotus Domino to work with WebSphere Application Server, search the Lotus Support Services website at <http://www-3.ibm.com/software/lotus/support/>. Enter the search term WebSphere in the keyword search field.

Tip: To unconfigure a web server, reverse the manual steps and remove what was manually added in this procedure.

Lotus Domino file locations and troubleshooting tips

Lotus Domino Server is one of the Web servers that WebSphere Application Server supports. This topic describes configuration file locations and provides other tips related to using Lotus Domino.

Lotus Domino Server file locations

Lotus Domino server file locations are:

- /QIBM/ProdData/LOTUS/NOTES/Notes.jar *data-directory*/names.nsf where *data-directory* is the data directory of your Domino server.

Perform the following steps to determine the directory name:

1. From a control language (CL) command prompt, enter the Work with Domino Server (WRKDOMSVR) command.
2. Type **13** next to the applicable server, then press **Enter**.
3. The value of the property named Directory is the name of the data directory of your Domino Server.

The Domino Server plug-in might fail to load on an iSeries® system

Error messages in the Domino console can indicate more detailed error messages in the Notes® spool files. For example, if you see the following error message on your Domino console, perform the following steps:

Sample error message:

```
01/05/2006 13:28:56 HTTP Server:
Failed to load DSAPI module
/QSYS.LIB/QWAS8.LIB/LIBDOMINOH.SRVPGM
```

1. From a CL command prompt, enter the Work with Spool Files (WRKSPLF) command:

```
WRKSPLF QNOTES
```

2. Use option **5** to open the applicable spool file for your notes server.

You might have to stop your Domino server to view the spool file.

3. Inspect the output to find applicable error messages. For example, suppose that the following entry is in the log:

```
ERROR: lib_sxp: sxpCreate: Can't open
'/QIBM/UserData/webas5/base/rb5025test/config
/cells/plugin-cfg.xml', OS Err: 3401
ERROR: ws_config_parser: configParserParse:
Failed to create the sxpParser object for
profile_root/config/plugin-cfg.xml
ERROR: ws_common: websphereUpdateConfig:
Failed parsing plugin config file:
ERROR: profile_root/config/plugin-cfg.xml
ERROR: The above file may not have correct authorities.
ERROR: Do WRKLNK, Opt 9 on above file. ERROR: Check that QTMHHTTP and QNOTES have correct authorities:
ERROR: QTMHHTTP *RX ERROR: QNOTES *RX ERROR: ws_common: websphereInit:
Failed to load the config file
ERROR: domino5_plugin: FilterInit:
Failed to initialize WebSphere
```

Configuring IBM HTTP Server powered by Apache 2.x

This topic describes how to change configuration settings for IBM HTTP Server powered by Apache 2.x.

Before you begin

If you are running IBM HTTP Server (powered by Apache) on IBM i, you can use the manual configuration steps outlined below with the IBM Web Administration for IBM i.

This topic describes how to configure the IBM HTTP Server. Other procedures in “Editing web server configuration files” on page 9 describe configuring other supported web servers.

About this task

Perform the step that configures IBM HTTP Server version 2.2 for your operating system. IBM HTTP Server powered by Apache 2.2 is supported on IBM i Versions 6.1 and 7.1.

Examples and messages are shown on more than one line for clarity. Place each directive in a web server configuration file on one line.

Local file path means a file path to the `plugin-cfg.xml` file on an application server that is on the same machine as the web server. Remote file path means the file path to the `plugin-cfg.xml` file when the application server is on a remote machine.

The web server definition name in the following examples is `webserver1`.

Procedure

Configure entries in the `httpd.conf` file.

Use the IBM Web Administration for IBM i GUI to configure the `httpd.conf` file. See the topic [Configuring an HTTP server instance on IBM i](#) for a description of how to use this GUI.

Use the following examples of the `LoadModule` and the `WebSpherePluginConfig` directives as models for configuring your file for IBM i:

```
LoadModule was_ap20_module
    /QSYS.LIB/product_library.LIB/QSVTAP22.SRVPGM
```

where *product_library* is the name of the WebSphere Application Server product library, such as `QWAS8A`, and `QWAS8B`. See the topic [Directory conventions](#) for information about how to determine the product library name.

Local distributed example (Network Deployment only - the web server is configured in a managed node):

```
WebSpherePluginConfig
    profile_root/config/cells/my_cell/
    nodes/my_managednode/servers/webserver1/plugin-cfg.xml
```

Local standalone example:

```
WebSpherePluginConfig /QIBM/UserData/WebSphere/AppServer/V8/
    ND/profiles/profile1/config/cells/my_cell/nodes/
    webserver1_node/servers/webserver1/plugin-cfg.xml
```

Remote example:

```
WebSpherePluginConfig
    /QIBM/UserData/WebSphere/AppServer/V8/
    ND/profiles/httpprofile1/config/webserver1/plugin-cfg.xml
```

Results

This procedure results in editing and re-configuring IBM HTTP Server powered by Apache 2.x.

What to do next

If the IBM HTTP Server 1.3.2x directive, `LoadModule ibm_app_server_http_module`, is present in an IBM HTTP Server 2.x `httpd.conf` file, the IBM HTTP Server cannot start. You must comment or delete the directive to start the Version 2.x server.

After configuring a web server, you can install applications on it. See the [Applications](#) section of the information center for more information.

Tip: To unconfigure a web server, reverse the manual steps and remove what was manually added in this procedure.

Configuring IBM HTTP Server Version 6.x

This topic describes how to change configuration settings for IBM HTTP Server.

Before you begin

IBM HTTP Server Version 6.x is not supported on IBM i. See the *Installing your application serving environment* PDF for information on how to configure IBM HTTP Server powered by Apache 2.0.

This topic describes how to configure IBM HTTP Server, Version 6.x. Other procedures in “Editing web server configuration files” on page 9 describe configuring other supported web servers.

About this task

Perform the step that configures IBM HTTP Server for your operating system.

Examples and messages are shown on more than one line for clarity. Place each directive in a web server configuration file on one line.

Local file path means a file path to the `plugin-cfg.xml` file on an application server that is on the same machine as the web server. Remote file path means the file path to the `plugin-cfg.xml` file when the application server is on a remote machine.

The `node_name` in the following application server local file paths is `web_server_name_node` for a standalone application server or `managed_node_name` for a managed node.

Procedure

Results

This procedure results in editing and re-configuring IBM HTTP Server.

What to do next

If the IBM HTTP Server V1.3.x directive, `LoadModule ibm_app_server_http_module`, is present in an IBM HTTP Server Version 6.x and later `httpd.conf` file, IBM HTTP Server cannot start. You must comment or delete the directive to start the Version 6.x server.

The `mod_was_ap20_http` plug-in module requires the GSKIT Secure Sockets Layer (SSL) encryption library if the plug-in is configured to support encrypted connections to back-end WebSphere Application Servers.

Installing the web server plug-ins installs the GSKIT SSL encryption library at the required level if it is not installed. If you manually copy the plug-in to a new machine, you might not have the required GSKIT libraries for encrypting back-end connections.

After configuring a web server, you can install applications on it. See the Applications section of the information center for more information.

Tip: To unconfigure a web server, reverse the manual steps and remove what was manually added in this procedure.

Configuring IBM HTTP Server Version 7.0

This topic describes how to change configuration settings for IBM HTTP Server.

Before you begin

IBM HTTP Server Version 7.0 is not supported on IBM i. See the *Installing your application serving environment* PDF for information on how to configure IBM HTTP Server powered by Apache 2.0, or IBM HTTP Server powered by Apache 2.0.

This topic describes how to configure IBM HTTP Server, Version 7.0. Other procedures in “Editing web server configuration files” on page 9 describe configuring other supported web servers.

About this task

Perform the step that configures IBM HTTP Server for your operating system.

Examples and messages are shown on more than one line for clarity. Place each directive in a web server configuration file on one line.

Local file path means a file path to the `plugin-cfg.xml` file on an application server that is on the same machine as the web server. Remote file path means the file path to the `plugin-cfg.xml` file when the application server is on a remote machine.

The `node_name` in the following application server local file paths is `web_server_name_node` for a standalone application server, or `managed_node_name` for a managed node.

Procedure

Results

This procedure results in editing and re-configuring IBM HTTP Server.

What to do next

The `mod_was_ap22_http` plug-in module requires the GSKIT Secure Sockets Layer (SSL) encryption library if the plug-in is configured to support encrypted connections to back-end WebSphere Application Servers.

Installing the web server plug-ins installs the GSKIT SSL encryption library at the required level if it is not installed. If you manually copy the plug-in to a new machine, you might not have the required GSKIT libraries for encrypting backend connections.

After configuring a web server, you can install applications on it. See the Applications section of the information center for more information.

Tip: To unconfigure a web server, reverse the manual steps and remove what was manually added in this procedure.

Configuring IBM HTTP Server Version 8.0

This topic describes how to change configuration settings for IBM HTTP Server.

Before you begin

IBM HTTP Server Version 8.0 is not supported on IBM i. See the *Installing your application serving environment* PDF for information on how to configure IBM HTTP Server powered by Apache 2.0, or IBM HTTP Server powered by Apache 2.0.

This topic describes how to configure IBM HTTP Server, Version 8.0. Other procedures in “Editing web server configuration files” on page 9 describe configuring other supported web servers.

About this task

Perform the step that configures IBM HTTP Server for your operating system.

Examples and messages are shown on more than one line for clarity. Place each directive in a web server configuration file on one line.

Local file path means a file path to the `plugin-cfg.xml` file on an application server that is on the same machine as the web server. Remote file path means the file path to the `plugin-cfg.xml` file when the application server is on a remote machine.

The `node_name` in the following application server local file paths is `web_server_name_node` for a standalone application server, or `managed_node_name` for a managed node.

Procedure

Results

This procedure results in editing and re-configuring IBM HTTP Server.

What to do next

The `mod_was_ap22_http` plug-in module requires the GSKIT Secure Sockets Layer (SSL) encryption library if the plug-in is configured to support encrypted connections to back-end WebSphere Application Servers.

Installing the web server plug-ins installs the GSKIT SSL encryption library at the required level if it is not installed. If you manually copy the plug-in to a new machine, you might not have the required GSKIT libraries for encrypting backend connections.

After configuring a web server, you can install applications on it. See the Applications section of the information center for more information.

Tip: To unconfigure a web server, reverse the manual steps and remove what was manually added in this procedure.

Creating web server templates

A web server template is used to define the configuration settings for a new web server. When you create a new web server, you can either create a new web server definition or use a previously created web server template that is based on another, already existing web server.

About this task

To create a web server template.

Procedure

1. In the administrative console, click **Servers > Server Types > Web servers >** , and then click **Templates**.

You can also use the `createWebServerTemplate` command for the AdminTask object to create a web server template.

2. On the Server Templates page, click **New**.

3. Select the web server that you want to use to create the new template, and then click **OK**.
4. Enter the name of the new template and, optionally, a description of that template that distinguishes it from your other templates.
5. Click **OK**.

Results

Your new template displays in the list of server templates that you can use to create a new web server.

What to do next

You can perform one of the following actions to display a list of all of the server templates that are available on your system:

- In the administrative console, click **Servers > Server Types > Web servers**, and then click **Templates**.
- Issue a `listServerTemplates` wsadmin command that includes the `-serverType WEB_SERVER` parameter.

Allowing web servers to access the administrative console

This topic describes how to add the virtual host that servers the administrative console to the plug-in configuration file so that you can access the administrative console through a web server.

Before you begin

Install your WebSphere Application Server product, a web server, the Web Server Plug-ins, and the WebSphere Customization Toolbox.

When you configure a web server plug-in, a Web server definition is created on the application server system, either directly when they are on the same machine or by a script for remote scenarios.

After creating the web server definition, the plug-in configuration file exists within the web server definition.

The `plugin-cfg.xml` file can be overwritten by the deployment manager synchronization operation, the `GenPluginCfg` script or any other method that regenerates the file. If you make changes to the `plugin-cfg.xml` file, and want to keep those changes, it is recommended that you create a copy of the file in a separate location. Make your manual updates each time the file is automatically refreshed by another process.

About this task

This task gives you the option of configuring the `admin_host` so that web servers can access the administrative console. When the web server plug-in configuration file is generated, it does not include `admin_host` on the list of virtual hosts.

Procedure

1. Use the administrative console to change the `admin_host` virtual host group to include the web server port (80 by default).
 - a. Click **Environment > Virtual Host > admin_host > Host Aliases > New**.

The default port that displays is 80, unless you specify a different port during profile creation.
 - b. Specify the IP address, or the name of the machine that is hosting the HTTP server.

For example, if you installed a WebSphere Application Server product on a machine that is named `waslwaj.rtp.ibm.com`, specify the name in this field.
2. Click **Apply > Save**.
3. Stop and restart the application server.

For example, to access the administrative console of a stand-alone application server, stop and restart the `server1` process.

Start a Qshell session and run the following command:

```
cd profile_root/bin
stopServer server1
```

Then issue the following command to stop the application server:

```
stopServer -profileName myProfile server1
```

After receiving the following message, you can restart the application server:

```
Server server1 stop completed.
```

To start the application server, issue the following command:

```
startServer server1
```

When the application server is running, a message is displayed that indicates that the process is running. This message includes the iSeries job ID and the administrative console port.

4. Stop and restart a deployment manager.

For example, to access the administrative console of a deployment manager, stop and restart the deployment manager.

Start a Qshell session and run the following command:

```
cd profile_root/bin
```

Then issue the following command to stop the deployment manager:

```
stopManager
```

After receiving the following message, you can restart the deployment manager:

```
Server dmgr stop completed.
```

To start the deployment manager, issue the following command:

```
startManager
```

When the deployment manager is running, a message is displayed that indicates that the process is running. This message includes the iSeries job ID and the administrative console port.

5. Edit the `plugin-cfg.xml` file to include the following entries:

```
<VirtualHostGroup Name="admin_host">
  <VirtualHost Name="*:13060"/>
</VirtualHostGroup>
...
...
...
<ServerCluster Name="my60Profile.dmgr_myiSeries_Cluster">
  <Server LoadBalanceWeight="1" Name="myiSeries_my60Profile.dmgr">
    <Transport Hostname="myiSeries" Port="11060" Protocol="http"/>
  </Server>

  <PrimaryServers>
    <Server Name="myiSeries_my60Profile.dmgr"/>
  </PrimaryServers>
</ServerCluster>
...
...
...
<UriGroup Name="admin_host_my60Profile.dmgr_myiSeries_Cluster_URIs">
  <Uri AffinityCookie="JSESSIONID"
    AffinityURLIdentifier="jsessionid" Name="/ibm/console/*"/>
</UriGroup>
<Route ServerCluster="my60Profile.dmgr_myiSeries_Cluster"
  UriGroup="admin_host_my60Profile.dmgr_myiSeries_Cluster_URIs" VirtualHostGroup="admin_host"/>
```

If your HTTP server has an HTTP port other than 80, add an entry to the `VirtualHostGroup`:

```
<VirtualHost Name="*:port"/>
```

The `port` variable is your HTTP server port.

Results

You can configure your supported web servers to access the administrative console application of a deployment manager or a stand-alone application server.

Administering web servers from the administrative console

Web server definition

To administer or manage a web server using the administrative console, you must create a web server definition or object in the WebSphere Application Server repository.

The creation of this object is exclusive of the actual installation of a web server. The web server object in the WebSphere Application Server repository represents the web server for administering and managing the web server from the administrative console.

The web server object contains the following web server properties:

- installation root
- port
- configuration file paths
- log file paths

In addition to web server properties, the web server contains a plug-in object. The plug-in object contains properties that define the `plugin-cfg.xml` file.

The definitions of the web server object are made using the **wsadmin** command or the administrative console. You can also define a web server object in the WebSphere Application Server repository using the profile create script during installation, a `.jac1` script, and by using the administrative console wizard.

There are three types of WebSphere Application Server nodes upon which you can create a web server. The type depends on the version of WebSphere Application Server, as follows:

- **Managed node.** A node that contains a node agent. This node can exist only in a deployment manager environment. The importance of defining a web server on a managed node is that the administration and configuration of the web server is handled through the node agent from the administrative console. Support for administration and configuration through the administrative console is limited to IBM HTTP Server only. Non-IBM HTTP Server web servers must be on a managed node to handle plug-in administrative functions and the generation and propagation of the `plugin-cfg.xml` file.
- **Stand-alone node.** A node that does not contain a node agent. This node usually exists in WebSphere Application Server (base) or WebSphere Application Server, Express environment. A stand-alone node can become a managed node in a deployment manager environment after the node is federated. A stand-alone node does not contain a node agent, so to administer and manage IBM HTTP Server, there must be an IBM HTTP Server administration server installed and running on the stand-alone machine that the node represents. IBM HTTP Server ships with the IBM HTTP Server administration server and is installed by default. Support for administration and configuration through the administrative console is limited to IBM HTTP Server only.
- **Unmanaged node.** A node that is not associated with a WebSphere Application Server node agent. This node cannot be federated. Typically, the unmanaged node represents a remote machine that does not have WebSphere Application Server installed. However, you can define an unmanaged node on a machine where WebSphere Application Server is installed. This node can exist in a WebSphere Application Server (base), WebSphere Application Server, Express, or deployment manager environment. An unmanaged node does not contain a node agent, so to administer and manage IBM HTTP Server, an IBM HTTP Server administration server must be installed and running on the stand-alone machine that the node represents. Support for administration and configuration through the administrative console is limited to IBM HTTP Server only.

Web servers, which are not IBM HTTP Servers for WebSphere Application Server, are not fully administered from the WebSphere Application Server administrative console. The administration functions for Web servers, which are not IBM HTTP Servers for WebSphere Application Server, are:

- On managed nodes:
 - Web server status in the web server collection panel or `serverStatus.sh`
 - Generation of the `plugin-cfg.xml`
 - Propagation of the `plugin-cfg.xml`
- On unmanaged nodes:
 - Web server status in the web server collection panel or `serverStatus.sh`
 - Generation of the `plugin-cfg.xml`

Web server configuration

Plug-in configuration involves configuring the web server to use the binary plug-in module that WebSphere Application Server provides. Plug-in configuration also includes updating the plug-in XML configuration file to reflect the current application server configuration. The binary module uses the XML file to help route web client requests.

The plug-ins configuration process uses the following files to configure a plug-in for the web server that you select:

- The **web server configuration file** on the web server machine, such as the `httpd.conf` file for IBM HTTP Server.
- The **binary web server plug-in file** on the web server machine.
- The **plug-in configuration file, `plugin-cfg.xml`**, on the application server machine that you propagate (copy) to a Web server machine.
- The **configuration script** for configuring the web server definition for your application server in a remote HTTP scenario.

See the following descriptions of each file.

Web server configuration file

The web server configuration file is installed as part of the web server.

Configuration consists of adding directives that identify file locations of two files:

- Binary web server plug-in file
- Plug-in configuration file, `plugin-cfg.xml`

Binary web server plug-in file

An example of a binary plug-in module is the `mod_was_ap22_http.dll` file for IBM HTTP Server on the Windows platform.

Another example of a binary plug-in module is the QSVTAP20 service program on the IBM i platform.

The binary plug-in file does not change. However, the configuration file for the binary plug-in is an XML file. The application server changes the configuration file when certain changes to your WebSphere Application Server configuration occur.

The binary module reads the XML file to adjust settings and to route requests to the application server.

Plug-in configuration file, plugin-cfg.xml

The plug-in configuration file is an XML file with settings that you can tune in the administrative console. The file lists all of the applications installed on the web server definition. The binary module reads the XML file to adjust settings and to route requests to the application server.

When you make application server configuration changes that affect deployed applications, regenerate the plug-in configuration XML file.

After regeneration, propagate (copy) the file to the web server machine. The binary plug-in then has access to the most current copy of its configuration file.

On IBM i systems, the plug-in is not automatically generated. You must regenerate and propagate the file manually.

Configuration script for the Web server definition

Configuring your web server with the `configure0s400WebserverDefinition` script or using the IBM i Administrative GUI creates the `configureweb_server_name` script on the web server machine in the `plugins_root/bin` directory. The script is created for remote installation scenarios only.

Copy the script from the web server machine to the `app_server_root/bin` directory in the IBM i partition. Run the script to create a web server definition in the configuration of the application server.

The IBM i Administrative GUI has plug-ins that allow the administrative console to manage IBM HTTP Servers. Use the administrative console to update your web server definition with remote web server management options. Click **Servers > Server Types > Web servers > web_server_name** to see configuration options. For example, click **Remote Web server management** to change such properties as:

- Host name
- Administrative port
- User ID
- Password

If a web server definition already exists for a standalone application server, running the script does not add a new web server definition. Each standalone application server can have only one Web server definition.

You cannot use the administrative console of a standalone application server to add or delete a web server definition. However, you can do both tasks using the administrative scripting interface:

- Add a web server definition through the wsadmin facility using the `configureweb_server_name` script. The script uses a Java Command Language (Jacl) script named `configureWebserverDefintion.jacl` to create and configure the web server definition.
- Delete a web server definition using wsadmin commands. The Web server is named `webserver1` in the following example:

```
set webserverName webserver1
set webserverNodeSuffix _node
set webserverNodeName
$webserverName$webserverNodeSuffix
$AdminConfig remove
  [$AdminConfig getid
    /Node:$webserverNodeName/Server:$webserverName]
$AdminConfig remove
  [$AdminConfig getid /Node:$webserverNodeName]
$AdminConfig save
```

Alternatively, you can use the `configure0s400WebServerDefinition` and `remove0s400WebServerDefinition` scripts to perform these tasks.

A managed node, on the other hand, can have multiple web server definitions. The script creates a new web server definition unless the web server name is the same.

Replacing the default plug-in configuration file with the file from the web server definition (propagation)

The default file uses fixed parameter values that might not match the parameter values in the actual file on the application server. The default file is a placeholder only.

The file cannot reflect changes that occur in the application server configuration. The file also cannot reflect nondefault values that might be in effect on the application server.

Web server collection

Use this page to configure, manage, and view information about your web servers.

Web servers

To view this administrative console page click **Servers > Server Types > Web Servers**.

To create a new web server, click **New** to launch the Create new web server entry wizard. To manage an installed web server, select the check box beside the application name in the list and click a button:

Button	Resulting Action
Generate Plug-in	When the plug-in configuration service is enabled, a plug-in configuration file is automatically generated for a web server whenever: <ul style="list-style-type: none"> • The WebSphere Application Server administrator defines new web server. • An application is deployed to an Application Server. • An application is uninstalled. • A virtual host definition is updated and saved.
Propagate Plug-in	Choosing this action will copy the plugin-cfg.xml file from the local directory where the Application Server is installed to the remote machine. If you are using IBM HTTP Server V6 or higher for your web server, WebSphere Application Server can automatically propagate the plug-in configuration file to remote machines provided there is a working HTTP transport mechanism to propagate the file.
New	Launches the wizard to create a new web server entry.
Delete	Deletes one or more of the selected web server entries.
Templates ...	Opens the web server templates list panel. From this panel you can create a new template or delete existing templates.
Start	Starts one or more of the selected web servers.
Stop	Stops one or more of the selected web servers.
Terminate	Terminates one or more of the selected web servers.

Name

Specifies a logical name for the web server. This can be the host name of the machine, or any name you choose.

Web server type

Indicates the type of web server you are using.

Node

Specifies a logical name for the web server. This can be the host name of the machine, or any name you choose.

Specifies the name of the node on which the web server is defined. This column only applies for the WebSphere Application Server, Network Deployment product.

Version

Specifies the version of the WebSphere Application Server on which the web server is defined.




Status

Indicates whether the web server is started, stopped, or unavailable.

If IBM HTTP Server is defined on an unmanaged node, you must start the IBM HTTP Server administration server before you can start and stop IBM HTTP Server.

If the status is unavailable, the node agent or IBM HTTP Server administration server is not running in that node, and you must start the node agent before you can start the web server.

Table 2. Status indicators. The following table describes the status indicators.

	Started	The web server is running.
	Stopped	The web server is not running.
	Unknown	Status cannot be determined. A web server with an unknown status might, in fact, be running but has an unknown status because the application server that is running the administrative console cannot communicate with this web server.

Web server configuration

Use this page to configure web server properties.

Web servers:

To view this administrative console page click **Servers > Server Types > Web Servers > web_server_name**.

Web server name

Specifies a logical name for the web server.

Type

Specifies the vendor of the web server. The default value is IBM HTTP Server.

The options for the type of web servers are:

- IHS
- APACHE
- IIS
- SUNJAVASYSTEM
- DOMINO

Port	<p>The port from which to ping the status of the web server. This field is required.</p> <p>You can use the WebSphere Application Server administrative console to check if the web server is started by sending a ping to attempt to connect to the web server port that is defined. In most cases the port is 80. If you have a firewall between the web servers and application servers, you will not use port 80 on the firewall between the two systems. In most cases, your port will be different, such as 9080 or 9443. You should set the alternate ports for the web server using the WebSphere Application Server administrative console, then set that port to the web server to listen on, in addition to the typical port 80 and 443.</p>
Installation path	<p>Enter the fully qualified path where the web server is installed. This field is required if you are using IBM HTTP Server. For all other web servers, this field is not required. If you enable any administrative function for non-IBM HTTP Server Web servers, the installation path will be necessary.</p>
Configuration file name	<p>There are two ways to view or modify the contents of the configuration file:</p> <ol style="list-style-type: none"> 1. Click Edit to view the configuration file. You will be able to make modifications from this view. This is valid for IBM HTTP Server only. 2. Click Configuration file under Additional properties. You will be able to make modifications from this view. This is valid for IBM HTTP Server only.
Service name - Microsoft Windows operating systems only	<p>Specifies the Microsoft Windows operating system name for the Web server. The name is the service name and you can find it by opening the General properties tab of the web server service name.</p>

Checking your IBM HTTP Server version

At times, you might need to determine the version of your IBM HTTP Server installation.

About this task

The following information describes how you can determine the IBM HTTP Server version and provides examples. The server versions that are provided in the output below are not necessarily the versions that are distributed with WebSphere Application Server.

Procedure

1. Change the directory to the installation root of the Web server.
2. Find the subdirectory that contains the executable. The executable for IBM HTTP Server is:
 - APACHEDFT
3. Issue the command with the -v option to display the version information.

Run the STRTCPSVR command with the -v option to display the version information.

```
STRTCPSVR SERVER(*HTTP) HTTPSVR(APACHEDFT '-V')
```

Results

This web server is not a part of WebSphere Application Server, but is distributed with IBM i. The version depends on the i/5OS release. The version is shown in the "Server version" field and will look something like the following:

i 6.1:
Server version: Apache/2.2.11 (i5)
Server built: Jul 21 2009 19:24:31

i7.1:
Server version: Apache/2.2.11 (i5)
Server built: Oct 7 2009 21:04:27

Web server log file

Use this page to view the log file for your web server.

To view this administrative console page, click **Servers > Server Types > Web Servers > *web_server_name* > Log file**.

Web server log file configuration:

Access log file name	Any request that is made to the web server displays in this file.
Error log file name	Any error that occurs in the web server displays in this file.

Web server log file runtime:

Access log file name	Click View to display the contents of this file.
Error log file name	Click View to display the contents of this file.

Web server custom properties

Use this page to view and manage arbitrary name-value pairs of data, where the name is a property key and the value is a string value that can be used to set internal system configuration properties.

The administrative console contains several Custom Properties pages that work similarly. To view one of these administrative pages, click a Custom Properties link.

Web servers:

To view this administrative console page click **Servers > Server Types > Web Servers > *web_server_name* > Custom properties**.

Name	Specifies the name (or key) for the property.
Value	Specifies the value paired with the specified name.
Description	Provides information about the name-value pair.

Compensation service custom properties

You can specify additional settings for the compensation service through setting a custom property.

Complete the following steps to set a custom property for the compensation service.

1. Start the administrative console.
2. In the navigation pane, click **Servers > Server Types > WebSphere application servers > *server_name* > [Container Settings] Container Services > Compensation Service > [Additional Properties] Custom Properties**.
3. Click **New**.
4. On the settings page, enter the property that you want to configure in the **Name** field and the value that you want to set it to in the **Value** field.
5. Click **Apply** or **OK**.

6. Click **Save** to save your changes to the master configuration.
7. Restart the server.

You can use the custom properties page to define the following compensation service custom property:

- “Suppressing the compensation service”

Suppressing the compensation service: Not all web servers are configured to handle SOAP messages containing CoordinationContext elements. You can use WebSphere Application Server to configure a custom property for the compensation service which processes a predefined list of Enterprise Java Beans for which no CoordinationContext should be sent on web service requests.

When the compensation service is used, CoordinationContext elements are included in the outgoing SOAP header. For example:

```
<wscoor:CoordinationContext soapenv:mustUnderstand="1"
...
</wscoor:CoordinationContext>
```

If such a SOAP message is received by a web server which is not configured to process CoordinationContext elements, an exception message is produced. See the following example:

```
Header block local name 'CoordinationContext' is not defined.
```

You can construct a file containing a list of all Enterprise Java Beans which should not send the CoordinationContext element in web service requests. This file must be in plain text format and must contain one entry per line, in the following format:

```
application_name#module#bean
application_name#module#bean
application_name#module#bean
```

Here application_name is the name of the application as known on the server; module is the name of the Enterprise Java Bean jar; and bean is the name of the Enterprise Java Bean.

Note: This file must only contain entries for beans not configured to use the compensation service. This custom property will not be effective for any beans listed in the file which have compensation service metadata associated with them.

Name	Value
SUPPRESS_CSCOPE_ON_WS_CALLS	The fully qualified file name

Remote web server management

Use this page to configure a remote IBM HTTP Server web server.

To view the administrative console page for Remote web server management, click **Servers > Server Types > Web Servers > web_server_name > Remote web server management**.

Note: For a WebSphere Application Server, Network Deployment configuration, click **System Administration > Nodes > Add node** to create a new, unmanaged node. Then click **Servers > Web Servers > New** to create a web server using the newly-created unmanaged node.

Web servers:

Port	Indicates the port to access the administration server (default is 8008).
Use SSL	The HTTP administration server port is 2001 on IBM i. Specifies if the port is secure.

User ID

Specifies a user ID in the `<install_dir>/conf/admin.passwd` file. Create this with the `htpasswd` script file, located in the `<install_dir>/bin` directory.

Password

Specifies a password in the `<install_dir>/conf/admin.passwd` file. Create this with the `htpasswd` script file, located in the `<install_dir>/bin` directory.

On IBM i, there is no `htpasswd` script in the `<install_dir>/bin` directory. The HTTP administrator is typically created as an IBM i SECOFR profile.

Web server configuration file

Use this page to view or modify the contents of the Web server configuration file in your web browser. To view this administrative console page click **Servers > Server Types > Web Servers > *web_server_name***. Under **Additional Properties**, click **Configuration File**.

Web servers:

If you have made changes to the configuration file you will need to restart your web server, in order for the changes to take effect.

Global directives

Use this page to configure the global directives for your web server.

To view this administrative console page, click **Servers > Server Types > Web Servers > *web_server_name* > Global directives**.

Security enabled:

Specifies if security is enabled in your web server.

Key store certificate alias:

If the **Security enabled** box is checked, specify the key store certificate alias.

Server name:

Specifies the hostname that the web server uses to identify itself.

Listen ports:

Specifies the port on which your web server will listen for requests.

Document root:

The directory where the web server will serve files.

Key store name:

Specifies the name you have assigned to your keystore. A button is also provided to **Manage keys and certificates**.

Target key store directory and file name:

Specifies the target directory and file name of your keystore on the machine where the web server is installed. A button is also provided to **Copy to web server key store directory**.

SSL Version 2 timeout:

Specifies the SSL Version 2 timeout.

SSL Version 3 timeout:

Specifies the SSL Version 3 timeout.

Web server virtual hosts collection

Use this page create or edit virtual hosts for your Web server.

To view this administrative console page, click **Servers > Server Types > Web Servers > *web_server_name* > Configuration settings > Virtual hosts.**

To create a new virtual host, click the **New** button to launch the virtual host configuration panel. To delete an existing virtual host, select the check box beside the virtual host in the list and click **Delete** .

IP address:Port:

The IP address and port number of your virtual host for the specified web server.

Server name:

Specifies the name of your virtual host for the specified web server.

Security enabled:

Specifies whether or not security is enabled for your virtual host for the specified web server. The values are **true** or **false**.

Web server virtual hosts detail

Use this page create or edit virtual hosts for your Web server.

To view this administrative console page, click **Servers > Server Types > Web Servers > *web_server_name* > Configuration settings > Virtual hosts > New.**

Security enabled:

Specifies whether or not security is enabled for your virtual host for the specified web server. Check the box to enable security

IP address:

The IP address of your virtual host for the specified Web server.

Port:

The port number of your virtual host for the specified web server.

Server name:

Specifies the name of your virtual host for the specified web server.

Document root:

Specifies the location of the htdocs directory for your web server.

Keystore filename:

Specifies the name you have assigned to your keystore.

Keystore directory:

Specifies the target directory for the key store file on the machine where your web server is installed.

Keystore certificate label:

Specifies the keystore certificate label. The certificate label specified here is the certificate that used in secure communication for this virtual host.

Editing the web server type

This topic provides information on how to change the type of Web server.

About this task

If you install a web server that is different from the one that is currently installed, you can modify the web server type from IBM HTTP Server to a non-IBM HTTP Server and vice versa, rather than delete the web server and create a new web server definition. If you change the web server type from IBM HTTP Server to non-IBM HTTP Server web server, the administration capabilities are lost accordingly.

Procedure

1. From the WebSphere Application Server administrative console, click **Servers > Server Types > Web servers**.
2. Select the server that you want to modify.
3. On the web server configuration panel, change your web server by selecting an option from the Type drop-down menu. If you are changing from a non-IBM HTTP Server to an IBM HTTP Server, you are also prompted for information such as IBM HTTP Server administration server port, user ID, and IBM HTTP Server administration server password.
4. Click **Apply**.

Results

You can verify your changes on the web servers collection panel. The web server type displays in the Web Server Type column.

Web server plug-ins

Web server plug-ins enable the web server to communicate requests for dynamic content, such as servlets, to the application server. A web server plug-in is associated with each web server definition. The configuration file (plugin-cfg.xml) that is generated for each plug-in is based on the applications that are routed through the associated web server.

A web server plug-in is used to forward HTTP requests from a supported web server to an application server. Using a web server plug-in to provide communication between a web server and an application server has the following advantages:

- XML-based configuration file
- Standard protocol recognized by firewall products
- Security using HTTPS, replacing proprietary Open Servlet Engine (OSE) over Secure Sockets Layer (SSL)

Each of the supported web server plug-ins runs on a number of operating systems. See the Supported Hardware and Software website for the product for the most current information about supported web servers. This site is located at <http://www.ibm.com/support/docview.wss?rs=180&uid=swg27006921>.

gotcha: The default behavior for the web server plug-in is to buffer requests up to 64 kilobytes, and retry the requests if there is no response from the application server. If you want to ensure high availability, and your HTTP requests tend to be large, set the **Maximum buffer size used when reading HTTP request content** property on the web server plug-in request routing property page in the administrative console to -1. Setting this property to -1 removes the maximum buffer size limit, and enables the web server plug-in to buffer all requests regardless of their size. Requests are retried if the request body fits within the buffer size. If you want to disable all request buffering, and thereby disable retries of requests with request bodies, you can set this property to 0.

Affinity requests

Affinity requests are requests that contain a JSESSIONID. Session affinity means that all requests of the same JSESSIONID are sent to the same application server. For example, if the first request is sent to clone5, then the next affinity request from that same browser is also sent to clone5 regardless of the weight valued specified for the LoadBalanceWeight property in the plugin-cfg.xml file.

If you select Round robin for the **Load balancing option** Web server plug-in request routing property, and leave the IgnoreAffinityRequests property in the plugin-cfg.xml file set to its default value of true, the affinity requests do not lower the weight. This behavior might cause an uneven distribution of requests across the servers in environments that make use of session affinity. Setting the IgnoreAffinityRequests property to false causes the weight to be lowered every time an affinity request is received, which results in a more balanced round robin environment.

If you select Random for the **Load balancing option** property, affinity requests are still sent to the same cloneid, but new requests are routed randomly, and the value specified for the LoadBalanceWeight property is ignored.

Failover

If a request connection exceeds the time limit specified on the ConnectTimeout property in the plugin-cfg.xml file, or a 5xx error is returned from the application server, the web server plug-in marks the server as down, and attempts to connect to the next application server in the list of primary servers that is specified for the PrimaryServers property in the plugin-cfg.xml file. If the web server plug-in successfully connects to another application server, all requests that were pending for the down application server are sent to this other application server. All other new and affinity requests are sent to other servers, based on whether round robin or random is the setting for the **Load balancing option** Web server plug-in request routing property.

Failover typically does not occur the first time that the time limit specified on the ServerIOTimeout property in the plugin-cfg.xml file is exceeded for either a request or a response. Instead, the web server plug-in tries to resend the request to the same application server, using a new stream. If the time specified on the ServerIOTimeout property is exceeded a second time, the web server plug-in marks the server as down, and initiates the failover process.

gotcha: Sending a large number of pending requests to the same application server might impact the performance of that application server if a failover situation occurs. You can use the MaxConnections property to limit the number of requests that might be pending for an application server.

Running multiple web server child processes

You can configure most web servers to start multiple child processes. In this situation, each child process loads its own instance of the web server. When running multiple web server child processes, remember that:

- Multiple running instances of the web server plug-in cannot share information. Therefore the dynamically changing load balance weight of each application server is not shared between the web server plug-in instances. For example, one instance of the web server plug-in might consider an application server to be running with a weight of 5, while another instance of the web server plug-in might be consider the same application server to be down and unusable. This difference in perspective might cause an incoming request to be handled differently, depending on which web server plug-in instance handles the request.
- The web server plug-in settings are handled on a per instance basis. For example, the MaxConnections property specifies the number of pending requests that are allowed on that web server, for each web server plug-in instance. If the MaxConnections property is set to 20, and you start three web server child processes, each of the three web server plug-in instances allow 20 pending connections to the same application server, which means that there could be up to 60 pending connections.

Selecting a front end for your WebSphere Application Server topology

You can use either a web server plug-in, a WebSphere Application Server proxy server, or a DMZ Secure Proxy Server for IBM WebSphere Application Server to provide session affinity, failover support, and workload balancing for your WebSphere Application Server topology.

After you install the product, you can set up either a web server plug-in, a WebSphere Application Server proxy server, or a DMZ Secure Proxy Server for IBM WebSphere Application Server to establish communication between an application and a remote client.

- A WebSphere Application Server web server plug-in provides an interface between a web server and an application server. The web server plug-in determines the server to which a client request for dynamic content, such as servlets, needs to be routed.
- A WebSphere Application Server proxy server is a specific type of application server that routes HTTP requests to content servers that perform the work. The WebSphere Application Server proxy server can be the initial point of entry for requests to servers in your enterprise environment. However, because a WebSphere Application Server proxy server is not safe for DMZ deployment, a WebSphere Application Server proxy server is typically fronted by a web server, or used in internal only environments where stringent host security requirements are not required.
- A DMZ Secure Proxy Server for IBM WebSphere Application Server is a WebSphere Application Server proxy server that is designed specifically to be safely installed on a stand-alone node in a demilitarized zone (DMZ). If you require the function of the WebSphere Application Server proxy server, and want to deploy it to the DMZ, you should use a DMZ Secure Proxy Server for IBM WebSphere Application Server to provide session affinity, failover support, and workload balancing for your WebSphere Application Server topology.

The DMZ is a safe zone between firewalls that is typically located between a client and a backend server. A DMZ Secure Proxy Server for IBM WebSphere Application Server accepts requests from clients on the Internet, and forwards the requests to servers in your enterprise environment.

You can also use the on demand router (ODR), that is provided with the WebSphere eXtended Deployment product, as a reverse proxy between an HTTP client and a clustered application, or a partitioned application. See the WebSphere eXtended Deployment Information Center at <http://publib.boulder.ibm.com/infocenter/wxsinfo/v7r0/index.jsp> for more information about using ODR.

The traditional topology, using your web server of choice and the corresponding web server plug-in, is recommended unless:

- You want to use specific features of the ODR or a WebSphere Application Server proxy server.

- You want to use another function, such as Session Initiation Protocol (SIP) or WS-Addressing affinity/failover, which requires a WebSphere Application Server proxy server.

The following tables compare the core application server frontend functionality, and the non-core functionality of a web server plug-in running in a modern web server, such as the IBM HTTP Server, based on Apache HTTP Server, a WebSphere Application Server proxy server, and a DMZ Secure Proxy Server for IBM WebSphere Application Server.

Table 3. Core functionality. This table compares the functionality that a web server plug-in, a WebSphere Application Server proxy server, and a DMZ Secure Proxy Server for IBM WebSphere Application Server provide.

Functionality	Web server plug-in used with either the IBM HTTP Server or the Apache Web Server	WebSphere Application Server proxy server	DMZ Secure Proxy Server for IBM WebSphere Application Server
Session affinity	Yes	Yes ^{1, 2}	Yes ^{1, 2}
DMZ ready	Yes	No	Yes
Custom advisors are supported	No	Yes	Yes
Service Level Agreement (SLA)	No	No	No
QoS/Throttling	No	No	No
SIP proxy	No	Yes	Yes
ESI dynamic Caching	Yes	Yes ³	Yes ³
Managed from the administrative console	Yes	Yes	Yes ⁴
Stream caching (large response caching)	Yes	Yes	Yes
Dynamically receive management events ⁵	No	Yes	Yes ⁶
Multi cells routing	No	Yes ⁷	Yes ⁸
Performance monitoring	Yes ⁹	Yes ¹⁰	Yes ¹⁰
Load Balancing (weighted round-robin)	Yes ¹¹	Yes ¹¹	Yes ¹¹
Routing rules are configurable	No ¹²	Yes	Yes
Interoperability with WLM	Yes ¹³	Yes ¹⁴	Yes
Web service affinity and failover	No	Yes ¹⁵	No
Rule expression and custom routing	No	Yes ¹⁶	Yes ¹⁵
Generic server cluster (GSC) affinity and failover	No	Yes ¹⁷	Yes ¹⁶

Table 3. Core functionality (continued). This table compares the functionality that a web server plug-in, a WebSphere Application Server proxy server, and a DMZ Secure Proxy Server for IBM WebSphere Application Server provide.

Functionality	Web server plug-in used with either the IBM HTTP Server or the Apache Web Server	WebSphere Application Server proxy server	DMZ Secure Proxy Server for IBM WebSphere Application Server
Table notes:			
<ol style="list-style-type: none"> 1. Session affinity is supported for WebSphere Application Server managed resources. However, some session management custom properties, such as HttpSessionCloneld, are not supported. 2. For generic server routing, where the resources are not WebSphere Application Server managed resources, active session affinity and passive session affinity need to be configured under generic server routing action. 3. WebSphere Application Server proxy servers and DMZ Secure Proxy Servers for IBM WebSphere Application Server do not support fragment caching. Only whole page caching, and the ESI invalidation servlet are supported. 4. Secure proxy profile on a DMZ installation can only be managed using scripting or an administrative agent. Configuration-only secure proxy profile can be managed through scripting or the administrative agent console. If you use an administrative agent console, you must register a proxy profile with the administrative agent. 5. As performed by ODR in a WebSphere Extended Deployment environment. 6. Static routing needs to be turned off and core group bridge tunneling needs to be enabled for both the DMZ Secure Proxy Server for IBM WebSphere Application Server, and the core group bridge interface for the WebSphere Application Server, Network Deployment cells. 7. Requires core group bridge setup between the proxy cell and other cells. 8. Static routing needs to be turned off and core group bridge tunneling needs to be enabled for both the DMZ Secure Proxy Server for IBM WebSphere Application Server, and the core group bridge interface for the WebSphere Application Server, Network Deployment cells. 9. The web server plug-in statistics are obtained from request metrics. 10. WebSphere Application Server proxy server statistics and DMZ Secure Proxy Server for IBM WebSphere Application Server statistics can be retrieved from Tivoli performance viewer, ARM, and performance mBeans. 11. Random Load balancing is supported in addition to weighted round robin. 12. Web server plug-in can only do static routing. 13. A web server plug-in indirectly has interoperability with WLM through the exchange of dynamic workload manager (DWLM) Partition Tables between the web server plug-in and WebSphere Application Server. The plug-in uses these tables for dynamic routing and failover scenarios within a cluster. 14. The proxy server uses the WebSphere Application Server WLM even if the proxy server is running on a z/OS operating system. 15. The DataPower appliance manager provides faster web service affinity and failover service than Java proxy provides. 16. Rule expression and custom routing allows administrators to override default WebSphere Application Server routing behavior. For example, you might not want requests forwarded to server1 in a cluster between 11:00 PM and 12:00 PM because you regularly apply maintenance to that server during that time interval. 17. Proxy server supports load balancing and failover for generic server clusters with passive and/or active affinity. 			

Table 4. Functionality provided outside of the web server plug-in. This table provides a comparison of the functionality that a typical web server, that is hosting a web server plug-in, a WebSphere Application Server proxy server, and a DMZ Secure Proxy Server for IBM WebSphere Application Server provide outside of the core application server frontend functionality. See your web server documentation for a complete description of the functionality that your particular web server provides.

Functionality	Web server plug-in used with either the IBM HTTP Server or the Apache Web Server	WebSphere Application Server proxy server	DMZ Secure Proxy Server for IBM WebSphere Application Server
Common Gateway Interface (CGI)	Yes	No	No

Table 4. Functionality provided outside of the web server plug-in (continued). This table provides a comparison of the functionality that a typical web server, that is hosting a web server plug-in, a WebSphere Application Server proxy server, and a DMZ Secure Proxy Server for IBM WebSphere Application Server provide outside of the core application server frontend functionality. See your web server documentation for a complete description of the functionality that your particular web server provides.

Functionality	Web server plug-in used with either the IBM HTTP Server or the Apache Web Server	WebSphere Application Server proxy server	DMZ Secure Proxy Server for IBM WebSphere Application Server
Request URI rewriting	Yes	No	No
Efficient static file serving	Yes	Basic ¹	Basic ¹
Compression	Yes	Yes	Yes
Response filtering	Yes	Yes ²	Yes ²
SSL termination	Yes	Yes	Yes
Cryptographic Accelerator ³	Yes	Yes ⁴	Yes ⁴
FIPS	Yes	Yes	Yes
Third-party/customer-written plug-ins	Yes	No	No
Logging	Yes	Yes ⁵	Yes ⁵
Custom Logging	Yes	No	No
Disk caching	Yes	Yes	Yes
Asynchronous request handling	none or partial ⁶	Yes ⁷	

Table notes:

1. WebSphere Application Server proxy servers support basic static file serving.
2. WebSphere Application Server proxy servers support HTML link rewriting.
3. This functionality only applies to Cryptographic Accelerators that WebSphere Application Server supports. See the Supported hardware and software web page .
4. The support is provided by IBM JDK/JCE.
5. Only NCSA common format is supported.
6. The connection between a web server plug-in and an application server is synchronous and consumes a thread while reading/writing or waiting for data. See your web server documentation for information about how your particular web server handles client connections.
7. Proxy server is optimized to handle AJAX long polling requests under large scale deployments.

Web server plug-in connections

The web server plug-ins are used to establish and maintain persistent HTTP and HTTPS connections to application servers.

When the plug-in is ready to send a request to the application server, it first checks its connection pool for existing connections. If an existing connection is available the plug-in checks its connection status. If the status is still good, the plug-in uses that connection to send the request. If a connection does not exist, the plug-in creates one. If a connection exists but has been closed by the application server, the plug-in closes that connection and opens a new one.

After a connection is established between a plug-in and an application server, it will not be closed unless the application server closes it for one of the following reasons:

- If the **Use Keep-Alive** property is selected and the time limit specified on the **Read timeout** or **Write timeout** property for the HTTP inbound channel has expired.

- The maximum number of persistent requests which can be processed on an HTTP inbound channel has been exceeded. This number is set using the **Maximum persistent requests** property that is specified for the HTTP inbound channel.
- The Application Server is shutting down.

Even if the application server closes a connection, the plug-in will not know that it has been closed until it tries to use it again. The connection will be closed if one of the following events occur:

- The plug-in receives a new HTTP request and tries to reuse the existing connection.
- The number of httpd processes drop because the web server is not receiving any new HTTP requests. For the IBM HTTP Server, the number of httpd processes that are kept alive depends on the value specified on the web server's MinSpareServers directive.
- The web server is stopped and all httpd processes are terminated, and their corresponding sockets are closed.

gotcha: Sometimes, if a heavy request load is stopped or decreased abruptly on a particular application server, a lot of the plug-in's connections to that application server will be in CLOSE_WAIT state. Because these connections will be closed the first time the plug-in tries to reuse them, having a large number of connections in CLOSE-WAIT state should not affect performance

Web server plug-in remote user information processing

You can configure your web server with a vendor-acquired authentication module and then configure the web server plug-in to route requests to an application server.

If an application calls the getRemoteUser method, it relies on a private HTTP header that contains the remote user information and is parsed by the plug-in. The plug-in sets the private HTTP header value whenever a web server authentication module populates the remote user in the web server data structure. If the private HTTP header value is not set, the call to getRemoteUser method by the application returns a null value.

- In the case of an Apache Web Server or the IBM HTTP Server, the plug-in builds the private header from the information contained in the associated request record.
- In the case of a Sun One Web Server, the plug-in builds the private header from the information contained in the **auth_user** property associated with the request. The private header is usually set to the name of the local HTTP user of the web browser, if HTTP access authorization is activated for the URL.
- In the case of a Domino Web Server, the plug-in builds the private header from the information contained in the **REMOTE_USER** environment variable. The plug-in sets this variable to **anonymous** for users who have not logged in and to the *username* for users who are logged into the application.
- In the case of an Internet Information Services (IIS) Web Server, the plug-in builds the private header from the information contained in the **REMOTE_USER** environment variable. The plug-in sets this variable to the name of the user as it is derived from the authorization header sent by the client.

Note: If the private header is not being set in the Sun One, IIS, or Domino Web Server plug-in, make sure the request record includes information about the user requesting the data.

Note: If an call to getRemoteUser method by the application returns a null value, or if the correct remote user information is not being added to the data structure for the web server plug-in, make sure the remote user parameter within the vendor-acquired authentication module is still set to **YES**. (Sometimes this parameter gets set to **NO** when service is applied.)

Private headers

A web server plug-in can use private headers to forward requests for dynamic content, such as servlets, to the application server.

After you configure a web server plug-in, in addition to regular plug-in functions, you can use private headers as a mechanism for forwarding proxy information from the plug-in to an application server. This information is not normally included in HTTP requests.

Private headers are implemented as a set of HTTP request header name and value pairs that the plug-in adds to the HTTP request header before the request is forwarded to an application server. The application server's web container removes this information from the header and then processes this information.

Private headers can include such information as the remote (client) user, the remote (client) host name, or an SSL client certificate. They conform to a naming standard so that there is no namespace collision with the architected HTTP header fields.

For example, authentication information, such as a client certificate, is normally requested by the web server once during the establishment of an HTTP session. It is not required again for individual requests within that session. However, a client certificate must accompany each request forwarded to the application server. The application server can then use the certificate as needed.

Similarly, the web server examines TCP/IP socket connections for information about the host address of the client. The application server cannot perform this examination because its socket connection is with the plug-in and not with the actual client. Therefore, one of the private headers is the host address of the actual client.

Gskit install images files

The Global Security Kit (GSKit) installation image files for the WebSphere Web server plug-ins are packaged on the CD with the web server plug-in files.

You can download the appropriate GSKIT file to the workstation on which your web server is running.

The Global Security Kit (GSKit) installation images files for the WebSphere Web Server Plug-ins are provided as a "local install" and are not installed globally nor are registered with the native package management utilities.

Plug-ins: Resources for learning

Use the following links to find relevant supplemental information about web server plug-ins. The information resides on IBM and non-IBM Internet sites, whose sponsors control the technical accuracy of the information.

These links are provided for convenience. Often, the information is not specific to the IBM WebSphere Application Server product, but is useful all or in part for understanding the product. When possible, links are provided to technical papers and Redbooks® that supplement the broad coverage of the release documentation with in-depth examinations of particular product areas.

View links to additional information about:

- Programming model and decisions
- Programming instructions and examples

Programming model and decisions

- Best Practice: WebSphere Plug-in Configuration Regeneration at http://www-128.ibm.com/developerworks/websphere/library/bestpractices/plug_in_configuration_regeneration.html

Programming instructions and examples

- WebSphere Application Server education at <http://www-128.ibm.com/developerworks/search/searchResults.jsp?searchType=1&searchSite=dW&searchScope=dW&query=WebSphere+education>
- Listing of all IBM WebSphere Application Server Redbooks at <http://publib-b.boulder.ibm.com/Redbooks.nsf/Portals/WebSphere>

Installing and configuring web server plug-ins

WebSphere Application Server supplies a unique binary plug-in module for each supported web server. The plug-in configuration file, which the WebSphere Application Server products create and maintain, interacts with the binary module to provide information about the application server configuration to the web server. The web server uses the information to determine how to communicate with the application server.

Before you begin

trns: In WebSphere Application Server Version 7 and earlier, you use the Plug-ins installation wizard to install the plug-in module, configure the web server for communicating with the application server, and create a web server configuration definition in the application server if possible. In WebSphere Application Server Version 8 and later, you must first install the Web Server Plug-ins, the web server, and the WebSphere Customization Toolbox; then, you run the Web Server Plug-ins Configuration Tool that is contained in the toolbox to configure the web server to communicate with the application server and, if possible, create a web server configuration definition in the application server. If you know how to set up your initial web server and plug-in configuration manually, you can do so in Version 7 and Version 8.

Go to <http://www-1.ibm.com/support/docview.wss?rs=180&context=SSEQTP&uid=swg21160581> for information about how to verify what Version 4.0 through Version 8.0 plug-in versions are installed on local or remote web servers and how to determine if the installation complies with supported configurations.

You must install a supported web server before you can install and configure a plug-in for the web server.

About this task


This article describes installing and configuring web server plug-ins for WebSphere Application Server. WebSphere Application Server products supplies a unique binary plug-in module for each supported web server. The plug-in configuration file, which the WebSphere Application Server products create and maintain, interacts with the binary module to provide information about the application server configuration to the web server. The web server uses the information to determine how to communicate with the application server.

Select one of the following topology scenarios and follow the steps below the diagram to install the plug-in and configure both the web server and the application server.


Procedure

- **Scenario 1: Local application server profile** The application server and the web server are on a single system or logical partition.


A local distributed installation includes the Web server plug-in, the web server, and a *managed* application server on the same system:



- **Scenario 2: Remote** The application server and the web server are on separate machines or logical partitions.




- **Scenario 3: Remote** Multiple standalone application servers are on one system, and each application server has a dedicated web server on a separate system or logical partition.




- **Scenario 4: Local custom profile** A managed node and the web server are on the same system or logical partition.

A local distributed installation includes the web server plug-in, the web server, and the managed custom node on the same system:



- **Scenario 5: Local deployment manager profile** A deployment manager node and the web server are on a single system or logical partition.

A local distributed installation includes the web server plug-in, the web server, and the application server on the same system:



Results

You can install a web server and the web server plug-ins for various standalone application server topologies by following the procedures described in this article.

What to do next

See “Selecting a web server topology diagram and roadmap” for an overview of the installation procedure.

Selecting a web server topology diagram and roadmap

Install and configure the Web Server Plug-ins to allow the application server to communicate with the web server.

Before you begin


The primary production configuration for a web server is an application server on one machine and a web server on a separate machine. This configuration is referred to as a *remote* configuration. Contrast the remote configuration to the local configuration, where the application server and the web server are on the same machine.

Procedure

- **Set up a remote web server installation for a standalone node.**

The remote web server configuration is recommended for production environments.

The remote installation installs the web server plug-in on the web server machine when the application server is on a separate machine, such as shown in the following graphic:



Remote installation scenario

Table 5. Installation and configuration. Remote installation scenario

Step	Machine	Task
1	A	Install your WebSphere Application Server product.
2	A	Create an application server profile.
3	B	If you plan to run IBM HTTP Server on IBM i, it is already installed as product 5761-DG1 or 5770-DG1. You can also use a Domino Web Server on IBM i. Refer to the Domino documentation for installation instructions. For either scenario, you must install the Web Server Plug-ins component of the WebSphere Application Server product.
4	B	Run the manageprofiles Qshell command to create an http profile. For example, run this command from Qshell: <pre>app_server_root/bin/manageprofiles -create -profileName myHttpProfile -templatePath http</pre> The <i>myHttpProfile</i> variable is the name of the profile.

Table 5. Installation and configuration (continued). Remote installation scenario

Step	Machine	Task
5	B	<p>Configure the IBM HTTP Server with your http profile myHttpProfile.</p> <p>If your web server's name is MyWebServer., an IBM i qshell script called <i>configureIHS_MyWebServer</i> is created in the <i>myHttpProfile_profile_root/config/IHS_myWebServer</i> directory on Machine B. For the default WebSphere Application Server install, the <i>myHttpProfile_profile_root</i> of the profile myHttpProfile is <i>/QIBM/UserData/WebSphere/AppServer/V61/Base/profiles/myHttpProfile</i>.</p> <p>Note: In the remainder of this example, <i>webServerName</i> refers to <i>IHS_myWebServer</i>. If you choose to configure a DOMINO web server as listed below, then <i>webServerName</i> refers to <i>DOMSRV01</i>.</p> <p>The following steps apply to DOMINO web servers only:</p> <ol style="list-style-type: none"> 1. Run the <i>configureOs400WebServerDefinition</i> script on the http profile myHttpProfile. For example: <pre>configureOs400WebServerDefinition -profileName myHttpProfile -websvr.name DOMSRV01 -websvr.type DOMINO -websvr.port 80</pre> 2. Using the WRKDOMSVR command to update the notes.ini file of your Domino server, insert the following directive: <i>WebSphereInit=myHttpProfile_profile_root/config/DOMSRV01/plugin-cfg.xml</i> 3. From the Lotus Notes® client connected to the Domino server, click the internet protocols tab and then click the HTTP tab. Under DSAPI filter names add the following: <i>/QSYS.LIB/ product_lib.LIB/LIBDOMINO.SRVPGM</i> 4. Save your changes
6	A	Copy the <i>configurewebServerName</i> script from Machine B to Machine A. The script is found in the <i>myHttpProfile_profile_root/config/webServerName</i> directory described above
7	A	Place the file you copied from the previous step into the <i>profile_root/bin</i> directory on Machine A, where <i>profile_root</i> is the directory where your application server profile is located.
8	A	<p>Start the application server and then run the script that you copied in the previous step.</p> <p>For example, run these commands from Qshell:</p> <pre>app_server_root/bin/startServer -profileName myProfile</pre> <pre>cd profile_root/bin</pre> <pre>./configurewebServerName [wasAdminUserId] [wasAdminPassword]</pre> <p>Note: <i>wasAdminUserId</i> and <i>wasAdminPassword</i> are optional and only needed when the application server of <i>myProfile</i> is running in secure mode.</p>
9	A	<p>If you use IBM HTTP Server on IBM i, verify that the application server is running. Open the administrative console (ISC) and do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers. 2. Select your web server, in this case it is <i>IHS_MyWebServer</i>, then click Remote web server management 3. Enter the user ID and password used to authenticate to Machine B. The authorities required by this profile are the same as that required to access the HTTP administration GUI. For details, see User profiles and required authorities for HTTP Server in the IBM i Information Center. 4. Save your configuration.
10	A	Configure a virtual host alias for the web server machine (B) and web server port of MyWebServer.
11	A	Stop and restart your application server.
12	A	<p>In the administrative console (ISC) do the following:</p> <ol style="list-style-type: none"> 1. Select <i>webServerName</i> and click Generate Plug-in to generate the plugin-cfg.xml file. 2. Select <i>webServerName</i> and click Propagate Plug-in to propagate the plugin-cfg.xml file to Machine B.
13	B	<p>If you use IBM HTTP Server on IBM i, start the web server. Open the administrative console (ISC) and do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers. 2. Select your web server, in this case it is <i>IHS_MyWebServer</i>, then click Start. <p>If you use Domino HTTP Server on IBM i, start the web server from a CL command line:</p> <ol style="list-style-type: none"> 1. Run the Work with Domino Servers (WRKDOMSVR) command. 2. Specify option 1 next to your Domino server. 3. Press Enter.
14	B	<p>Run the Snoop servlet. Access the following URL in your browser:</p> <pre>http://host_name_of_machine_B:http_transport_port/Snoop</pre> <p>If you get an error, retrace your steps. Add a virtual host to Machine A before restarting the application server on Machine A.</p>

Regeneration of the plugin-cfg.xml file

The web server plug-in configuration service regenerates the plugin-cfg.xml file automatically.

However, if the service is disabled or if you want to force regeneration, use the administrative console or the GenPluginCfg script. In the administrative console, perform these steps:

1. Expand **Servers > Server Types > Web servers** .
2. Select the web server for which you want to regenerate the plugin-cfg.xml file.
3. Click **Generate Plugin**.


Propagation of the plugin-cfg.xml file

The plugin-cfg.xml file can be propagated manually. Manual propagation of the plugin-cfg.xml file is required for DOMINO web servers. Copy the plugin-cfg.xml file from the application server machine to the myHttpProfile_profile_root/config/IHS_MyWebServer directory on the web server Machine B. The plugin-cfg.xml file is generated in the directory named profile_root/config/cells/cell_name/nodes/host_name_of_machine_B-node/servers/IHS_myWebServer on the application server Machine A.

- **Set up a local web server configuration for a standalone node.**

The local web server configuration is recommended for a development or test environment.

A local installation includes the web server plug-in, the web server, and the Application Server on the same machine:



Local installation scenario

Table 6. Installation and configuration. Local installation scenario

Step	Machine	Task
1	A	Install your WebSphere Application Server product.
2	A	Create an application server profile.
3	A	IBM HTTP Server on IBM i is already installed as product 5761-DG1 or 5770-DG1. Alternatively, you can also run Domino Web Server on IBM i. Refer to the Domino documentation for installation instructions.
4	A	<p>Configure the IBM HTTP Server with your WebSphere Application Server profile.</p> <p>The following steps apply to DOMINO web servers only. For these steps, assume your web server's name is <i>MyWebServer</i>.</p> <ol style="list-style-type: none"> 1. Run the <code>configureOs400WebServerDefinition</code> script on the application server profile. For example: <pre>configureOs400WebServerDefinition -profileName myAppServerProfile -webserver.name DOMSRV01 -webserver.type DOMINO -webserver.port 80</pre> 2. Configure a virtual host alias for the web server machine and web server port of DOMSRV01. 3. Using the <code>WRKDOMSVR</code> command to update the notes.ini file of your Domino server, insert the following directive: <pre>WebSphereInit=profile_root/config/cells/cell_name/nodes/node_name/ servers/DOMSRV01/plugin-cfg.xml</pre> 4. From the Lotus Notes client connected to the Domino server, click the Internet protocols tab, then click the HTTP tab. Under DSAPI filter names add the following: <code>/QSYS.LIB/ product_lib.LIB/LIBDOMINO.SRVPGM</code> 5. Save your changes

Table 6. Installation and configuration (continued). Local installation scenario

Step	Machine	Task
5	A	Stop and restart the application server.
6	A	<p>If you use IBM HTTP Server on IBM i, open the administrative console (ISC) do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers. 2. Select your web server, in this case it is <i>IHS_MyWebServer</i>, then click Remote web server management. 3. Enter the user ID and password used to authenticate to Machine A. The authorities required by this profile are the same as that required to access the HTTP administration GUI. For details, see User profiles and required authorities for HTTP Server in the IBM i Information Center. 4. Save your changes.
7	A	<p>In the administrative console (ISC) do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers. 2. If you use IBM HTTP Server on IBM i, Select <i>IHS_MyWebServer</i> and click Generate Plug-in to generate the plugin-cfg.xml file. 3. If you use Domino HTTP Server on IBM i, Select DOMSRV01 and click Generate Plug-in to generate the plugin-cfg.xml file.
8	A	<p>If you use IBM HTTP Server on IBM i, start the web server. Open the administrative console (ISC) and do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers. 2. Select your web server, in this case it is <i>IHS_MyWebServer</i>, then click Start. <p>If you use Domino HTTP Server on IBM i, start the web server from a CL command line:</p> <ol style="list-style-type: none"> 1. Run the Work with Domino Servers (WRKDOMSVR) command. 2. Specify option 1 next to your Domino server. 3. Press Enter.
9	A	<p>Run the Snoop servlet. Access the following URL in your browser:</p> <p><code>http://host_name_of_machine_A:http_transport_port/Snoop</code></p> <p>If you get an error, retrace your steps. Add a <i>virtual host</i> to Machine A before restarting the application server on Machine A.</p>

Regeneration of the plugin-cfg.xml file

The web server plug-in configuration service regenerates the plugin-cfg.xml file automatically.

However, if the service is disabled or you want to force regeneration, use the administrative console or the GenPluginCfg script. In the administrative console, perform these steps:

1. Expand **Servers > Server Types > Web servers**.
2. Select the web server for which you want to regenerate the plugin-cfg.xml file.
3. Click **Generate Plug-in**.


Propagation of the plugin-cfg.xml file

The local file does not require propagation.

- **Set up a remote web server configuration for a managed node.**

The remote web server configuration is recommended for production environments.

The remote distributed installation installs the web server plug-in on the web server machine when the application server is on a separate machine, such as shown in the following graphic:



Remote distributed installation scenario

Table 7. Installation and configuration. Remote distributed installation scenario

Step	Machine	Task
1	A	Install WebSphere Application Server Network Deployment.
2	A	Create a deployment manager profile or use the one created during installation.
3	A	Start the deployment manager. From Qshell, run this command: <pre>app_server_root/bin/startManager -profileName name_of_dmgr_profile</pre>
4	B	Install WebSphere Application Server Network Deployment.
5	B	Create an application server profile or use the one created during installation.
6	B	Federate the node. From Qshell, run this command: <pre>app_server_root/bin/addNode dmgrHost SOAP_port -profileName appProfile -includeapps</pre> <p>Variable descriptions:</p> <ul style="list-style-type: none"> The <i>dmgrHost</i> variable is the host name of the machine where your deployment manager profile exists. The <i>SOAP_port</i> variable is the SOAP port of the dmgr profile. The default SOAP port is 8879. To determine which port your dmgr profile uses, run the following command: <pre>app_server_root/bin/dspwasinst -profileName name_of_dmgrProfile</pre> The <i>appProfile</i> variable is the name of the application server profile that you want to federate. <p>Map the application modules to servers after this step.</p>
7	C	IBM HTTP Server on IBM i is already installed as product 5761-DG1 or 5770-DG1. Alternatively, you can also run Domino Web Server on IBM i. Refer to the Domino documentation for installation instructions. For either scenario, you must install the Web Server Plug-ins component of the WebSphere Application Server product.
8	C	Run the manageprofiles Qshell command to create an http profile. The <i>myHttpProfile</i> variable is the name of the profile.

Table 7. Installation and configuration (continued). Remote distributed installation scenario

Step	Machine	Task
9	C	<p>Configure the IBM HTTP Server with your http profile myHttpProfile.</p> <p>Assuming your Web server's name is MyWebServer, an IBM i qshell script called <i>configureIHS_MyWebServer</i> will be created in the myHttpProfile_profile_root/config/IHS_MyWebServer directory on Machine C. For the default WebSphere Application Server install, the <i>myHttpProfile_profile_root</i> of the profile myHttpProfile is /QIBM/UserData/WebSphere/AppServer/V61/Base/profiles/myHttpProfile.</p> <p>Note: In the remainder of this example, webServerName refers to IHS_myWebServer. If you choose to configure a DOMINO web server as listed below, then webServerName refers to DOMSRV01.</p> <p>The following steps apply to DOMINO web servers only:</p> <ol style="list-style-type: none"> 1. Run the <i>configureOs400WebServerDefinition</i> script on the http profile myHttpProfile. For example: <pre>configureOs400WebServerDefinition -profileName myHttpProfile -websvr.name DOMSRV01 -websvr.type DOMINO -websvr.port 80</pre> 2. Using the WRKDOMSVR command to update the notes.ini file of your Domino server, insert the following directive: WebSphereInit=myHttpProfile_profile_root/config/DOMSRV01/plugin-cfg.xml 3. From the Lotus Notes client connected to the Domino server, click the Internet protocols tab, then click the HTTP tab. Under DSAPI filter names add the following: /QSYS.LIB/ product_lib.LIB/LIBDOMINO.SRVPGM 4. Save your changes.
10	C	Copy the <i>configurewebServerName</i> script to Machine A. The script is found in the myHttpProfile_profile_root/config/webServerName directory described above.
11	A	Place the file you copied from the previous step into the <i>profile_root/bin</i> directory on Machine A, where <i>profile_root</i> is the directory where your deployment manager profile is located.
12	A/B	<p>Start the node agent and the deployment manager if they are not already running, then run the script that you copied in the previous step. For example, run these commands from Qshell:</p> <p>Machine A:</p> <pre>app_server_root/bin/startManager -profileName name_of_dmgr_profile</pre> <pre>cd profile_root/bin ./configurewebServerName [wasAdminUserId] [wasAdminPassword]</pre> <p>Note: <i>wasAdminUserId</i> and <i>wasAdminPassword</i> are optional and only needed when the deployment manager of <i>name_of_dmgr_profile</i> is running in secure mode.</p> <p>Machine B:</p> <pre>app_server_root/bin/startNode -profileName appProfile</pre>
13	A	Use the administrative console of the deployment manager on Machine A to start the application server on Machine B. Wait for synchronization to occur and save the new configuration.
14	A	<p>If you use IBM HTTP Server on IBM i, verify that the deployment manager is running. Open the administrative console (ISC) and do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers. 2. Select your web server, in this case it is IHS_MyWebServer, then click Remote web server management. 3. Enter the user ID and password used to authenticate to Machine C. The authorities required by this profile are the same as that required to access the HTTP administration GUI. For details, see User profiles and required authorities for HTTP Server in the IBM i information center. 4. Save your configuration.
15	A	Configure a virtual host alias for the web server machine (C) and web server port of MyWebServer.
16	A	<p>In the administrative console (ISC) do the following:</p> <ol style="list-style-type: none"> 1. Select webServerName and click Generate Plug-in to generate the plugin-cfg.xml file. 2. Select webServerName and click Propagate Plug-in to propagate the plugin-cfg.xml file to Machine C.
17	A	Stop and restart the federated application server.
18	A/C	<p>If you use IBM HTTP Server on IBM i, start the web server. Open the administrative console (ISC) on Machine A and do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers. 2. Select your web server, in this case it is IHS_MyWebServer, then click Start. <p>If you use Domino HTTP Server on IBM i, start the web server, on Machine C, from a CL command line:</p> <ol style="list-style-type: none"> 1. Run the Work with Domino Servers (WRKDOMSVR) command. 2. Specify option 1 next to your Domino server. 3. Press Enter.

Table 7. Installation and configuration (continued). Remote distributed installation scenario

Step	Machine	Task
19	C	Run the Snoop servlet. Access the following URL in your browser: <code>http://host_name_of_machine_C:http_transport_port/Snoop</code> If you get an error, retrace your steps.

Regeneration of the plugin-cfg.xml file

The web server plug-in configuration service regenerates the plugin-cfg.xml file automatically.

However, if the service is disabled or you want to force regeneration, use the administrative console or the **GenPluginCfg** script. In the administrative console, perform these steps:

1. Expand **Servers > Server Types > Web servers**.
2. Select the web server for which you want to regenerate the plugin-cfg.xml file.
3. Click **Generate Plug-in**.


Propagation of the plugin-cfg.xml file

The plugin-cfg.xml file can be propagated manually. Manual propagation of the plugin-cfg.xml file is required for DOMINO web servers. Copy the plugin-cfg.xml file from the application server machine to the myHttpProfile_profile_root/config/IHS_MyWebServer directory on the web server Machine C. The plugin-cfg.xml file is generated in the directory named profile_root/config/cells/cell_name/nodes/node_name/servers/IHS_myWebServer on the application server Machine B.

- **Set up a local web server configuration for a managed node.**

The local web server configuration is recommended for a development or test environment.

A local distributed installation includes the web server plug-in, the Web server, and the managed application server on the same machine:



Local distributed installation scenario

Table 8. Installation and configuration. Local distributed installation scenario

Step	Machine	Task
1	A	Install WebSphere Application Server Network Deployment.
2	A	Create a deployment manager profile or use the one created during installation.
3	A	Start the deployment manager. From Qshell, run this command: <code>app_server_root/bin/startManager -profileName name_of_dmgr_profile</code> Alternatively, issue the following commands: <code>cd profile_root/bin</code> <code>startManager</code>

Table 8. Installation and configuration (continued). Local distributed installation scenario

Step	Machine	Task
4	B	Install WebSphere Application Server Network Deployment.
5	B	Create an application server profile or use the one created during the installation. Assume the profile name is appProfile.
6	B	<p>Federate the node. From Qshell, run the following commands:</p> <pre>app_server_root/bin/addNode dmgrHost SOAP_port -profileName appProfile -includeapps</pre> <p>Variable descriptions:</p> <ul style="list-style-type: none"> The <i>dmgrHost</i> variable is the host name of the machine where your deployment manager profile exists. The <i>SOAP_port</i> variable is the SOAP port of the dmgr profile. The default SOAP port is 8879. To determine which port your dmgr profile uses, run the following command: <pre>app_server_root/bin/dspwasinst -profileName name_of_dmgrProfile</pre> The <i>appProfile</i> variable is the name of the application server profile that you want to federate. <p>Map the application modules to servers after this step.</p>
7	B	IBM HTTP Server on IBM i is already installed as product 5761-DG1 or 5770-DG1. Alternatively, you can also run Domino Web Server on IBM i. Refer to the Domino documentation for installation instructions.
8	B	<p>Configure the IBM HTTP Server with your application server profile appProfile.</p> <p>Note: In the remainder of this example, webServerName refers to IHS_MyWebServer. If you choose to configure a DOMINO web server as listed below, then webServerName refers to DOMSRV01.</p> <p>Also in this example, assume your web server's name is MyWebServer.</p>
9	A/B	<p>(Domino only) The following steps apply to the DOMINO web server on Machine B:</p> <ol style="list-style-type: none"> Run the <i>configureOs400WebServerDefinition</i> script on the deployment manager profile. For example: <pre>configureOs400WebServerDefinition -profileName name_of_dmgr_profile -webserver.name DOMSRV01 -webserver.type DOMINO -webserver.node name_of_federated_node -webserver.port 80.</pre> In this case, <i>name_of_federated_node</i> is <i>name_of_machine_B_appProfile</i>. Using the administrative console (ISC) on Machine A, configure a virtual host alias for the web server machine and web server port of DOMSRV01. On Machine B, Use the WRKDOMSVR command to update the notes.ini file of your Domino server. Insert the following directive: <i>WebSphereInit=appProfile_root/config/cells/cell_name/nodes/node_name/servers/DOMSRV01/plugin-cfg.xml</i>. <i>appProfile</i> is the application server profile name on Machine B. On Machine B, from the Lotus Notes client connected to the Domino server, click the Internet protocols tab, then click the HTTP tab. Under DSAPI filter names add the following: <i>/QSYS.LIB/ product_lib.LIB/LIBDOMINO.SRVPGM</i> Save your changes.
10	A	Use the administrative console of the deployment manager on Machine A to start the application server on Machine B.
11	A	<p>If you use IBM HTTP Server on IBM i, update the user ID and password of your web server configuration. This step enables your deployment manager to perform remote operations on the web server:</p> <ol style="list-style-type: none"> Open the administrative console for your deployment manager profile on Machine A. Expand Servers > Server Types > Web servers Select your web server, in this case it is IHS_MyWebServer, then click Remote web server management Enter the user ID and password used to authenticate to Machine B. The authorities required by this profile are the same as that required to access the HTTP administration GUI. For details, see User profiles and required authorities for HTTP Server in the IBM i information center Save your configuration.
12	A	In the administrative console (ISC), configure a virtual host alias for the web server machine (B) and web server port of MyWebServer.
13	A	<p>In the administrative console (ISC) do the following:</p> <ol style="list-style-type: none"> Select <i>webServerName</i> and click Generate Plug-in to generate the <i>plugin-cfg.xml</i> file. Select <i>webServerName</i> and click Propagate Plug-in to propagate the <i>plugin-cfg.xml</i> file.
14	A	In the administrative console (ISC), stop and restart the federated application server.

Table 8. Installation and configuration (continued). Local distributed installation scenario

Step	Machine	Task
15	A/B	<p>If you use IBM HTTP Server on IBM i, start the web server. Open the administrative console (ISC) on Machine A and do the following:</p> <ol style="list-style-type: none"> 1. Expand Servers > Server Types > Web servers 2. Select your web server, in this case it is IHS_MyWebServer, then click Start. <p>If you use Domino HTTP Server on IBM i, start the web server, on Machine B, from a CL command line:</p> <ol style="list-style-type: none"> 1. Run the Work with Domino Servers (WRKDOMSVR) command. . 2. Specify option 1 next to your Domino server. 3. Press Enter. .
16	B	<p>Run the Snoop servlet. Access the following URL in your browser:</p> <p><code>http://host_name_of_machine_B:http_transport_port/Snoop</code></p> <p>If you get an error, retrace your steps.</p>

Regeneration of the plugin-cfg.xml file

The web server plug-in configuration service regenerates the plugin-cfg.xml file automatically.

However, if the service is disabled or you want to force regeneration, use the administrative console or the GenPluginCfg script. In the administrative console, perform these steps:

1. Expand **Servers > Server Types > Web servers**.
2. Select the web server for which you want to regenerate the plugin-cfg.xml file.
3. Click **Generate Plug-in**.

The plugin-cfg.xml file is generated at the location *profile_root/config/cells/cell_name/nodes/node_name/servers/webServerName* directory, when the web server definition is created.

Regenerate the plugin-cfg.xml file in the web server definition in the application server whenever the configuration changes. The web server has immediate access to the file whenever it is regenerated.

Propagation of the plugin-cfg.xml file

Node synchronization is used to propagate the plugin-cfg.xml file from Machine A to Machine B.

Results

You can set up a remote or local web server by installing Application Server, the web server, and then the Web Server Plug-ins.

What to do next

See “Installing and configuring web server plug-ins” on page 38 for information about other installation scenarios for installing Web Server Plug-ins.

Installing and uninstalling the Web Server Plug-ins on IBM i operating systems

IBM Installation Manager is a common installer for many IBM software products that you use to install or uninstall the Web Server Plug-ins.

About this task

For more information on using Installation Manager, read the IBM Installation Manager Information Center.

Perform one of these procedures to install or uninstall the product using Installation Manager.

Procedure

- “Installing the Web Server Plug-ins on IBM i operating systems using response files” on page 50
- “Uninstalling the Web Server Plug-ins from IBM i operating systems using response files” on page 53

Results

- The following locations are the defaults for Installation Manager files on IBM i systems:
 - **Installation location:** /QIBM/ProdData/InstallationManager
 - **Agent data location:** /QIBM/UserData/InstallationManager
 - **Registry:** /QIBM/InstallationManager/.ibm/registry/InstallationManager.dat
- Logs are located in the logs directory of Installation Manager's agent data location. For example:

/QIBM/UserData/InstallationManager/logs

The main log files are time-stamped XML files in the logs directory, and they can be viewed using any standard web browser.

Installing the Web Server Plug-ins on IBM i operating systems using response files

You can use Installation Manager to install the Web Server Plug-ins using response files.

Before you begin

Before you install the Web Server Plug-ins, ensure that your user profile has *ALLOBJ and *SECADM special authorities.

Install Installation Manager on the system onto which you want to install the product.

- If you want to use the Installation Manager that comes with this product, perform the following actions:

1. Obtain the necessary files from the physical media or the web.

There are three basic options for obtaining and installing the product.

- **Access the physical media, and use local installation**

You can access the product repositories on the product media.

- a. Install Installation Manager on your system.

You can install Installation Manager using the product media, using a file obtained from the Passport Advantage® site, or using a file containing the most current version of Installation Manager from the IBM Installation Manager website.

- b. Use Installation Manager to install the product from the product repositories on the media.

- **Download the files from the Passport Advantage site, and use local installation**

Licensed customers with a Passport Advantage ID and password can download the necessary product repositories from the Passport Advantage site.

- a. Download the files from the Passport Advantage site.

- b. Install Installation Manager on your system.

You can install Installation Manager using the product media, using a file obtained from the Passport Advantage site, or using a file containing the most current version of Installation Manager from the IBM Installation Manager website.

- c. Use Installation Manager to install the product from the downloaded repositories.

- **Access the live repositories, and use web-based installation**

If you have a Passport Advantage ID and password, you can install the product from the web-based repositories.

- a. Install Installation Manager on your system.

You can install Installation Manager using the product media, using a file obtained from the Passport Advantage site, or using a file containing the most current version of Installation Manager from the IBM Installation Manager website.

- b. Use Installation Manager to install the product from the web-based repository located at

<http://www.ibm.com/software/repositorymanager/com.ibm.websphere.PLG.v80>

Whenever possible, you should use the remote web-based repositories so that you are accessing the most up-to-date installation files.

Note: If you do not have a Passport Advantage ID and password, you must install the product from the product repositories on the media or local repositories.

2. Install Installation Manager silently.

- a. Sign on to the IBM i system with a user profile that has *ALLOBJ and *SECADM special authorities.
- b. On a CL command line, run the STRQSH command to start the Qshell command shell.
- c. Make sure that the umask is set to 022.

To verify the umask setting, issue the following command:

```
umask
```

To set the umask setting to 022, issue the following command:

```
umask 022
```

- d. Change to the temporary directory where you unpacked the Installation Manager files.
- e. Run the following command in the temporary folder:

```
installc -acceptLicense -log log_file_path_and_name
```

Notes:

- For more information on installing Installation Manager silently, see the IBM Installation Manager Information Center.
- Use only the installc command to install Installation Manager.
- If you already have a version of Installation Manager installed on your system and you want to use it to install and maintain the product, obtain the necessary product files from the physical media or the web. There are three basic options for installing the product.
 - **Access the physical media, and use local installation**

You can access the product repositories on the product media. Use Installation Manager to install the product from the product repositories on the media.
 - **Download the files from the Passport Advantage site, and use local installation**

Licensed customers with a Passport Advantage ID and password can download the necessary product repositories from the Passport Advantage site.

 1. Download the product repositories from the Passport Advantage site.
 2. Use Installation Manager to install the product from the downloaded repositories.
 - **Access the live repositories, and use web-based installation**

If you have a Passport Advantage ID and password, you can use Installation Manager to install the product from the web-based repositories. Use Installation Manager to install the product from the web-based repository located at

<http://www.ibm.com/software/repositorymanager/com.ibm.websphere.PLG.v80>

Whenever possible, you should use the remote web-based repositories so that you are accessing the most up-to-date installation files.

Note: If you do not have a Passport Advantage ID and password, you must install the product from the product repositories on the media or local repositories.

About this task

Using Installation Manager, you can work with response files to install the Web Server Plug-ins.

Procedure

1. Optional: If the repository requires a username and password, create a keyring file to access this repository.

For more information on creating a keyring file for Installation Manager, read the IBM Installation Manager Information Center.

2. Sign on to the IBM i system with a user profile that has *ALLOBJ and *SECADM special authorities.
3. On a CL command line, run the STRQSH command to start the Qshell command shell.
4. Make sure that the umask is set to 022.

To verify the umask setting, issue the following command:

```
umask
```

To set the umask setting to 022, issue the following command:

```
umask 022
```

5. Use a response file to install the Web Server Plug-ins silently.

Change to the `eclipse/tools` subdirectory in the directory where you installed Installation Manager, and install the Web Server Plug-ins silently. For example:

```
./imcl -acceptLicense  
input $HOME/WASFiles/temp/install_response_file.xml  
-log $HOME/WASFiles/temp/install_log.xml  
-keyring $HOME/WASFiles/temp/im.keyring
```

Notes:

- The relevant terms and conditions, notices, and other information are provided in the license-agreement files in the `lafiles` or `product_name/lafiles` subdirectory of the installation image or repository for this product.
- `/QIBM/ProdData/InstallationManager` is the default installation location for Installation Manager files on IBM i systems.
- The program might write important post-installation instructions to standard output.

Read the IBM Installation Manager Information Center for more information.

Example

The following is an example of a response file for silently installing the Web Server Plug-ins.

```
<?xml version="1.0" encoding="UTF-8"?>  
<agent-input>  
<server>  
  <repository location='http://www.ibm.com/software/repositorymanager/com.ibm.websphere.PLG.v80' />  
</server>  
<profile id='Web Server Plug-ins for IBM WebSphere Application Server V8.0' installLocation='/QIBM/ProdData/WebSphere/Plugins/V8/webserver'>  
  <data key='eclipseLocation' value='/QIBM/ProdData/WebSphere/Plugins/V8/webserver' />  
  <data key='was.install.os400.profile.location' value='/QIBM/UserData/WebSphere/Plugins/V8/webserver' />  
  <data key='user.import.profile' value='false' />  
  <data key='cic.selector.nl' value='en' />  
</profile>  
<install modify='false'>  
  <offering profile='Web Server Plug-ins for IBM WebSphere Application Server V8.0' features='core.feature' id='com.ibm.websphere.PLG.v80' />  
</install>  
<preference name='com.ibm.cic.common.core.preferences.eclipseCache' value='/QIBM/UserData/InstallationManager/IMShared' />  
<preference name='com.ibm.cic.common.core.preferences.connectTimeout' value='30' />  
<preference name='com.ibm.cic.common.core.preferences.readTimeout' value='30' />  
<preference name='com.ibm.cic.common.core.preferences.downloadAutoRetryCount' value='0' />  
<preference name='offering.service.repositories.areUsed' value='true' />  
<preference name='com.ibm.cic.common.core.preferences.ssl.nonsecureMode' value='false' />  
<preference name='com.ibm.cic.common.core.preferences.http.disablePreemptiveAuthentication' value='false' />  
<preference name='http.ntlm.auth.kind' value='NTLM' />  
<preference name='http.ntlm.auth.enableIntegrated.win32' value='true' />  
<preference name='com.ibm.cic.common.core.preferences.preserveDownloadedArtifacts' value='true' />  
<preference name='com.ibm.cic.common.core.preferences.keepFetchedFiles' value='false' />  
<preference name='PassportAdvantageIsEnabled' value='false' />  
<preference name='com.ibm.cic.common.core.preferences.searchForUpdates' value='false' />  
</agent-input>
```

What to do next

You can create a plug-ins profile using the **manageprofiles** command.

The following is an example of using the **manageprofiles** command to create a default plug-ins profile.

```
manageprofiles -create
-templatePath /QIBM/ProdData/WebSphere/Plugins/V8/webserver/profileTemplates/http
-profileName PluginsSrv01
```

Note: After you create a profile successfully, the console prints a message that indicates success and advises you to check the `AboutThisProfile.txt` file. However, a `AboutThisProfile.txt` file is not generated when you create a plug-ins profile on IBM i.

The following is an example of using the **manageprofiles** command to make profile `PluginsSrv01` the default profile.

```
manageprofiles -setDefaultName -profileName PluginsSrv01
```

Uninstalling the Web Server Plug-ins from IBM i operating systems using response files

You can use Installation Manager to uninstall the on IBM i operating systems using response files.

Before you begin

Removing the plug-ins will break communication between any web servers and their associated application servers. Be sure to unconfigure any web and applications servers that are using these plug-ins before uninstalling them.

About this task

Using Installation Manager, you can work with response files to uninstall the Web Server Plug-ins.

Procedure

1. Stop all servers and applications on the WebSphere Application Server installations that contain the Web Server Plug-ins.
2. Sign on to the IBM i system with a user profile that has `*ALLOBJ` and `*SECADM` special authorities.
3. On a CL command line, run the `STRQSH` command to start the Qshell command shell.
4. Use a response file to uninstall the Web Server Plug-ins silently.

Complete one of the following actions:

- From a command line on each of the systems from which you want to uninstall the Web Server Plug-ins, run the **uninstall** script (which uses the `uninstall.xml` response file in the same directory) to silently uninstall the Web Server Plug-ins. For example:

```
app_server_root/uninstall/uninstall
```

- From a command line on each of the systems from which you want to uninstall the Web Server Plug-ins, change to the `eclipse/tools` subdirectory in the directory where you installed Installation Manager and use the `uninstall.xml` response file in the same directory to silently uninstall the Web Server Plug-ins. For example:

```
./imcl
input app_server_root/uninstall/uninstall/uninstall.xml
-log $HOME/WASFiles/temp/uninstall_log.xml
```

- From a command line on each of the systems from which you want to uninstall the Web Server Plug-ins, change to the `eclipse/tools` subdirectory in the directory where you installed Installation Manager and use a response file that you created to silently uninstall the on IBM i operating systems. For example:

```
./imcl
input $HOME/WASFiles/temp/uninstall_response_file.xml
-log $HOME/WASFiles/temp/uninstall_log.xml
```


Go to the Installation Manager information center for more information.

5. Optional: Uninstall IBM Installation Manager.

Important: Before you can uninstall IBM Installation Manager, you must uninstall all of the packages that were installed by Installation Manager.

Read Uninstalling Installation Manager silently in the Installation Manager information center for information about using the uninstall script to perform this procedure.

Example

The `app_server_root/uninstall/uninstall/uninstall.xml` file is an example of a response file for silently uninstalling the Web Server Plug-ins.

Web server configuration

Plug-in configuration involves configuring the web server to use the binary plug-in module that WebSphere Application Server provides. Plug-in configuration also includes updating the plug-in XML configuration file to reflect the current application server configuration. The binary module uses the XML file to help route web client requests.

The plug-ins configuration process uses the following files to configure a plug-in for the web server that you select:

- The **web server configuration file** on the web server machine, such as the `httpd.conf` file for IBM HTTP Server.
- The **binary web server plug-in file** on the web server machine.
- The **plug-in configuration file, `plugin-cfg.xml`**, on the application server machine that you propagate (copy) to a Web server machine.
- The **configuration script** for configuring the web server definition for your application server in a remote HTTP scenario.

See the following descriptions of each file.

Web server configuration file

The web server configuration file is installed as part of the web server.

Configuration consists of adding directives that identify file locations of two files:

- Binary web server plug-in file
- Plug-in configuration file, `plugin-cfg.xml`

Binary web server plug-in file

An example of a binary plug-in module is the `mod_was_ap22_http.dll` file for IBM HTTP Server on the Windows platform.

Another example of a binary plug-in module is the QSVTAP20 service program on the IBM i platform.

The binary plug-in file does not change. However, the configuration file for the binary plug-in is an XML file. The application server changes the configuration file when certain changes to your WebSphere Application Server configuration occur.

The binary module reads the XML file to adjust settings and to route requests to the application server.

Plug-in configuration file, plugin-cfg.xml

The plug-in configuration file is an XML file with settings that you can tune in the administrative console. The file lists all of the applications installed on the web server definition. The binary module reads the XML file to adjust settings and to route requests to the application server.

When you make application server configuration changes that affect deployed applications, regenerate the plug-in configuration XML file.

After regeneration, propagate (copy) the file to the web server machine. The binary plug-in then has access to the most current copy of its configuration file.

On IBM i systems, the plug-in is not automatically generated. You must regenerate and propagate the file manually.

Configuration script for the Web server definition

Configuring your web server with the `configure0s400WebserverDefinition` script or using the IBM i Administrative GUI creates the `configureweb_server_name` script on the web server machine in the `plugins_root/bin` directory. The script is created for remote installation scenarios only.

Copy the script from the web server machine to the `app_server_root/bin` directory in the IBM i partition. Run the script to create a web server definition in the configuration of the application server.

The IBM i Administrative GUI has plug-ins that allow the administrative console to manage IBM HTTP Servers. Use the administrative console to update your web server definition with remote web server management options. Click **Servers > Server Types > Web servers > web_server_name** to see configuration options. For example, click **Remote Web server management** to change such properties as:

- Host name
- Administrative port
- User ID
- Password

If a web server definition already exists for a standalone application server, running the script does not add a new web server definition. Each standalone application server can have only one Web server definition.

You cannot use the administrative console of a standalone application server to add or delete a web server definition. However, you can do both tasks using the administrative scripting interface:

- Add a web server definition through the wsadmin facility using the `configureweb_server_name` script. The script uses a Java Command Language (Jacl) script named `configureWebserverDefintion.jacl` to create and configure the web server definition.
- Delete a web server definition using wsadmin commands. The Web server is named `webserver1` in the following example:

```
set webserverName webserver1
set webserverNodeSuffix _node
set webserverNodeName
$webserverName$webserverNodeSuffix
$AdminConfig remove
  [$AdminConfig getid
    /Node:$webserverNodeName/Server:$webserverName]
$AdminConfig remove
  [$AdminConfig getid /Node:$webserverNodeName]
$AdminConfig save
```

Alternatively, you can use the `configure0s400WebServerDefinition` and `remove0s400WebServerDefinition` scripts to perform these tasks.

A managed node, on the other hand, can have multiple web server definitions. The script creates a new web server definition unless the web server name is the same.

Replacing the default plug-in configuration file with the file from the web server definition (propagation)

The default file uses fixed parameter values that might not match the parameter values in the actual file on the application server. The default file is a placeholder only.

The file cannot reflect changes that occur in the application server configuration. The file also cannot reflect nondefault values that might be in effect on the application server.

Creating or updating a global web server plug-in configuration file

If all of the application servers in a cell use the same web server to route requests for dynamic content, such as servlets, from web applications to application servers, you can create a global web server plug-in configuration file for that cell. The resulting `plugin-cfg.xml` file is located in the `profile_root/config/cells` directory.

Before you begin

Note: You can update the *global* `plugin-cfg.xml` file using the administrative console or running the `GenPluginCfg` command for all of the clusters in a cell. However, you must delete the `config/cells/plugin-cfg.xml` file before you update the *global* `plugin-cfg.xml` file. If you do not delete the `config/cells/plugin-cfg.xml` file, only the new properties and their values are added to the *global* `plugin-cfg.xml` file. Any updates to existing plug-in property values are not added to the *global* `plugin-cfg.xml` file.

About this task

You must update the global web server plug-in configuration file whenever you perform one of the following actions:

- Change the configuration settings for an application server, cluster, virtual host, or web container transport that is part of that cell.
- Add a new application server, cluster, virtual host, or web container transport to that cell.

To update the configuration settings for a global web server plug-in, you can either use the Update global web server plug-in configuration page in the administrative console, or issue the following command:

```
%was_profile_home%/config/cells/GenPluginCfg.sh|bat
```

Both methods for regenerating the global web server plug-in configuration create a `plugin-cfg.xml` file in ASCII format.

To use the Update global web server plug-in configuration page in the administrative console:

Procedure

1. Click **Environment > Update global web server plug-in configuration**.
2. Click **OK** to update the `plugin-cfg.xml` file.
3. Optional: Click **View or download the current web server plug-in configuration file** if you want to view or download the current version of this file.

You can select this option if you want to:

- View the current version of the file before you update it.
- View the file after it is updated.
- Download a copy of this file to a remote machine.

Results

Regenerating the configuration might take a while to complete. After it finishes, all objects in the administrative cell use their newest settings, which the web server can access. Whether triggered manually or occurring automatically, plug-in regeneration requires about 30 to 60 seconds to complete when the application server is on the same physical machine (node) as the web server. In other cases, it takes more time.

The delay is important because it determines how soon the new plug-in configuration takes effect. Suppose you add a new served path for a servlet, then regenerate the plug-in configurations. The regeneration requires 40 seconds, after which a user should be able to access the servlet by the new served path.

For an HTTP plug-in, the length of the delay is determined by the Refresh Interval attribute of the Config element in the `plugin-cfg.xml` file. The plug-in polls the disk, or file system, at this interval to see whether the configuration has changed. The default interval is 60 seconds. To regenerate the plug-in configuration requires twice the refresh interval.

In a development environment in which you are frequently changing settings in the administrative console, it is recommended that you set the refresh interval to 3 to 5 seconds.

In a production environment, set a longer refresh interval, perhaps as long as 30 minutes, depending on the frequency of changes.

What to do next

You might need to stop the application servers in the cell and then start the application servers again before the changes to the plug-in configuration go into effect.

If the web server is running on a remote machine, click **View or download the current web server plug-in configuration file** to download a copy of the `plugin-cfg.xml` file to a that machine.

When the deployment manager is installed on a machine that is remote from where the product is installed, one of the following solutions must be implemented in order for the `plugin-cfg.xml` file to retain the application server directory structures, and not assume those of the deployment manager after the plug-in is regenerated and a full synchronization occurs.

- **Command line:**

At a command prompt, enter the following command to change the `DeploymentManager/bin` directory and type on the machine where the deployment manager is installed. This command creates or updates the `plugin-cfg.xml` file, and changes all of the directories in the `plugin-cfg.xml` file to `app_server_root` directories.

```
GenPluginCfg -destination.root <app_server_root>
```

For example, issue the following command from the `DeploymentManager/bin` directory.

```
GenPluginCfg -destination.root "E:\WebSphere\AppServer"
```

- **plugin-cfg.xml file:**

Edit the `plugin-cfg.xml` file to point to the correct directory structure for the log file, keyring, and stashfile.

Perform a full synchronization so the `plugin-cfg.xml` file is replicated in all the nodes. You can use scripting or the administrative console to synchronize the nodes in the cell.

The deployment manager `plugin-cfg.xml` file can point to the application server directories without any conflict.

Creating or updating a global web server plug-in configuration file

If all of the application servers in a cell use the same web server to route requests for dynamic content, such as servlets, from web applications to application servers, you can create a global web server plug-in configuration file for that cell. The resulting `plugin-cfg.xml` file is located in the `profile_root/config/cells` directory.

Before you begin

Note: You can update the *global* `plugin-cfg.xml` file using the administrative console or running the `GenPluginCfg` command for all of the clusters in a cell. However, you must delete the `config/cells/plugin-cfg.xml` file before you update the *global* `plugin-cfg.xml` file. If you do not delete the `config/cells/plugin-cfg.xml` file, only the new properties and their values are added to the *global* `plugin-cfg.xml` file. Any updates to existing plug-in property values are not added to the *global* `plugin-cfg.xml` file.

About this task

You must update the global web server plug-in configuration file whenever you perform one of the following actions:

- Change the configuration settings for an application server, cluster, virtual host, or web container transport that is part of that cell.
- Add a new application server, cluster, virtual host, or web container transport to that cell.

To update the configuration settings for a global web server plug-in, you can either use the Update global web server plug-in configuration page in the administrative console, or issue the following command:

```
%was_profile_home%/config/cells/GenPluginCfg.sh|bat
```

Both methods for regenerating the global web server plug-in configuration create a `plugin-cfg.xml` file in ASCII format.

To use the Update global web server plug-in configuration page in the administrative console:

Procedure

1. Click **Environment > Update global web server plug-in configuration**.
2. Click **OK** to update the `plugin-cfg.xml` file.
3. Optional: Click **View or download the current web server plug-in configuration file** if you want to view or download the current version of this file.

You can select this option if you want to:

- View the current version of the file before you update it.
- View the file after it is updated.
- Download a copy of this file to a remote machine.

Results

Regenerating the configuration might take a while to complete. After it finishes, all objects in the administrative cell use their newest settings, which the web server can access. Whether triggered manually or occurring automatically, plug-in regeneration requires about 30 to 60 seconds to complete when the application server is on the same physical machine (node) as the web server. In other cases, it takes more time.

The delay is important because it determines how soon the new plug-in configuration takes effect. Suppose you add a new served path for a servlet, then regenerate the plug-in configurations. The regeneration requires 40 seconds, after which a user should be able to access the servlet by the new served path.

For an HTTP plug-in, the length of the delay is determined by the Refresh Interval attribute of the Config element in the `plugin-cfg.xml` file. The plug-in polls the disk, or file system, at this interval to see whether the configuration has changed. The default interval is 60 seconds. To regenerate the plug-in configuration requires twice the refresh interval.

In a development environment in which you are frequently changing settings in the administrative console, it is recommended that you set the refresh interval to 3 to 5 seconds.

In a production environment, set a longer refresh interval, perhaps as long as 30 minutes, depending on the frequency of changes.

What to do next

You might need to stop the application servers in the cell and then start the application servers again before the changes to the plug-in configuration go into effect.

If the web server is running on a remote machine, click **View or download the current web server plug-in configuration file** to download a copy of the `plugin-cfg.xml` file to a that machine.

When the deployment manager is installed on a machine that is remote from where the product is installed, one of the following solutions must be implemented in order for the `plugin-cfg.xml` file to retain the application server directory structures, and not assume those of the deployment manager after the plug-in is regenerated and a full synchronization occurs.

- **Command line:**

At a command prompt, enter the following command to change the `DeploymentManager/bin` directory and type on the machine where the deployment manager is installed. This command creates or updates the `plugin-cfg.xml` file, and changes all of the directories in the `plugin-cfg.xml` file to `app_server_root` directories.

```
GenPluginCfg -destination.root <app_server_root>
```

For example, issue the following command from the `DeploymentManager/bin` directory.

```
GenPluginCfg -destination.root "E:\WebSphere\AppServer"
```

- **plugin-cfg.xml file:**

Edit the `plugin-cfg.xml` file to point to the correct directory structure for the log file, keyring, and stashfile.

Perform a full synchronization so the `plugin-cfg.xml` file is replicated in all the nodes. You can use scripting or the administrative console to synchronize the nodes in the cell.

The deployment manager `plugin-cfg.xml` file can point to the application server directories without any conflict.

Update the global web server plug-in configuration setting

Use this page to create or update a global plug-in configuration file. The configuration settings this file contains are based on the topology of the cell that contains the applications servers that use this web server plug-in. The web server plug-in configuration file settings determine whether an application server or the web server handles user requests.

A global web server plug-in configuration file must be regenerated whenever:

- You change the configuration settings for an application server, cluster, web container transport, or virtual host alias that is contained in the cell.

- You add a new application server, cluster, web container transport, or virtual host alias to the cell.

The generated `plugin-cfg.xml` file is placed in the `%was_profile_home%/config/cells` directory. If your web server is located on a remote machine, you must manually move this file to that machine.

Note: You can update the *global* `plugin-cfg.xml` file using the administrative console or running the `GenPluginCfg` command for all of the clusters in a cell. However, you must delete the `config/cells/plugin-cfg.xml` file before you update the *global* `plugin-cfg.xml` file. If you do not delete the `config/cells/plugin-cfg.xml` file, only the new properties and their values are added to the *global* `plugin-cfg.xml` file. Any updates to existing plug-in property values are not added to the *global* `plugin-cfg.xml` file.

To view this administrative console page, click **Environment > Update global web server plug-in configuration**.

Click **OK** to update the `global plugin-cfg.xml` file.

Click **View or download the current web server plug-in configuration file** if you want to:

- View the current version of the file before you update it.
- View the file after it is updated.
- Download a copy of this file to a remote machine.

Directory conventions

References in product information to *app_server_root*, *profile_root*, and other directories imply specific default directory locations. This topic describes the conventions in use for WebSphere Application Server.

Default product locations - IBM i

These file paths are default locations. You can install the product and other components in any directory where you have write access. You can create profiles in any valid directory where you have write access. Multiple installations of WebSphere Application Server products or components require multiple locations.

app_client_root

The default installation root directory for the Application Client for IBM WebSphere Application Server is the `/QIBM/ProdData/WebSphere/AppClient/V8/client` directory.

app_client_user_data_root

The default Application Client for IBM WebSphere Application Server user data root is the `/QIBM/UserData/WebSphere/AppClient/V8/client` directory.

app_client_profile_root

The default Application Client for IBM WebSphere Application Server profile root is the `/QIBM/UserData/WebSphere/AppClient/V8/client/profiles/profile_name` directory.

app_server_root

The default installation root directory for WebSphere Application Server Network Deployment is the `/QIBM/ProdData/WebSphere/AppServer/V8/ND` directory.

java_home

Table 9. Root directories for supported Java Virtual Machines.

This table shows the root directories for all supported Java Virtual Machines (JVMs).

JVM	Directory
32-bit IBM Technology for Java	<code>/QOpenSys/QIBM/ProdData/JavaVM/jdk60/32bit</code>
64-bit IBM Technology for Java	<code>/QOpenSys/QIBM/ProdData/JavaVM/jdk60/64bit</code>

plugins_profile_root

The default Web Server Plug-ins profile root is the /QIBM/UserData/WebSphere/Plugins/V8/webserver/profiles/*profile_name* directory.

plugins_root

The default installation root directory for Web Server Plug-ins is the /QIBM/ProdData/WebSphere/Plugins/V8/webserver directory.

plugins_user_data_root

The default Web Server Plug-ins user data root is the /QIBM/UserData/WebSphere/Plugins/V8/webserver directory.

product_library

product_lib

This is the product library for the installed product. The product library for each Version 8.0 installation on the system contains the program and service program objects (similar to .exe, .dll, .so objects) for the installed product. The product library name is QWAS8x (where x is A, B, C, and so on). The product library for the first WebSphere Application Server Version 8.0 product installed on the system is QWAS8A. The *app_server_root*/properties/product.properties file contains the value for the product library of the installation, was.install.library, and is located under the *app_server_root* directory.

profile_root

The default directory for a profile named *profile_name* for WebSphere Application Server Network Deployment is the /QIBM/UserData/WebSphere/AppServer/V8/ND/profiles/*profile_name* directory.

shared_product_library

The shared product library, which contains all of the objects shared by all installations on the system, is QWAS8. This library contains objects such as the product definition, the subsystem description, the job description, and the job queue.

user_data_root

The default user data directory for WebSphere Application Server Network Deployment is the /QIBM/UserData/WebSphere/AppServer/V8/ND directory.

The profiles and profileRegistry subdirectories are created under this directory when you install the product.

web_server_root

The default web server path is /www/*web_server_name*.

Administering web server plug-ins

Using the same HTTP server to handle HTTP and HTTPS requests for multiple cells

In a multiple cell environment you might want to use the same HTTP server to send and receive HTTP and HTTPS requests for multiple cells. To accomplish this setup, you must merge the web server plug-in configuration files that are being used by the application servers in those cells into a single web server plug-in configuration file.

About this task

You can use the following different configurations of the application server to combine the plug-in configuration files of multiple WebSphere Application Server, Network Deployment cells into a single configuration file.

This technique can also be employed to merge all of the web server plug-in configuration files into a single configuration file when you are migrating to a new release of the product and need to route traffic to multiple cells running an older version of WebSphere Application Server, Network Deployment as well as the new version.

To create a single plug-in configuration file for all of your cells, you must first create a separate plug-in configuration file for each of the cells, and then combine these files into a single configuration file. The web server plug-in for each cell then uses the same web server plug-in configuration file.

Complete the following steps to merge multiple web server plug-in configuration files into a single configuration file.

Procedure

1. Use either the GenPluginCfg script, the administrative console, or wsadmin scripting to generate the plugin-cfg.xml file for each cell.

See the topic *GenPluginCfg command* for a description of how to use the GenPluginCfg script to generate the plugin-cfg.xml file.

See the topic *Implementing a web server plug-in* for a description of how to use the administrative console to generate the plugin-cfg.xml file.

See the topic *Regenerating the node plug-in configuration using scripting* for a description of how to use wsadmin scripting to generate the plugin-cfg.xml file.

2. Merge the plugin-cfg.xml files from multiple application server cells.

You can either manually merge the plugin-cfg.xml files or use the pluginCfgMerge tool to automatically merge the plugin-cfg.xml file from multiple application server profiles into a single output file. The pluginCfgMerge.bat and pluginCfgMerge.sh files are located in the *install_root/bin* directory.

gotcha: The pluginCfgMerge tool is provided in Fix Pack 7.0.0.13 for the z/OS and distributed platforms, and in Fix Pack 7.0.0.17 for the IBM i platform.

To use the pluginCfgMerge tool, complete the following steps:

- a. Rename the plugin-cfg.xml files to a unique name across your application server cells.
- b. Copy the plugin-cfg.xml file for all application server cell profiles into a common directory.
- c. Use the pluginCfgMerge tool to combine the plugin-cfg.xml files from each of the application server cells into a single output file. For example:

```
install_root/bin/pluginCfgMerge.sh plugin_configuration_file1 plugin_configuration_file2 resulting_plugin_configuration_file
```

The *resulting_plugin_configuration_file* variable value is normally plugin-cfg.xml

For more information about manually merging the plugin-cfg.xml files, see the technote on merging plugin-cfg.xml files from multiple application server profiles.

3. Ensure that the cloneID value for each application server is unique.

Examine the cloneID value for each application server in the merged file to ensure that this value is unique for each application server. If the cloneID values in the merged file are not all unique, or if you are running with memory to memory session replication in peer to peer mode, use wsadmin scripting or the administrative console to configure unique HTTP session cloneIDs.

To use wsadmin commands for the Jython or Jacl programming language, see the documentation on configuring a unique HTTP session clone ID for each application server using scripting.

To configure a unique HTTP session clone ID using the administrative console, complete the following steps:

- a. Click **Servers > Server Types > WebSphere application servers > server_name**.
- b. Under Container Settings, click **Web Container Settings > Web container**.
- c. Under Additional Properties, click **Custom properties > New**.
- d. Enter HttpSessionCloneId in the **Name** field, and a unique value for the server in the **Value** field.

The unique value must be 8 - 9 alphanumeric characters in length. For example, test1234 is a valid cloneID value.

- e. Click **Apply** or **OK**.
 - f. Click **Save** to save the configuration changes to the master configuration.
4. Copy the merged `plugin-cfg.xml` file to the `plugin_installation_root/config/web_server_name/` directory on the web server host.

Results

When you complete this process, you have one plug-in configuration file for multiple application server cells, and can use the same HTTP server to handle HTTP and HTTPS requests for multiple cells.

Web server plug-in properties

Use this page to view or change the settings of a web server plug-in configuration file. The plug-in configuration file, `plugin_cfg.xml`, provides properties for establishing communication between the Web server and the Application Server.

To view this administrative console page, click **Servers > Server Types > Web servers > web_server_name > Plug-in Properties**.

On the **Configuration** tab, you can edit fields. On the **Runtime** tab, you can look at read-only information.

The **Runtime** tab is available only when this web server has accessed applications running on application servers and there is an `http_plugin.log` file.

Note: This topic references one or more of the application server log files. Beginning in WebSphere Application Server Version 8.0 you can configure the server to use the High Performance Extensible Logging (HPEL) log and trace infrastructure instead of using `SystemOut.log`, `SystemErr.log`, `trace.log`, and `activity.log` files or native z/OS logging facilities. If you are using HPEL, you can access all of your log and trace information using the LogViewer command-line tool from your server profile bin directory. See the information about using HPEL to troubleshoot applications for more information on using HPEL.

Ignore DNS failures during web server startup

Specifies whether the plug-in ignores DNS failures within a configuration when starting.

This field corresponds to the `IgnoreDNSFailures` element in the `plugin-cfg.xml` file.

When you set the value to **true**, the plug-in ignores DNS failures within a configuration and starts successfully if at least one server in each `ServerCluster` is able to resolve the host name. If a server host name cannot be resolved, it is marked **unavailable** for the continued existence of the configuration. Further attempts to resolve the host name are not made during the routing of requests. If a DNS failure occurs, a message is written to the plug-in log file and the plug-in initialization process continues.

By default, when the value is **false**, DNS failures cause the plug-in to not initialize and requests fail. However, the web server starts.

Data type	String
Default	false

Refresh configuration interval

Specifies the time interval, in seconds, at which the plug-in should check the configuration file to see if updates or changes have occurred. The plug-in checks the file for any modifications that have occurred since the last time the plug-in configuration was loaded.

In a development environment in which changes are frequent, a lower setting than the default setting of 60 seconds is preferable. In production, a higher value than the default is preferable because updates to the configuration will not occur so often. If the plug-in reload fails for some reason, a message is written to the plug-in log file and the previous configuration is used until the plug-in configuration file successfully reloads. If you are not seeing the changes you made to your plug-in configuration, check the plug-in log file for indications of the problem.

Data type	Integer
Default	60 seconds.

Plug-in configuration file name

Specifies the file name of the configuration file for the plug-in. The Application Server generates the `plugin-cfg.xml` file by default. The configuration file identifies applications, Application Servers, clusters, and HTTP ports for the web server. The web server uses the file to access deployed applications on various Application Servers.

Note: This field is disabled and cannot be changed, but the value is displayed for information purposes only.

If a different location is desired, you need to rerun the Plugin installer to define the new location, and then run the new **configureWebserver** script that is produced from the install process on your WebSphere Application Server machine.

If you select a web server plug-in during installation, the installer program configures the web server to identify the location of the `plugin-cfg.xml` file, if possible. The plug-in configuration file, by default, is installed in the `plugins_root/config/web_server_name` directory.

The installer program adds a directive to the web server configuration that specifies the location of the `plugin-cfg.xml` file.

For remote web servers, you must copy the file from the local directory where the Application Server is installed to the remote machine. This is known as propagating the plug-in configuration file. If you are using IBM HTTP Server V6.1 or higher for your web server, WebSphere Application Server can automatically propagate the plug-in configuration file for you to remote machines provided there is a working HTTP transport mechanism to propagate the file.

You can click **View** to display a copy of the current plug-in configuration file.

Data type	String
Default	<code>plugin-cfg.xml</code>

Automatically generate plug-in configuration file

To automatically generate a plug-in configuration file to a remote web server:

- This field must be checked.
- The plug-in configuration service must be enabled

When the plug-in configuration service is enabled, a plug-in configuration file is automatically generated for a web server whenever:

- The WebSphere Application Server administrator defines new web server.
- An application is deployed to an Application Server.
- An application is uninstalled.
- A virtual host definition is updated and saved.

By default, this field is checked. Clear the check box if you want to manually generate a plug-in configuration file for this web server.

Automatically propagate plug-in configuration file

Specifies whether or not you want the application server to automatically propagate a copy of a changed plug-in configuration file to a Web server:

- This field must be checked.
- The plug-in configuration service must be enabled
- In a Network Deployment environment, a WebSphere Application Server node agent must be on the node that hosts the web server associated with the changed plug-in configuration file.

By default, this field is checked.

Note: The plug-in configuration file can only be automatically propagated to a remote web server if that web server is an IBM HTTP Server V6.1 or higher web server and its administration server is running.

Because the plug-in configuration service runs in the background and is not tied to the administrative console, the administrative console cannot show the results of the automatic propagation.

Plug-in key store file name

Specifies the fully qualified directory path and file name of the database file containing your security key rings that the Web server plug-in uses for HTTPS requests. This file resides on the Web server that is associated with this web server plug-in. After you specify the fully qualified directory path and file name of the database file, you can:

- Click **Manage keys and certificates** to update this file.
- Click **Copy to web server key store directory** to add a copy of this file to the key store directory for the web server.

Data type	String
Default	None

Plug-in configuration directory and file name

Specifies the fully qualified path of the web server copy of the web server plug-in configuration file. This path is the name of the file and its location on the machine where the web server is running.

Note: This field is disabled and cannot be changed, but the value is displayed for information purposes only.

Plug-in key store directory and file name

Specifies the fully qualified path of the web server copy of the database file that contains your security key rings. This path is the name of the file and its location on the machine where the web server is running.

Note: This field is disabled and cannot be changed, but the value is displayed for information purposes only.

Plug-in logging

Specifies the location and name of the `http_plugin.log` file. Also specifies the scope of messages in the log.

The log describes the location and level of log messages that are written by the plug-in. If a log is not specified within the configuration file, then, in some cases, log messages are written to the web server error log.

On a distributed platform, if the log file does not exist then it will be created. If the log file already exists, it will be opened in append mode and the previous plug-in log messages will remain.

Log file name - The fully qualified path to the log file to which the plug-in will write error messages.

Data type	String
Default	<code>plugins_root/logs/web_server_name/http_plugin.log</code>

Specify the file path of the `http_plugin.log` file.

Log level- The level of detail of the log messages that the plug-in should write to the log. You can specify one of the following values for this attribute:

- Trace. All of the steps in the request process are logged in detail.
- Stats. The server selected for each request and other load balancing information relating to request handling is logged.
- Warn. All warning and error messages resulting from abnormal request processing are logged.
- Error. Only error messages resulting from abnormal request processing are logged.
- Debug. All of the critical steps performed in processing requests are logged.
- Detail. All of the information about requests and responses are logged.

If a Log level is not specified, the default value **Error** is used.

Be careful when setting the level to **Trace**. A lot of messages are logged at this level which can cause the disk space/file system to fill up very quickly. A **Trace** setting should never be used in a normally functioning environment as it adversely affects performance.

Important: If the web server and web server plug-in are running on an AIX, HP-UX, Linux, or Solaris system, and you change the log level, in the `plugin-cfg.xml` file, this change is not picked up dynamically. You must restart the web server to pick up the change. For example on Solaris, if you do not restart the web server, the following error message appears in the `Plugin_Home/logs/http_plugin.log` file:

```
ERROR: ws_config_parser:handleLogEnd: Failed to open log file
'/opt/IBM/WebSphere/Plugin/logs/sunwebserver/http_plugin.log', OS
```

Data type	String
Default	Error

Web server plug-in request and response optimization properties

Use this page to view or change the request and response optimization properties for a web server plug-in.

To view this administrative console page, click **Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and response**.

Maximum chunk size used when reading the HTTP response body:

Specifies the maximum chunk size the plug-in can use when reading the response body.

This field corresponds to the `ResponseChunkSize` element in the `plugin-cfg.xml` file.

The plug-in reads the response body in 64K chunks until all of the response data is read. This approach causes a performance problem for requests whose response body contains large amounts of data.

If the content length of the response body is unknown, the values specified for this property is used as the size of the buffer that is allocated. The response body is then read in this size chunks, until the entire body

is read. If the content length is known, then a buffer size of either the content length or the specified size (whichever is less) is used to read the response body.

Data type	Integer
Default	64 kilobytes
	Specify the size in kilobytes (1024 byte blocks).

Enable Nagle algorithm for connections to the Application Server:

When checked, the Nagle algorithm is enabled for connections between the plug-in and the Application Server.

This field corresponds to the ASDisableNagle element in the plugin-cfg.xml file.

The Nagle algorithm is named after engineer John Nagle, who invented this standard part of the transmission control protocol/internet protocol (TCP/IP). The algorithm reduces network overhead by adding a transmission delay (usually 200 milliseconds) to a small packet, which lets other small packets arrive and be included in the transmission. Because communications has an associated cost that is not as dependent on packet size as it is on frequency of transmission, this algorithm potentially reduces overhead with a more efficient number of transmissions.

By default, this field is not checked, and the Nagle algorithm is disabled. Select this field to enable the Nagle algorithm.

Enable Nagle Algorithm for the IIS Web Server:

When checked, the Nagle algorithm is used for connections from the Microsoft Internet Informations Services (IIS) Web Server to the application server.

This field corresponds to the IISDisableNagle element in the plugin-cfg.xml file. It only applies if you are using the Microsoft Internet Informations Services (IIS) Web Server.

By default, this field is not checked, and the Nagle algorithm is disabled. Select this field to enable the Nagle algorithm for this connection.

Chunk HTTP response to the client:

When checked, responses to the client are broken into chunks if a Transfer-Encoding : Chunked response header is present in the response.

This field corresponds to the ChunkedResponse element in the plugin-cfg.xml file. It only applies if you are using a Microsoft Internet Informations Services (IIS) Web Server, a Java System web server, or a Domino Web Server. The IBM HTTP Server automatically handles breaking the response into chunks to send to the client.

By default, this field is not checked, and responses are not broken into chunks. Select this field to enable responses to the client to be broken into chunks if a Transfer-Encoding : Chunked response header is present in the response.

Accept content for all requests: This field corresponds to the AcceptAllContent element in the plugin-cfg.xml file.

When selected, you can include content in GET, and HEAD requests when a Content-Length or Transfer-encoding header is contained in the request header.

By default, this field is checked.

Select this field to enable users to include content in GET, and HEAD requests when a Content-Length or Transfer-encoding header is contained in the request header.

Note: The **Accept content for all requests** setting on the administrative console corresponds to the AcceptAllContent attribute in the plugin-cfg.xml file. For Version 8, the default for the setting is checked and for the attribute is true. Before Version 8, the default for the setting is not checked and for the attribute is false.

Virtual host matching:

When selected, virtual host mapping is performed by physically using the port number for which the request was received.

This field corresponds to the VHostMatchingCompat element in the plugin-cfg.xml file.

By default, this field is not checked, and matching is done logically using the port number contained in the host header. Select this field if you want virtual host mapping performed by physically using the port number for which the request was received.

Use the radio buttons to make your physical or logical port selection.

Application server port preference:

Specifies which port number the Application Server should use to build URIs for a sendRedirect. This field is only applicable for a sendRedirect if you use relative URIs and does not affect absolute redirects. This field also specifies where to retrieve the value for HttpServletRequest.getServerPort().

This field corresponds to the AppServerPortPreference element in the plugin-cfg.xml file.

Specify:

- hostHeader if the port number from the host header of the HTTP request coming in is to be used.
- webserverPort if the port number on which the web server received the request is to be used.

The default is hostHeader.

Web server plug-in caching properties

Use this page to view or change the caching properties for a web server plug-in.

To view this administrative console page, click **Servers > Server Types > Web servers > web_server_name > Plug-in properties > Caching**.

Enable Edge Side Include (ESI) processing to cache the responses:

Specifies whether to enable Edge Side Include processing to cache the responses.

This field corresponds to the esiEnable element in the plugin-cfg.xml file.

By default, this field is checked. Select this field if you want Edge Side Include (ESI) processing used to cache responses. If ESI processing is disabled for the plug-in, the other ESI plug-in properties are ignored. Clear the checkbox to disable Edge Side Include processing.

Enable invalidation monitor to receive notifications:

When checked, the ESI processor receives invalidations from the application server.

This field corresponds to the `ESIInvalidationMonitor` element in the `plugin-cfg.xml` file. It is ignored if Edge Side Include (ESI) processing is not enabled for the plug-in.

By default, this field is not selected. Clear the check box if you do not want the application server to send invalidations to the ESI processor.

Maximum cache size:

Specifies, in 1K byte units, the maximum size of the cache. The default maximum size of the cache is 1024K bytes (1 megabyte). If the cache is full, the first entry to be evicted from the cache is the entry that is closest its expiration time.

This field corresponds to the `esiMaxCacheSize` element in the `plugin-cfg.xml` file.

Data type	Integer
Default	1024 kilobytes
	Specify the size in kilobytes (1024 byte blocks).

Web server plug-in request routing properties

Use this page to view or change the request routing properties for a web server plug-in.

To view this administrative console page, click **Servers > Server Types > Web servers > *web_server_name* > Plug-in properties > Request routing**.

Load balancing option:

Specifies the load balancing option that the plug-in uses in sending requests to the various application servers associated with that web server.

This field corresponds to the `LoadBalance` element in the `plugin-cfg.xml` file.

Select the appropriate load balancing option:

- Round robin
- Random

The Round Robin implementation has a random starting point. The first application server is picked randomly. Round Robin is then used to pick application servers from that point forward. This implementation ensures that in multiple process based web servers, all of the processes don't start up by sending the first request to the same Application Server.

The default load balancing type is Round Robin.

Retry interval:

Specifies the length of time, in seconds, that should elapse from the time an application server is marked down to the time that the plug-in retries a connection.

This field corresponds to the `RetryInterval` element in the `plugin-cfg.xml` file.

Data type	Integer
Default	60 seconds

Maximum size of request content:

Select whether there is a limit on the size of request content. If limited, this field also specifies the maximum number of kilobytes of data a request can contain. When a limit is set, the plug-in fails any request that is received that contains more data than the specified limit.

This field corresponds to the PostSizeLimit element in the plugin-cfg.xml file.

Select whether to limit the size of request content:

- No limit
- Set limit

If you select Set limit, specify a limit size.

Data type	Integer
Default	Specify the size in kilobytes (1024 byte blocks). -1, which indicates there is no limit for the post size.

Maximum buffer size used when reading HTTP request content:

Specifies, in kilobytes, the maximum buffer size that is used when the content of an HTTP request is read. If the application server that initially receives a request cannot process that request, the data contained in this buffer is sent to another application server in an attempt to have that application server process the request.

This field corresponds to the PostBufferSize element in the plugin-cfg.xml file.

If **Set limit** is selected, specify a limit size.

Data type	Integer
Default	Specify the size in kilobytes (1024 byte blocks). 64

Remove special headers:

When checked, the plug-in will remove any headers from incoming requests before adding the headers the plug-in is supposed to add before forwarding the request to an application server.

This field corresponds to the RemoveSpecialHeaders element in the plugin-cfg.xml file.

The plug-in adds special headers to the request before it is forwarded to the application server. These headers store information about the request that will need to be used by the application. Not removing the headers from incoming requests introduces a potential security exposure.

By default, the special headers are not retained. Clear the check box to retain special headers.

Clone separator change:

When this option is selected, the plug-in expects the plus character (+) as the clone separator.

This field corresponds to the ServerCloneID element in the plugin-cfg.xml file.

Some pervasive devices cannot handle the colon character (:) used to separate clone IDs in conjunction with session affinity. If this field is checked, you must also change the configurations of the associated application servers such that the application servers separates clone IDs with the plus character as well.

By default, this option is selected. Clear the field if you want to use the colon character to separate clone IDs.

Web server plug-in configuration service property

Use this page to view or change the configuration settings for the web server plug-in configuration service.

Note: This topic references one or more of the application server log files. Beginning in WebSphere Application Server Version 8.0 you can configure the server to use the High Performance Extensible Logging (HPEL) log and trace infrastructure instead of using `SystemOut.log`, `SystemErr.log`, `trace.log`, and `activity.log` files or native z/OS logging facilities. If you are using HPEL, you can access all of your log and trace information using the LogViewer command-line tool from your server profile bin directory. See the information about using HPEL to troubleshoot applications for more information on using HPEL.

If you are using a stand-alone application server, click **Servers > Server Types > WebSphere application servers > *server_name* > Administration Services > Web server plug-in configuration service** to view this administrative console page.

For a WebSphere Application Server, Network Deployment configuration, if you are using the deployment manager, click **System Administration > Deployment manager > Administration Services > Web server plug-in configuration service**.

Enable automated web server configuration processing

The web server plug-in configuration service is selected by default. The service automatically generates the plug-in configuration file whenever the web server environment changes, with a few exceptions. For example, the plug-in configuration file is regenerated whenever one of the following activities occurs:

- A new application is deployed on an associated application server
- The web server definition is saved
- An application is removed from an associated application server
- A new virtual host is defined

In WebSphere Application Server, Network Deployment configurations, the plug-in configuration file does not regenerate when:

- A cluster member is added to a cluster.
- TCP channel settings are updated for an application server.

By default, this option is selected. Clear the field to disable automated web server configuration processing.

Application Server property settings for a web server plug-in

Use this page to view or change application server settings for a web server plug-in.

To view this administrative console page, click **Servers > Server Types > WebSphere application servers > *server_name***, and then, in the Additional Properties section, click **Web server plug-in properties**.

Server Role

Specifies the role this application server is assigned.

Select **Primary** to add this application server to the list of primary application servers. The plug-in initially attempts to route requests to the application servers on this list.

Select Backup to add this application server to the list of backup application servers. The plug-in does not load balance across the backup application servers. A backup server is only used if a primary server is not available. When the plug-in determines that a backup application server is required, it goes through the list of backup servers, in order, until no servers are left in the list or until a request is successfully sent and a response received from one of the servers on this list.

Default setting Primary

Connection timeout

Specifies whether there is a limited amount of time during which the application server maintains a connection with the web server.

This field corresponds to the ConnectTimeout element in the plugin-cfg.xml file.

The setting for this field determines whether the plug-in performs non-blocking connections with the application server. Non-blocking connections are beneficial when the plug-in is unable to contact the destination to determine whether or not the port is available.

If the **Use connection timeout** setting is not selected, the plug-in performs nonblocking connections with the application server. If the **Use connection timeout** setting is selected, you must specify a value in the **seconds** field:

- If you specify a value greater than 0 in the **seconds** field, the plug-in waits the specified number for seconds to perform a successful connection. If a connection does not occur during that time interval, the plug-in marks the server unavailable, and sends the request to another application server in the cluster.
- If you specify a value of 0 in the **seconds** field, the plug-in performs a blocking connection.
- If you do not specify a value in the **seconds** field, the plug-in performs a blocking connection where the plug-in sits until the operating system times out, which might be as long as two minutes, depending on the platform, before it marks the server unavailable.

Data type Integer
Default 5

Use read/write timeout

Specifies whether there is a time limit for how long the plug-in waits to send a request to or receive a response from the application server.

This field corresponds to the ServerIOTimeout element in the plugin-cfg.xml file.

Select the **Use read/write timeout** property to set a read/write timeout. When you select this setting, you must specify the length of time, in seconds that the plug-in waits to send a request or to receive a response. When selecting a value to specify for this field, remember that it might take a couple of minutes for an application server to process a request. Setting the value too low might cause the plug-in to send a false server error response to the client. If the checkbox is not checked, the plug-in uses blocked I/O to write requests to and read responses from the application server until the TCP connection times out.

Note: The **Use read/write timeout** setting on the administrative console corresponds to the ServerIOTimeout attribute in the plugin-cfg.xml file. The default value for this setting is different from the default value in previous versions of the product.

Data type Integer
Default 900 seconds

Use maximum number of connections

Specifies the maximum number of pending connections to an Application Server that can be flowing through a web server process at any point in time.

This field corresponds to the `ServerMaxConnections` element in the `plugin-cfg.xml` file.

Select the **Use maximum number of connections** property to set a maximum number of connections. When you select this setting, you, must specify the maximum number of connections that can exist between the web server and the Application Server at any given point in time.

For example, assuming that:

- The application server is fronted by 5 nodes that are running an IHS web server.
- Each node starts 2 processes.
- This property is set to 50.

In this example, the application server could potentially get up to 500 connections. (You take the number of nodes, 5, multiply it by the number of processes, 2, and then multiply that number by the number specified for this property, 50, for a total of 500 connections.)

If this property is set to either zero or -1, there is no limit to the number of pending connections to the Application Servers.

Data type	Integer
Default	0

Use extended handshake to check whether application server is running

When selected, the web server plug-in uses an extended handshake to check whether the application server is running.

This field corresponds to the `ExtendedHandshake` element in the `plugin-cfg.xml` file.

Select this property if a proxy firewall is between the plug-in and the application server.

The plug-in marks a server as down when the `connect()` fails. However, when a proxy firewall is in between the plug-in and the application server, the `connect()` will succeed, even though the back end application server is down. This causes the plug-in to not failover correctly to another application server.

If the plug-in performs some handshaking with the application server to ensure that the application server is started before the plug-in sends a request, the plug-in can failover to another application server if it detects that the application server with which it is attempting to perform a handshake is not available.

By default, this field is not selected. Select this field if you want to use extended handshake to check whether an application server is running.

Send the header "100 Continue" before sending the request content

Specifies whether the web server plug-in sends the header "100 Continue" to the application server before it sends the request content.

This field corresponds to the `WaitForContinue` element in the `plugin-cfg.xml` file.

When selected, the web server plug-in sends the header "100 Continue" to the application server before it sends the request content.

By default, this field is not selected. Select this field to enable this function.

plugin-cfg.xml file

There are two types of plugin-cfg.xml files: application-centric and topology-centric.

An application-centric file has an application that is mapped to both web server and application server definitions. Changes that you make to the plug-in by using the administrative console persist to the plugin-cfg.xml file upon generation.

A topology-centric file represents everything that is defined in the environment. Typically, this plugin-cfg.xml file is used when you do not have web servers defined. Consider the following rules when you want to update a topology-centric plugin-cfg.xml file:

- If the plugin-cfg.xml file *exists* within the `app_server_root\dmgr\cells` directory, the plug-in generation process ignores the updated values from the **application server > Web Server Plugin Properties** panel of the administrative console and uses the existing values within the XML file. In this case, you must manually update the XML file for those values to persist.
- If the plugin-cfg.xml file *does not exist* within the `app_server_root\dmgr\cells` directory, the plug-in generation process creates a new plugin-cfg.xml file. The process persists the latest values that are set on the **Application Server > Web Server Plugin Properties** panel within the administrative console.

The design of this file and its related function enable the product to support different types of configurations. For example, web server definitions might not exist. In addition, many web server plug-in properties, such as RefreshInterval, LogLevel, and the Edge Side Include (ESI) processor properties, can be updated manually only. Those values must be maintained through each iteration.

The plugin-cfg.xml file includes the following elements and attributes. Unless indicated otherwise, you can specify each element and attribute only once within the plugin-cfg.xml file.

gotcha: Use the administrative console to set these properties for each web server definition. Any manual changes you make to the plug-in configuration file for each web server are overridden whenever the file is regenerated.

Note: You can update the *global* plugin-cfg.xml file using the administrative console or running the GenPluginCfg command for all of the clusters in a cell. However, you must delete the config/cells/plugin-cfg.xml file before you update the *global* plugin-cfg.xml file. If you do not delete the config/cells/plugin-cfg.xml file, only the new properties and their values are added to the *global* plugin-cfg.xml file. Any updates to existing plug-in property values are not added to the *global* plugin-cfg.xml file.

The file can include one or more of the following elements and attributes. The Config element is required.

- “Config” on page 75
- “IgnoreDNSFailures” on page 75
- “RefreshInterval” on page 75
- “ASDisableNagle” on page 75
- “IISDisableNagle” on page 75
- “VHostMatchingCompat” on page 76
- “AppServerPortPreference” on page 76
- “ResponseChunkSize” on page 76
- “AcceptAllContent” on page 76
- “ChunkedResponse” on page 76
- “IISPluginPriority” on page 77
- “TrustedProxyEnable” on page 77
- “TrustedProxyList” on page 77

- “SSLConsolidate” on page 77
- “plugin-cfg.xml file” on page 74
- “plugin-cfg.xml file” on page 74
- “Log” on page 77
- “Property Name=“esiEnable” Value=“true/false”” on page 78
- “Property Name=“esiMaxCacheSize” Value=“integer”” on page 78
- “Property Name=“ESIInvalidationMonitor” Value=“true/false” ” on page 78
- “Property Name=“FIPSEnable” Value=“true/false” ” on page 79
- “Property Name=“PluginInstallRoot” Value=“C:\IBM\WebSphere\Plugins” ” on page 79
- “ServerCluster” on page 79
- “VirtualHostGroup” on page 85
- “UriGroup” on page 85
- “Route” on page 86
- “RequestMetrics” on page 87

Config

This element, which is required, starts the HTTP plug-in configuration file.

IgnoreDNSFailures

Specifies whether the plug-in ignores DNS failures within a configuration when starting. When set to true, the plug-in ignores DNS failures within a configuration and starts successfully if at least one server in each server cluster is able to resolve the host name. Any server for which the host name cannot be resolved is marked *unavailable* for the life of the configuration. No attempts to resolve the host name are made during the routing of requests. If a DNS failure occurs, a log message is written to the plug-in log file, and the plug-in initialization continues rather than causing the web server not to start. The default value is false, meaning DNS failures cause the web server not to start.

RefreshInterval

Specifies the time interval, in seconds, at which the plug-in checks the configuration file to see if updates or changes have occurred. The plug-in checks the file for any modifications that have occurred since the last time the plug-in configuration was loaded.

In a development environment in which changes are frequent, a lower setting than the default setting of 60 is preferable. In production, a higher value than the default is preferable because updates to the configuration do not occur so often. If the plug-in reload fails for some reason, a message is written to the plug-in log file and the previous configuration is used until the plug-in configuration file successfully reloads. If you are not seeing the changes you made to your plug-in configuration, check the plug-in log file for indications of the problem.

ASDisableNagle

Specifies whether the user wants to disable the nagle algorithm for the connection between the plug-in and the application server. By default, the nagle algorithm is enabled.

The value can be true or false.

IISDisableNagle

Specifies whether the user wants to disable the nagle algorithm on Microsoft Internet Information Services (IIS). By default, the nagle algorithm is enabled.

The value can be `true` or `false`.

VHostMatchingCompat

Specifies that the port number is to be used for virtual host matching. Specify one of the following values:

- `true` if matching is to be done physically by using the port number for which the request was received.
- `false` if matching is to be done logically by using the port number contained in the host header.

The default value is `false`.

AppServerPortPreference

Specifies which port number the application server uses to build URIs for a `sendRedirect()` method. The following values can be specified:

- `hostHeader` if the port number from the host header of the HTTP request coming in is to be used.
- `webserverPort` if the port number on which the web server received the request is to be used.

The default value is `hostHeader`.

ResponseChunkSize

Specifies the maximum chunk size to use when reading the response body. For example, specify `Config ResponseChunkSize="N">`, where *N* equals the chunk size in kilobytes.

The plug-in reads the response body in 64 K chunks until all of the response data is read. This approach causes a performance problem for requests whose response body contains large amounts of data.

If the content length of the response body is unknown, a buffer size of *N* KBs is allocated and the body is read in *N* KB size chunks, until the entire body is read. If the content length is known, then a buffer size of either content length or *N* (whichever is less) is used to read the response body.

The default chunk size is 64 K.

AcceptAllContent

Specifies whether users can include content in POST, PUT, GET, and HEAD requests when a Content-Length or Transfer-encoding header is contained in the request header. You can specify one of the following values for this attribute:

- `True` if content is expected and read for all requests
- `False` if content is only expected and read for POST and PUT requests.

The default value is `True`.

ChunkedResponse

Specifies whether the plug-in must use chunks the response to the client when a Transfer-Encoding: Chunked response header is present in the response.

This attribute applies to the IIS, Oracle iPlanet, and Lotus Domino web servers only. The IBM HTTP Server automatically handles the chunking of the response to the client.

You can specify one of the following values for this attribute:

- `true` if the plug-in is to chunk the response to the client when a Transfer-Encoding: Chunked response header is present in the response.
- `false` if the response is not to be chunked.

The default value is `false`.

IISPluginPriority

Specifies the priority in which the IIS web server loads the WebSphere web server plug-in. Specify one of the following values for this attribute:

- High
- Medium
- Low

The default value is High.

Note: The IIS web server uses this value during startup. Therefore, you must restart the web server before this change takes effect.

Note: The default value of High ensures that all requests are handled by the WebSphere web server plug-in before they are handled by any other filter or extensions. If problems occur when using a priority of Medium or Low, you must rearrange the order or change the priority of the interfering filter or extension.

TrustedProxyEnable

Permits the web server plug-in to interface with the proxy servers and load balancers that are listed for the `TrustedProxyList` custom property. When this property is set to `true`, the proxy servers and load balancers in this trusted proxy list can set values for the `$WSRA` and `$WSRH` internal headers. The `$WSRA` internal header is the IP address of the remote host, which is typically the browser, or an internal address that is obtained by Network Address Translation (N.A.T.). The `$WSRH` internal header is the host name of the remote host. This header information enables the web server plug-in to interface with that specific proxy server or load balancer.

When you use this custom property you must also use the `TrustedProxyList` custom property to specify a list of trusted proxy servers and load balancers. Also, you must clear the Remove special headers check box on the Request Routing panel within the administrative console. For more information, see the documentation on web server plug-in request routing properties.

TrustedProxyList

Specifies a comma delimited list of all proxy servers or load balancers that have permission to interface with this web server plug-in. You must use this property with the `TrustedProxyEnable=true` custom property setting. If the `TrustedProxyEnable` custom property is set to `false`, this list is ignored.

SSLConsolidate

Specifies whether the web server plug-in is to compare the setup of each new SSL transport with the setup of other SSL transports that are already defined in the configuration file. When you set this property to `true`, and the plug-in determines that the keyring and `CertLabel` values specified for the new SSL transport match the values specified for an already defined SSL transport, the plug-in uses the existing SSL environment instead of creating a new SSL environment. Creating fewer SSL environments means that the plug-in requires less memory, and the plug-in initialization time decreases, thereby optimizing your overall GSKit environment.

Log

Describes the location and level of log messages that are written by the plug-in. If a log element is not specified within the configuration file, then, in some cases, log messages are written to the web server error log.

For example, you might specify the following line of code:

```
<Log LogLevel="Error" Name="/opt/WebSphere/AppServer60/logs/http_plugin.log"/>
```

- **Name**

Specifies the fully qualified path to the log file to which the plug-in writes error messages. Specify exactly one attribute for each log.

If the file does not exist, then one is created. If the file exists, then it is opened in append mode, and the previous plug-in log messages remain.

- **LogLevel**

Specifies the level of detail of the log messages that the plug-in writes to the log. Specify zero or one of the following values for each log.

Log Level Value	Log Level Description
Trace	All of the steps in the request process are logged in detail.
Stats	The server selected for each request and other load balancing information relating to request handling is logged.
Warn	All warning and error messages resulting from abnormal request processing are logged
Error	Only error messages resulting from abnormal request processing are logged
Debug	All of the critical steps performed in processing requests are logged.
Detail	All of the information about requests and responses are logged.

If a LogLevel value is not specified for the Log element, the default value, Error, is used.

Note: Be careful when setting the level to Trace. Multiple messages are logged at this level, which can consume disk space quickly. Do not use a Trace setting in a normally functioning environment because it adversely affects performance.

Property Name="esiEnable" Value="true/false"

Enables or disables the Edge Side Include (ESI) processor. If the ESI processor is disabled, the other ESI elements in this file are ignored.

You can set Value to true or false. By default, the ESI processor is enabled with its value set to true.

Property Name="esiMaxCacheSize" Value="integer"

Specifies, in 1 KB units, the maximum size of the cache. The default maximum size of the cache is 1024 KB (1 MB). If the cache is full, the first entry deleted from the cache is the entry that is closest its expiration time.

Property Name="ESIInvalidationMonitor" Value="true/false"

Specifies whether the ESI processor receives invalidations from the application server.

You can set Value to true or false. By default, this property is set to false.

Property Name="FIPSEnable" Value="true/false"

Specifies whether the Federal Information Processing Standard (FIPS) is enabled for making Secure Sockets Layer (SSL) connections to the application server. Set this property to true, if FIPS is enabled on the application server.

You can set Value value to true or false. By default, this property is set to false.

Property Name="PluginInstallRoot" Value="C:\IBM\WebSphere\Plugins"

Specifies the installation path for the plug-in. This property is mandatory if using the Global Security Kit (GSKit) because WebSphere Application Server supports the local installation of the GSKit instead of a global installation. The attribute value is set to a fully qualified path to the plug-in installation root.

Supported names recognized by the transport are keyring, stashfile, and password. By default, this property is set to none.

ServerCluster

Specifies a group of servers that are generally configured to service the same types of requests. Specify one or more clusters for each configuration.

In the simplest case, the cluster contains only one server definition. In the case in which more than one server is defined, the plug-in load balances across the defined servers by using either a Round Robin or a Random algorithm. The default algorithm is Round Robin.

The following code is an example of a ServerCluster element.

```
<ServerCluster Name="Servers">
  <ClusterAddress Name="ClusterAddr">
    <Transport Hostname="192.168.1.2" Port="9080" Protocol="HTTP"/>
    <Transport Hostname="192.168.1.2" Port="9443" Protocol="HTTPS">
      <Property Name="Keyring" value="c:/WebSphere/AppServer/keys/keyring.kdb"/>
      <Property Name="Stashfile" value="c:/WebSphere/AppServer/keys/keyring.sth"/>
    </Transport>
  </ClusterAddress>
  <Server Name="Server1">
    <Transport Hostname="192.168.1.3" Port="9080" Protocol="HTTP"/>
    <Transport Hostname="192.168.1.3" Port="9443" Protocol="HTTPS">
      <Property Name="Keyring" value="c:/WebSphere/AppServer/keys/keyring.kdb"/>
      <Property Name="Stashfile" value="c:/WebSphere/AppServer/keys/keyring.sth"/>
    </Transport>
  </Server>
  <Server Name="Server2">
    <Transport Hostname="192.168.1.4" Port="9080" Protocol="HTTP"/>
    <Transport Hostname="192.168.1.4" Port="9443" Protocol="HTTPS">
      <Property Name="Keyring" value="c:/WebSphere/AppServer/keys/keyring.kdb"/>
      <Property Name="Stashfile" value="c:/WebSphere/AppServer/keys/keyring.sth"/>
    </Transport>
  </Server>
  <Server Name="Server3">
    <Transport Hostname="192.168.1.5" Port="9080" Protocol="HTTP"/>
    <Transport Hostname="192.168.1.5" Port="9443" Protocol="HTTPS">
      <Property Name="Keyring" value="c:/WebSphere/AppServer/keys/keyring.kdb"/>
      <Property Name="Stashfile" value="c:/WebSphere/AppServer/keys/keyring.sth"/>
    </Transport>
  </Server>
  <PrimaryServers>
    <Server Name="Server1"/>
    <Server Name="Server2"/>
  </PrimaryServers>
</ServerCluster>
```

```

<BackupServers>
<Server Name="Server3"/>
</BackupServers>
</ServerCluster>

```

The z/OS PTF UK35083 package includes the SSL interface change for the z/OS HTTP Server, Version 5.3, that corresponds to this web server plug-in change. Therefore, you must apply this PTF to your system before the new web server plug-in SSL interface can function properly.

- | You must also include the SSLMODE=MULTI option in the httpd.conf file for the IBM HTTP Server for z/OS,
- | Version 5.3. The SSLMODE=ON option is not supported in Version 7.0 or higher.

If the SSLMode multi option is not specified in the httpd.conf file, or if you do not have the z/OS PTF UK35083 package applied to your system, you might receive error message IMW0584W. This message indicates that the SSL mode, which is specified for the HTTP Server, is not compatible with the SSL mode for the web server plug-in that is used with the IBM HTTP Server for z/OS, Version 5.3. In either of these situations, unpredictable results might occur.

For the web server plug-ins for both the IBM HTTP Server for z/OS, Version 5.3 and the IBM HTTP Server on z/OS powered by Apache:

- If you use a kdb file with a stashfile in the hierarchical file system (HFS), specify both the Property Name=keyring and the Property Name=stashfile elements, as shown in the preceding example.

- | **gotcha:** The format of the values you specify for these elements is different from what you specified in
- | earlier versions of the product.

- If you use a System Authorization Facility (SAF) keyring, instead of a kdb file, you must create the following two custom plug-in properties from the administrative console:

KeyringLocation

Specify the directory location of the SAF keyring as the value for this property. When you save this configuration change, this directory location becomes the value of the keyring property in the plugin-cfg.xml file.

StashfileLocation

Specify "" (null) as the value for this property. When you save this configuration change, "" (null) becomes the value of the stashfile property in the plugin-cfg.xml file

See “Web server plug-in configuration properties” on page 90 for instructions on how to create KeyringLocation and StashfileLocation from the administrative console.

Use the following example for the SAF keyring:

```

<Transport Hostname="appserver.example.com" Port="9443" Protocol="https">
<Property name="keyring" value="safkeyring:///SAF_keyring_name"/>
<Property Name="stashfile" value=""/>
</Transport>

```

- **Name**

Specifies the logical or administrative name to be used for this group of servers. Specify one attribute for each ServerCluster.

- **LoadBalance**

The following values can be specified for this attribute:

Round Robin

Random

The Round Robin implementation has a random starting point. the first application server is picked randomly. Round Robin is then used to pick application servers from that point forward. This implementation ensures that in multiple process based web servers, all of the processes don't start up by sending the first request to the same Application Server.

The Random implementation also has a random starting point. However with this implementation all subsequent servers are also randomly selected. Therefore, the same server might get selected repeatedly while other servers remain idle.

The default load balancing type is Round Robin.

- **IgnoreAffinityRequests**

Specifies whether the plug-in ignores the number of affinity requests made to a server when selecting servers based on the Round Robin algorithm. Specify zero or one attribute for each ServerCluster. The value is `true` or `false`. If the value is set to `false`, the number of affinity requests made is also taken into account in the server selection process.

The default value is `true`, which means the number of affinity requests made are not used in the Round Robin algorithm.

- **RetryInterval**

Specifies an integer value for the length of time that elapses from the time that a server is marked down to the time that the plug-in tries a connection again. The default is 60 seconds. Specify zero or one attribute for each ServerCluster.

- **RemoveSpecialHeaders**

The plug-in adds special headers to the request before it is forwarded to the application server. These headers store information about the request that is used by the application. By default, the plug-in removes these headers from incoming requests before adding the headers it is supposed to add. Specify zero or one attribute for each ServerCluster.

The value can be `true` or `false`. Setting the attribute to `false` introduces a potential security exposure by not removing headers from incoming requests.

- **CloneSeparatorChange**

Tells the plug-in to expect the plus character (+) as the clone separator. Some pervasive devices cannot handle the colon character (:) that is used to separate clone IDs in conjunction with session affinity. You must change application server configurations so that an application server separates clone IDs with the plus character as well. Specify zero or one attribute for each ServerCluster.

The value can be `true` or `false`.

- **PostSizeLimit**

The maximum number of KBs (1024 byte) blocks of request content allowed for the plug-in to attempt to send the request to an application server. If a request is received that is greater than this size, the plug-in fails the request. The default value is -1 byte, which indicates that there is no limit for the post size. Specify zero or one attribute for each ServerCluster.

- **PostBufferSize**

Specifies, in KBs, the maximum buffer size that is used when the content of an HTTP request is read. If the application server that initially receives a request cannot process that request, the data contained in this buffer is sent to another application server. It then attempts to have that application server process the request.

This option improves the availability of the plug-in. Pending requests with content are tried again if the selected application server is not responding. If the value is set to zero, the requests with content are not buffered and are not tried again. The default value is 64. Specify zero or one attribute for each ServerCluster.

- **Server**

Specifies a WebSphere Application Server instance that is configured to handle requests routed to it, based on the routing rules of the plug-in configuration. The server corresponds to an application server running on either the local machine or a remote machine. Specify zero or one attribute for each ServerCluster.

- **Name**

Specifies the administrative or logical name for the server. Specify exactly one attribute for each Server.

– **CloneID**

If this unique ID is present in the HTTP cookie header of a request, or the URL if using URL rewriting, the plug-in routes the request to this particular server, provided all other routing rules are met. If a CloneID is not specified in the server, then session affinity is not enabled for this server. There can be zero or one attribute for each Server.

This attribute is used with session affinity. When this attribute is set, the plug-in checks the incoming cookie header or URL for **JSESSIONID**. If **JSESSIONID** is found, then the plug-in looks for one or more clone IDs. If clone IDs are found, and a match is made to the value specified for this attribute, then the request is sent to this server rather than load balanced across the cluster.

Note: If you are not using session affinity, then remove these clone IDs from the configuration because there is added request processing in the plug-in when these values are set. If clone IDs are not in the plug-in, then it is assumed that session affinity is not enabled, and the request is load balanced across the cluster.

– **WaitForContinue**

Specifies whether to use the HTTP 1.1 100 Continue support before sending the request content to the application server. Possible attribute values are true or false. The default value is false; the plug-in does not wait for the 100 Continue response from the application server before sending the request content because it is a performance hit. Specify zero or one attribute for each Server.

This property is ignored for POST requests to prevent a failure from occurring if the application server closes a connection because of a keep-alive timeout.

Enable this function true when configuring the plug-in to work with certain types of proxy firewalls.

– **LoadBalanceWeight**

Specifies the weight associated with this server when the plug-in performs weighted Round Robin load balancing. Specify zero or one attribute for each Server. The starting value for a server can be any integer between 0 and 20. However, specify zero only for a server that is not running.

The LoadBalanceWeight value for each server is decremented for each request that is processed by that server. After the weight for a particular server in a server cluster reaches zero, only requests with session affinity are routed to that server. When all servers in the cluster reach a weight of zero, the weights for all servers in the cluster are reset, and the algorithm restarts.

Note: When a server is not running, set the weight for that server to zero. The plug-in can then reset the weights of the servers that are still running, and maintain proper load balancing.

– **ConnectTimeout**

Enables the plug-in to perform non-blocking connections with the application server. Non-blocking connections are beneficial when the plug-in is unable to contact the destination to determine if the port is available or unavailable. Specify zero or one attribute for each Server.

If a ConnectTimeout value is not specified, the plug-in performs a blocking connect in which the plug-in sits until an operating system times out (as long as 2 minutes depending on the platform) and allows the plug-in to mark the server *unavailable*. A value of 0 causes the plug-in to perform a blocking connect. A value greater than 0 specifies the number of seconds you want the plug-in to wait for a successful connection. If a connection does not occur after that time interval, the plug-in marks the server *unavailable* and fails over to one of the other servers defined in the cluster. The default value is 5 seconds.

– **ExtendedHandshake**

Is used when a proxy firewall is between the plug-in and the application server. In such a case, the plug-in is not failing over, as expected. Specify zero or one attribute for each Server.

The plug-in marks a server as down when the connect() method fails. However, when a proxy firewall is in between the plug-in and the application server, the connect() method succeeds, even though the back-end application server is down. This causes the plug-in to not failover correctly to other application servers.

The plug-in performs some handshaking with the application server to ensure that it is started before sending the request. This scenario enables the plug-in to failover in the event the application server is down.

The value can be true or false.

– **MaxConnections**

Specifies the maximum number of pending connections to an application server that can be flowing through a web server process at any point in time. Specify one element for each Server.

For example, in the following scenario:

- The application server is fronted by five nodes that are running an IBM HTTP Server.
- Each node starts two processes.
- The MaxConnections attribute is set to 50.

In this example, the application server can potentially get up to 500 connections. Multiply the number of nodes, 5, by the number of processes, 2, and then multiply that number by the number specified for the MaxConnections attribute, 50, for a total of 500 connections.

By default, MaxConnections is set to -1. If this attribute is set to either zero or -1, there is no limit to the number of pending connections to the application servers.

– **Transport**

Specifies the transport for reading and writing requests to a particular WebSphere Application Server instance. The transport provides the information that is necessary to determine the location of the application server to which the request is sent. If the server has multiple transports that are defined to use the same protocol, the first one is used. Specify one or more elements for each Server.

It is possible to configure the server to have one non-secure transport and one that uses SSL. In this configuration, a match of the incoming request protocol is performed to determine the appropriate transport to use to send the request to the application server.

- **Hostname**

Specifies the host name or IP address of the machine on which the WebSphere Application Server instance is running. There is exactly one attribute for each transport.

- **Port**

Specifies the port on which the WebSphere Application Server instance is listening. There is exactly one attribute for each transport.

- **Protocol**

Specifies the protocol to use when communicating over this transport -- either HTTP or HTTPS. There is exactly one attribute for each transport.

– **Property**

Specify zero, one, or more elements for each transport. When the protocol of the transport is set to HTTPS, use this element to supply the various initialization parameters, such as password, keyring and stashfile. For example, the portion of the plugin-cfg.xml file containing these elements might look like the following code:

```
<Transport Hostname="192.168.1.2" Port="9443" Protocol="HTTPS">
<Property Name="keyring" value="c:/WebSphere/AppServer/keys/keyring.kdb"/>
<Property Name="stashfile" value="c:/WebSphere/AppServer/keys/keyring.sth"/>
<Property Name="password" value="WebAS"/>
```

- **Name**

Specifies the name of the property that is being defined. Supported names recognized by the transport are keyring, stashfile, and password.

Note: The only name that can be specified for the WebSphere HTTP plug-in for z/OS is password. If you specify keyring and stashfile, they are ignored.

Specify exactly one attribute for each Property.

- **Value**

Specifies the value of the property being defined. Specify exactly one attribute for each property.

– ServerIOTimeout

Enables the plug-in to set a timeout value, in seconds, for sending requests to and reading responses from the application server.

If you set the ServerIOTimeout attribute to a positive value, this attempt to contact the server ends when the timeout occurs. However, the server is not considered unavailable and future requests are still sent to the server on which the unavailable timeout occurred.

If you set the ServerIOTimeout attribute to a negative value, the server is considered unavailable whenever a timeout occurs, and no future requests are sent to the server on which the timeout occurred.

If a value is not set for the ServerIOTimeout attribute, the plug-in, by default, uses blocked I/O to write request to and read response from the application server until the TCP connection times out. For example, you might specify the following setting:

```
<Server Name="server1" ServerIOTimeout=300>
```

In this situation, if an application server stops responding to requests, the plug-in waits 300 seconds (5 minutes) before timing out the TCP connection. Setting the ServerIOTimeout attribute to a reasonable value enables the plug-in to timeout the connection sooner, and transfer requests to another application server when possible.

When selecting a value for this attribute, remember that sometimes it might take several minutes for an application server to process a request. Setting the value of the ServerIOTimeout attribute too low might cause the plug-in to send a false server error response to the client.

The default value is 900, which is equivalent to 15 minutes.

Note: The ServerIOTimeout limits the amount of time the plug-in waits for each individual read or write operation to return. ServerIOTimeout does not represent a timeout for the overall request.

For additional recommendations on how to configure the ServerIOTimeout attribute, see the web server plug-in configuration technote on the IBM Support website.

• ClusterAddress

A ClusterAddress is like a server element in that you can specify the same attributes and elements as for a server element. The difference is that you can define only one of them within a ServerCluster. Use a ClusterAddress when you do not want the plug-in to perform any type of load balancing because you already have some type of load balancer in between the plug-in and the application server.

Note: If you include a ClusterAddress tag, you must include the Name attribute on that tag. The plug-in uses the Name attribute to associate the cluster address with the correct host and port. If you do not specify the Name attribute, the plug-in assigns the cluster address the name that is specified for the server that is using the same host and port.

```
<ClusterAddress Name="MyClusterAddr">  
<Transport Hostname="192.168.1.2" Port="9080" Protocol="HTTP"/>  
<Transport Hostname="192.168.1.2" Port="9443" Protocol="HTTPS">  
</ClusterAddress>
```

If a request comes in that does not have affinity established, the plug-in routes it to the cluster address, if defined. If affinity has been established, then the plug-in routes the request directly to the clone, bypassing the cluster address entirely. If no cluster address is defined for the server cluster, then the plug-in load balances across the servers in the primary servers list.

There can be zero or one element for each ServerCluster.

• PrimaryServers

Specifies a list of servers to which the plug-in routes requests for this cluster. If a list of primary servers is not specified, the plug-in routes requests to servers defined for the server cluster. Specify zero or one element for each ServerCluster.

• BackupServers

Specifies a list of servers to which requests are sent if all servers that are specified in the primary servers list are unavailable. The plug-in does not load balance across the backup servers, but traverses the list in order until no servers are left in the list or until a request is successfully sent and a response is received from an application server. Specify zero or one element for each ServerCluster.

VirtualHostGroup

Specifies a group of virtual host names that are specified in the HTTP Host header. Use this property to group virtual host definitions together that are configured to handle similar types of requests.

The following example shows a `VirtualHostGroup` element and associated elements and attributes:

```
<VirtualHostGroup Name="Hosts">
<VirtualHost Name="www.x.com"/>
<VirtualHost Name="www.x.com:443"/>
<VirtualHost Name="*:8080"/>
<VirtualHost Name="www.x.com:*/>
<VirtualHost Name="*:*/>
</VirtualHostGroup>
```

- **Name**

Specifies the logical or administrative name to be used for this group of virtual hosts. Specify exactly one attribute for each `VirtualHostGroup`.

- **VirtualHost**

Specifies the name used for a virtual or real machine used to determine if incoming requests must be handled by WebSphere Application Server. Use this element to specify host names that are in the HTTP Host header which must be seen for requests that need to be handled by the application server. You can specify specific host names and ports for incoming requests or specify an asterisk (*) for either the host name, port, or both.

There can be one or more elements for each `VirtualHostGroup`.

- **Name**

Specifies that the name in the HTTP Host header that matches the name in the `VirtualHost`. Specify exactly one attribute for each `VirtualHost`.

The value is a host name or IP address and port combination, separated by a colon.

You can configure the plug-in to route requests to the application server based on the incoming HTTP Host header and port for the request. The `Name` attribute specifies those combinations.

You can use a wildcard for this attribute. The only acceptable solutions are either an asterisk (*) for the host name, an asterisk for the port, or an asterisk for both. An asterisk for both means that any request matches this rule. If no port is specified in the definition, the default HTTP port of 80 is assumed.

UriGroup

Specifies a group of URIs that are specified on the HTTP request line. The same application server must be able to handle the URIs. The route compares the incoming URI with the URIs in the group to determine if the application server handles the request.

The following example shows a `UriGroup` element and associated elements and attributes:

```
<UriGroup Name="Uris">
<Uri Name="/servlet/snoop"/>
<Uri Name="/webapp/*"/>
<Uri Name="*.jsp"/>
</UriGroup>
```

- **Name**

Specifies the logical or administrative name for this group of URIs. Specify exactly one attribute for each `UriGroup`.

- **Uri**

Specifies the virtual path to the resource that is serviced by WebSphere Application Server. Each URI specifies the incoming URLs that the application server needs to handle. You can use a wildcard in these definitions. There can be one or more attributes for each UriGroup.

- **Name**

Specifies the actual string to specify in the HTTP request line to match successfully with this URI. You can use a wildcard within the URI definition. You can specify rules such as *.jsp or /servlet/* to be handled by WebSphere Application Server. When you assemble your application, if you specify **File Serving Enabled**, then only a wildcard URI is generated for the web application, regardless of any explicit servlet mappings. If you specify **Serve servlets by classname**, then the following URI is generated: `<Uri Name="Web_application_URI/servlet/*">`

There is exactly one attribute for each URI.

- **AffinityCookie**

Specifies the name of the cookie that the plug-in uses when trying to determine if the inbound request has session affinity. The default value is **JSESSIONID**.

See the description of the CloneID attribute for additional session affinity information.

There can be zero or one attribute for each URI.

- **AffinityURLIdentifier**

Specifies the name of the identifier that the plug-in uses when trying to determine if the inbound request has affinity specified in the URL to a particular clone. The default value is **jsessionid**.

See the description of the CloneID attribute for additional session affinity information.

There can be zero or one attribute for each URI.

Route

Specifies a request routing rule by which the plug-in determines if an incoming request must be handled by WebSphere Application Server.

The route definition is the central element of the plug-in configuration. It specifies how the plug-in handles requests, based on certain characteristics of the request. The route definition contains the other main elements: a required ServerCluster, and either a VirtualHostGroup, UriGroup, or both.

Using the information that is defined in the VirtualHostGroup and the UriGroup for the route, the plug-in determines if the incoming request to the web server is sent on to the ServerCluster element that is defined in this route.

See the following example of this element:

```
<Route VirtualHostGroup="Hosts" UriGroup="Uris" ServerCluster="servers"/>
```

- **VirtualHostGroup**

Specifies the group of virtual hosts that are used in route determination. The incoming host header and server port are matched to determine if this request is handled by the application server.

It is possible to omit this property from the route definition. If it is not present, then every request matches during the virtual host match portion of route determination.

There can be zero or one attribute for each Route.

- **UriGroup**

Specifies the group of URIs to use for determining the route. Select zero or one group for each route. The incoming URI for the request is matched to the defined URIs in this group to determine whether this request is handled by the application server.

It is possible to omit this property from the route definition. If it is not present, then every request matches during the URI match portion of route determination.

- **ServerCluster**

Specifies the cluster that receives the requests that successfully matches the route. Select exactly one cluster for each route.

The cluster is used to handle this request. If both the URI and the virtual host matching is successful for this route, then the request is sent to one of the servers that is defined within this cluster.

RequestMetrics

Used to determine whether request metrics are enabled, and how to filter the requests based on the Internet Protocol (IP) and Uniform Resource Identifiers (URI) filters when request metrics are enabled.

See the following example of this element:

```
<RequestMetrics armEnabled="false" loggingEnabled="true"
  rmEnabled="false" traceLevel="PERF_DEBUG">
```

- **armEnabled**

Specifies whether the ARM 4 agent is enabled in the plug-in. When it is set to `true`, the ARM 4 agent is called.

Note: For the SunOne (iPlanet) web Server the following directive must be included in the `obj.conf` file to enable ARM 4 support:

```
AddLog fn="as_term"
```

If this directive is not included, the `arm_stop` procedure is never called.

Select zero or one attribute for RequestMetrics

- **loggingEnabled**

Specifies whether request metrics logging is enabled in the plug-in. When it is set to `true` and the `traceLevel` is not set to `NONE`, the request response time, and other request information, is logged. When it is set to `false`, there is no request logging. The value of `loggingEnabled` depends on the value specified for the system property, `com.ibm.websphere.pmi.reqmetrics.loggingEnabled`. When this system property is not present, `loggingEnabled` is set to `true`. Specify exactly one attribute for RequestMetrics.

- **rmEnabled**

Specifies whether the request metrics are enabled in the plug-in. When it is set to `true`, the plug-in, request metrics, inspects the filters and logs the request trace record in the plug-in log file. This action is performed if a request passes the filters. When this attribute is set to `false`, the rest of the request metrics attributes are ignored. Specify exactly one attribute for RequestMetrics.

- **traceLevel**

Indicates how much information is logged when the `rmEnabled` attribute is set to `true`. When this attribute is set to `NONE`, no request logging is performed. When this attribute is not set to `NONE`, and `loggingEnabled` is set to `true`, the request response time, and other request information, is logged when the request is done. Specify exactly one attribute for RequestMetrics.

- **filters**

When `rmEnabled` is `true`, the filters control which requests are traced. Specify zero, one, or two attributes for RequestMetrics.

- **enable**

When `enable` is `true`, the type of filter is on and requests must pass the filter. Specify exactly one attribute for each filter.

- **type**

There are two types of filters: `SOURCE_IP` (for example, client IP address) and `URI`. For the `SOURCE_IP` filter type, requests are filtered based on a known IP address. You can specify a mask for an IP address using the asterisk (*). If the asterisk is used, the asterisk must always be the last character of the mask, for example `127.0.0.*`, `127.0.*`, `127*`. For performance reasons, the pattern matches character by character, until either an asterisk is found in the filter, a mismatch occurs, or the filters are found as an exact match.

For the URI filter type, requests are filtered based on the URI of the incoming HTTP request. The rules for pattern matching are the same as matching SOURCE_IP address filters.

If both URI and client IP address filters are enabled, request metrics requires a match for both filter types. If neither is enabled, all requests are considered a match.

There is exactly one attribute for each filter.

- **filterValues**

Specifies the detailed filter information. Specify one or multiple attributes for each filter.

- **value**

- Specifies the filter value for the corresponding filter type. This value might be either a client IP address or a URI. Specify exactly one attribute for each filterValue.

- **enableESIToPassCookies**

Specifies whether to allow forwarding of session cookies to WebSphere Application Server when processing ESI include requests. If the value is set to `true`, this custom property is enabled. If the value is set to `false`, the custom property is disabled. By default, the value is set to `false`.

- **GetDWLMTable**

Specifies whether to allow a newly created plug-in process to proactively request a partition table from WebSphere Application Server before it handles any HTTP requests. This custom property is used only when memory-to-memory session management is configured. If the value is set to `true`, this custom property is enabled. If the value is set to `false`, the custom property is disabled. By default, the value is set to `false`.

Web server plug-in custom properties

If you are using a web server plug-in, you can add one or more of the following custom properties to the configuration settings for that plug-in.

Complete these steps to add a web server plug-ins custom property.

1. In the administrative console, select **Servers > Server Types > Web servers > *web_server_name* > Plug-in properties > Custom properties > New**.
2. Under **General Properties**, specify the name of the custom property in the **Name** field and a value for this property in the **Value** field. You can also specify a description of this property in the **Description** field.
3. Click **Apply** or **OK**.
4. Click **Save** to save your configuration changes.
5. Re-generate and propagate the `plugin-cfg.xml` file.

Note: You can update the *global* `plugin-cfg.xml` file using the administrative console or running the `GenPluginCfg` command for all of the clusters in a cell. However, you must delete the `config/cells/plugin-cfg.xml` file before you update the *global* `plugin-cfg.xml` file. If you do not delete the `config/cells/plugin-cfg.xml` file, only the new properties and their values are added to the *global* `plugin-cfg.xml` file. Any updates to existing plug-in property values are not added to the *global* `plugin-cfg.xml` file.

CertLabel

Specifies the label of the certificate within the keyring that the plug-in is to use when the web container requests a client certificate from the plug-in. This custom property does not apply to any client certificate that is coming from the SSL connection with the browser. If you are using an SSL co-processor, and the plug-in is not running on a z/OS or IBM i system, if you specify the token label, followed by a colon, as the value for this custom property the entire `CertLabel` value is used as the keyring label.

gotcha: You can only use this custom property if you are running on Version 7.0.0.3 or later.

Data type	Boolean
Default	False

GetDWLMTable

Specifies whether the plug-in should prefetch the partition table. When this custom property is enabled, the plugin prefetches the partition table so that affinity requests are maintained. The GetDWLMTable custom property must be enabled when memory-to-memory session management is configured for WebSphere Application Server.

Data type	String
Default	False

HTTPMaxHeaders

Specifies the maximum number of headers that can be included in a request or response that passes through the web server plug-in. If a request or response contains more than the allowable number of headers, the web server plug-in drops the extra headers.

Data type	Integer
Range	1 - 4000
Default	300

If you prefer, instead of adding this custom property, you can manually add the following values to the plugin-cfg.xml file:

```
HTTPMaxHeaders = "<value>" in the Config tag. Example :
<Config ASDisableNagle="false" AcceptAllContent="false"
AppServerPortPreference="HostHeader" ChunkedResponse="false"
FIPSEnable="false" HTTPMaxHeaders="2500"
IISDisableNagle="false" IISPluginPriority="High"
IgnoreDNSFailures="false" RefreshInterval="60"
ResponseChunkSize="64" VHostMatchingCompat="false">
```

SSLConsolidate

Specifies whether the web server plug-in is to compare the setup of each new SSL transport with the setup of other SSL transports that are already defined in the configuration file. When you set this property to true, and the plug-in determines that the keyring and CertLabel values specified for the new SSL transport match the values specified for an already defined SSL transport, the plug-in uses the existing SSL environment instead of creating a new SSL environment. Creating fewer SSL environments means that the plug-in requires less memory, and the plug-in initialization time decreases, thereby optimizing your overall GSKit environment.

Data type	Boolean
Default	False

TrustedProxyEnable

Permits the web server plug-in to interface with the proxy servers and load balancers that are listed for the TrustedProxyList custom property. When this property is set to true, the proxy servers and load balancers in this trusted proxy list can set values for the \$WSRA and \$WSRH internal headers. The \$WSRA internal header is the IP address of the remote host, which is typically the browser, or an internal address that is

obtained by Network Address Translation (N.A.T.). The \$WSRH internal header is the host name of the remote host. This header information enables the web server plug-in to interface with that specific proxy server or load balancer.

When you use this custom property you must also use the TrustedProxyList custom property to specify a list of trusted proxy servers and load balancers. Also, you must clear the Remove special headers check box on the Request Routing panel within the administrative console. For more information, see the documentation on web server plug-in request routing properties.

Data type Boolean
Default False

TrustedProxyList

Specifies a comma delimited list of all proxy servers or load balancers that have permission to interface with this web server plug-in. You must use this property with the TrustedProxyEnable=true custom property setting. If the TrustedProxyEnable custom property is set to false, this list is ignored.

Example:

TrustedProxyList = myProxyServer1.myDomain.com,myProxyServer2.com,192.168.0.1

Data type String
Default None

Web server plug-in configuration properties

Web server plug-in configuration properties are set on various panels of the administrative console. The table provided indicates on which panel a particular property is set.

Table 10. Web server plug-in configuration properties. The following table indicates which panel in the administrative console you need to use to manually configure a web server plug-in property.

Administrative console panel	Field name	Configuration property name
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties	Refresh configuration interval	RefreshInterval
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties	Plug-in log file name	Log->name
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties	Plug-in logging	Log->LogLevel
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties	Ignore DNS failures during web server startup	IgnoreDNSFailures
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties	KeyringLocation	Keyring

Table 10. Web server plug-in configuration properties (continued). The following table indicates which panel in the administrative console you need to use to manually configure a web server plug-in property.

In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties	StashfileLocation	Stashfile
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Custom properties > New	FIPSEnable	FIPSEnable
In the administrative console, click Servers > Web Servers > Web_server_name > Plug-in properties > Custom properties > New	TrustedProxyEnable	TrustedProxyEnable
In the administrative console, click Servers > Web Servers > Web_server_name > Plug-in properties > Custom properties > New	TrustedProxyList	TrustedProxyList
In the administrative console, click Servers > Web Servers > Web_server_name > Plug-in properties > Custom properties > New	SSLConsolidate	SSLConsolidate
In the administrative console, click Servers > Server Types > Web servers > Web_server_name > Plug-in properties > Request routing	Load balancing option	LoadBalance
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request Routing	Clone separator change	CloneSeparatorChange
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request Routing	Retry interval	RetryInterval
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request routing	Maximum size of request content	PostSizeLimit
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request routing	Size of the buffer that is used to cache POST requests	PostBufferSize

Table 10. Web server plug-in configuration properties (continued). The following table indicates which panel in the administrative console you need to use to manually configure a web server plug-in property.

In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request routing	Remove special headers	RemoveSpecialHeaders
In the administrative console, click Servers > Server Types > WebSphere application servers > server_name > Web server plug-in properties	Server role	PrimaryServers and BackupServers list
In the administrative console, click Servers > Server Types > WebSphere application servers > server_name > Web server plug-in properties	Connect timeout	Server ConnectTimeout
In the administrative console, click Servers > Server Types > WebSphere application servers > server_name , and then, in the Additional Properties section, click Web server plug-in properties .	The read and write timeouts for all the connections to the application server	ServerIOTimeout
In the administrative console, click Servers > Server Types > WebSphere application servers > server_name > Web server plug-in properties	Use extended handshake to check whether Application Server is running	Server Extended Handshake
In the administrative console, click Servers > Server Types > WebSphere application servers > server_name > Web server plug-in properties	Send the header "100 Continue" before sending the request content	WaitForContinue
In the administrative console, click Servers > Server Types > WebSphere application servers > server_name > Web server plug-in properties	Maximum number of connections that can be handled by the Application Server	Server MaxConnections
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and Response	Application server port preference	AppServerPortPreference
In the administrative console, click Servers > Web Servers > Web_server_name > Plug-in properties > Request and Response	Enable Nagle algorithm for connections to the Application Server	ASDisableNagle
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and Response	Enable Nagle Algorithm for the IIS Web Server	IISDisableNagle

Table 10. Web server plug-in configuration properties (continued). The following table indicates which panel in the administrative console you need to use to manually configure a web server plug-in property.

In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and Response	Virtual host matching	VHostMatchingCompat
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and Response	Maximum chunk size used when reading the response body	ResponseChunkSize
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and Response	Accept content for all requests	AcceptAllContent
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and Response	Chunk HTTP response to the client	ChunkedResponse
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Request and Response	Priority used by the IIS Web Server when loading the plug-in configuration file	IISPluginPriority
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Caching	Enable Edge Side Include (ESI) processing to cache the responses	ESIEnable
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Caching	Maximum cache size	ESIMaxCacheSize
In the administrative console, click Servers > Server Types > Web servers > web_server_name > Plug-in properties > Caching	Enable invalidation monitor to receive notifications	ESIInvalidationMonitor
In the administrative console, click Servers > Web Servers > Web_server_name > Plug-in properties > Caching	Forwarding of session cookies to WebSphere Application Server.	enableESIToPassCookies

Web server plug-in tuning tips

Important tips for web server plug-in tuning include how to balance workload and improve performance in a high stress environment. Balancing workloads among application servers in a network fronted by a web server plug-in helps improve request response time.

Balancing workloads

During normal operation, the backlog of connections pending to an application server is bound to grow. Therefore, balancing workloads among application servers in a network fronted by a web server plug-in helps improve request response time.

You can limit the number of connections that can be handled by an applications server. To do this:

1. Go to the **Servers > Server Types > WebSphere application servers > *server_name***.
2. In the Additional Properties section, click **Web Server Plug-in properties** .
3. Select **Use maximum number of connections** for the Maximum number of connections that can be handled by the Application server field.
4. Specify in the Connections field the maximum number of connections that you want to allow.
5. Then click **Apply** and **Save**.

When this maximum number of connections is reached, the plug-in, when establishing connections, automatically skips that application server, and tries the next available application server. If no application servers are available, an HTTP 503 response code will be returned to the client. This code indicates that the server is currently unable to handle the request because it is experiencing a temporary overloading or because maintenance is being performed.

The capacity of the application servers in the network determines the value you specify for the maximum number of connections. The ideal scenario is for all of the application servers in the network to be optimally utilized. For example, if you have the following environment:

- There are 10 application servers in a cluster.
- All of these application servers host the same applications (that is, Application_1 and Application_2).
- This cluster of application servers is fronted by five IBM HTTP Servers.
- The IBM HTTP Servers get requests through a load balancer.
- Application_1 takes approximately 60 seconds to respond to a request
- Application_2 takes approximately 1 second to respond to a request.

Depending on the request arrival pattern, all requests to Application_1 might be forwarded to two of the application servers, say Appsvr_1 and Appsvr_2. If the arrival rate is faster than the processing rate, the number of pending requests to Appsvr_1 and Appsvr_2 can grow.

Eventually, Appsvr_1 and Appsvr_2 are busy and are not able to respond to future requests. It usually takes a long time to recover from this overloaded situation.

If you want to maintain 2500 connections, and optimally utilize the Application Servers in this example, set the number of maximum connections allowed to 50. (This value is arrived at by dividing the number of connections by the result of multiplying the number of Application Servers by the number of web servers; in this example, $2500/(10 \times 5) = 50$.)

Limiting the number of connections that can be established with an application server works best for web servers that follow use a single, multithreaded process for serving requests.

ServerLimit	1
ThreadLimit	1024
StartServers	1
MaxClients	1024
MinSpareThreads	1
MaxSpareThreads	1024
ThreadsPerChild	1024
MaxRequestsPerChild	0

Improving performance in a high stress environment

To tune the TcpTimedWaitDelay setting, change the value of the tcp_time_wait_interval parameter from the default value of 240 seconds, to 30 seconds:

1. Locate in the Windows Registry:

```
HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services\tcpip\Parameters\TcpTimedWaitDelay
```

If this entry does not exist in your Windows Registry, create it by editing this entry as a new DWORD item.

2. Specify, in seconds, a value between 30 and 300 inclusive for this entry. (It is recommended that you specify a value of 30.)

To tune the MaxUserPort setting:

1. Locate in the Windows Registry:

```
HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services\tcpip\Parameters\MaxUserPort
```

If this entry does not exist in your Windows Registry, create it by editing this entry as a new DWORD item.

2. Set the maximum number of ports to a value between 5000 and 65534 ports, inclusive. (It is recommended that you specify a value of 65534.)

See the Microsoft website for more information about these settings.

Chapter 3. Using the DataPower appliance manager

The DataPower® appliance manager automatically starts if you issue a request to the DataPower appliance manager and it is not already started. You can initiate a request using the wsadmin tool, or by selecting any of the administrative console pages that enable you to view or change settings for DataPower appliances, firmware, or managed sets, or the administrative console page that is used to monitor DataPower appliance manager tasks. The appliance manager also automatically starts when the deployment manager starts if there are any DataPower appliances configured in the appliance manager.

Before you begin

The first time that you use the DataPower appliance manager, you must add at least one appliance to the appliance manager. Before adding an appliance to the appliance manager, you must verify that:

- The appliance that you are adding is at a Version 3.6.0.4 or higher firmware level. The appliance manager cannot manage an appliances that is not at a Version 3.6.0.4 or higher firmware level.
- The appliance manager can communicate with the port that is used for the XML Management interface AMP endpoint on the appliance. The appliance manager uses this port to send commands to an appliance.
- The appliance can communicate with the port that is used for the DataPowerMgr_inbound_secure endpoint on the deployment manager. The appliance uses this port to send events to the appliance manager.
- The Appliance Management Protocol (AMP) endpoint is enabled for each appliance. If the XML Management interface AMP endpoint was disabled during installation, use the DataPower WebGUI to enable the AMP endpoint.
- There is not a firewall between the deployment manager and the appliances that will be part of a managed set. If there is a firewall between the deployment manager and the appliances, that firewall might prevent the appliance manager from communicating with the appliances in a managed set.

gotcha: Remember that the XML management interface port, which defaults to port number 5550, is different from the Web Management Service port, which defaults to port number 9090. The DataPower appliance manager uses the XML management interface port to manage the DataPower appliances. You use the Web Management Service port to access the WebGUI on the DataPower appliance. You can use the same user ID and password to access both the XML management interface and the WebGUI.

About this task

When the DataPower appliance manager starts, it automatically starts the channel chain which causes a bind to the port that is defined for the DataPower appliance manager.

To access the DataPower appliance manager, in the administrative console, click **Servers > DataPower**, and then perform one or more of the following actions. As previously stated, if this is the first time that you are using the DataPower appliance manager, you must add at least one appliance to the appliance manager before completing any of the other actions.

If you need to shut down the DataPower appliance manager, in the administrative console, click **Servers > DataPower > Appliance manager**, and then click **Shutdown Manager**.

Procedure

- Add an appliance to the DataPower appliance manager.
- Add a new firmware version to the DataPower appliance manager.
- Create a new managed set.

- Monitor the tasks that are queued for the DataPower appliance manager
- Modify appliance manager settings.
- Manage the DataPower appliance domains.
- View the managed domains history.
- Manage versions of sharable appliance settings.

What to do next

You can configure Secure Sockets Layer (SSL) for the DataPower appliance manager.

WebSphere DataPower appliance manager overview

WebSphere DataPower appliance manager provides a set of capabilities for managing sets of appliances. DataPower appliance manager can be used to manage appliances with a 3.6.0.4 or higher level of firmware.

IBM® WebSphere® DataPower SOA Appliances are purpose-built, easy-to-deploy network devices that simplify, help secure, and accelerate your XML and Web services deployments.

The first time you use DataPower appliance manager, you must add appliances, firmware versions, and managed sets. Verify that each appliance that you want to add has a 3.6.0.4 or higher level of firmware. Also verify that the Appliance Management Protocol (AMP) endpoint is enabled for each appliance. If the XML Management interface AMP endpoint was disabled during installation, use the DataPower WebGUI to enable the AMP endpoint.

For security reasons, the DataPower appliance manager does not include Crypto material, such as keys and certificates, in the shareable settings and domain versions that it creates. Therefore, after you add or replace an appliance, you must manually add any Crypto material that you want to apply for that appliance.

gotcha: The DataPower WebGUI is different from the WebSphere Application Server administrative console that you use to administer the DataPower appliance manager. The DataPower WebGUI is a separate user interface on the DataPower appliance that is used to configure the appliance.

Managed sets

A managed set is a collection of appliances that share the same hardware type, model type, and feature license set. A managed set synchronizes sharable appliance settings, managed domains, and firmware across multiple appliances.

A managed set can contain one or more appliances. An appliance is not actively managed unless it is a member of a managed set. You must first add an appliance to the DataPower appliance manager, and then add the appliance to a managed set.

Sharable appliance settings

Sharable appliance settings are the global attributes for an appliance that can be shared with other appliances. For example, NTP configuration and SNMP configuration are sharable appliance settings, but appliance-specific settings, such as IP address and role-based management attributes are not sharable appliance settings,

Sharable appliance settings are not managed until an appliance is added to a managed set. After you add an appliance to a managed set, any changes that you make to the sharable appliance settings, using the DataPower WebGUI or command line interface, are synchronized from the master appliance to all of the subordinate appliances in the managed set.

Master appliances

The master appliance is the appliance in the managed set that is used to synchronize sharable appliance settings and managed domains for all appliances within the managed set. Each managed set must have at least one master appliance. Each managed set might also have subordinate appliances.

All subordinate appliances are synchronized with the master appliance, and have the same sharable appliance settings and managed domains as the master appliance. You use the DataPower WebGUI or command line interface to change the sharable appliance settings, or a managed domain on a master appliance. The DataPower command line interface is a command line user interface on the DataPower appliance that can be used to configure the appliance.

Sharable appliance settings and managed domains on subordinate appliances are automatically overwritten whenever a change is made to the master appliance. If you use the DataPower WebGUI or the DataPower command line interface to change the sharable appliance settings, or a managed domain on a master appliance, the appliance manager detects the change, and propagates the changes to the remaining appliances in the managed set. Therefore, if the sharable appliance settings or a managed domain is changed on a subordinate appliance, making the sharable appliance settings or a managed domain different from what is on the master appliance, the appliance manager automatically overwrites the changes on the subordinate appliance with the sharable appliance settings, or managed domain values that are on the master appliance.

gotcha: Ensure that any changes that you make to the shareable appliance settings or a managed domain on a master appliance can be used for all of the appliances in the managed set.

Managed domains

DataPower supports the use of application domains to partition configuration information into self contained units that are easier to manage. Because an application domain consists of resources that are configured to provide and support one or more services, you can use domains to group configuration information on a appliance. For example, you might set up a domain for a set of business applications because you want to keep their DataPower appliance configuration separate from the DataPower appliance configuration for the other applications on that appliance.

A managed domain is a domain on the master appliance that has been added to a managed set in the DataPower appliance manager. The DataPower appliance manager uses the managed domain to synchronize configuration changes to the subordinate appliances that are part of the managed set.

Both master appliances and subordinate appliances can also have unmanaged domains. The DataPower appliance manager does not make configuration changes to unmanaged domains.

gotcha: The DataPower appliance manager synchronizes managed domains from the master appliance to the subordinate appliances in the managed set. However, it is possible that the managed domain might not be completely functional on all of the subordinate appliances. For example, the managed domain might not be completely functional on a subordinate appliance if a service object, such as an XML firewall, in the managed domain has a listening port conflict on that subordinate appliance.

Versions of sharable appliance settings

Whenever the appliance manager detects that you have used the DataPower WebGUI or DataPower command line interface to change the sharable appliance settings for a master appliance, the appliance manager automatically creates a new version of the sharable appliance settings. This new version of the sharable appliance settings is called a settings version. The newest settings version is, by default, the active version for the managed set. This new settings version is automatically copied to all of the appliances in the managed set.

You can deploy any version of the sharable appliance settings to a managed set. Whenever you deploy a settings version, the deployed version becomes the active version until the sharable appliance settings are changed, or you deploy a different settings version. If you have more than one version of sharable appliance settings for a managed set, you can complete these tasks.

gotcha: Changes to sharable appliance settings only apply for appliances that are members of the same managed set. Changes are not propagated to appliances that are members of a different managed set.

- Copy a version of sharable appliance settings to another managed set. The sharable appliance settings are applied to all appliances in this other managed set.

gotcha: After the initial copy of the sharable appliance settings, the two managed sets are managed independently. Therefore, future changes to the sharable appliance settings in one managed set are not reflected in the other managed set.

- Delete an inactive version of sharable appliance settings. You cannot delete an active version. You can also specify the maximum number of versions that you want to keep.
- Deploy a version of the sharable appliance settings. You deploy a version of the sharable appliance settings to make a different version active. When the different version becomes the active version, that version is deployed to all of the members of the managed set.

Versions of managed domains

When you change a managed domain on a master appliance, the appliance manager automatically detects the change and creates a new version of the managed domain. The newest version of the managed domain is, by default, the active version for the managed set. This new version of the domain is automatically copied to all appliances in the managed set. You can deploy any version of a managed domain to a managed set, and that deployed version automatically becomes the active managed domain for that managed set.

When a managed domain is deleted from a master appliance, the domain is automatically recreated on the master appliance. To delete a managed domain, you must convert the managed domain to an unmanaged domain.

When you have multiple versions of a managed domain, you can perform the following tasks:

- Copy a version of the managed domain to another managed set. The domain is applied to all of the appliances in the managed set.

gotcha: After the initial copy of the managed domain, the two managed sets are managed independently. Therefore, future changes to the sharable appliance settings in one managed set are not reflected in the other managed set.

- Delete an inactive version of the managed domain. You cannot delete an active version. You can also specify the maximum number of versions that you want to keep.
- Deploy a version of the managed domain. You deploy a version of a managed domain to make that version the active version. The active version is then deployed to all members of the managed set.

Firmware

Firmware version files must be obtained from the IBM support website and are specific to appliance types, model types, and licensed features. When a firmware version is loaded to an appliance, it must be compatible with the appliance type, model type, and licensed features. DataPower appliance manager manages appliances with a 3.6.0.4 or higher level of firmware. A firmware file is typically in a scrypt2 format.

Versions of firmware

The appliance manager automatically determines the firmware version, intended model type, appliance type, and licensed features provided by libraries in the firmware. The appliance manager allows the firmware types to be deployed only to matching appliances.

A firmware version must exist in the DataPower appliance manager before that version can be deployed to appliances. If the firmware version that is running on an appliance is not in this file, a managed set that includes that appliance can only contain that single appliance, because the appliance manager cannot deploy that firmware version to any other appliance.

When you deploy a particular version of firmware, that version becomes the active version. When you have more than one version of firmware, you can perform the following tasks:

- Deploy a version firmware to the managed set. You deploy a version of firmware to roll back, or upgrade the firmware on the appliances to a specific version. Whenever a new version is deployed, that version becomes the active version for the managed set, and is deployed to all of the appliances in that managed set.

The firmware versions, that are in the DataPower appliance manager, can be used with multiple managed sets if the appliance type and model type are the same and the licensed features are compatible.

- Delete a version of firmware. You cannot delete an active version of firmware. As an alternative to deleting firmware versions, you can configure the maximum number of versions of any one object that you want to keep.

gotcha: Do not use the DataPower 3.6.0.28, 3.6.0.29, or 3.6.0.30 level of firmware for a managed set. These firmware levels might cause the DataPower appliance manager to unnecessarily create new shareable appliance settings versions, or domain versions, and then synchronize these new versions across the managed set.

Setting up and administering a managed set

If you want to create at least one managed set, you must complete the following tasks. These tasks make it possible for the DataPower appliance manager to manage the appliances in a managed set:

- Add one or more DataPower appliances to the appliance manager.
- Create the firmware version in the appliance manager that you want used on all of the appliances in the managed set. You can have different firmware versions for different managed sets, or you can share the firmware versions between managed sets.
- Create a managed set for all of the appliances that are intended to share the same firmware version, shared appliance settings and managed domains.

After at least one managed set is created, you can complete the following tasks in any order:

- Add appliances to a managed set.

Note: Do not add the same DataPower appliance to a managed set in two different DataPower appliance managers. If a DataPower appliance manager discovers that another DataPower appliance manager is managing an appliance, the discovering DataPower appliance manager removes that appliance from its managed set. If this appliance is the only appliance in that managed set, the discovering DataPower appliance manager also removes all of the shareable settings and domain versions that are associated with that managed set. When this situation occurs, you cannot recover any historical versions of the shareable appliance settings and domains that do not exist on the other DataPower appliance manager.

For example, if you create the following managed sets:

- Managed set MS1 on DataPower appliance manager A that contains DataPower appliance X.

- Managed set MS2 on DataPower appliance manager B that also contains DataPower appliance X.

When DataPower appliance manager A discovers that DataPower appliance manager B is also managing DataPower appliance called X, DataPower appliance manager A issues an error message to the deployment manager log file, that indicates that the appliance is being managed by DataPower appliance manager B, and removes appliance X from the managed set MS1. Because appliance X was the only managed appliance in MS1, DataPower appliance manager A removes all of the shareable appliance settings and domain versions that are associated with MS1. You will not be able to recover any historical versions that existed on DataPower appliance manager A, but do not exist on DataPower appliance manager B.

- Manage versions of the firmware, sharable appliance settings, and managed domains with roll back capability.
- Monitor appliance synchronization and operation status.

You can also use the administrative console to manage long running tasks for the DataPower appliance manager, view the status of these tasks, or delete one or more of these task. However, you cannot delete a task to stop the task from being completed. The only way to interrupt a running task, or prevent the appliance manager from running a task, is to shutdown the appliance manager. Shutting down the appliance manager terminates all running and queued tasks.

Propagating sharable appliance settings and managed domains from master to non-master appliances

If there are multiple appliances in the managed set, then the changes made to the active version of the sharable appliance settings are propagated to the subordinate appliances in the managed set. Likewise, changes made to the managed domains of master appliances are propagated to the subordinate appliances in the managed set.

The appliance manager also detects when subordinate appliances are available. For example, if sharable appliance settings are changed for the master appliance, but the subordinate appliances are not available, then the master appliance and the subordinate appliances cannot be synchronized. When the subordinate appliances are available, the appliance manager detects the change in status and initiates synchronization from the master appliance to the subordinate appliances in the managed set.

Adding DataPower appliances to the DataPower appliance manager

You can use the DataPower appliance manager that is provided with the product to administer a DataPower appliance. After you add an appliance to the DataPower appliance manager, you can make it part of a managed set of appliances if you want the DataPower appliance manager to keep the shared appliance settings for this appliance synchronized with the shared appliance settings of the other appliances that are part of that managed set.

Before you begin

- Verify that the appliance that you are adding is at a Version 3.6.0.4 or higher firmware level. The appliance manager cannot manage an appliances that is not at a Version 3.6.0.4 or higher firmware level.
- Verify that the appliance manager can communicate with the port that is used for the XML Management interface AMP endpoint on the appliance. The appliance manager uses this port to send commands to an appliance.
- Verify that the appliance can communicate with the port that is used for the DataPowerMgr_inbound_secure endpoint on the deployment manager. The appliance uses this port to send events to the appliance manager.

- Verify that the Appliance Management Protocol (AMP) endpoint is enabled for each appliance. If the XML Management interface AMP endpoint was disabled during installation, use the DataPower WebGUI to enable the AMP endpoint.
- Verify that there is not a firewall between the deployment manager and the appliances that will be part of a managed set. If there is a firewall between the deployment manager and the appliances, that firewall might prevent the appliance manager from communicating with the appliances in a managed set.

About this task

You can use the administrative console to add a new DataPower appliance or to access the DataPower WebGUI. If you want to access the DataPower WebGUI, in the administrative console, click **Servers > DataPower > Appliances**, and then click **Launch**. Complete the following steps if you want to add a new DataPower appliance.

gotcha: Remember that the XML management interface port, which defaults to port number 5550, is different from the Web Management Service port, which defaults to port number 9090. The DataPower appliance manager uses the XML management interface port to manage the DataPower appliances. You use the Web Management Service port to access the WebGUI on the DataPower appliance. You can use the same user ID and password to access both the XML management interface and the WebGUI.

Procedure

1. In the administrative console, click **Servers > DataPower > Appliances > New**.
2. Specify a unique name for the appliance in the **Name** field. An appliance name must be unique and cannot contain an invalid character. The name field cannot contain the characters # \$ @ \ / , ; " * ? < > | = + & % or '.
3. Specify an IP address or fully qualified host name in the **Host name** field.
4. Specify the XML management interface port that the DataPower appliance uses in the **Administrative port** field.
5. Specify the ID that you want to use to connect to the DataPower appliance in the **User ID** field.
6. Specify the password that you want to associate with the user ID in the **Password** and **Verify password** fields.
7. Click **OK** to add the new appliance.

Results

The DataPower appliance manager is managing this appliance.

What to do next

You can change appliance settings, add the appliance to a managed set, or remove the appliance from the DataPower appliance manager.

gotcha: For security reasons, the DataPower appliance manager does not include Crypto material, such as keys and certificates, in the shareable settings and domain versions that it creates. Therefore, after you add an appliance to the appliance manager, you must manually add any Crypto material that you want to apply for the new appliance.

Modifying DataPower appliance settings

You can use the administrative console to modify the shared appliance settings for an appliance.

Before you begin

Verify that the DataPower appliance manager is managing this appliance. You cannot use the administrative console to change the sharable appliance settings for an appliance that has not been added to the DataPower appliance manager.

About this task

Complete the one or more of the following actions to make modifications to the settings for an appliance.

Procedure

1. From the administrative console, click **Servers > DataPower > Appliances > *appliance_name***.
2. Specify a different IP address or fully qualified host name in the **Host name** field.
3. Specify a different XML management interface port for the DataPower appliance to use in the **Administrative port** field.

gotcha: Remember that the XML management interface port, which defaults to port number 5550, is different from the Web Management Service port, which defaults to port number 9090. The DataPower appliance manager uses the XML management interface port to manage the DataPower appliances. You use the Web Management Service port to access the WebGUI on the DataPower appliance. You can use the same user ID and password to access both the XML management interface and the WebGUI.

4. Specify a different user ID in the **User ID** field.
5. Specify a new password to associated with the user ID in the **Password** and **Verify password** fields.
6. Select an appliance type from the list of appliance types in the **Appliance type** field.
7. In the Domains section, expand **Managed Domains**, or **Unmanaged Domains** to view a list of managed and unmanaged domains that are associated with this appliance.

If you want to change one or more managed domains to unmanaged domains, click **Servers > DataPower > Managed sets > *managedset_name***, select the domains that you want to change, and then click **Unmanage**. Similarly, if you want to change one or more unmanaged domains to managed domains, select the domains that you want to change, and then click **Manage**.

Clicking either **Manage** or **Unmanage**, creates an appliance manager task. If you want to know when this task completes, you can click **Servers > DataPower > Tasks** to check the status of this task.

8. Click **OK** to save a copy of your changed settings as a new settings version.

Removing a DataPower appliance

You can use the administrative console to remove an appliance from the DataPower appliance manager.

About this task

If you no longer want the DataPower appliance manager to manage one of you appliances, complete the following steps to remove that appliance from the DataPower appliance manager.

gotcha: Do not remove a DataPower appliance from a managed set if it is the only appliance in that managed set, until you have added the replacement appliance to that managed set. Removing the last appliance from a managed set causes the managed set to be deleted, and all of the versions of the shareable settings and domains to be removed from the DataPower appliance manager. There is not any way for you to recover these removed versions.

Procedure

1. In the administrative console, click **Servers > DataPower > Appliances**.
2. Verify that the appliance that you want to remove is not part of a managed set.

You cannot remove an appliance from the DataPower appliance manager if that appliance is part of a managed set. If the appliance that you want to remove has the value unmanaged in the Managed Set column, the appliance is not part of a managed set.

If the name of a managed set is specified in the Managed Set column, you must remove the appliance from the managed set before you remove it from the DataPower appliance manager.

- If the appliance that you want to remove from a managed set is the last appliance in that managed set, you must delete the managed set before you can remove the appliance from the DataPower appliance manager. When you delete the managed set, the appliance automatically becomes an unmanaged appliance and can be removed from the DataPower appliance manager.
 - If the appliance that you want to remove from a managed set is not the last appliance in that managed set, complete the following actions to remove the appliance from that managed set.
 - a. Click **Managed sets**, and then click the name of the managed set that includes the appliance that you want to remove.
 - b. Click **Edit Membership**, select the appliance that you want to remove from the DataPower appliance manager, and then click **Remove**.
 - c. Click **Save** to save your changes.
3. Select the appliance that you want to remove from the DataPower appliance manager.

If you want to remove multiple appliances from the DataPower appliance manager, you can select all of the appliances that you want to remove.
 4. Click **Remove**.

Appliance collection

Use this page to add, change, or remove a DataPower appliance in the DataPower appliance manager. You can also use this page to view information about the DataPower appliances that are in the appliance manager. Adding appliances to a DataPower appliance manager enables you to automatically keep synchronized the settings for all of the appliances that are in a DataPower appliance manager managed set.

To view this administrative console page, click **Servers > DataPower > Appliances**.

To view the values specified for a DataPower appliance, click the name of that appliance name in the list of available appliances. The displayed appliance settings page shows the values specified.

To initiate an operation on a DataPower appliance, select the name of the appliance that you want to manage, and click the operation that you want performed on that appliance. Click **Launch** to access the DataPower WebGUI in the default domain on the selected appliance. Pop-ups must be enabled for your browser.

Name

Specifies the symbolic name of the DataPower appliance.

An appliance name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \$ @ \ / , : ; " * ? < > | = + & % ' .

Host Name

Specifies the host name or IP address of the DataPower appliance.

Managed Set

Specifies the name of the managed set that the appliance is assigned to. Appliances that are assigned to a managed set must be removed from the managed set before they can be removed from the appliance manager.

Master

Specifies the master appliance for the managed set to which this appliance is a member. All appliances in the managed set are synchronized using the settings of the master appliance.

Operational Status

Specifies the operational status of the appliance. The status is always unknown if the appliance is not part of a managed set or if the managed set has no managed domains. If the appliance is part of a managed set, the status reflects the aggregated operational status of all of the managed domains on this appliance.

This field is read-only. The following values might appear in this field:

up Indicates that all of the service objects in all the managed domains on the appliance are enabled.

partial Indicates that the service objects in all the managed domains on the appliance are a mix of enabled, disabled and unknown.

down Indicates that all of the service objects in all the managed domains on the appliance are disabled.

unknown

Indicates that the state of all of the managed domains on the appliance could not be determined. It is possible that the state has yet to be retrieved, or that communication to the appliances has been lost. An appliance always has a status of unknown if the appliance is not part of a managed set, or if the appliance is part of a managed set that has no managed domains.

Synchronization Status

Specifies whether the appliances are synchronized with other appliances in the managed set.

This field is read-only. The following values might appear in this field:

synced

Indicates that the firmware, sharable appliance settings and managed domains for the appliance are synchronized with the active firmware, sharable appliance and domain versions for the managed set.

changes pending

Indicates that at least one firmware synchronization, sharable appliance settings synchronization, or managed domains synchronization is queued for the appliance.

in progress

Indicates that the synchronization is currently being processed. The appliance has at least one firmware synchronization, settings synchronization, or managed domain synchronization active. Other firmware synchronizations, settings synchronizations, or managed domain synchronizations might also be pending for this appliance.

unknown

Indicates that the synchronization status is not known for at least one firmware synchronization, settings synchronization, or managed domain synchronization. Typically, this status means that the appliance manager has not yet contacted the appliance to get the management status. Firmware synchronizations, settings synchronizations, or managed domain synchronizations might also be pending, or in progress, for this appliance.

error

Indicates that an attempt to process a firmware synchronization, settings synchronization, or managed domain synchronization for this appliance has failed because of an error on the appliance. The appliance did respond, but responded with an error. This appliance might also have a management status of unknown, in progress or changes pending for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

unreachable

Indicates that an attempt to synchronize the appliance has failed because the appliance is not responding. This appliance might also have a management status of unknown, in progress,

changes pending or error for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

New appliance settings for the DataPower appliance

Use this page to specify the settings for an appliance that you are adding to the DataPower appliance manager.

To view this administrative console page, click **Servers > DataPower > Appliances > New**.

Name

Specifies a user-defined symbolic name for a DataPower appliance.

An appliance name must be unique, and cannot contain the following invalid characters: # \$ @ \ / , ; " * ? < > | = + & % '.

Host name

Specifies an IP address or the fully qualified host name of a DataPower appliance.

Administrative port

Specifies the XML management interface port used by the appliance.

User ID

Specifies the user ID used by DataPower appliance manager to log into an appliance.

Password

Specifies the password for the user ID provided.

Verify password

Also specifies the password for the user ID provided. If you change the password value, you must respecify the new value in this field to ensure that you entered it correctly.

Appliance settings

Use this page to change the settings for a DataPower appliance. Appliances are added to the DataPower appliance manager to synchronize the firmware, shareable appliance settings and managed domains of a group of appliances called a managed set.

To view this administrative console page, click **Servers > DataPower > Appliances > *appliance_name***.

In the Domains section, you can expand **Managed domains** to view a list of the managed domains that are on the appliance, and the status of each of these domains. You can also expand **Unmanaged domains** to view the unmanaged domains that are on the appliance. Domains, by default, are not managed. Unmanaged domains are not copied to subordinate appliances in the managed set. Managed domains are copied to subordinate appliances in the managed set.

Name

Specifies a user-defined symbolic name for a DataPower appliance.

An appliance name must be unique, and cannot contain the following invalid characters: # \$ @ \ / , ; " * ? < > | = + & % '.

Host name

Specifies an IP address or the fully qualified host name of a DataPower appliance.

Administrative port

Specifies the XML management interface port used by the appliance.

User ID

Specifies the user ID used by DataPower appliance manager to login to an appliance.

Password

Specifies the password for the user ID provided.

Verify password

Also specifies the password for the user ID provided. If you change the password value, you must respecify the new value in this field to ensure that you entered it correctly.

Serial number

Specifies the serial number for the appliance. This field is read-only.

Appliance type

Specifies the appliance type, such as XA35, XS40, or XI50.

Licensed features

Specifies a comma-separated list of the licensed features that are on this appliance. All of the appliances in a managed set must have the same appliance type, model type and licensed features. Firmware has a list of the licensed features that are contained in the firmware. Any firmware that is loaded onto an appliance must have a list of licensed features that is compatible with the licensed features that are on that appliance.

Because managed sets contain appliances that all must be of the same appliance type, model type and licensed features, you cannot use a firmware with a managed set that has licensed features that are incompatible with the appliances in that managed set. If you attempt to load a firmware that has a list of features that is incompatible with the licensed features of the appliance, the firmware does not load, and an error message is issued.

Firmware level

Specifies the numeric level of the firmware that is currently on the appliance. Each firmware version in the DataPower appliance manager is for a specific appliance type, model type, list of licensed features, and level.

It is possible that a firmware version might already exist in the DataPower appliance manager that has the same appliance type, model type, list of licensed features, and level as the firmware that is currently on this appliance.

Firmware synchronization status

Specifies whether the firmware version for an appliance is synchronized with the active firmware version for the managed set. The status is unknown if the appliance is not part of a managed set. If the appliance is part of a managed set, the status indicates whether the firmware that is associated with the appliance is synchronized with the designated firmware for the managed set.

This field is read-only. The following values might appear in this field:

synched

Indicates that the firmware version for this appliance is the same as the firmware version for the managed set.

changes pending

Indicates that the firmware is being synchronized.

in progress

Indicates that the synchronization for the firmware on this appliance is currently being processed.

unknown

Indicates that the synchronization status for the firmware on this appliance is not known. Typically,

this status indicates that the appliance manager has not yet contacted the appliance to get the synchronization status, or the appliance is not a member of a managed set.

error Indicates that an attempt to synchronize the firmware that is associated with the managed set has failed because of an error on the appliance. The appliance did respond, but responded with an error. See the error log for the deployment manager for more information.

unreachable

Indicates that an attempt to synchronize the firmware on this appliance failed because the appliance is not responding. See the error log for the deployment manager for more information.

Settings synchronization status

Specifies whether the shareable appliance settings for an appliance are synchronized with the active settings version for the managed set. The status is unknown if the appliance is not part of a managed set. If the appliance is part of a managed set, the status indicates whether or not the sharable settings for the appliance are synchronized with the designated sharable appliance settings version for the managed set.

This field is read-only. The following values might appear in this field:

synched

Indicates that the sharable appliance settings for this appliance are the same as the sharable appliance settings version for the managed set.

changes pending

Indicates that the synchronization for the sharable appliance settings on this appliance is queued.

in progress

Indicates that the shareable appliance settings are being synchronized.

unknown

Indicates that the synchronization status for sharable appliance settings on this appliance is not known. Typically, this status indicates that the appliance manager has not yet contacted the appliance to get the synchronization status, or the appliance is not a member of a managed set, or the appliance is not a member of a managed set.

error Indicates that an attempt to synchronize the sharable appliance settings on this appliance failed because of an error. The appliance did respond, but responded with an error. See the error log for the deployment manager for more information.

unreachable

Indicates that an attempt to synchronize the sharable appliance settings on this appliance failed because the appliance is not responding. See the error log for the deployment manager for more information.

Model type

Specifies a numeric value for the appliance model. Some model types include 9001, 9002, and 9003. Each appliance is assigned a model type.

Synchronization status

Specifies the combined status of the firmware synchronization, the sharable settings synchronization, and the managed domains synchronization for the appliance.

This field is read-only. The following values might appear in this field:

synched

Indicates that the firmware, sharable appliance settings and managed domains for the appliance are synchronized with the active firmware, sharable appliance and domain versions for the managed set.

changes pending

Indicates that at least one firmware synchronization, sharable appliance settings synchronization, or managed domains synchronization is queued.

in progress

Indicates that the synchronization is currently being processed. The appliance has at least one firmware synchronization, settings synchronization, or managed domain synchronization active. Other firmware synchronizations, settings synchronizations, or managed domain synchronizations might also be pending for this appliance.

unknown

Indicates that the synchronization status is not known for at least one firmware synchronization, settings synchronization, or managed domain synchronization. Typically, this status means that the appliance manager has not yet contacted the appliance to get the management status. It is possible that other firmware synchronization, settings synchronization, or managed domain synchronizations are also pending or in progress for the appliance.

error Indicates that an attempt to process a firmware synchronization, settings synchronization, or managed domain synchronization for this appliance has failed because of an error. The appliance did respond, but responded with an error on the appliance. This appliance might also have a management status of unknown, in progress or changes pending for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

unreachable

Indicates that an attempt to synchronize the appliance has failed because the appliance is not responding. This appliance might also have a management status of unknown, in progress, changes pending or error for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

Name (in the Managed domains section)

Specifies the name of the managed domain.

Operational Status

Specifies the operational status of the managed domain. Each service inside of a DataPower domain on an appliance has an operational state of either enabled or disabled. The operational state of the domain in the DataPower appliance manager represents the aggregated operational status of all the service objects in the domain.

This field is read-only. The following values might appear in this field:

up Indicates that all of the service objects in the managed domain on the appliance are enabled.

partial Indicates that the service objects in the managed domain on the appliance are a mix of enabled, disabled and unknown.

down Indicates that all of the service objects in the managed domain on the appliance are disabled

unknown

Indicates that the state of the managed domain on the appliance cannot be determined. It is possible that the state has yet to be retrieved, or that communication to the appliance has been lost.

Synchronization status (in the Managed domains section)

Specifies the synchronization status of the managed domain on the appliance.

This field is read-only. The following values might appear in this field:

synched

Indicates that the managed domain on this appliance is synchronized with the domain version for the managed set.

changes pending

Indicates that the synchronization is queued.

in progress

Indicates that the synchronization is currently being processed.

unknown

Indicates that the synchronization status is not known. The managed domain synchronization state for the appliance is unknown. Typically, this status means that the appliance manager has not yet contacted the appliance to get the management status.

error Indicates that an attempt to synchronize the managed domain on the appliance has failed because of an error. The appliance did respond, but responded with an error. See the error log for the deployment manager for more information.

unreachable

Indicates that an attempt to synchronize the managed domain on the appliance has failed because the appliance is not responding. See the error log for the deployment manager for more information.

Name (in the Unmanaged domains section)

Specifies the name of any unmanaged domain on the device.

Replacing a DataPower appliance

If a problem occurs that makes a DataPower appliance unable to function properly, you can use the DataPower appliance manager to copy the configuration of that appliance to a different appliance.

Before you begin

Verify that the replacement DataPower appliance:

- Has the same device type, model type, and licensed features as the DataPower appliance that this appliance is replacing. The DataPower appliance manager requires all appliances in a managed set to be homogenous.
- Has been added to the DataPower appliance manager.

About this task

gotcha: Do not remove a DataPower appliance from a managed set if it is the only appliance in that managed set, until you have added the replacement appliance to that managed set. Removing the last appliance from a managed set causes the managed set to be deleted, and all of the versions of the shareable settings and domains to be removed from the DataPower appliance manager. There is not any way for you to recover these removed versions.

For security reasons, the DataPower appliance manager does not include Crypto material, such as keys and certificates, in the shareable settings and domain versions that it creates. Therefore, the following procedure does not include the restoration of Crypto material. After you replace an appliance, you must manually add the Crypto material for the replacement appliance.

Procedure

1. From the administrative console, click **Servers > DataPower > Managed sets >**
2. Click the name of the managed set to which the DataPower appliance that is being replaced belongs, and then click **Edit Membership**.
3. Select the replacement appliance, and then click **Add**
4. Click **Synchronize** to manually synchronize the firmware, shared appliance settings and managed domains throughout the managed set.

The appliance manager always attempts to keep the firmware, shared appliance settings and managed domains synchronized across all of the appliances in a managed set. However, when you can click **Synchronize**, you are forcing an immediate synchronization to occur.

5. Click **Edit Membership**, and select the appliance that you are replacing, and then click **Remove**.

Results

The replacement appliance is being added to the managed set, and the original appliance is being removed from the managed set.

What to do next

Click **Servers > DataPower > Tasks** to monitor the progress of the addition of the replacement appliance to the managed set, and the removal of the original appliance from the managed set.

Adding new firmware versions to the DataPower appliance manager

You can use the DataPower appliance manager to add a new firmware version to the DataPower appliance manager. Appliances that the DataPower appliance manager manages must have a 3.6.0.4 or higher firmware level.

Before you begin

Download one or more firmware versions from the IBM support site.

About this task

Complete the following steps if you want to use the administrative console to add a new firmware version.

Procedure

1. From the administrative console, click **Servers > DataPower > Firmware > New**.
2. Select either **Upload from local system**, or **Upload from remote system**.
If you select **Upload from local system**, the firmware version is uploaded to the DataPower appliance manager, from your local file system.
If you select **Upload from remote system**, the firmware version is uploaded to the DataPower appliance manager, from a remote file system.
3. Specify the fully qualified name of the file that you are uploading.
If you do not know the fully qualified name of the file that you are uploading, you can use the browse function to search for the correct file.
4. Optional: Add a description of this firmware version in the **Comments** field.
You might want to use this field to provide information that differentiates this firmware version from other firmware versions that are stored on the local or remote system.
After you enter your comment, click **Apply**.
5. Click **Submit**.

What to do next

After a new firmware version is added, you can use the DataPower appliance manager to modify the settings for the new firmware version, add the new firmware version to a managed set, or delete the new firmware version when it is no longer needed.

Modifying settings for firmware versions

You can use the administrative console to add new firmware versions to the DataPower appliance manager, or to delete existing firmware versions. You can also use the administrative console to view the settings for the firmware versions that are on the DataPower appliance manager.

About this task

When you add a new firmware version to the DataPower appliance manager, you are not creating a new version. You are actually uploading a file that contains an existing firmware version, from either a remote or local file system, to the DataPower appliance manager. If you need to create a new firmware version, you must use the DataPower WebGUI. To access the DataPower WebGUI, in the administrative console, click **Servers > DataPower > Appliance**, and then click **Launch**.

To use the administrative console to view the settings for the current firmware version or to add or delete a firmware version, perform one or more of the following actions.

Procedure

1. To view the settings for the firmware versions on the DataPower appliance manager, click **Servers > DataPower > Firmware**.
2. To add a new firmware version to the DataPower appliance manager, click **New**. After you select the file to upload, click **Submit**.
3. To delete firmware versions from the DataPower appliance manager, select the versions to delete, and then click **Delete**.
4. To add a comment about a firmware version that is on the DataPower appliance manager, click the name of that firmware version and add the comment in the **Comment** field.
After you enter your comment, click **Apply**, and then click **Submit**.

Deleting firmware versions

You can delete a firmware version from the DataPower appliance manager, unless a managed set is using that firmware version. You cannot delete a firmware version that a managed set is using.

About this task

You can use the administrative console to delete firmware versions. Complete the following actions.

Procedure

1. In the administrative console, click **Servers > DataPower > Firmware**.
2. Select the firmware versions that you want to delete.
3. Click **Delete**.

Results

The firmware version is deleted from the DataPower appliance manager.

Firmware collection

Use this page to add a new firmware version to the appliance manager, view existing firmware versions, or delete a firmware version from the appliance manager. A firmware version must exist in the appliance manager before that version can be designated as the active firmware version for a managed set.

This page lists the firmware versions that can be used for appliances managed by DataPower appliance manager.

To view this administrative console page, click **Servers > DataPower > Firmware**.

To view the settings for a specific firmware version, click that firmware version in the list of available versions. The displayed firmware settings page shows the values that are specified for that firmware version. On the settings page, you can change the settings for the selected firmware version.

To add a new firmware version, click **New**.

To delete an existing firmware version, select the version that you want to delete and click **Delete**.

Version

Specifies the numeric version, or level, of the firmware. When combined with an appliance type, model type, and licensed features, the numeric version, or level, uniquely identifies a firmware version.

Appliance Type

Specifies the type of appliance that the firmware version is used for. Some appliance types include XA35, XS40, and XI50. The appliance type is based on the purpose for using the appliance.

Model Type

Specifies a numeric value for the appliance model. Some model types include 9001, 9002, and 9003.

Licensed Features

Specifies a comma-separated list of the licensed features that are on this appliance. All of the appliances in a managed set must have the same appliance type, model type and licensed features. Firmware has a list of the licensed features that are contained in the firmware. Any firmware that is loaded onto an appliance must have a list of licensed features that is compatible with the licensed features that are on that appliance.

Because managed sets contain appliances that all must be of the same appliance type, model type and licensed features, you cannot use a firmware with a managed set that has licensed features that are incompatible with the appliances in that managed set. If you attempt to load a firmware that has a list of features that is incompatible with the licensed features of the appliance, the firmware does not load, and an error message is issued.

Release Date

Specifies the date when the firmware was released by the manufacturer.

Firmware settings

Use this page to specify firmware settings for a firmware version in the DataPower appliance manager. A firmware version is a firmware image of a specific level that is used with a specific appliance type, model type, and set of licensed features.

To view this administrative console page, click **Servers > DataPower > Firmware > *firmware_version***.

Version

Specifies the numeric version, or level, of the firmware. This field is read-only.

Release date

Specifies the date when the firmware was released by the manufacturer. This field is read-only.

Appliance type

Specifies the type of appliance that the firmware version is used for. Some appliance types include XA35, XS40, and XI50. This field is read-only.

Model type

Specifies a numeric value for the appliance model. Some model types include 9001, 9002, and 9003. This field is read-only.

Licensed features

Specifies a comma-separated list of the licensed features that are contained in this firmware. The firmware that is loaded onto an appliance must have a list of licensed features that is compatible with the licensed features of the appliance. This field is read-only.

All of the appliances that are part of a managed set must have the same appliance type, model type and licensed features. Therefore, you cannot use a firmware with a managed set if the firmware includes a list of licensed features that is not compatible with the appliances in the managed set. If you attempt to load firmware that includes a list of licensed features that is not compatible with the licensed features of the appliances in the managed set, the firmware does not load, and an error message is issued.

Comments

Specifies user-defined information about a firmware version.

Managed sets

Specifies a list of managed sets that use this firmware version. The firmware version must have the same appliance type, model type and licensed features as the appliances that are in the managed set. This field is read-only.

Managed set firmware settings

Use this page to change the firmware on a managed set. You can upload a file from a local or remote file system. The firmware for a managed set, must have the same value for appliance type, model type and licensed features as the devices in the managed set.

Note: Do not use the DataPower 3.6.0.28, 3.6.0.29, or 3.6.0.30 level of firmware for a managed set.

Typically, when you create a managed set of DataPower appliances, the DataPower appliance manager completes the following process:

- Creates a shareable appliance settings version from the shareable appliance settings on the master appliance.
- Synchronizes the settings across the managed set. This synchronization process is repeated whenever the shareable appliance settings change on the master appliance.

Similarly, when a domain is added to a managed set in the DataPower appliance manager, the DataPower appliance manager typically completes the following process:

- Creates a domain version from the domain on the master appliance.
- Synchronizes the domain version across the managed set. This synchronization process is repeated every time that the domain changes on the master appliance.

If you use the DataPower 3.6.0.28, 3.6.0.29, or 3.6.0.30 level of firmware for a managed set, the firmware level might cause the DataPower appliance manager to unnecessarily create new shareable appliance settings versions, or domain versions, and then synchronize these new versions across the managed set.

To view this administrative console page, click **Servers > DataPower > Managed sets > *managed_set_name* > Change firmware**.

From a version already in the DataPower appliance manager

Select this option if you want to use a firmware version that already exists in the appliance manager, and then select the version that you want to use from the list of available versions.

Upload from local system

Select this option if you want to upload a firmware version from a local file system. You can either type a fully qualified path name in the **Location** field, or you can select a file from the local file system.

Upload from remote system

Select this option if you want to upload a firmware version from a remote file system. You can either type a fully qualified path name in the **Location** field, or you can select a file from the remote file system.

Comments

Specifies user-defined information about a firmware version.

New firmware version settings

Use this page to upload a new firmware version from either a local or remote file system.

To view this administrative console page, click **Servers > DataPower > Managed sets > New**.

Upload from local system

Select this option if you want to upload a firmware version from a local file system. You can either type a fully qualified path name in the **Location** field, or you can select a file from the local file system.

Upload from remote system

Select this option if you want to upload a firmware version from a remote file system. You can either type a fully qualified path name in the **Location** field, or you can select a file from the remote file system.

Comments

Specifies user-defined information about a firmware version.

Adding a new managed set

Add a new managed set to synchronize settings for multiple appliances. A managed set is a grouping of appliances that share the same shareable appliance settings, managed domains and firmware version. Shareable appliance settings and managed domains are propagated to the subordinate appliances from the master appliance.

Before you begin

Verify the names of the DataPower appliances and firmware versions that you want to add to the new managed set.

About this task

Complete these steps to add a new managed set from the administrative console. You can click **Launch** to access the DataPower WebGUI to configure an appliance before you add the appliance to a managed set.

Procedure

1. From the administrative console, click **Servers > DataPower > Managed sets > New**. This starts the New managed set wizard.
2. Enter a unique name for the new managed set in the **Name** field. A managed set name must be unique and cannot contain an invalid character. The name field cannot contain the characters # \$ @ \ / , ; " * ? < > | = + & % or '.
3. Choose a master appliance, and then click **Next**.
4. Select appliances to add to the managed set, and click **Next**.
5. View the summary of actions, and then click **Finish**.

What to do next

Creating a new managed set might take several minutes to complete. When a new managed set is added, the DataPower appliance manager automatically creates a version of the shareable appliance settings from the master appliance and copies it to any subordinate appliances in the managed set. The firmware version for the managed set might also be automatically deployed to all of the appliances in the managed set that do not already have this firmware version.

After you create a managed set, you can use the administrative console to add, replace, or remove appliances from that managed set.

gotcha: Do not remove a DataPower appliance from a managed set if it is the only appliance in that managed set, until you have added the replacement appliance to that managed set. Removing the last appliance from a managed set causes the managed set to be deleted, and all of the versions of the shareable settings and domains to be removed from the DataPower appliance manager. There is not any way for you to recover these removed versions.

Modifying a managed set

You can change the members of a managed set, manually synchronize the shareable appliance settings, administer the versions of shareable appliance settings that are available for a managed set, change firmware versions, administer domains, or deploy a domain or shareable appliance settings version.

About this task

To modify a managed set, in the administrative console, click **Servers > DataPower > Managed sets > *managedset_name***, and then complete one or more of the following actions.

Procedure

- To add appliances to the managed set, click **Edit Membership**, and then select the appliances that you want to add to this managed set.
- To remove appliances from the managed set, click **Edit Membership**, and then select the appliances that you want to remove from this managed set.
- To choose a different appliance as the master appliance, click **Edit Membership**, and then select a different appliance as the master appliance.
- Click **Synchronize** to manually synchronize the firmware, shared appliance settings and managed domains throughout the managed set.

The appliance manager always attempts to keep the firmware, shared appliance settings and managed domains synchronized across all of the appliances in a managed set. However, you can click **Synchronize** if you need to manually force a synchronization to occur.

- To access the DataPower WebGUI to configure an appliance or a firmware version, click **Launch**.
- To modify which firmware version is the active firmware version for the managed set, in the Firmware section, click **Change firmware**.

Note: Do not use the DataPower 3.6.0.28, 3.6.0.29, or 3.6.0.30 level of firmware for a managed set.

Typically, when you create a managed set of DataPower appliances, the DataPower appliance manager completes the following process:

- Creates a shareable appliance settings version from the shareable appliance settings on the master appliance.
- Synchronizes the settings across the managed set. This synchronization process is repeated whenever the shareable appliance settings change on the master appliance.

Similarly, when a domain is added to a managed set in the DataPower appliance manager, the DataPower appliance manager typically completes the following process:

- Creates a domain version from the domain on the master appliance.
- Synchronizes the domain version across the managed set. This synchronization process is repeated every time that the domain changes on the master appliance.

If you use the DataPower 3.6.0.28, 3.6.0.29, or 3.6.0.30 level of firmware for a managed set, the firmware level might cause the DataPower appliance manager to unnecessarily create new shareable appliance settings versions, or domain versions, and then synchronize these new versions across the managed set.

- To view a list of settings versions that have been used for the managed set, in the Settings section, click **Version history**.
You can then click **Detail**, if you want to change the version that is being used for this managed set, or if you want to delete a version.
- To view a list of appliances assigned to the managed set, click **Appliances**.
- To view a list of all of the managed domains on the master appliance, in the Managed domains section, expand the **Managed domains** field. Within this field, you can change a domain from managed to unmanaged, or access the DataPower WebGUI to configure a domain.
 1. To change a domain from managed to unmanaged, select the domain, and then click **Unmanage**.
 2. To access the DataPower WebGUI to configure a domain, click **Launch** at the top of the Managed Domains table.
Clicking **Launch** launches the DataPower WebGUI in the managed domain on the master appliance.
- To view a list of all of the managed domains for this managed set, in the Managed domains section, expand the **Unmanaged domains on the master appliance** field. Within this field, you can change a domain from unmanaged to managed, or click **Launch** to access the DataPower WebGUI, and configure a domain.
 1. To change a domain from unmanaged to managed, select the domain, and then click **Manage**
 2. To access the DataPower WebGUI to configure a domain, click **Launch** at the top of the Managed Domains table.

What to do next

When you add appliances to or remove appliances from a managed set, perform a manual synchronization, change firmware versions, shareable settings or domain versions, an appliance manager task is created. To monitor the progress of these tasks, in the administrative console, click **Servers > DataPower > Tasks**.

Removing a managed set from the DataPower appliance manager

You can remove a managed set from the DataPower appliance manager if that managed set is not being used to manage appliances.

Before you begin

Verify that there are no appliances in the managed set that you want to remove from the DataPower appliance manager. If the managed set contains appliances, you must remove those appliances from that managed set before you try to remove the managed set from the appliance manager.

About this task

Complete the following actions to remove a managed set from the DataPower appliance manager.

Procedure

1. From the administrative console, click **Servers > DataPower > Managed sets**.
2. Select the managed set that you want to remove.

You can select multiple managed sets if there are multiple managed sets that you want to remove.

3. Click **Remove**.

Managed set collection for a DataPower appliance

Use this page to add, view, or delete a managed set. A managed set is a group of appliances whose firmware, shareable appliance settings and managed domains are all kept synchronized.

To view this administrative console page, click **Servers > DataPower > Managed sets**.

You can then:

- Click the name of one of the managed sets to view the values specified for that managed set configuration. The settings page displays and shows the current settings for the selected managed set.
- Click **New** if you want to create a new managed set.
- Select one of the managed sets in the list, and then click **Delete** if you want to delete that managed set.
- Click **Launch** to access the DataPower WebGUI in the default domain on the master appliance in the selected managed set. Pop-ups must be enabled. See the documentation for the DataPower WebGUI for information about the tasks that you can perform from the DataPower WebGUI.

Name

Specifies a user-defined symbolic name for a managed set.

A managed set name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \$ @ \ / , ; " * ? < > | = + & % '.

Operational Status

Specifies the aggregated operational status of all the managed domains on all of the appliances in the managed set.

This field is read-only. The following values might appear in this field:

up Indicates that all of the service objects in all the managed domains on all of the appliances in the managed set are enabled.

partial Indicates that the service objects in all the managed domains on all of the appliances in the managed set are a mix of enabled, disabled and unknown.

down Indicates that all of the service objects in all the managed domains on all of the appliances in the managed set are disabled.

unknown

Indicates that the state of all of the all the managed domains on all of the appliances in the managed set cannot be determined. It is possible that there are no managed domains, or the state of the managed domains has yet to be retrieved, or that communication has been lost to the appliances.

Synchronization Status

Specifies whether the designated firmware version, sharable appliance settings, and managed domain versions for the managed set are synchronized across all of the appliances in the managed set. This synchronization status combines the firmware synchronization status, the settings synchronization status, and the synchronization status of all the managed domains on all the appliances of the managed set.

This field is read-only. The following values might appear in this field:

synced

Indicates that the managed set is synchronized.

changes pending

Indicates that the synchronization is queued. At least one appliance in the managed set has a firmware synchronization, settings synchronization, or managed domain synchronization queued.

in progress

Indicates that the synchronization is currently being synchronized. At least one appliance in the managed set has a firmware synchronization, settings synchronization, or managed domain synchronization in progress. Other firmware synchronizations, settings synchronizations, or managed domain synchronizations might also be pending for appliances in the managed set.

unknown

Indicates that the synchronization status is not known. At least one appliance in the managed set has a firmware synchronization, settings synchronization, or managed domain synchronization for which the synchronization state is unknown. Typically, this means that the appliance manager has not yet contacted the appliance to get the management status. Other firmware synchronizations, settings synchronizations, or managed domain synchronizations might also have changes pending, or in progress for appliances in the managed set.

error Indicates that an attempt to synchronize the managed set has failed because of an error on an appliance in the managed set. The appliance did respond, but responded with an error. Appliances in the managed set might also have a management status of unknown, in progress or changes pending for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

unreachable

Indicates that the appliance is unreachable. An attempt to synchronize the managed set has failed because an appliance is not responding. Appliances in the managed set might also have a management status of unknown, in progress, changes pending or error for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

Managed set settings

Use this page to view the general properties for the managed set, and a list of the appliances that are part of this managed set. You can also use this page to view lists of the shareable appliance settings versions, and managed and unmanaged domains that can be used with this managed set.

To view this administrative console page, click **Servers > DataPower > Managed sets > *managedset_name***.

In addition to specifying values for a managed set, you can use the following buttons to edit appliance membership, synchronize appliances or access the DataPower WebGUI to configure an appliance.

Button	Resulting action
Edit Membership	Accesses a list of DataPower appliances that are members of the managed set. You can use this list to add appliances, remove appliances, or mark an appliance as the master appliance.
Synchronization	Forces a synchronization of the appliances in the managed set. The appliance manager attempts to maintain the synchronization automatically, but this option allows you to request that a synchronization be performed.

Button	Resulting action
Launch gotcha: You can also use the Launch button that is located in the Unmanaged domains section to launch the DataPower WebGUI in the default domain on the master appliance. The Launch button that is located in the Managed domains section provides a similar function. However, if you click that button, the DataPower WebGUI is launched in the managed domain on the master appliance instead of in the default domain.	Launches the DataPower WebGUI in the default domain on the master appliance in the managed set using the credentials that are defined in the DataPower appliance manager. Whenever you modify shareable appliance settings or a managed domain on the master appliance, the changes are distributed to every appliance in the managed set. Verify that pop-ups are enabled on your browser before you launch the DataPower WebGUI.

In the Firmware section, click **Change firmware** to change the firmware for the managed set. The firmware must have the same appliance type, model type and licensed features as the appliances in the managed set.

In the Settings section, click **Version history** to view the versions of shareable appliance settings that are available for this managed set

In the Appliance section, click **Appliance** to display a table of all of the appliances that are assigned to the managed set.

Name

Specifies a user-defined symbolic name for a managed set. This field is read-only

Firmware version

Specifies the firmware version that is to be synchronized to all of the appliances in the managed set.

If you have a single appliance managed set, and if there is not a firmware version in the DataPower appliance manager that matches the firmware that is used by the master appliance for that managed set, this field might be blank. In this situation, you can either add a firmware to the DataPower appliance manager that has the same version number, appliance type, model type and compatible licensed features as the single appliance in the managed set, or you can click **Change firmware** in the Firmware section, and select a firmware version for the managed set. This new firmware automatically becomes the firmware for the single appliance in this managed set, and must have the same appliance type, model type and licensed features as that appliance.

Operational status

Specifies the aggregated operational status of all the managed domains on all of the appliances in the managed set.

The status is unknown if the managed set does not have any managed domains. If the managed set has managed domains, the status reflects the aggregated operational status of all of the managed domains on all of the appliances in this managed set.

This field is read-only. The following values might appear in this field:

up Indicates that all of the service objects in all the managed domains on all of the appliances in the managed set are enabled.

partial Indicates that the service objects in all the managed domains on all of the appliances in the managed set are a mix of enabled, disabled and unknown.

down Indicates that all of the service objects in all the managed domains on all of the appliances in the managed set are disabled.

unknown

Indicates that the state of all of the managed domains on all of the appliances in the managed set

cannot be determined. This status might mean that the state has not yet been retrieved, or communication to the appliance has been lost. A managed set that does not have any managed domains always has a status of unknown.

Synchronization status

Specifies whether the designated firmware version, sharable appliance settings, and managed domain versions for the managed set are synchronized across all of the appliances in the managed set. This synchronization status combines the firmware synchronization status, the settings synchronization status, and the synchronization status of all the managed domains on all the appliances of the managed set.

This field is read-only. The following values might appear in this field:

synced

Indicates that the managed set is synchronized.

changes pending

Indicates that the synchronization is queued. The appliance has at least one firmware synchronization, settings synchronization, or managed domain synchronization queued.

in progress

Indicates that the synchronization is currently being processed. At least one appliance in the managed set has a firmware synchronization, settings synchronization, or managed domain synchronization in progress. Other firmware synchronizations, settings synchronizations, or managed domain synchronizations might also be pending for appliances in the managed set.

unknown

Indicates that the synchronization status is not known. At least one appliance in the managed set has a firmware synchronization, settings synchronization, or managed domain synchronization for which the synchronization state is unknown. Typically, this means that the appliance manager has not yet contacted the appliance to get the management status. Firmware synchronizations, settings synchronizations, or managed domain synchronizations might also be pending or in progress for appliances in the managed set.

error Indicates that an attempt to synchronize the managed set has failed because of an error on an appliance in the managed set. The appliance did respond, but responded with an error. Appliances in the managed set might also have a management status of unknown, in progress or changes pending for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

unreachable

Indicates that the appliance is unreachable. An attempt to synchronize the managed set has failed because an appliance is not responding. Appliances in the managed set might also have a management status of unknown, in progress, changes pending or error for a firmware synchronization, settings synchronization, or managed domain synchronization. See the error log for the deployment manager for more information.

Managed domains

Specifies a list of managed domains. You can use this list to change a managed domain to an unmanaged domain.

The managed domains of a master appliance are copied to all appliances in the managed set. Expand this section to view a list of the managed domains. You can then select one or more managed domain, and click **Unmanage** if you want to turn the selected domains into unmanaged domains. When a managed domain becomes an unmanaged domain, it displays in the Unmanaged domains table instead of in the Managed domains table.

If you need to modify a managed domain on the master appliance, select that managed domain, and then click **Launch** to launch the DataPower WebGUI on the selected managed domain on the master appliance.

in the managed set. A new domain version is automatically created whenever you save changes in the managed domain on the master appliance. This new version becomes the current version and the changes are synchronized across the managed set.

Unmanaged domains on the master appliance

Specifies a list of unmanaged domains. You can use this list to manage these unmanaged domain.

The managed domains of a master appliance are copied to all appliances in the managed set. By default, domains are not managed. Unmanaged domains are not copied to subordinate appliances in the managed set.

Expand this section to view a list of the unmanaged domains. You can then select one or more unmanaged domain and click **Manage** to turn the selected domains into managed domains. When a unmanaged domain becomes a managed domain, it displays in the Managed domains table instead of in the Unmanaged domains table.

If you need to modify the configuration of the master DataPower appliance that is contains in an unmanaged domain, select that domain, and then click **Launch** to launch the DataPower WebGUI on the default domain of the master appliance in the managed set. You can then navigate to the unmanaged domain in the DataPower WebGUI. Clicking this **Launch** button is equivalent to clicking the **Launch** button at the top of this administrative console page.

Edit membership for a managed set

Use this page to add appliances to the managed set, remove appliances from the managed set, or mark an appliance as the master appliance for the managed set. All of the appliances in a managed set must have the same appliance type, model type and licensed features.

This page lists appliances that are members of this managed set.

To view this administrative console page, click **Servers > DataPower > Managed sets > *managedset_name* > Edit membership**.

To mark an appliance as the master appliance for the managed set, select the appliance that you want to make the master appliance, click **Mark as master**, and then click **Save**. After you click **Save**, the selected appliance becomes the master appliance.

To remove appliances from the managed set, select the appliances that you want to remove, click **Remove**, and then click **Save**. After you click **Save**, all the appliances that you selected are removed from the managed set.

Add appliances to the Managed Set.

Specifies a list of DataPower appliances that you can add to a managed set. Because all of the appliances in a managed set must have the same appliance type, model type and licensed features, only the appliances that meet these conditions are included in this list.

To add appliances to a managed set, select the appliances that you want to add from the list of appliances, and then click **Apply > Save**. After you click **Save**, all of the appliances that you selected are added to the managed set.

Appliance

Specifies the user-defined appliance name for a DataPower appliance. This field is read-only

Host name

Specifies an IP address or the fully qualified host name of a DataPower appliance. This field is read-only

Appliance type

Specifies the appliance type, such as XA35, XS40, and XI50. This field is read-only

Master

Specifies whether or not an appliance is the master appliance for the managed set. All appliances in the managed set are synchronized using the firmware version, settings, and managed domains of the master appliance. This field is read-only

Modifying DataPower appliance manager settings

You can change the global settings that apply to the DataPower appliance manager.

About this task

Complete the following actions to change the global settings that apply to the DataPower appliance manager.

Procedure

1. From the administrative console, click **Servers > DataPower > Appliance manager settings**.
2. To change the maximum number of domain and settings versions that can be stored in the DataPower appliance manager, specify a new value in the **Maximum number of versions to store** field.
When the value specified in this field is exceeded, the DataPower appliance manager does not allow you to create any new versions until you delete one or more of the existing versions.
gotcha: If you decrease the value for this setting, you might lose versions if the current number of versions stored exceeds the new maximum number of versions stored.
3. To change the directory where firmware versions, shareable appliance settings and managed domain versions are saved, specify that new directory in the **Versions directory** field.
gotcha: If you change the versions directory, you must move all of the current versions from the current directory to the new directory. This process might take a considerable amount of time, depending on how many versions you have, and could keep the appliance manager from performing other operations
4. View the status for the appliance manager.
The DataPower appliance manager automatically starts when the deployment manager starts, if the appliance manager has appliances to manage. The appliance manager also automatically starts when a user submits a request to the appliance manager. For example, displaying the list of appliances that are defined in the appliance manager causes the appliance manager to start if it is not already running.
5. In the Operations section, click **Export** to export a copy of the DataPower appliance manager configuration to a file. This process is useful if you want to create backup copies of the appliance manager configuration.
6. In the Operations section, click **Import** to import the DataPower appliance manager configuration from a file. The file that you import from must reside on the same system as the deployment manager.
7. If you changed the maximum number of versions that you want stored, or you changed the version directory, click **Apply** to apply your changes.
8. Click **Shutdown Manager** if you need to stop the appliance manager.

Appliance manager settings

Use this page to specify global settings for the DataPower appliance manager. You can also use this page to shutdown the appliance manager.

To view this administrative console page, click **Servers > DataPower > Appliance manager settings**.

You can then click:

- **Export**, if you want to start the wizard that is used to export your DataPower appliance manager configuration to a file. After the wizard starts, you must specify the fully qualified name of the file into which you want to export the DataPower appliance manager configuration. The Export wizard exports the specified file onto the file system of the deployment manager.
- **Import** to start the wizard that is used to import a previously exported copy of your DataPower appliance manager configuration from a file. After the wizard starts, you must select either **Upload from local system** or **Upload from remote system**. Then specify the fully qualified file path of the file from which you want to import your DataPower appliance manager configuration. If you do not know the fully qualified name of the file, you can use the browse function to locate the file.
- **Shutdown Manager** if you want to shutdown the appliance manager.

Maximum versions stored

Specifies the maximum number of domain and settings versions that can be stored in the DataPower appliance manager. For example, if you specify a value of 3, for each managed set, you can have 3 sharable settings versions, and 3 versions of each managed domain.

You can view the shareable appliance settings version history, or the domain versions history to determine which versions are available for specific managed sets.

To view the sharable settings version history for a managed set, click **Servers > DataPower > Managed sets > *managed_set_name* > Settings Version history**

To view the version history for a managed domain for a managed set, click **Servers > DataPower > Managed sets > *managed_set_name* > Managed Domains > *.managed_domain_name* > Version history**

Versions directory

Specifies the directory into which you want the versions stored. Whenever the DataPower appliance manager detects a change in the sharable appliance settings, or a managed domain on the master appliance for a managed set, a new sharable appliance settings, or managed domain version is automatically created.

Status

Specifies whether the appliance manager is started or stopped. Click **Shutdown Manager** to stop the appliance manager.

DataPower appliance manager automatically starts when the deployment manager starts if there are appliances for the appliance manager to control. The appliance manager also automatically starts when requests are sent to the appliance manager.

If the status is stopped, the DataPower appliance manager automatically restarts the next time that you send a request to the appliance manager.

Importing an exported DataPower appliance manager configuration

You can import an exported DataPower appliance manager configuration if you want to use that configuration, instead of the current configuration, as the configuration for the appliance manager. For example, if the current configuration is corrupted, you might want to import a backup copy of that configuration that you have stored in either a local or remote file system.

About this task

Like a file that contains a firmware version, a file that contains an exported DataPower® appliance manager configuration can be stored on the system on which the browser is running, or it can be stored on the system on which the deployment manager is running. A file that is on stored on the system on

which the browser is running is considered stored on a local system. A file that is stored on the system on which the deployment manager is running is considered stored on a remote system.

Complete these steps to use the administrative console to import a repository file from a remote system.

Procedure

1. In the administrative console, click **Servers > DataPower > Appliance manager settings**.
2. In the Operations section, click **Import** to import an exported DataPower appliance manager configuration.
3. Select **Upload from local system** or **Upload from remote system**.
4. In the **Fully qualified file name** field, enter the fully qualified file name for the file that you want to import. The fully qualified name of a file includes the full directory path to that file, and the file name. If you don't know the fully qualified name of the file, use the browse function to locate the file.
5. Click **Next**.
6. View the summary information, and then click **Finish**.

Exporting the DataPower appliance manager configuration

You can export the DataPower appliance manager configuration to a file on the system where the deployment manager is running.

About this task

Complete these steps if you want to use the administrative console to export the DataPower appliance manager configuration to a file on the system where the deployment manager is running.

Procedure

1. From the administrative console, click **Servers > DataPower > Appliance manager settings**.
2. In the Operations section, click **Export** to export the file to the system where the deployment manager is running.
3. In the **Fully qualified file name** field, enter the fully qualified file name for the file that you want to export. The fully qualified name of a file includes the full directory path to that file, and the file name.
4. Click **Next**.
5. View the summary information, and if the summary information is correct, click **Finish**.

Monitoring tasks that DataPower appliance manager is handling

Use this page to view the status of long running requests, or tasks, that are queued for the DataPower appliance manager to complete.

About this task

There are additional tasks that the appliance manager automatically runs that are used to maintain the state of the managed sets. These tasks are not included in the list of long running tasks. However, if an error occurs while one of these tasks are running, the error is recorded in the log to help you diagnose the problem.

Complete the following steps if you want to use the administrative console to view the long-running tasks that are in queue for the DataPower appliance manager.

Procedure

1. From the administrative console, click **Servers > DataPower > Tasks**.
2. From the Tasks collection page, view information about the tasks.

- Optional: Select the Task ID of the task that you want to delete, and then click **Remove**.
When you click **Remove**, the task is removed from your view, but the appliance manager still runs the task as soon as it is able to do so.
Tasks are automatically deleted after 24 hours to save memory.

Note: You cannot remove a task to stop the task from being completed. The only way to interrupt a running task, or prevent the appliance manager from running a task, is to shutdown the appliance manager. Shutting down the appliance manager terminates all running and queued tasks.

DataPower appliance manager tasks collection

Use this page to view the status of a task. A task is a long running request that you have asked the DataPower appliance manager to process. You can remove a task from the list of pending tasks. However, removing a task from that list does not prevent that task from running.

This page lists the long running tasks that need to be completed for an appliance. If you notice that a error has occurred during the processing of a task, you can find additional information about that error in the deployment manager log. This additional information might help you to diagnose the problem.

There are additional tasks that the appliance manager automatically runs that are used to maintain the state of the managed sets. These tasks are not included in the list of long running tasks. However, if an error occurs while one of these tasks are running, the error is also recorded in the deployment manager log.

To view this administrative console page, click **Servers > DataPower > Tasks**.

To remove a task, select the task identifier (ID) in the list of tasks, and click **Remove**.

Tasks are automatically deleted after 24 hours to save memory.

gotcha: Removing a task does not stop the task from being completed, nor does it delete the task. Even though you are no longer able to view the task, the appliance manager still executes the task when it gets to that task in the queue of tasks to execute. The only way to interrupt a running task, or prevent the appliance manager from running a task, is to shutdown the appliance manager. Shutting down the appliance manager terminates all running and queued tasks.

Task ID

Specifies an automatically generated ID number for a task.

Creation Date

Specifies the date on which the task was created

Description

Specifies information about the task.

Result

Specifies the result for the completed task, such as the serial number for an added appliance.

Created By

Specifies the username of the user who issued the request that resulted in the task being created. This field is blank if security is not enabled for the deployment manager.

Status

Specifies whether the task is completed, or is still in progress. Valid states include: Completed, Error, In progress, and Queued.

Administering managed domain versions

You can change the version of a managed domain that the DataPower appliance manager uses for a managed set, or you can copy a version of a managed domain to another managed set.

About this task

Each time domain settings are changed, DataPower appliance manager automatically creates a copy of the previous domain settings as a new domain version. You can use the administrative console to view a history of domain versions, change a different domain version to the active version, or copy a domain version to another managed set. Complete one or more of the following steps to administer managed domains.

Procedure

1. From the administrative console, click **Servers > DataPower > Managed sets > *managedset_name***.
2. In the Managed domains section, expand Managed domains, and then click the name of the managed domain whose history you want to view.
3. Click **Versions > Version history > Details** to view a list of the versions of that managed domain. From the Domains history settings page, you can perform the following actions:
 - a. Select a version, and click **Change Domain Version** to change the selected version to be the new active version
 - b. Click a version number to view information about the version, or change the description for the version.
 - c. In the Additional Properties section, click **Copy to another managed set** to copy the domain version to another managed set.

Domain history collection

Use this page to view the domain history for DataPower appliance manager. A domain version is an automatically generated copy of a managed domain.

To view this page, in the administrative console, click **Servers > DataPower > Managed sets > *managed_set_name* > Managed domains > *domain_name* > Versions > Version history > Details**.

The newest version of the domain is, by default, the active version. To change from the current domain version to a domain version in the list, select the version number in the list of available versions, and click **Change Domain Version**.

Version

Specifies a numeric value that represents a domain version. When you change the settings for a domain on the master appliance in a managed set, the appliance manager automatically detects the change and creates a copy of the change as a new domain version.

Date

Specifies the date when the domain version was created and stored in the DataPower appliance manager. Each time a domain is changed, a new version is created and stored in the DataPower appliance manager.

Description

Specifies information about the domain version. When a domain version is automatically generated, a default description is provided.

In Use

Specifies which version is active. The active version is automatically synchronized to all of the appliances in the managed set. Only one version can be active at a time.

Domain history detailed information

Use this page to view detailed information about a specific domain version for a managed domain in a managed set. A domain version is an automatically generated copy of an existing domain.

You can also use this page to specify a description for this domain version, or copy this domain version to a managed set.

To view this administrative console page, click **Servers > DataPower > Managed sets > *managed_set_name* > Managed domains > *domain_name* > Versions > Version history > Details > *version_number***.

Version

Specifies the automatically generated version number of this domain version. This field is read-only.

Whenever you change a managed domain, the appliance manager automatically detects the change and creates a copy of the changed domain as a new domain version. Because the version number is automatically generated, you cannot change the value that appears in this field.

Date stored

Specifies the date when the domain version was created and stored in the DataPower appliance manager. This field is read-only.

Whenever a domain is changed, a new version is created and stored in the DataPower appliance manager. Because the date is automatically generated, you cannot change the value that appears in this field.

Description

Specifies information about the domain version. When a domain version is automatically generated, a default description is provided.

Managing versions of sharable appliance settings

Every time that sharable appliance settings are changed, the DataPower appliance manager automatically creates a copy of the new shareable appliance settings as a new settings version. You can view a list of all of the available settings versions that are available for a managed set, you can change which version is the active version, or you can copy a version to another managed set.

About this task

To manage the versions of sharable appliance settings for a managed set, in the administrative console, click **Servers > DataPower > Managed sets > *managedset_name***, and then, in the Settings section, click **Version history**. Then complete one or more of the following actions if you want to display a list of all of the versions of sharable appliance settings that are available for a managed set, display information about a specific version, deploy a previous version, or associate a version with another managed set.

Procedure

- View the list of available versions.
- To change which sharable appliance settings version is the active version, select a version, and then click **Change Settings Version**. The DataPower appliance manager automatically synchronizes all of the appliances in the managed set to use the new active version.
- To view information about a specific version, click the name of that version.
- To change the description that is specified for a specific version, click the name of that version and update the **Description** field.

- To associate the selected version to another managed set, click the name of that version, and then, in the Additional Properties section, click **Copy to another managed set**.
 1. Using the wizard, choose a managed set from the list of managed sets, and then click **Next**
 2. View the summary information to verify that you have selected the correct managed set, and then click **Finish**

The Copy to another Managed Set wizard starts and enables you to copy the selected version to a different managed set. The sharable appliance settings are applied to all appliances in this other managed set.

gotcha: After the initial copy of the sharable appliance settings, the two managed sets are managed independently. Therefore, future changes to the sharable appliance settings in one managed set are not reflected in the other managed set.

If you click **Servers > DataPower > Managed sets**, click the name of the managed set that you selected in the wizard, and then, in the Settings section, click **Version history**, you should see a new version as the active sharable appliance settings version for that managed set. The new active version is the version that the Copy to another Managed Set wizard created during the copy process.

What to do next

Changing the active settings version or copying the settings to another managed set causes a task to be created. If you want to monitor the progress of this task, in the administrative console, click **Servers > DataPower > Tasks**

Settings history collection for a DataPower appliance manager

Use this page to view the settings history for a DataPower appliance manager. A settings version is an automatically generated copy of the sharable appliance settings for the master appliance in a managed set.

To view this page, in the administrative console, click **Servers > DataPower appliances > Managed sets > *managedset_name* > Settings > Version history > Details**.

The newest version of the settings is, by default, the active version. To change from the current settings version to a settings version in the list, select the appropriate version number in the list, and click **Change Settings Version**.

Version

Specifies a numeric value that represents a settings version. When you change the shareable appliance settings for a master appliance in a managed set, the appliance manager automatically detects the change, and creates a copy of the change as a new settings version.

In Use

Specifies which version is active. The active version is automatically synchronized to all of the appliances in the managed set. Only one version can be active at a time.

Date stored

Specifies the date when the settings version was created and stored in the DataPower appliance manager.

Description

Specifies user-defined information about the settings version.

Settings version Collection

Use this page to view detailed information about a specific settings version for the appliances in a managed set. A settings version is an automatically generated copy of the shareable appliance settings for the appliances in a managed set.

You can also use this page to specify a description for this settings version, or you can click **Copy settings version to another managed set** to copy this settings version to another managed set. For example, if you have a managed set on a test system, and a different managed set on a production system, you can use this copy capability to ensure that you are using the same sharable appliance settings version on both managed sets.

When you copy a settings version to a different managed set, the copied settings version becomes the active version for the destination managed set.

To view this administrative console page, click **Servers > DataPower > Managed sets > *managedset_name***, and then, in the Settings section, click **Version history**.

Version

Specifies a numeric value that represents a settings version. When you change the sharable appliance settings for the master appliance in a managed set, the appliance manager automatically detects the change, and creates a copy of the change as a new settings version. This is a read-only field.

Date stored

Specifies the date when the settings version was created and stored in the DataPower appliance manager. This is a read-only field.

Description

Specifies information about the settings version. When a settings version is automatically generated, a default description is provided.

Administering DataPower appliance domains

A DataPower appliance domain is a group of configuration information for an appliance. By default, these domains are unmanaged. You can use the administrative console to change an unmanaged domain to a managed domain, or to change a managed domain to an unmanaged domain. However, you cannot use the administrative console to configure a domain. You must use the DataPower WebGUI to configure a domain. See the DataPower WebGUI documentation for information about configuring a domain.

About this task

You can use the administrative console to change an unmanaged domain to a managed domain. However, you cannot use the administrative console to configure a domain. Use the DataPower WebGUI to configure a domain. See the DataPower WebGUI documentation for information about configuring a domain.

gotcha: The DataPower appliance manager synchronizes managed domains from the master appliance to the subordinate appliances in the managed set. However, it is possible that the managed domain might not be completely functional on all of the subordinate appliances. An example of this situation is when a service object, such as an XML firewall, in the managed domain has a listening port conflict on one of the subordinate appliances.

Complete one or more of the following steps to administer domains.

Procedure

1. From the administrative console, click **Servers > DataPower > Managed sets > *managedset_name***.
2. To change an unmanaged domain to a managed domain, complete the following actions.
 - a. In the Managed Domains section, expand Unmanaged domains.
 - b. Select the unmanaged domains that you want to convert to managed domains, and then click **Manage**.
3. To change an managed domain to an unmanaged domain, complete the following actions.

- a. In the Managed Domains section, expand Managed domains.
 - b. Select the managed domains that you want to convert to unmanaged domains, and then click **Unmanage**.
4. To access the DataPower WebGUI and re-configure a managed or unmanaged domain, select the domain that you want to re-configure, and click **Launch**.
 5. To delete a managed domain, select the domain that you want to delete, and click **Delete**.

Results

If you changed any managed domains to unmanaged, those domains are now listed under Unmanaged domains. Similarly if you changed any unmanaged domains to managed, those domains are now listed under Managed domains.

Managed domain settings

Use this page to view the settings for a managed domain. You can also use this page to view the version history for this managed domain, or to view the managed domains that exist for a specific appliance.

DataPower appliances support the use of application domains. An application domain consists of resources that are configured to provide and support one or more services.

Domains are used to partition configuration information on the appliance into self contained units that make the information easier to manage. A managed domain is a domain on the master appliance that has been added to a managed set in the DataPower appliance manager. The DataPower appliance manager synchronizes the managed domain across all of the appliances in the managed set.

To view this administrative console page, click **Servers > DataPower > Managed sets > *managedset_name* > Managed domains > *domain_name***.

Click **Launch** to access the DataPower WebGUI in the domain on the master appliance in the managed set. Pop-ups must be enabled to launch the DataPower WebGUI.

Click **Appliance** to display a table of all of the appliances that are assigned to the managed set and are synchronized for this managed domain. The table provides the following information for each appliance:

- The Name column specifies the name of the appliance in the appliance manager.
- The Master column indicates whether the appliance is the master in the managed set that the contains this managed domain.
- The Operational Status column indicates the operational status of the managed domain in the appliance. The following values might appear in this column:
 - up** Indicates that all of the service objects in the managed domain on the appliance are enabled.
 - partial** Indicates that the service objects in the managed domain on the appliance are a mix of enabled, disabled and unknown.
 - down** Indicates that all of the service objects in the managed domain on the appliance are disabled
 - unknown** Indicates the state of all of the in the managed domain on the appliance could not be determined. Possible causes are that the state has yet to be retrieved or communication has been lost to the appliance.
- The Synchronization Status column indicates whether the managed domain on the appliance is the same as the specified domain version for the managed set. The following values might appear in this column:

synced

Indicates that the managed domain on this appliance is the same as the specified domain version for the managed set.

changes pending

Indicates that the synchronization is queued for the managed domain on the appliance.

in progress

Indicates that the synchronization is currently being processed for the managed domain on the appliance.

unknown

Indicates that the synchronization status is not known. Typically, this means that the appliance manager has not yet contacted the appliance to get the synchronization status.

error

Indicates that an attempt to synchronize the managed domain on the appliance has failed because of an error on an appliance. The appliance did respond, but responded with an error. See the log for the deployment manager for more information.

unreachable

Indicates that the appliance is unreachable. An attempt to synchronize the managed domain has failed because the appliance is not responding. See the log for deployment manager for more information.

Click **Version History** to display a table of the versions for the managed domain. The table provides the following information for each version:

- The Version column specifies the version of the managed domain.
- The Date column indicates the date that the domain version was created.
- The In Use column indicates which domain version is active. The active domain version is the version this is synchronized across all of the appliances in the managed set.
- The Description column provides a description of the domain version.

Name

Specifies the name for the managed domain.

Secure Socket Layer communication with DataPower

Based on the default installations of the application server and the DataPower appliance manager, secure sockets layer (SSL) communication is used to send commands and receive events. The default SSL configuration used by the DataPower appliance manager can be strengthened by customizing the SSL connection. Modifying the default SSL configuration is optional and only needs to be done if the default configuration is not sufficient for your requirements.

SSL is used to send commands to each known appliance manager. In this scenario, the application server and the DataPower appliance manager behave as the SSL client and the DataPower appliances are acting as the SSL servers. This SSL connection uses the `ibmPKIX` trustmanager to do some verification of the DataPower appliance. Neither the certificate chain nor the revocation list for the certificate of the DataPower appliance are checked. The default configuration also does not do any SSL client validation for this scenario.

SSL is also used for the events received by the application server and the DataPower appliance manager from each DataPower appliance being managed. In this scenario, the application server and the DataPower appliance manager is the SSL server and the DataPower appliances are the SSL client. SSL client validation is also not performed in this scenario by default.

Most customizations that are available for SSL connections in WebSphere Application Server can be applied to the connections used by the DataPower appliance manager. To customize the SSL connections

used for communication between the DataPower appliance manager and the DataPower appliances, each change made to the SSL connection on the DataPower appliance manager must also be accompanied by a complimentary change on each of the DataPower appliances that it manages. The DataPower appliance manager uses the **DataPowerMgr_sslConfig SSL** profile to connect with the DataPower appliances to send the appliances commands. You may make changes to this profile to influence the SSL connection that is used to send commands to the appliances. The DataPower appliance manager uses the **DataPowerMgr_inbound_secure** inbound endpoint on the Dmgr to receive events from the appliances it manages. You may make changes to the profile used by this endpoint to influence the SSL connection used to send events from the managed appliances.

Tip: For instructions on how to modify the AMP XML Management Interface SSL configuration on a DataPower appliance, refer to the DataPower appliance WebGUI Guide section on the XML Management Interface and how to create a custom SSL Proxy profile.

Adding the DataPower signer certificate to the WebSphere Application Server default truststore to enable an SSL connection

When configuring a DataPower appliance when security is enabled, the signer certificate of the DataPower server must be added to the WebSphere Application Server default truststore to enable an Secure Sockets Layer (SSL) connection to be made from WebSphere Application Server to the DataPower server.

About this task

You can add the signer certificate of the DataPower server to the WebSphere Application Server default truststore to enable an Secure Sockets Layer (SSL) connection using the administrative console or by using the `addSignerCertificate wsadmin` command.

The DataPower signer certificate should be installed in the `DataPower-root-ca-cert.pem` file under the Deployment managers profile in the `WAS_HOME/profiles/<DMGR profile>/etc` directory.

Procedure

1. From the administrative console, click **Security > SSL certificate and key management > Key stores and certificates > CellDefaultTrustStore > Signer certificates > Add signer certificate**.
2. In the Alias box, enter an alias name in which to identify the DataPower signer certificate.
3. In the File name box, enter the full path to the `DataPower-root-ca-cert.pem` file.
4. Click **Apply** and **Save**.

Note: You can alternately use the `addSignerCertificate wsadmin` command to add the DataPower server to the WebSphere Application Server default truststore by entering the following:

```
wsadmin> AdminTask.addSignerCertificate(['-keyStoreName
CellDefaultTrustStore -certificateFilePath
c:/wasHomeDir/profiles/Dmgr01/etc/DataPower-root-ca-cert.pem
-certificateAlias datapower']).
```

If the `DataPower-root-ca-cert.pem` certificate file is not installed on the system, you can retrieve the DataPower certificate from the port using the administrative console:

- a. Click **Security > SSL certificate and key management > Key stores and certificates > CellDefaultTrustStore > Signer certificates > Retrieve from port**.
- b. In the Host box, enter the DataPower server hostname.
- c. In the Port box, enter the port of the DataPower server.
- d. In the Alias box, enter an alias name to identify the DataPower signer certificate.
- e. Click **Retrieve signer information**.
- f. Verify that the certificate information is correct, then click **Apply** and **Save**.

Chapter 4. Setting up the proxy server

A *proxy server* is a specific type of application server that routes HTTP requests to content servers that perform the work. You can classify a proxy server according to the role that it plays in a system. This specific proxy server is classified as a *reverse proxy server* because the main function is to act as the first point of contact, not including the firewall, for client requests *into* the enterprise server. By contrast, a *forward proxy server* acts as the first point of contact for *outbound* traffic.

Before you begin

Review the topic that describes how to select a front end for your WebSphere Application Server topology. This topic helps you determine whether you should set up a web server plug-in, a proxy server, or a secure proxy server to provide session affinity, failover support, and workload balancing for your WebSphere Application Server topology.


If you are familiar with the functionality of the legacy proxy server that existed in versions of the product prior to Version 6.0, review the following list of functions that were available in the legacy proxy server but are not available in the current proxy server:

- Forward proxy configuration, including SSL tunneling, transparent proxy, and FTP protocol
- Request URI rewrite (response URI rewrite is available)
- Authentication and authorization on the proxy server
- NCSA combined logging
- Custom logging
- Cache sharing
- Common Gateway Interface (CGI)

About this task

The proxy server acts as a surrogate for content servers within the enterprise. As a surrogate, you can configure the proxy server with rules to route to and load balance the clusters of content servers. The proxy server is also capable of securing the transport, using Secure Sockets Layer (SSL), and the content using various authentication and authorization schemes. Another important feature is its capability to protect the identity of the content servers from the web clients by using response transformations (URL rewriting). The proxy server can also improve performance by caching content locally and by protecting the content servers from surges in traffic.

A proxy server configuration provides settings that control how a proxy server can provide services for the enterprise applications and their components. This section describes how to create and configure proxy servers in an existing application server environment.



In Version 6.0.2 of the product, you had to augment the deployment manager profile to manage the proxy server. For Version 6.1 and higher, the proxy server is managed from the administrative console without initial augmentation.

Procedure

- Create an HTTP or Session Initiation Protocol proxy server to route requests to application server nodes.
- Install a Session Initiation Protocol proxy server.
- Migrate profiles for the proxy server.
- Modify or add HTTP endpoints

What to do next

- Create proxy servers in the cell.
- Deploy applications to the proxy server.

Creating a proxy server

This topic provides information to create and configure a proxy server. When creating a proxy server, only the application server profile can be used as the target node.

About this task

The proxy server routes requests to application server nodes. The proxy server can dynamically route requests to all on-demand configuration (ODC) enabled application servers without additional configuration.

When you install the product, two profiles are created: a stand-alone application server profile, which is the default profile, and a deployment manager profile, which is called dmgr. When creating a proxy server, do not choose the deployment manager profile. Only the application server profile can be used as the target node.

Procedure

1. Create a proxy server in the administrative console by clicking **Servers > Server Types > WebSphere proxy servers > New**.
2. Select the node on which you want the proxy server to reside.
3. Enter a name for the new proxy server and click **Next**.
4. The supported protocols HTTP and SIP are selected for you. Select HTTP if your proxy server will route requests to and from a web container. Select Session Initiation Protocol (SIP) if your proxy server will route requests to and from a SIP container. Determine whether or not to generate unique HTTP ports by selecting or clearing Generate unique HTTP ports. Click **Next**.

Note: If you create multiple proxy servers on the same node for vertical scaling, then you might select the option to generate unique ports to avoid port conflicts. Certain advanced scenarios pertain to port mapping that might require unique ports. For example, a load balancer can load balance requests to the proxy servers within the same node, assuming that each proxy server is listening on a unique HTTP port. For the proxy server to accept requests for a specific virtual host, it is necessary to add the unique HTTP ports that are generated to the host alias of the virtual host. It might also be necessary to modify the port values that the wizard generates, if these ports conflict with other local servers on the same node.

5. Select a proxy server template on which to base your proxy server. Click **Next**. You can select a default template, or you can choose to map to an existing proxy server.

Mapping to a pre-existing proxy server is a time-saving technique. You can build one proxy server and apply all of the specific configurations your environment needs, and then use that proxy server as a template.

6. Review the summary panel and click **Finish**.

Results

You now have a functional proxy server that automatically routes HTTP requests to the cell that the proxy server belongs to or SIP requests to and from a SIP container. To enable routing to another cell, configure your cell to communicate with other cells.

gotcha: When using the proxy server, one should use the default port. If any other port is used, any HTTPS URL redirection might go to the wrong port. This is because the virtual host named default_host might also be using this new port. The HTTPS redirection is based on the first HTTPS port that it finds in the default_host.

gotcha: As the number of SIP containers grow in a deployment, the larger the heap settings need to be on the SIP proxy server. For example, a deployment of 20 containers requires a minimum heap size of 60 MB, so a -Xmo60m parameter should be added to the Generic JVM arguments field on the Java virtual machine panel of the admin console. However, a deployment of 70 containers requires a larger value such as 200 MB (-Xmo200m). See the information center topic *Java virtual machine settings* for more information about Generic JVM arguments.

Proxy server collection

This topic lists the proxy servers in the cell. A proxy server resides within a node.

A proxy server is used to classify, prioritize, and route HTTP and SIP requests to servers in the enterprise as well as cache content from servers. You can use this page to create, delete, or modify a proxy server.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers** .

To configure the proxy server to route work to WebSphere Application Servers in another cell, use core group bridge settings (**Servers > Core Groups > Core group bridge settings**), which sets up communication between cells.

Currently, configuring the proxy server to route work to a WebSphere Application Server Express cell requires advanced configuration. See the information on routing rules to learn more about setting the advanced configuration routing rules.

To configure the proxy server to route work to an application server that is not a WebSphere Application Server, the following advanced configuration is required:

1. Define a generic server cluster. From the administrative console, click **Servers > Clusters > Generic server clusters**.
2. Define a URI group. From the administrative console, click **Environment > URI groups**.
3. Create routing rules. From the administrative console, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy Server Properties > Routing rules**.

Both generic server clusters and URI groups are also accessible in the administrative console under Related Items for the proxy server.

Name

Specifies a logical name for the proxy server. For WebSphere Application Server, server names must be unique within a node.

If you have multiple nodes in a cluster, the server names must also be unique within the cluster. You cannot use the same server name within two nodes that are part of the same cluster. WebSphere Application Server uses the server name for administrative actions, such as referencing the server in scripting.

Node

The name of the node where the proxy server resides.

Version

Indicates the WebSphere Application Server version you are running.

Security level

The current overall security level of the proxy server.

The overall security level is determined based on the custom security settings. The possible values for Security level are High, Medium, Low, and Not applicable. The overall security level is equal to the security level of the setting that is considered the least secure. For example, to have an overall security level of High, all settings must be configured to the values associated with a HIGH level of security. If any of the settings are configured with a less secure value, the overall security level is the value of that setting.

Protocol

Indicates the protocol or protocols that the proxy server is configured to handle. This information is based on the types of transport channels that are included in the transport chains that are configured for the proxy server.

For example, if a transport chain includes an HTTP channel, HTTP displays in this field. If a transport chain includes both a SIP and an HTTP channel, SIP,HTTP displays in this field.




Status

Indicates whether the proxy server is started, stopped, or unavailable.

If the status is unavailable, the node agent is not running in that node and you must restart the node agent before you can start the server.

Table 11. Status settings of the proxy server.

This table lists the status settings of the proxy server.

  	<p>Started</p> <p>Stopped</p> <p>Unknown</p>	<p>The server is running.</p> <p>The server is not running.</p> <p>Status cannot be determined.</p> <p>A server with an unknown status might, in fact, be running but has an unknown status because the application server that is running the administrative console cannot communicate with this server.</p>
---	---	--

Proxy server configuration

You can modify an existing proxy server to perform advanced routing options, such as routing requests to a non-WebSphere Application Server cell, and to perform caching. The options to configure the proxy server from this panel are under Proxy server properties.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name**

Name

Indicates a logical name for the proxy server. Proxy server names must be unique within a node.

Run in development mode

Enabling this option can reduce the startup time of a proxy server. This time can include Java Virtual Machine (JVM) settings, such as disabling bytecode verification and reducing just-in-time (JIT) compilation costs. Do not enable this setting on production servers.

Specify this option if you want to use the -Xverify and -Xquickstart JVM settings on startup. After selecting this option, save the configuration and restart the proxy server to activate development mode.

The default setting for this option is `false`, which indicates that the proxy server is not started in development mode. Setting this option to `true` specifies that the proxy server is started in development mode with settings that speed server startup time.

Data type Boolean
Default false

Parallel start

Select this field to start the proxy server on multiple threads. This option might shorten the startup time.

Specify this option if you want the proxy server components, services, and applications to start in parallel, rather than sequentially.

The default setting for this option is `true`, which indicates that the proxy server is started using multiple threads. Setting this option to `false` specifies that the server does not start using multiple threads which might lengthen startup time.

The order in which the applications start depends on the weights that you assigned to each of them. Applications that have the same weight are started in parallel. You set the weight of an application with the **Starting weight** option on the **Applications > Application Types > WebSphere enterprise applications > application_name** page of the administrative console.

Data type	Boolean
Default	true

Start components as needed

Select this check box if you want the server components started as they are needed by an application that is running on this server.

When this check box is selected, server components are dynamically started as they are needed. When this check box is not selected, all of the server components are started during the server startup process. Therefore, selecting this option can improve startup time, and reduce the memory footprint of the server, because fewer components are started during the startup process.

Starting components as they are needed is most effective if all of the applications, that are deployed on the server, are of the same type. For example, using this option works better if all of your applications are web applications that use servlets, and JavaServer Pages (JSP). This option works less effectively if your applications use servlets, JavaServer Pages files and Enterprise JavaBeans™ (EJB).

Current Security Level

The current overall security level of the proxy server.

The overall security level is determined by evaluating the security settings. The possible values for Current Security Level are High, Medium, Low, and Not applicable. The overall security level is equal to the security level of the setting that is considered the least secure. For example, to have an overall security level of High, all settings must be configured to the values associated with a HIGH level of security. If any of the settings are configured with a less secure value, the overall security level is the value of that setting.

Proxy server settings

Use this topic to perform advanced configuration on a proxy server. Proxy settings enable the system administrator to fine tune the behavior of the proxy server. In particular, you can configure the connections and requests to the application server, enable caching, configure the requests that must be rejected, define how error responses are handled, and specify the location of the proxy logs.

The proxy server, upon creation, auto-senses the environment and is capable of routing requests to the product. Additional configuration can be applied to the proxy server to meet the needs of a particular environment.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > *proxy_server_name* > HTTP Proxy Server Settings > Proxy settings**.

You can edit configurable field settings for the proxy server on the Configuration tab.

Enable web services support

Specifies whether to enable the proxy server to route Web services traffic.

Data type	Boolean
Default	True

Static routing file directory

Specifies the directory on the proxy server where the static routing file is located.

Data type	String
Default	<i>profile_home</i> /staticRoutes

HTTP methods disabled

Specifies a list of HTTP methods that are disabled for the proxy server. Select the checkbox to enable this setting. Click **New** or **Delete** to add or remove HTTP methods from the list.

Data type	String
Default	Blank

Outbound connection settings

Specifies basic HTTP connection parameters between the proxy server and content servers.

Outbound request timeout

Specifies the default number of seconds the proxy server waits for a response before timing out a request to a content server. Consider this option carefully when changing the value.

Outbound connect timeout

Specifies the number of milliseconds that the proxy server waits to connect to a server. If this time expires, the proxy server attempts to connect to a different server. If no other available servers exist, the request times out. A value of 0 indicates that the proxy server should use the operating system kernel timeout value.

Pool connections to content server

Specifies the option to pool connections to the server is an optimization feature. Pooling prevents the need to frequently create and destroy socket connections to the server, by allowing the proxy server to pool these connections and reuse them.

Maximum connections per server

Specifies the maximum number of connections that will be pooled to any single content server.

Local outbound TCP address

Specifies the local outbound Transmission Control Protocol (TCP) address for data that enters and exits the SIP container. The value for this setting is the hostname or IP address to use for all communications between the SIP proxy and the SIP containers when the network is segmented.

Data type	String
Default	*
Range	IP address or valid host name

The following proxy custom properties are available to adjust the outbound connections.

- **key=http.maxTargetReconnects:** Maximum number of reconnects to the same target content server for each request. The default is 5.
- **key=http.maxTargetRetries:** Maximum number of times the proxy will attempt to select a new target content server for each request. The default is 5.
- **key=http.routing.sendReverseProxyNameInHost:** Determines whether or not the host header is rewritten for content that is not on a WebSphere Application Server content server. The options are `true` or `false` and are not case sensitive. If the value of this property is `false`, which is the default setting, then the host header is rewritten as the host of the target server. If the value for this property is `true`, then the host header is not rewritten.
- **key=http.compliance.disable:** Determines whether HTTP V1.1 compliance is enforced on proxy content server connections. The options are `true` or `false` and are not case sensitive. The default is `false`.
- **key=http.compliance.via:** The value of the via header that is appended to requests and responses for HTTP compliance. If the value is null, a via header will not be appended. If the value is `true`, a default via value is appended. Otherwise, the specified string via value is appended. The default is null.

Inbound connection SSL configuration

Specifies the SSL configuration from one of several sources.

Centrally managed

When selected, specifies to use the SSL configuration that is scoped for this endpoint.

Specific to this endpoint

When selected, enables the **Select SSL Configuration** list.

Select SSL Configuration

Specifies a predefined SSL configuration.

Data type	String
Default	None
Range	NONE, CellDefaultSSLSettings, or NodeDefaultSSLSettings

Caching

Specifies whether to enable the proxy server to cache the content of servers.

When **Enable caching** is selected, static content caching is enabled for the proxy server, as defined by HTTP 1.1 specifications. By default, caching content is enabled.

The properties that follow apply only if caching is enabled:

Cache instance name

Specifies the dynamic cache object cache instance that is configured in **Resources > Cache instances > Object cache instances**, which is used to cache all static and dynamic content responses. This object cache instance must be configured to support new I/O (NIO) application program interfaces (APIs).

Cache SSL content

Determines whether client proxy server SSL connections that are terminated by the proxy server should have their responses cached.

Cache aggressively

Enables caching of HTTP responses that would not normally be cached. Caching rules that are defined by HTTP 1.1 may be broken in order to gain caching optimizations.

Cache dynamic content

Specifies whether dynamic content that is generated by WebSphere Application Servers V6.02 or later is cached. Caching dynamic content generated by content servers prior to WebSphere Application Server V6.02 is not supported.

Limit memory cache entry size

When selected, the setting **Memory cache entry size** is enabled.

Memory cache entry size

Specifies the maximum size of an individual cached response in MB. Any cached response larger than this will not be cached.

Logging

The proxy server has logs that are generated for proxy and stored cache requests. When **Enable access logging** is selected, you can specify the size and location of the access logs.

Access log maximum size

Specify the maximum size, in megabytes, for an access log.

Data type	Integer
Units	Megabytes
Default	500

Proxy access log

Specifies a directory location for a proxy access log.

Data type String
Default `${SERVER_LOG_ROOT}/proxy.log`

Cache access log

Specifies a directory location for a cache access log.

Data type String
Default `${SERVER_LOG_ROOT}/cache.log`

Local access log

Specifies a directory location for a local access log.

Data type String
Default `${SERVER_LOG_ROOT}/local.log`

Note: There is a log called `${SERVER_LOG_ROOT}/local.log` that logs locally served proxy content. This content is not in the proxy cache.

HTTP requests are logged in one of three logs: proxy, cache, and local. Local log configuration is not currently available in the administrative console, but it is available at `${SERVER_LOG_ROOT}/local.log`. Specify the location of this log by setting the `http.log.localFileName` custom property to the file location. The content of each log is formatted using National Center for Supercomputing Applications (NCSA) common log format.

- Proxy access log: Logs responses that are received from remote servers.
- Cache access log: Logs responses that are served from the local cache.
- Local access log: Logs all non-cache local responses, for example, redirects and internal errors.

Proxy custom properties that can be used to tweak logging are as follows:

- `key=http.log.disableAll`: This property disables all logging. A value of `true` stops proxy, cache, and local logging.
- `key=http.log.maxSize`: The maximum log size in megabytes (MB). A value of `UNLIMITED` indicates unlimited. 25 MB is the default.
- `key=http.log.localFileName`: Contains the name of the local log. A value of `NULL` indicates that the default `${SERVER_LOG_ROOT}/local.log` is used.

Security

Use this section to set up security options.

Use a proxy-masking server header

When selected, specifies to forward the content server's name to the client.

Use the backend server header

When selected, specifies the default server name is sent as the content server name.

Specify a server header value

When selected, the **Server header** setting is enabled.

Server header

Specifies the server name that is used in HTTP responses.

Trusted security proxies

Specifies intermediaries other than the proxy server to handle requests. This setting identifies which proxy servers can be trusted. WebSphere Application Server plug-in clients add private headers to the requests that they forward. For the proxy server to use those headers, the request must come from one of the trusted security proxies. If the request does not come from one of the trusted security proxies, then those private headers are ignored and removed from the request before the proxy server

forwards the request. Use an IP or fully qualified host name in this field. If there are multiple IP addresses on the system where a WebSphere Application Server plug-in client is running, then the value in the trusted list must match the IP address of the outbound connection from that system. If you do not know the IP address that is used on the plug-in side of the connection, you should specify all of the IP addresses for that system to ensure that no matter which IP address is used on the outbound connection to the Proxy Server, that IP address matches one of the IP addresses in the trusted list.

Select the checkbox to enable **Security proxy**. Click **New** or **Delete** to add or remove proxies from the list.

Note: An empty list of trusted security proxies, which is the default value, indicates that no WebSphere Application Server plug-in clients are trusted.

Data type	String
Default	Blank
Range	IP address or valid host name

Proxy plug-in configuration policy

Use this section to configure proxy plug-ins.

Generate plug-in configuration

Specifies the generation of a proxy plug-in configuration file that you can use on a web server that is deployed in front of the proxy server. The plug-in can determine the URI that the proxy is handling on behalf of the application server. The plug-in can determine the endpoint, or boundaries of the proxy so that it can properly route requests that it receives to the proxy.

The options available to generate the plug-in are described in the following table:

Scope	Description
None	No scope.
All	The proxy server generates a plug-in configuration that includes all of the URIs that are handled by proxy servers in the local cell and all cells that are connected by a core group bridge.
Cell	The proxy server generates a plug-in configuration that includes all of the URIs that are handled by all the proxy servers in the cell.
Node	Includes all of the URIs that are configured for the node.
Server	The proxy server generates a plug-in configuration file only for the proxy server that is currently configured.

Plug-in config change script

Specifies the path to a script that is run after the WebSphere Application Server plug-in configuration is generated.

Custom error page policy

Use this section to configure settings for error pages when errors occur during the processing of a request.

The default is for no customized error pages to be generated.

Error page generation application URI

Specifies that if a valid uniform resource locator (URI) to an installed application is provided, the custom error page policy is enabled. If a valid URI to an installed application is not provided, the custom error page policy does not handle requests.

Handle remote errors

When selected, specifies HTTP response error status codes generated by the proxy server and HTTP

response error status codes generated elsewhere after the proxy on the proxy content server connection error responses are handled. When not selected, only HTTP response error status codes generated by the proxy server are handled. A best practice is to configure an error page application on the same physical machine as the proxy server.

Headers to forward to error page application

Specifies additional header values from the client request to forward to the error page application as query parameters. The responseCode and URI query parameters are always sent to the error page application, in addition to the ones that are configured. The responseCode parameter is the HTTP status code that generates internally or is returned by the content server. The URI parameter is the request URI for the client.

Example - The error page URI is /ErrorPageApp/ErrorPage, the headers to forward contain Host, and a client sends the following request:

```
GET /house/rooms/kitchen.jpg HTTP/1.1
Host: homeserver.companyx.com
```

The request results in a HTTP 404 response (local or remote), and the request URI to the error page application would be:

```
/ErrorPageApp/ErrorPage?responseCode=404&uri=/house/rooms/kitchen.jpg&Host= homeserver.companyx.com
```

HTTP status codes that are to be recognized as errors

Specifies the status codes that the error page policy provides a response for. If a status code is not specified, the original content of responses with that status code are returned. If no HTTP status codes are specified, the defaults, 404 and 5XX, are used. Instead of specifying status codes individually, the following method is recommended to represent a range:

- 5XX: 500-599
- 4XX: 400-499
- 3XX: 300-399
- 2XX: 200-299

Proxy custom property to use when tweaking the custom error page:

key=http.statuscode.errorPageRedirect. This custom property determines whether error page generation is done using the redirect, instead of using the proxy error page application. The values are true or false. The default is false.

Static file serving

Specifies the values needed for the proxy server to perform static file serving.

Static file document root

Specifies the location on the file system where the static document files are located.

Data type String
Default \${USER_INSTALL_ROOT}/staticContent

Content mappings

Specifies the content type mapping for a particular file extension. Specify a value for the following settings.

Extension	The subject file extension to map to a context type
Header	The header name to send to the client
Value	The value of the header to send to the client in the context-type header
Weight	A float value used to calculate the rank of files with this extension

Workload management

Specifies the values needed for the proxy server to perform workload management.

High availability monitor timeout

Specifies the amount of time, in seconds, before a high availability monitor timeout.

Data type	String
Units	Seconds
Default	300

Advisor URI

Specifies the uniform resource identifier (URI) for an advisor.

Data type	String
Default	/

Load balancing algorithm

Specifies the algorithm for the load balancer.

Data type	String
Default	Blank

Generic server clusters collection

Use this page to create, delete or modify a generic server cluster. Creating a generic server cluster is the next step towards generating the ability to route requests to a non-IBM application server, after creating the proxy server.

To view this administrative console page, click **Servers > Clusters > Generic server clusters**.

The system administrator can use the Generic Server Cluster panel to configure external servers, which are non-IBM application servers to create a logical cluster the proxy server can route work to. A generic server cluster defines the server endpoints that URI groups that are mapped to.

After you have created a generic server cluster, you want to create cluster members and define the cluster endpoints. Select the generic server cluster you created and click **Ports**.

Name

Specifies a logical name for the cluster. This is a user-defined field.

The name field cannot contain the following characters: # \ / , : ; " * ? < > | = + & % ' .

The name that defined must be unique among generic server clusters and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

Generic server clusters configuration

Use this topic to configure a generic server cluster. Creating a generic server cluster is the next step, after creating the proxy server, towards generating the ability to route requests to a non-IBM application server.

To view this administrative console page, click **Servers > Clusters > Generic server clusters > cluster_name**.

Now that you have configured a generic server cluster, you can create cluster members and define the cluster endpoints. Click **Additional properties > Ports**.

You can edit generic server cluster configurable field settings on the Configuration tab.

Name

Specifies the user-defined name for the cluster.

Protocol

The protocol field determines whether or not secure communication is used when connecting to members of the cluster.

The choices are HTTP and HTTPS.

Generic server cluster ports collection

After defining the generic server cluster name, use this page to create, delete, and configure the members of the cluster.

To view this administrative console page, click **Servers > Clusters > Generic server clusters > *cluster_name*Ports**.

Host

The host name is either an IP address or the qualified host name of the cluster member. Specify a valid host name.

Port

Specify a valid port number to associate with the host.

Generic server cluster members

After defining the generic server cluster name, use this page to define the members of the cluster.

To view this administrative console page, click **Servers > Clusters > Generic server clusters > *cluster_name* > ports > *host_name***.

After you complete this task, you can create a URI group and then define routing rules.

You can edit generic server cluster member field settings on the Configuration tab.

Host

The host name is either an IP address or the qualified host name of the cluster member.

Specify a valid host name.

Port

Enter the port on which the host name is listening. This entry ensures that the proxy server can communicate with the cluster member.

Specify a valid port number.

Weight

The load balancing weight is used to determine how frequently the cluster member is routed, relative to the other members in the group. The higher the weight the more frequently the cluster member is routed to.

The recommended weight value is between 1 and 20. A value of 0 will result in a cluster member that will never be routed to.

URI groups

A group of URI patterns, which you define, that can be mapped back to generic server clusters. When creating a URI group, verify that you are planning for URIs that form a logical collection. From this topic, you can create, delete, or modify a URI group.

To view this administrative console page, click **Environment > URI Groups**.

Name

The URI group name is a user-specified name.

The name field cannot contain the following characters: # \ / , : ; " * ? < > | = + & % ' ' .

The name that is defined must be unique among URI groups and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

URI group configuration

Use this topic to configure a URI group that can be mapped back to generic server clusters. When creating a URI group, ensure that you are planning for URIs that form a logical collection.

After you create a generic server cluster and a URI group, you are ready to define the routing rules that map the URI group to the generic server cluster. The routing rules ensure that the requests for specific URIs go to the proper generic server cluster.

To view this administrative console page, click **Environment > URI Groups > URI_group_name**.

You can edit URI groups configuration fields on the Configuration tab.

Name

The name field is required and is a user-defined field.

The name field cannot contain the following characters: # \ / , : ; " * ? < > | = + & % ' ' .

The name that is defined must be unique among URI groups and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

URI pattern

Use this field to define URI patterns that constitute the URI group.

The patterns can be any valid URI and can contain one or more wildcard characters.

Routing rules

Use this topic to set the advanced configuration routing rules to ensure work requests arrive at the proper generic server cluster. From this topic you can create, delete, or modify a routing rule.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP Proxy Server Settings > Routing Rules**.

Before you create routing rules, which are used to route requests to servers, you must define a generic server cluster (**Servers > Clusters > Generic server clusters**), a URI group (**Environment > URI groups**), and optionally appropriate virtual hosts (**Environment > Virtual hosts > default host**).

Routing rules are used to assist the routing of work requests to non-IBM application server nodes. In addition, using routing rules, a system administrator can reroute work without heavily impacting the environment. This capability is useful when nodes are taken down for maintenance.

For example, the system administrator can set up a routing rule to route `/images/*` to the ImageServerCluster generic server cluster. If the **ImageServerCluster** cluster has to come down, the administrator can then route `/images/*` to another cluster with similar capability, or use a redirect rule. This situation explains why the URI group can be defined independently of the generic server cluster. If the generic server cluster must come down, the URI group can be rerouted elsewhere. When you create the generic server cluster by providing a name, you can configure the cluster by using the ports link to create the actual cluster members.

Routing rules function by using the configured virtual hosts and URIs as matching criteria. The proxy server scans all incoming requests and compares the URI and host header from it and matches it against the virtual host and URIs that are configured in the rule. You must create the URI group for a routing rule before creating the routing rule. If you are routing to a generic server cluster, you must also create the cluster before defining the routing rule. You can create the URI group by completing the following tasks:

1. Create the routing rule name.
2. Determine if you want to enable this rule. You can create routing rules and not enable them. This capability is useful when planning for the maintenance of nodes or for emergency planning.
3. Select the virtual host name from the drop-down menu. The virtual host name field is a selectable field that is preconfigured with the defined virtual hosts in the cell. If you do not see the virtual host that you want in the menu, click **Environment >> Virtual hosts** and define the host there.
4. Select the URI group for the routing rule. The URI group field is populated with all the preconfigured URI groups in the cell. If you do not see the URI group that you are looking for, click **Environment >> URI groups** and create one.
5. Select and define a routing rule. This option specifies how to route a request that matches the defined virtual host and URI group. The three options for this field are:
 - Generic Server Cluster: Routes requests to a preconfigured generic server cluster. Use the drop-down box to select the generic server cluster.
 - Fail: Rejects requests by returning the specified HTTP status code.
 - Redirect: Redirects a client to the specified URL. This option can be used to ensure a request is routed through Secure Sockets Layer (SSL).

Name

The name field is required and is a user-defined field.

The name field cannot contain the following characters: `# \ / , : ; " * ? < > | = + & % '`

The name that is defined must be unique among routing rules and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

Routing rules configuration

Use this topic to create the advanced configuration routing rules to ensure that work requests arrive at the proper generic server cluster.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy Server Properties > Routing Rules > rule_name**.

You can edit routing rules configurable field settings on the Configuration tab.

Name

The name field is required and is a user-defined field.

The name field cannot contain the following characters: `# \ / , : ; " * ? < > | = + & % '`

The name that is defined must be unique among routing rules and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

Enable this rule

You can create routing rules and then not enable them. This capability is useful when planning for the maintenance of nodes or emergencies.

By default, the rule is enabled.

Virtual host name

The virtual host name field is a selectable field that is preconfigured with the defined virtual hosts in the cell.

If you do not see the virtual host that you are looking for in the menu, click **Environment > Virtual Hosts** from the administrative console and define the virtual host there.

URI group

The URI group field is populated with all the preconfigured URI groups in the cell.

If you do not see the URI group that you are looking for, click **Environment > URI Groups** and create one.

Routing action

This option specifies to the proxy server how to route a request that matches the given criteria (virtual host and URI group) that you defined. You have three options for this field.

Generic Server Cluster: If you want only the proxy server to seek a preconfigured generic server cluster, select that option and use the drop-down box to select the generic server cluster.

Failure Status Code: If you want to reject the requests that match the specific criteria, you use the failure status code and provide an HTTP status code to use in the response to the sender.

Redirect URL: Use this option to send a redirect to the client. If you select this option, enter a fully qualified URL like `http://abc.xyz.com`. Usually, the URL is somewhere within the enterprise, sometimes right back to the proxy on a different port. You can use this option to ensure a request is routed through protocols like Secure Sockets Layer (SSL).

Local route: Use this option to route requests to the root directory on the file system where static files are located.

Rewriting rules collection

Use this page to define how to rewrite URLs in a request or response.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Rewriting rules**.

From URL pattern

Specifies the original URL pattern in the 302 response header from the target server.

To URL pattern

Specifies how that URL should be modified so that the client is redirected to the proxy server or an appropriate public URL.

Rewriting rules configuration

Rewriting rules define how the proxy server rewrites URLs. Responses that have been redirected by target servers typically return a 302 status code with a location header that defines the URL that the client should be redirected to. Rewriting this URL is necessary if the target server is not aware of the proxy servers. The

redirected URL is modified to correctly point clients to the proxy server instead of directly to a target server that may not be visible to clients. Use the following properties to configure the URL rewriting rules for a proxy server

gotcha: The proxy server only supports rewriting redirected responses. Therefore, these the following settings only apply to redirected responses. These settings do not apply to requests because the proxy server does not support URL rewriting for requests.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Rewriting rules > New.**

From URL Pattern

Specifies the original URL pattern in the 302 response header from the target server.

The pattern can include the following wild card symbol: *

To URL Pattern

Specifies how that URL should be modified so that the client is redirected to the proxy server or an appropriate public URL.

The pattern can include the following wild card symbol: *

A rule with a from URL pattern of `http://internalserver/*` and to url pattern of `http://publicserver/*` would cause a redirected response with the original location header of `http://internalserver/secure/page.html` to be rewritten as `http://publicserver/secure/page.html`.

HTTP proxy inbound channel settings

Use this page to view and configure an HTTP proxy inbound channel. This type of transport channel provides the HTTP proxy capabilities.

To view this administrative console page, click **Servers > Proxy Servers > server_name > HTTP Proxy Server Settings > Proxy server transports > HTTP_PROXY_CHAIN > HTTP_proxy_inbound_channel_name.**

Transport channel name

Specifies the name of the HTTP proxy inbound channel.

The name field cannot contain the following characters: # \ / , : ; " * ? < > | = + & % '

This name must be unique across all channels in a WebSphere Application Server environment. For example, an HTTP proxy inbound channel and a TCP transport channel cannot have the same name if they reside within the same system.

Data type String

Discrimination weight

Specifies the priority this channel has in relation to the other channels in this transport chain. This property is only used when port sharing is enabled and the channel chain includes multiple channels to which it might forward data. The channel in the chain with the lowest discrimination weight is the first one given the opportunity to look at incoming data and determine whether or not it owns that data.

Data type Positive integer
Default 0

Starting a proxy server

Starting a proxy server starts a new server process based on the process definition settings of the current proxy server configuration.

Before you begin

Before you start a proxy server, verify that all of the resources that the proxy requires are available. You must also start all prerequisite subsystems.

About this task

This procedure for starting a server also applies to restarting a server. However, if a server fails and you want the recovery functions to complete their processing prior to new processes being started on the server, you must restart the server in recovery mode.

Use one of the following options to start a proxy server.

Procedure

- You can use the administrative console to start a proxy server.
 1. In the administrative console, click **Servers > Server Types > WebSphere proxy servers > .**
 2. Select the proxy server that you want to start, and click **Start**.
 3. Confirm that you want to start the proxy server.
 4. View the **Status** value and any messages or logs to see whether the proxy server was started.
- You can use the startServer Qshell command to start a proxy server.
- You can use the Submit Job (SBMJOB) CL command to start a proxy server. Enter the following line of code to use the SBJOB CL command.

```
SBMJOB JOB(jobNumber/QEJBSVR/jobName) OPTION(*CNTRLD) DELAY(delayTime)
```

In this example, *jobNumber* is the job number, *jobName* is the name of the proxy server job, and *delayTime* is the amount of time, in seconds, to wait for the job to start. You can initially set *delayTime* to 600 seconds and then adjust the value, if necessary, to a value that is more appropriate for your environment.

Results

The specified proxy server starts. To verify that the proxy server was started, in the administrative console, click **Servers > Server Types > WebSphere proxy servers > .**

What to do next

If you need to start the proxy server with standard Java debugging enabled, then complete these steps:

1. From the administrative console, expand **Servers > Server Types > WebSphere proxy servers > proxy_server_name**.
2. From Server Infrastructure, click **Java and process management > Process definition**.
3. Click **Java virtual machine**.
4. Select **Debug mode** to enable the standard Java debugger. Set **Debug mode** arguments, if needed, and click **OK**.
5. Save the changes to a configuration file.
6. Stop the proxy server, and restart the proxy server.

Stopping a proxy server

Stopping a proxy server ends a server process based on the process definition settings in the current application server configuration.

Before you begin

Ensure that you understand how stopping a particular server affects your ability to handle work requests, especially if you need to maintain a highly available environment.

About this task

There are times you need to stop a proxy server. For example, you might want to upgrade the operating system, or you might want to change a configuration setting for the proxy server. You can use one of the following options to stop a proxy server.

Note: To perform a proxy quiesce for your Session Initiation Protocol (SIP) proxy server, you must shut down the SIP proxy server by issuing the stopServer command from the command line. If you attempt to shut down the proxy server from the administrative console, then the server shuts down immediately and the proxy quiesce is not completed.

Procedure

- You can use the administrative console to stop a proxy server.
 1. From the administrative console, click **Servers > Server Types > WebSphere proxy servers**.
 2. Select the proxy server, and click **Stop**.
 3. Confirm that you want to stop the selected proxy server.
 4. View the **Status** value and any messages or logs to see whether the proxy server stops.
- You can use the stopServer Qshell script to stop a proxy server:
- You can use the End Job (ENDJOB) CL command to stop a proxy server. Enter the following line of code to use the ENDJOB CL command.

```
ENDJOB JOB(jobNumber/QEJBSVR/jobName) OPTION(*CNTRLD) DELAY(delayTime)
```

In this example, *jobNumber* is the job number, *jobName* is the name of the proxy server job, and *delayTime* is the amount of time, in seconds, to wait for the job to end. You can initially set *delayTime* to 600 seconds and then adjust the value, if necessary, to a value that is more appropriate for your environment.

Results

The specified proxy server stops as soon as requests assigned to that server finish processing. To verify that the proxy server is in the stop state, in the administrative console, click **Servers > Server Types > WebSphere proxy servers**.

Note: If the stopServer command is issued from the command line, then the server delays shutdown for a period of time until new inbound messages to route are not no longer being received. The quiesce feature notifies the load balancer to discontinue routing inbound messages by sending error responses to the advisor messages.

What to do next

If errors occur when you shut down a server, then read the *Troubleshooting and support* PDF.

By default, the SIP proxy server stops the flow of messages between the load balancer and the back-end containers to prevent calls from being lost when the proxy server shuts down. This process is called a proxy quiesce.

During proxy quiesce, the SIP proxy server notifies the load balancer and the back-end containers that the server is shutting down. After the devices stop forwarding messages through the proxy server, the server shuts down.

The default quiesce timeout period is three minutes. The SIP proxy server also waits a minimum of 20 seconds to allow the quiesce process to complete. The SIP proxy server continues to forward messages to the back-end containers while it responds to advisor messages from the load balancer with an error response. During a quiesce, the SIP proxy server also notifies the back-end containers that the proxy server is no longer a member of the cluster. After the initial 20 seconds, the SIP proxy server shuts down based on the specified amount of time configured for the proxy quiesce, which ranges from one second to a maximum of three minutes.

Complete these steps if you want to change the timeout period for proxy quiesce.

1. From the administrative console, expand **Servers > Server Types > WebSphere proxy servers > proxy_server_name**.
2. From Server infrastructure, click **Java and Process management > Process definition**.
3. Click **Java virtual machine**.
4. Set the Generic JVM argument to `-Dcom.ibm.ejs.sm.server.quiesceTimeout=120`.
5. Define these SIP proxy custom properties to set the SIP proxy server to be fronted by a load balancer running a SIP advisor: **LBIPADDR** and **SIPAdvisorMethodName**.

HTTP proxy server custom properties

You can add the following custom properties to the configuration settings for an HTTP proxy server.

To specify custom properties for a specific HTTP proxy server, navigate to the custom properties page, and specify a value for the custom property.

1. In the administrative console, expand **Servers > Server Types > WebSphere proxy servers > proxy_server_name** to open the configuration tab for the server.
2. Expand **HTTP Proxy Server Settings**, click **Proxy settings**.
3. Under **Additional properties**, click **Custom properties > New**.
4. On the settings page, type the custom property to configure in the **Name** field, and type the value of the custom property in the **Value** field.
5. Click **Apply** or **OK**.
6. Click **Save** on the console task bar to save your configuration changes.
7. Restart the server.

The following list of HTTP proxy server custom properties is provided with the product. These properties are not shown on the settings page for an HTTP proxy server.

- “cache.ignore.header.Authorization” on page 155
- “cache.ignore.header.Cookie” on page 155
- “cache.ignore.header.Proxy-Authorization” on page 155
- “cache.query.string” on page 155
- “http.auto.redirect.correction” on page 155
- “http.cache.nocache.headers” on page 156
- “http.clientInfoFromTrustedIntermediary” on page 156
- “http.connectionPoolUseForPOST” on page 156
- “http.disable.retry.on.503.uriprefix” on page 156
- “http.disable.response.buffering.urls” on page 157
- “http.isDisable10ResponseCaching” on page 157

- “http.log.history” on page 157
- “http.maxCachedPayload” on page 157
- “http.odcUpdateTimeout” on page 158
- “http.pmiTimerInterval” on page 158
- “http.routing.sendReverseProxyNameInHost” on page 158
- “http.virtual.port.map” on page 158
- “HTTPProxyAdvisorMethodName” on page 159
- “HTTPProxyAdvisorStartupDelay” on page 159
- “HTTPProxyAdvisorURI” on page 159
- “HTTPProxyAdvisorUserAgent” on page 159
- “LBIPAddr” on page 160
- “localOutboundTCPAddress” on page 160

cache.ignore.header.Authorization

Specifies the proxy will ignore the Authorization header in the requests if you set the custom property to true. If the response is also able to be cached, proxy will cache the response.

Data type	Boolean
Default	false

cache.ignore.header.Cookie

Specifies the proxy to ignore the cookie header in the requests if you set the custom property to true. If the response is also able to be cached, proxy will cache the response.

Data type	Boolean
Default	false

cache.ignore.header.Proxy-Authorization

Specifies the proxy will ignore the Proxy-Authorization header in the requests if you set the custom property to true. If the response is also able to be cached, proxy will cache the response.

Data type	Boolean
Default	false

cache.query.string

Specifies whether the default proxy cache key generator uses both the URL path and query string information to generate the cache key. To enable this function, set the custom property to true. However, if you enable Edge Side Include (ESI) caching on the proxy server, this custom property is not used. If you do not set this custom property, the proxy server generates a cache key based on the URL path only and not based on the query string information.

For more information on ESI caching, see [Configuring Edge Side Include caching](#).

Data type	String
------------------	--------

http.auto.redirect.correction

Specifies whether the proxy server should try to correct the value in the location header when a 302 response is returned from the generic server cluster.

If you specify none for this property, the proxy server never tries to correct the value in the location header when a 302 response is returned.

If you specify `gsc` for this property, the proxy server tries to correct the value in the location header only when the 302 response is returned from the generic server cluster.

If you specify `managed` for this property, the proxy server tries to correct the value in the location header only when the 302 response is returned from a managed server.

If you specify `all` for this property, the proxy server tries to correct the value in the location header whenever a 302 response is returned.

gotcha: The junction rewrite rule overrides the value specified for this custom property.

Data type	String
Acceptable values	none, gsc, managed, or all
Default	gsc

http.cache.nocache.headers

Specifies the set-cookie headers that you do not want to cache when the proxy server receives a response. By default, the proxy server stores set-cookie headers in the proxy cache. If the Cache-Control header information is not set properly, the proxy server might store some session-related, user private cookies. You can use this custom property to specify which set-cookie headers you do not want to store in the proxy cache.

Data type	A comma-separated string of HTTP header names
------------------	---

For example, you might provide the following values: `Set-Cookie,Set-Cookie2`. As a result, the proxy server does not store `Set-Cookie` and `Set-Cookie2` HTTP headers in the proxy cache.

http.clientInfoFromTrustedIntermediary

Specifies whether the proxy should extract the IP address from a WebSphere Application Server private header in a request. When the plug-in is deployed in front the proxy, the proxy server extracts the client IP address from the channels instead of from private headers forwarded from the plug-in. If this property is set to `true`, the proxy server extracts client information from private HTTP headers sent from the trusted plug-in instead of the channels.

Data type	String
Default	false

http.connectionPoolUseForPOST

Specifies whether the proxy server uses connection pooling for POST requests. POST requests, by default, are neither pooled, nor persistent requests. Therefore, if excessive POST requests are sent through the proxy server, port exhaustion might occur, resulting in bind exceptions. If this property is set to `true`, connection pooling is used for POST requests.

Data type	boolean
Default	false

http.disable.retry.on.503.uriprefix

Specifies URI prefixes for which you do not want the proxy server to automatically retry other servers when the proxy server receives a 503 response from the backend server to which it sent the initial request.

Typically when the proxy server receives a 503 response from a backend server, it marks the backend server as being down, and tries to send the request to another server. If, for specific URI prefixes, you do not want the proxy server to mark the backend server down, and to automatically retry other servers, you

can specify those prefixes as the value of this custom property. For any URI prefix specified for this property, if the proxy server receives a 503 response to that request from the backend server, the proxy server returns a 503 response directly to the client instead of retrying the request. The proxy server also does not mark the backend server as being down.

Data type	string that consists URI prefixes separated by commas
Default	No default value

http.disableResponseBufferingUris

Specifies under what conditions a proxy server buffers a response for heartbeat applications.

The value of the property is a comma-separated URL pattern, such as `/application_a/*.html;/application_b/*.html`. For example, if the proxy server receives a `/application_a/heartbeat.html` request, which matches one of the URI patterns in the custom property, the proxy server does not buffer the response body for the request. In this example, if the proxy server returns a byte, it forwards the byte to the client side without buffering.

Without this custom property, the proxy server receives responses and buffers the response body until the partial response body limit is reached.

Important: The buffering process might improve proxy server performance, however, it might cause client-side connection time-outs for some heartbeat applications.

http.isDisable10ResponseCaching

Specifies whether the proxy should unchunk, and buffer the response for an HTTP 1.0 client.

If the `http.isDisable10ResponseCaching` property is set to `true`, the proxy server does not generate the content length header, and does not include chunked data in the client side response. Instead, the proxy server closes the connection at the end mark of the response body.

Data type	boolean
Default	false

http.log.history

Enables you to increase the number of history files for the proxy server log files.

The proxy server log files are the `proxy.log`, `local.log`, and `cache.log` files. Without this custom property, you have one history file for these proxy server log files.

Data type	Boolean
Default	1

http.maxCachedPayload

Specifies the maximum size of a chunked response, for which the proxy server will generate a content-length header.

When the proxy server receives a chunked response for an HTTP 1.0 client, the proxy server assumes that the HTTP 1.0 client cannot handle the chunked message, and tries to un-chunk the message, and calculate the content length for the response body. If the size of the chunked response is equal to, or less than the size limit specified for this property, the proxy server generates a content-length header for the response. If the chunked response exceeds the size limit specified for this property, the proxy returns a 500 error message.

Data type	integer
------------------	---------

Default 100000 bytes

http.odcUpdateTimeout

Specifies the amount of time, in seconds, for the HTTP proxy server to wait during server startup before routing information. The proxy server waits for the specified number of seconds before binding its ports.

This custom property can be used to configure a delay in startup (before the HTTP/HTTPS ports are bound) for a period of time to allow for the propagation of the routing information. If you set the value to 300, the proxy server waits for 300 seconds to allow time for the routing information to propagate to the proxy server. If the routing information is propagated to the proxy server before 300 seconds, server startup resumes.

Data type String
Default 150

http.pmiTimerInterval

Specifies the estimated time interval, in milliseconds, after which PMI statistics are recorded in the proxy server.

gotcha: Specifying a value that is lower than the default of 100 milliseconds might impact proxy server performance because the proxy needs to check the current time more frequently.

Data type Integer
Default 100

http.routing.sendReverseProxyNameInHost

Specifies whether the host header is rewritten for content that is not on a WebSphere Application Server content server.

The options for this property are `true` or `false` and are not case sensitive. If the value of this property is `false`, then the host header is rewritten as the host of the target server. If the value for this property is `true`, then the host header is not rewritten.

Data type Boolean
Default false

http.virtual.port.map

Specifies the server port mapping information that the backend server uses to send responses back to the correct external website ports.

When port mapping information is configured on a load balancer that is sitting in front of the proxy server, the proxy server might not be able to forward the correct external website port information to the backend server because the external website port number is probably different from the web server plug-in, or proxy server listening port. You can use this custom property to correct the port information before the proxy server passes it on to the backend server.

For example, if the proxy server, or the web server plug-in is listening on ports 20080 and 20443, but the external website ports are 80, and 443, setting the following custom property for the proxy server enables the proxy server to provide the correct port information to the backend server. The backend server can then send responses to the correct external website ports.

Name: http.virtual.port.map
Value: 20080:80;20443:443

Data type	String value of port mapping pairs separated by semicolons
Default	none

HTTPProxyAdvisorMethodName

Specifies the HTTP method name, which is commonly HEAD, GET for the methods used. The HTTP method name is also the advisor method set on the front end load balancer. The custom property is enabling the proxy to match incoming requests and determine whether the requests are from the load balancer or not.

Data type	String value (HTTP method name, such as GET or READ)
Default	none

HTTPProxyAdvisorStartupDelay

Specifies the HTTP Advisor start up delay in seconds. The default value is 0 seconds.

When the proxy receives a request, it tries to match the request against the custom properties (LBIPAddr, HTTPProxyAdvisorURI, HTTPProxyAdvisorURI, HTTPProxyAdvisorStartupDelay) if they are defined

Note: You do not need to define all of these custom properties.

If all of the custom properties are matched, the request is considered to be the advisor request from the front end load balancer.

If current proxy start time is less than the value defined in the HTTPProxyAdvisorStartupDelay custom property, an HTTP 503 error code is returned directly from the proxy server to inform the load balancer that the proxy/backend servers are not ready to service HTTP requests.

If current proxy start time is greater than the value defined in the HTTPProxyAdvisorStartupDelay custom property, the proxy forwards the advisor request to the backend and returns the response back to the front end load balancer. Based on the status code returned from the back-end server, the front end load balancer determines whether the proxy/backend server(s) are ready to service requests.

If the proxy is shutting down, the proxy server returns a 503 error code for the advisor requests. This error code informs the load balancer that the proxy and the backend servers are not able to service further requests and the front end load balancer needs to stop sending requests to this proxy server.

Data type	Integer (time in seconds)
Default	0

HTTPProxyAdvisorURI

Specifies a fully qualified URI string. This is also the advisor URI set on the front end load balancer. An application on the back-end server must be configured to answer this request URI. The custom property is enabling the proxy to match incoming requests and determine whether the requests are from the load balancer or not.

Data type	String value (fully qualified URI)
Default	none

HTTPProxyAdvisorUserAgent

Specifies the front end load balancer user agent name. This custom property is enabling the proxy to match incoming requests and determine whether the requests are from the load balancer or not.

Data type	String value (HTTP User-Agent header value)
------------------	---

Default none

LBIPAddr

Specifies a semicolon separated IP address list. This custom property is allowing the proxy to match incoming requests and determine whether the requests are from the load balancer or not.

Data type String value (IP addresses separated by semicolons)
Default none

localOutboundTCPAddress

Specifies the host interface that is dedicated to HTTP traffic. This property determines the interface that is used to make outbound HTTP connections to the HTTP container.

Data type String
Default *

SIP proxy server custom properties

You can add the following custom properties to the configuration settings for the Session Initiation Protocol (SIP) proxy server.

To specify custom properties for a specific SIP proxy server, navigate to the custom properties page, and specify a value for the custom property.

Important: The custom properties are supported as the primary method of configuration. Therefore, if a custom property is set and then you set the corresponding setting in the administrative console, the custom property value is used.

1. In the administrative console, expand **Servers > Server Types > WebSphere application servers > server_name** to open the configuration tab for the server.
2. From **SIP proxy server settings**, expand **SIP proxy settings**, and click **Custom properties**.
3. From **Additional properties**, select **Custom properties > New**.
4. On the settings page, type the custom property to configure in the **Name** field, and type the value of the custom property in the **Value** field.
5. Click **Apply** or **OK**.
6. Click **Save** on the console task bar to save your configuration changes.
7. Restart the server.

You can define the following SIP proxy custom properties that are provided with the product. These properties are not shown on the settings page for a proxy server.

- “Overload custom properties” on page 161
- “burstResetFactor” on page 162
- “deflatorRatio” on page 162
- “dropOverloadPackets” on page 162
- “inDialogAveragingPeriod” on page 162
- “IsnLookupFailureResponseCode” on page 162
- “IsnLookupFailureReasonPhrase” on page 162
- “maxThroughputFactor” on page 162
- “numFailuresSipAdvisorRequests” on page 163
- “outDialogAveragingPeriod” on page 163
- “overloadResponseCode” on page 163

- “overloadResponseReasonPhrase” on page 163
- “perSecondBurstFactor” on page 163
- “proxyTransitionPeriod” on page 163
- “sipProxyStartupDelay” on page 164
- “sipAdvisorRequestTimeout” on page 164
- “trustedIPAddressList” on page 164

The following SIP general custom properties allow you to apply a variety of settings.

- “defaultTCPChainName” on page 164
- “defaultTLSChainName” on page 164
- “defaultUDPChainName” on page 165
- “identityAssertionHeaderRemovalEnabled” on page 165
- “isSipComplianceEnabled” on page 165
- “keepAliveFailures” on page 165
- “keepAliveInterval” on page 165
- “LBIPAddr” on page 166
- “localOutboundTCPAddress” on page 166
- “maxForwardsHeaderRequired” on page 166
- “maxWriteQueueEntries” on page 166
- “receiveBufferSizeChannel” on page 166
- “receiveBufferSizeSocket” on page 167
- “retryAfterValue” on page 167
- “sendBufferSizeSocket” on page 167
- “serverUDPInterface” on page 167
- “serverUDPPort” on page 167
- “SIPAdvisorMethodName” on page 168
- “sipClusterCellName” on page 168
- “tcp.IPSprayer.host” on page 168
- “tcp.IPSprayer.port” on page 168
- “tls.IPSprayer.host” on page 168
- “tls.IPSprayer.port” on page 168
- “udp.IPSprayer.host” on page 168
- “udp.IPSprayer.port” on page 168

Overload custom properties

Several of the SIP custom properties allow you to apply proxy-managed overload protection (PMOP). The PMOP overload settings allow for real-time protection against container overload.

- burstResetFactor
- deflatorRatio
- dropOverloadPackets
- inDialogAveragingPeriod
- maxThroughputFactor
- outDialogAveragingPeriod
- perSecondBurstFactor
- proxyTransitionPeriod
- sipProxyStartupDelay

- overloadResponseCode
- overloadResponseReasonPhrase

For more information on overload controls, refer to the Information Center topic *Session Initiation Protocol overload protection*.

burstResetFactor

Specifies the percentage of bursts during a given period of time. This custom property controls the amount of bursts that occur during the averaging period.

Data type Integer
Default 100

deflatorRatio

Specifies a static ratio. This custom property is only used during the transition period when a transition period is specified.

Data type Integer
Default 0

dropOverloadPackets

Specifies whether or not to drop packets when the SIP container is in an overloaded state. When this value is set to `False`, the proxy server responds with a 503 error when overloaded, otherwise the packet is dropped.

Data type Boolean
Default False

inDialogAveragingPeriod

Specifies the period of time, in seconds, during which in-dialog messages are averaged.

Data type Integer
Default 180

IsnLookupFailureResponseCode

Specifies the response code when a SIP request for affinity fails. This custom property enables you to override the default 404 error response that normally displays when affinity fails.

Data type Integer value that is a valid SIP response code
Default 404

IsnLookupFailureReasonPhrase

Specifies the response text to display when a SIP request for affinity fails. This custom property enables you to override the default "Not Found" error text that normally displays when affinity fails.

Data type String
Default "Not Found"

maxThroughputFactor

Specifies the percentage of the maximum number of messages per averaging period set. If this value is set to 0, then the maximum throughput feature is disabled. This custom property is used to calculate the maximum number of messages allowed per second before the proxy server begins to reject requests for new sessions. This custom property should be set to the same value for each proxy server.

Data type Integer
Default 0

numFailuresSipAdvisorRequests

Indicates the number of SIP advisor requests to miss before the SIP proxy recognizes that it is not processing any data. With this custom property, the SIP proxy will notice the failure to receive load balancer advisor requests.

If you use this custom property, consider setting its value to 3.

Data type Integer
Default No default value - this property is not enabled unless you specify a value.

outDialogAveragingPeriod

Specifies the period of time, in seconds, during which out-dialog messages are averaged.

Data type Integer
Default 360

overloadResponseCode

Specifies the value for the response code returned from the proxy when overload occurs and SIP requests from the container are rejected. When the proxy is configured for overload protection, the SIP proxy can be configured to detect overload status. The proxy monitors the amount of traffic processed at the proxy and limits the number of new requests. If a container is overloaded, the proxy rejects requests with a 503 response code. If you prefer to use a different response code for overload protection, you can configure this custom property to return a different response code.

Data type Integer
Default 503

overloadResponseReasonPhrase

Specifies the the response reason phrase that the proxy server issues when overload occurs and SIP requests from the container are rejected. When the proxy is configured for overload protection, the SIP proxy can be configured to detect overload status. The proxy monitors the amount of traffic processed at the proxy and limits the number of new requests. If a container is overloaded, the proxy rejects requests with a Service Unavailable response phrase. If you prefer to use a different response phrase, you can configure this custom property to return a different response phrase.

Data type String
Default Service Unavailable

perSecondBurstFactor

Specifies the percentage of bursts allowed through periodically (BTF).

Data type Integer
Default 150

proxyTransitionPeriod

Specifies the period of time, in seconds, to lock the deflator after the container shuts down.

Data type Integer

Default 0

sipAdvisorRequestTimeout

Specifies, in milliseconds, the amount of time the SIP proxy server waits for a DNS lookup to return from the Load Balancer.

If you do not specify a value for this custom property, the SIP proxy server waits for 2 seconds.

Specify a value of 0 to disable the monitoring of DNS lookups.

Data type	Integer
Default	3000 milliseconds

sipProxyStartupDelay

Specifies the period of time, in seconds, before the proxy server restarts to allow the proxy to become stable in the cluster and avoid an erroneous overloaded state.

Data type	Integer
Default	0

trustedIPAddressList

Specifies a colon-delimited list of IP addresses from which messages with a p-asserted identity header can flow through the SIP proxy server for WebSphere Application Server. If a p-asserted identity header exists in a message from an IP address that is not in this list of IP addresses, the header is removed.

The list of IP addresses must be specific, such as 192.168.0.1.

Beginning with this service release, the custom property requires a semicolon-delimited list. Also, you can specify a range of IP addresses such as 192.168.0.* instead of a list of specific IP addresses.

Data type	Numerical list of IP addresses
Default	None

defaultTCPChainName

Specifies the default TCP chain name to use when setOutboundInterface is not called. If you are using the web collaboration feature of the Feature Pack for Communications Enabled Applications (CEA) in a multihome environment, you must set this variable properly so that the web collaboration component can pick up the proper interface to use when routing data.

Data type	String
Default	None

defaultTLSChainName

Specifies the default TLS chain name to use when setOutboundInterface is not called. If you are using the web collaboration feature of the Feature Pack for Communications Enabled Applications (CEA) in a multihome environment, you must set this variable properly so that the web collaboration component can pick up the proper interface to use when routing data.

Data type	String
Default	True

defaultUDPChainName

Specifies the default UDP chain name to use when `setOutboundInterface` is not called. If you are using the web collaboration feature of the Feature Pack for Communications Enabled Applications (CEA) in a multihome environment, you must set this variable properly so that the web collaboration component can pick up the proper interface to use when routing data.

Data type	String
Default	None

identityAssertionHeaderRemovalEnabled

Specifies that all identity assertion related headers in SIP requests coming through the SIP Proxy to the SIP containers should be removed. If you set this property to `false`, the identity assertion related headers are kept as part of the requests.

Data type	Boolean
Default	true

isSipComplianceEnabled

Specifies whether SIP compliance checking is enabled in the SIP proxy server. SIP compliance checking ensures that the SIP messages conform to the Session Initiation Protocol standard. When this property is set to `true`, SIP compliance checking is enabled.

gotcha: If you are running a proxy server in a z/OS WebSphere Application Server, Network Deployment environment, and your proxy server is not part of a cluster, you can use this custom property to enable or disable SIP compliance checking for that SIP proxy server. However if you are running a stand-alone application server or your proxy server is part of a cluster, you must use the `DisSipComplianceEnabled` to generic JVM argument to enable or disable SIP compliance checking.

Data type	Boolean
Default	true

keepAliveFailures

Specifies the number of keepalive messages that must be missed before the proxy determines that the connection with the SIP container is down.

The proxy sends a keepalive message to the container at each `keepAliveInterval`. If the proxy does not receive a response to the message, it considers the lack of response as a failure. If the proxy receives a specific number of consecutive failures, it considers the container down and begins forwarding messages to a different SIP container.

Data type	Integer
Default	0

keepAliveInterval

Specifies the interval, in milliseconds, at which keepalive messages are sent to the SIP containers. A keepalive message is sent at the specified interval. If the specified number of **keepAliveFailures** messages is received from the SIP container, the proxy considers the container to be down. The proxy then routes data to a back-up SIP container until the connection between the proxy and the primary container is restored.

The first keepalive message contains the interval of time between the keep alive messages and the number of failures that are required before the container is considered down. The starting values should be specified based on the high availability (HA) heartbeat configuration.

Data type	Integer
Default	0

LBIPAddr

Specifies the IP address, such as 192.101.1.5, of the load balancer used to load balance the SIP proxy. Multiple load balancer addresses can be configured by separating each IP address using a semicolon (;).

When SIP messages with the method configured as `SIPAdvisorMethodName` are received by the SIP proxy from the specified IP address, the SIP proxy responds with a success message if the SIP proxy can forward the messages to the SIP container. The SIP proxy responds with a failure message if messages cannot be forwarded to the SIP container. The load balancer then determines if the messages should be routed to the SIP proxy.

Data type	String
Default	null

localOutboundTCPAddress

Specifies the source interface to which the proxy binds when establishing connections to back-end SIP containers. This property is used when your proxy server is multihomed and needs to be configured to use a specific interface to send SIP traffic to the SIP containers. This property applies to both Transmission Control Protocol (TCP) and Transport Layer Security (TLS) connections.

Data type	String
Default	*

maxForwardsHeaderRequired

Specifies whether a Max-Forwards header must be present in all SIP requests and responses. The Max-Forwards header is used to limit the number of proxies or gateways that can forward a request.

The SIP Proxy requires that the Max-Forwards header be present in all SIP requests and responses. When this property is set to `true`, which is the default setting, and a Max-Forwards header is not included in a request, the SIP proxy issues a warning message that sends a 400 error response to that SIP request.

If you set this custom property to `false` the Max-Forwards header requirement is not enforced the requirement of the Max-Forwards header being required. Even if this property is set to `false` the SIP proxy decrements the value of this header if it is present in the request.

Data type	Boolean
Default	true

maxWriteQueueEntries

Specifies the number of messages that can be queued when a connection is slow or cannot be established. If the value is a large number, then more memory is consumed. A small number causes packets to be lost if the endpoint clears.

Data type	Integer
Default	100000

receiveBufferSizeChannel

Specifies the value, in bytes, for the maximum size of an incoming UDP packet, which is the size of the receive buffer that is allocated in the proxy server-side UDP connection.

Data type Integer
Default 65535

receiveBufferSizeSocket

Specifies the value, in bytes, for the lower-level datagram buffers, which is the size of the DatagramSocket receive buffer (SO_RCVBUF) in the proxy server-side User Datagram Protocol (UDP) connection.

Use this property to buffer multiple packets in the DatagramSocket layer. If the value of the property is too small, then packets might be lost if the server is overloaded. If the value is too large, then the packets might be delayed.

Data type Integer
Default 1024000

retryAfterValue

Specifies the amount of time, in seconds, before the client tries again to route a request to the proxy server. This custom property value is returned to the client in the error response if the SIP container is overloaded or if the SIP proxy cannot locate a server to which to route a request.

Data type Integer
Default 5

sendBufferSizeSocket

Specifies the value, in bytes, for the lower-level datagram buffers, which is the size of the DatagramSocket send buffer (SO_SNDBUF) in the proxy server-side UDP connection.

Use this property to buffer multiple packets in the DatagramSocket layer. If the value of the property is too small, then packets might be lost if the server is overloaded. If the value is too large, then the packets might be delayed.

Data type Integer
Default 1024000

serverUDPInterface

Specifies the host name or IP address that is used for all communications between the SIP proxy and the SIP containers when the network is segmented. This interface is the specific network interface for all UDP data that enters or exits the SIP containers. You must use this property with the serverUDPPort property.

Data type String
Default *

serverUDPPort

Specifies the UDP port that is used for SIP container communications. When the firewall is between the SIP proxy and the SIP container, you might set this value if a specific interface is needed to communicate with the SIP containers or if a specific port is required to pass through the firewall.

Data type String
Default dynamic

SIPAdvisorMethodName

Specifies a string value for the method sent by the load balancer to the SIP proxy for health checks.

The format is OPTIONS or INFO. This property is used with the LBIPAddr property.

Data type	String
Default	null

sipClusterCellName

Specifies the actual cell name that contains the cluster of SIP containers.

Set the **sipClusterCellName** custom property to be the cell name that contains the configured cluster of SIP containers

Data type	String
Default	Cell name in which the proxy resides

tcp.IPSprayer.host

Specified the host name for the IP Sprayer for Transmission Control Protocol (TCP) packets.

Data type	String
Default	None

tcp.IPSprayer.port

Specified the port for the IP Sprayer for Transmission Control Protocol (TCP) packets.

Data type	String
Default	None

tls.IPSprayer.host

Specified the host name for the IP Sprayer for Transport Layer Security (TLS) packets.

Data type	String
Default	None

tls.IPSprayer.port

Specified the port for the IP Sprayer for Transport Layer Security (TLS) packets.

Data type	String
Default	None

udp.IPSprayer.host

Specified the host name for the IP Sprayer for User Datagram Protocol (UDP) packets.

Data type	String
Default	None

udp.IPSprayer.port

Specified the port for the IP Sprayer for User Datagram Protocol (UDP) packets.

Data type	String
Default	None

SIP container custom properties

You can add any of the following custom properties to the configuration settings for a Session Initiation Protocol (SIP) container.

To specify custom properties for a specific SIP container, navigate to the custom properties page, and then specify a value for the custom property.

Important: The custom properties are supported as the primary method of configuration. Therefore, if a custom property is set and then you set the corresponding setting in the administrative console, the custom property value is used.

1. In the administrative console, expand **Servers > Server Types > WebSphere application servers > *server_name*** to open the configuration tab for the server.
2. From **Container settings**, expand **SIP Container settings**, and click **SIP container**.
3. From **Additional properties**, select **Custom Properties > New**.
4. On the settings page, type the custom property to configure in the **Name** field, and then type the value of the custom property in the **Value** field.
5. Click **Apply** or **OK**.
6. Click **Save** on the console task bar to save your configuration changes.
7. Restart the server.

The following list of SIP container custom properties is provided with the product. These properties are not shown on the settings page for the container.

You can define the following SIP container custom properties that are provided with the product. These properties are not shown on the settings page for the container.

- “auth.int.enable” on page 170
- “com.ibm.sip.sm.lnm.size” on page 170
- “com.ibm.websphere.sip.security.digest.ldap.cachecleanperiod” on page 170
- “com.ibm.websphere.sip.security.tai.usercachecleanperiod” on page 171
- “com.ibm.ws.sip.key.set” on page 171
- “com.ibm.ws.sip.tai.DisableSIPBasicAuth” on page 171
- “DigestPasswordServerClass” on page 171
- “enable.system.headers.modify” on page 171
- “end.of.service.replication” on page 171
- “immediate.replication” on page 171
- “javax.servlet.sip.ar.dar.configuration” on page 172
- “javax.servlet.sip.ar.spi.SipApplicationRouterProvider” on page 172
- “javax.sip.bind.retries” on page 172
- “javax.sip.bind.retry.delay” on page 172
- “javax.sip.detect.pre.escaped.params” on page 172
- “javax.sip.force.connection.reuse” on page 173
- “javax.sip.hide.message.body” on page 173
- “javax.sip.hide.message.headers” on page 173
- “javax.sip.hide.request.uri” on page 173
- “javax.sip.OUTBOUND_PROXY” on page 174
- “javax.sip.PATH_MTU” on page 174
- “javax.sip.stat.report.interval” on page 174
- “javax.sip.trace.msg.in” on page 174

- “javax.sip.trace.msg.out” on page 174
- “javax.sip.transaction.invite.auto100” on page 175
- “javax.sip.transaction.timer.a” on page 175
- “javax.sip.transaction.timer.b” on page 175
- “javax.sip.transaction.timer.cancel” on page 175
- “javax.sip.transaction.timer.d” on page 175
- “javax.sip.transaction.timer.e” on page 176
- “javax.sip.transaction.timer.f” on page 176
- “javax.sip.transaction.timer.g” on page 176
- “javax.sip.transaction.timer.h” on page 177
- “javax.sip.transaction.timer.i” on page 177
- “javax.sip.transaction.timer.invite.server” on page 177
- “javax.sip.transaction.timer.j” on page 177
- “javax.sip.transaction.timer.k” on page 178
- “javax.sip.transaction.timer.non.invite.server” on page 178
- “javax.sip.transaction.timer.t1” on page 178
- “javax.sip.transaction.timer.t2” on page 178
- “javax.sip.transaction.timer.t4” on page 179
- “on.outgoing.message.replication” on page 179
- “pws_atr_name” on page 179
- “replicate.with.confirmed.dialog.only” on page 179
- “sip.container.heartbeat.enabled” on page 179
- “sip.jsr289.parse.address” on page 179
- “SIP_RFC3263_nameserver” on page 180
- “thread.message.queue.max.size” on page 180
- “weight.overload.watermark” on page 181

auth.int.enable

Specifies the **auth-int** quality of protection (QOP) for digest authentication. Digest authentication defines two types of QOP: **auth** and **auth-int**. By default, **auth** is used. When this custom property is set to True, the highest level of protection is used, which is the **auth-int** QOP.

Data type	String
Default	False

com.ibm.sip.sm.lnm.size

Specifies the number of logical names in the application server. Each SIP object that can be replicated, such as a SIP session, is associated with a logical name. All objects with the same logical name are replicated to the same back-up container. The proxy can route messages to the correct container using the logical name found in the message. The value must be greater than 1.

Data type	String
Default	10

com.ibm.websphere.sip.security.digest.ldap.cachecleanperiod

Specifies the clean Lightweight Directory Access Protocol (LDAP) cache period in minutes.

Data type	String
Default	120

com.ibm.websphere.sip.security.tai.usercachecleanperiod

Specifies the clean security subject cache period in minutes.

Data type	String
Default	15

com.ibm.ws.sip.key.set

Specifies the key to use for SIP flow token security. When a value is specified for this property, SIP flow token security is automatically enabled.

Data type	String
Default	There is no default value

com.ibm.ws.sip.tai.DisableSIPBasicAuth

Specifies whether to allow basic authentication for SIP.

Data type	String
Default	False

DigestPasswordServerClass

Specifies types of user registries that are supported, except LDAP. To configure DigestTAI without the LDAP user registry, complete the following steps.

1. Create a class that implements this interface: `com.ibm.ws.sip.security.digest.DigestPasswordServer`
2. Add the following property to the SIP container custom property:
Default `LdapPasswordServer`
3. Ensure that all users declared by the impl class are declared in the user registry configured for the product security.

Data type	String
Default	impl

enable.system.headers.modify

Specifies whether the application has access to headers that are otherwise restricted.

Data type	String
Default	False

end.of.service.replication

Specifies whether changes are buffered until the thread for a siplet is about to end. If the value is set to `true`, then each change is buffered until the thread for the siplet is about to end.

Data type	Boolean
Default	true

immediate.replication

Specifies whether each change is immediately sent to the Data Replication Service. When this property is set to `true`, when replication is issued from a non-SIP container thread, the replication is immediately performed on the calling thread. When this property is set to `false`, the changes are buffered, and replication does not occur until all changes are made.

Setting this property to true might have a negative impact on performance.

Data type	Boolean
Default	false

javax.servlet.sip.ar.dar.configuration

Specifies the location of the default application router (DAR) properties file. The properties file defines the order in which the application router sends SIP requests to applications as described in Appendix C of the JSR 289 specification.

Data type	String
Default	Null

javax.servlet.sip.ar.spi.SipApplicationRouterProvider

Specifies the custom application router implementation fully qualified class name as described in section 15.4.2 of the JSR 289 specification. The custom application router implementation class defines the order in which the application router sends SIP requests to applications.

Data type	String
Default	Null

javax.sip.bind.retries

Specifies the amount of time, in milliseconds, between attempts to start the SIP channel if the SIP port is busy with another process during server startup.

Data type	String
Default	60

javax.sip.bind.retry.delay

Specifies the delay, in milliseconds, between attempts to start the SIP channel if the SIP port is busy with another process during server startup.

Data type	String
Default	5000

javax.sip.detect.pre.escaped.params

Specifies whether to prevent the container from re-escaping Uniform Resource Identifier (URI) parameters that were pre-escaped by the application.

Enabling this property provides the application with more control over escaping URI parameters, when calling the **javax.servlet.sip.SipFactory.createURI()** and the **javax.servlet.sip.SipURI.setParameter()** parameters.

By default, the container only escapes characters that it must encode according to the RFC 3261 25.1 specification. In some cases, however, escaping additional characters might be required. Due to a limitation in the JSR 116 (5.2.1) specification, the application cannot perform its own escaping. Because of this limitation, attempts by the application to encode URI parameters causes the container to re-encode the percent sign. If the value of this property is set to true, the container cannot re-encode the percent sign.

Setting the value to true is not in compliance with the JSR 116 (5.2.1) specification, but provides the application with greater control over URI parameter escaping. APAR PK37192 describes the problem and the workaround.

Data type	String
Default	False

javax.sip.force.connection.reuse

Specifies whether to force reuse of inbound connections for outbound requests. This custom property is only relevant for stream transports, such as Transmission Control Protocol (TCP) and Transport Layer Security (TLS). Disabling this property causes the container to create a separate connection for outbound requests, even if an existing connection is already established to the same peer address. The connection is automatically reused if the top Via header in the inbound request contains an alias parameter. (<http://www.ietf.org/internet-drafts/draft-ietf-sip-connect-reuse-07.txt>)

Data type	String
Default	False

defeat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.hide.message.body

Specifies to hide message content in logs. Set the value of this property to true to remove the message body text from SIP messages printed in the log files. This property only affects the representation of the messages in log files.

Data type	String
Default	False

defeat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.hide.message.headers

Specifies to hide the specified message header field names in log files. The value of this property is a comma-separated list of header field names that you want removed from SIP messages printed in the log files. This property only affects the representation of the messages in log files.

Data type	String
Default	None

javax.sip.hide.request.uri

Specifies to hide request URIs in log files. Set the value of this property to true to remove request URIs from SIP messages printed in the log files. This property only affects the representation of the messages in log files.

Data type	Boolean
Default	False

javax.sip.OUTBOUND_PROXY

Specifies the fixed address for routing all outbound SIP messages. The format is *address:port/transport*, such as 1.2.3.4:5065/tcp.

Note: Do not use this property if the container is fronted by an application server SIP proxy.

Data type	String
Default	null

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.PATH_MTU

Specifies the maximum transmission unit, in bytes, for outbound User Datagram Protocol (UDP) requests. The SIP stack measures the size of a request before sending it out on the UDP channel. If the request is larger than the value specified for **PATH_MTU-200** (1300 bytes by default), then the transport is switched from UDP to TCP before transmission. Increase this value to send larger requests over the UDP channel; however, messages might be truncated or dropped. See the RFC 3261-18.1.1 specification for details.

Data type	String
Default	1500

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.stat.report.interval

Specifies the amount of time, in milliseconds, for reporting dispatch and timer statistics to a system.out file. A value of zero indicates no report.

Data type	String
Default	0

javax.sip.trace.msg.in

Specifies whether to print incoming messages to a system.out file.

Data type	String
Default	False

javax.sip.trace.msg.out

Specifies whether to print outbound messages to a system.out file.

Data type	String
Default	False

javax.sip.transaction.invite.auto100

Specifies whether to automatically reply to invite requests with a 100 Trying response. Disabling this property might increase the number of invite retransmissions.

Data type	String
Default	True

defeat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.a

Specifies, for UDP only, the amount of time, in milliseconds, before retransmitting invite requests for timer A for the RFC 3261 specification. This property is relevant for the invite client transaction.

Data type	String
Default	javax.sip.transaction.timer.t1

defeat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.b

Specifies the amount of time, in milliseconds, for the invite client transaction timeout timer (timer B) for the RFC 3261 specification.

Data type	String
Default	64*javax.sip.transaction.timer.t1

defeat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.cancel

Specifies the amount of timer, in milliseconds, for the timer to keep the cancelled client transaction in the proceeding state before completing the cancelled transaction for the RFC 3261 9.1 specification. This property is relevant for the invite client transaction.

Data type	String
Default	64*javax.sip.transaction.timer.t1

javax.sip.transaction.timer.d

Specifies the wait time, in milliseconds, before retransmission of the invite response for timer D for the RFC 3261 specification. This property is relevant for the invite client transaction.

Data type String
Default 32000

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.e

Specifies, for UDP only, the amount of time, in milliseconds, before the retransmission of the initial non-invite request for timer E for the RFC 3261 specification. This property is relevant for the non-invite client transaction.

Data type String
Default javax.sip.transaction.timer.t1

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.f

Specifies the amount of time, in milliseconds, for the non-invite transaction timeout timer (timer F) for the RFC 3261 specification. This property is relevant for the non-invite client transaction.

Data type String
Default 64*javax.sip.transaction.timer.t1

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.g

Specifies the amount of time, in milliseconds, before retransmission of an initial invite response for timer G for the RFC 3261 specification. This property is relevant for the invite server transaction.

Data type String
Default javax.sip.transaction.timer.t1

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.h

Specifies the amount of time, in milliseconds, to wait for an acknowledgement (ACK) receipt for timer H for the RFC 3261 specification. This property is relevant for the invite server transaction.

Data type	String
Default	64*javax.sip.transaction.timer.t1

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.i

Specifies the amount of time in milliseconds to wait for an ACK retransmission for timer I for the RFC 3261 specification. This property is relevant for the invite server transaction.

Data type	String
Default	javax.sip.transaction.timer.t4

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.invite.server

Specifies the amount of time, in milliseconds, for the timer to keep the invite server transaction in the complete state. This timer is not defined in the RFC specification.

To avoid creating a new server transaction when a client retransmits an invite request, keep the completed server transaction for a period of time before removing invite retransmissions. This timer is started when the transaction changes to the terminated state. When the timer completes, the transaction is removed.

Data type	String
Default	32000

javax.sip.transaction.timer.j

Specifies the amount of time in milliseconds to wait for non-invite request retransmission for timer J for the RFC 3261 specification. This property is relevant for the non-invite server transaction.

Data type	String
Default	64*javax.sip.transaction.timer.t1

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.k

Specifies the amount of time, in milliseconds, to wait for non-INVITE response retransmissions for timer K for the RFC 3261 specification. This property is relevant for the non-invite client transaction.

Data type	String
Default	javax.sip.transaction.timer.t4

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.non.invite.server

Specifies the amount of time, in milliseconds, for an Application Programming Interface (API) timer for the application to respond to a non-invite request. This property is relevant for non-invite server transactions.

This timer is not defined in the RFC specification. This property is needed to stop the transaction if the application does not generate a final response to the request. The timer starts when the request arrives in the stack and stops when a response is generated by the application. If no response is generated before the timer stops, then the transaction completes.

Data type	String
Default	34000

javax.sip.transaction.timer.t1

Specifies the amount of time, in milliseconds, for a network round trip delay for timer T1 for the RFC 3261 specification. The value is used as a base for calculating some timers and is relevant for all types of transactions, such as client, server, invite, and non-invite transactions.

Data type	String
Default	500

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.t2

Specifies the maximum time in milliseconds before retransmitting non-invite requests and invite responses for timer T2 for the RFC 3261 specification.

Data type	String
Default	4000

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

javax.sip.transaction.timer.t4

Specifies the maximum amount of time, in milliseconds, for a message to remain in the network. This value is used as a base for calculating other timers for timer T4 for the RFC 3261 specification.

Data type	String
Default	5000

depfat: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

on.outgoing.message.replication

Specifies whether changes are buffered until a siplet issues a `request.send()` or `response.send()` call. If the value is set to `true`, then each change is buffered until a siplet issues a `request.send()` or `response.send()` call.

Data type	Boolean
Default	false

pws_atr_name

Specifies the LDAP attribute name that stores the user password.

Data type	String
Default	userpassword

replicate.with.confirmed.dialog.only

Specifies whether to replicate the application session, even when no dialogs are confirmed. If the value is set to `false`, then the application session is replicated immediately after the session is created. Otherwise, the application session is only replicated when an associated dialog is confirmed.

Data type	String
Default	False

sip.container.heartbeat.enabled

Specifies whether or not SIP network outage detection is enabled for the SIP container. SIP network outage detection allows the SIP proxy to send keepalive messages to the SIP container if the value of this property is set to `true`.

If the value is set to `false` for the SIP container, then this property has no effect on the SIP proxy. However, if the value is set to `true` for the SIP container, the value should also be set to `true` for the SIP proxy to ensure that keepalive messages are answered at the SIP container and not presented to the application.

Data type	String
Default	true

sip.jsr289.parse.address

Specifies to use the SIP Servlet Specification 1.1, JSR 289 required format for `createRequest()` and `createAddress()` methods.

Note: The JSR 289 API requires that for any SIP URI that contains address parameters, you must enclose the SIP URI in angle brackets. The default behavior of the `sip.jsr289.parse.address` property is compliant with JSR 289 and correctly parses the address parameter as if it belongs to the SIP address. For example, when the property is set to `false`, the SIP address, `sip:fred@acme.com;param1=1`, is converted to `<sip:fred@acme.com;param1=1>`. When the property is set to `true`, the SIP address `sip:fred@acme.com;param1=1`, is converted to `<sip:fred@acme.com;>param1=1`.

Data type	String
Default	True

SIP_RFC3263_nameserver

Specifies whether to allow a SIP URI to be resolved through Domain Name System (DNS) into the IP address, port, and transport protocol of the next hop.

The value of the property is a string containing one or two address and port tuples, where two tuples are separated by a space. The following examples specify a one address and port tuple or a two address and port tuple.

```
dottedDecimalAddress@.port  
hostname.domain@port  
IPV6address@port
```

The following example values represent a single tuple.

- 1.2.3.4@53
- example.com@53
- a:b:c::d@53

The following example values represent two tuples separated by a space.

- 1.2.3.4@53 example.com@53
- a:b:c::d@53 9.32.211.14@53

Data type	String
Default	null

depreaf: This custom property is deprecated. Do not use this custom property unless you are running in a mixed cell environment that includes at least one core group that contains a mixture of Version 7.0 and Version 6.x processes.

mixv: If you are running in a mixed cell environment, and you have core groups that contain a mixture of Version 7.0 and Version 6.x processes, you must continue to use this custom property.

thread.message.queue.max.size

Specifies the maximum number of events allowed in the container threads queue. When this number is exceeded, the proxy server is notified that the container is overloaded and requests for new sessions are not accepted. Instead, the container returns an error message that indicates that the container is temporarily unavailable.

This value represents the total number of messages for all queues and reflects the state of the CPU. When the CPU approaches 100%, the maximum value for this custom property is reached quickly. Configure your system to limit the queue size and prevent the queue from reaching this threshold.

Data type	String
Default	1000

weight.overload.watermark

Specifies the threshold value for the internal weight calculated by the container. When the container calculates the internal weight to be higher than the value specified, an overloaded container becomes available for service again.

This custom property represents a percentage of the maximum internal weight, such as 30 percent when the default value is set. When the high-water mark, or maximum threshold, is exceeded, the container waits until the weight drops below the maximum weight. This value cannot exceed 10.

Data type	String
Default	3

Creating a proxy server cluster

A proxy server cluster consists of a group of proxy servers. You can use either the wsadmin tool, or the administrative console to create a cluster of proxy servers that can route requests to applications in a cell.

Before you begin

Member proxy servers in a proxy cluster can be created on any node in a cell and share the same proxy configuration. Before you define your proxy server cluster:

- Determine whether a domain name server (DNS), a load balancer, or a proxy server is going to be used to route requests to the proxy server cluster.
- Verify that Version 8.0 of the product is installed on the nodes that will belong to the proxy server cluster.

The main reason for creating a proxy cluster is to make it easier to administer multiple proxy servers. For example, if your proxy servers are members of a proxy server cluster, you can specify configuration settings for that proxy server cluster, and the settings are automatically applied to all of the proxy servers in that cluster. Creating a proxy server cluster also enables you to simultaneously start and stop all of the proxy servers in that cluster.

gotcha: A proxy server cluster does not have some of the same functionality that an application server cluster has. For example, because there is no data replication among members of a proxy cluster, failover between proxy servers in the cluster is not supported. If a proxy server is down, all active connections owned by the proxy server go away and then incoming requests fail. Both proxy servers and proxy clusters, on the other hand, support the high availability and failover of backend servers, such that the proxy server can detect if a backend server is down and then forward the requests to a server that has the session replicated.

About this task

Complete the following steps to create a proxy server cluster.

Procedure

Click **Servers > Clusters > Proxy server clusters > New** to start the Create a new proxy server cluster wizard.

Results

You have created a proxy server cluster.

What to do next

Click **Servers > Clusters > Proxy server clusters**, select the newly created cluster, and then click **Start** to start the cluster, or click on the name of the new cluster to change its configuration settings, or add additional members to the cluster.

Proxy server cluster collection

Use this page to view information about and change configuration settings for a proxy server cluster. A proxy cluster consists of a group of proxy servers.

To view this administrative console page, click **Servers > Clusters > Proxy server clusters** .

To define a new proxy server cluster, click **New** to start the Create a new proxy server cluster wizard.

Name

Specifies a logical name for the proxy cluster. The name must be unique among proxy clusters within the containing cell.

Supported Protocols

Indicates the protocol or protocols that the proxy server is configured to handle.

This information is based on the types of transport channels that are included in the transport chains that are configured for the proxy server. For example, if a transport chain includes an HTTP channel, HTTP displays in this field. If a transport chain includes both a SIP and an HTTP channel, SIP,HTTP displays in this field.






Status

This field indicates whether the proxy cluster is partially started, started, partially stopped, stopped, or unavailable. If the status is unavailable, the node agent is not running in that node and you must restart the node agent before you can start the proxy server.

After you click **Start** or **Ripplestart** to start a proxy cluster, each server that is a member of that proxy cluster launches if it is not already running. When the first member launches, the status changes to partially started. The status remains partially started until all proxy cluster members are running. When all proxy cluster members are running, the state changes to running and the status changes to started. Similarly, when you click **Stop** or **ImmediateStop** to stop a proxy cluster, the status changes to partially stopped when the first member stops, then changes to stopped when all proxy cluster members are not running.

Table 12. Status settings of the proxy server cluster.

This table lists the status settings of the proxy server cluster.

	Started	All of the proxy cluster members are running.
	Partially started	At least one of the proxy cluster members is running.
	Stopped	All of the proxy cluster members have stopped running.
	Partially stopped	At least one of the proxy cluster members has stopped running.
	Unavailable	Status cannot be determined. All of the members of a proxy cluster with an unavailable status might, in fact, be running but the proxy cluster has an unavailable status because the proxy server that is running the administrative console cannot communicate with all of the proxy cluster members. The node agent should be started on all proxy nodes to ensure that the correct status is shown.

Proxy server cluster settings

Use this page to view a list of the proxy server clusters that are defined for your system, and the status of each of these clusters. You can also use this page to view or change the configuration settings for a specific proxy server cluster or to view the local topology of a specific proxy server cluster.

To view a list of the proxy server clusters that are defined for your system, and the status of each of these clusters, in the administrative console click **Servers > Clusters > Proxy server clusters**.

To display the topology of your proxy server clusters, click **Servers > Clusters > Proxy server clusters > proxy_server_cluster_name**, and then click the **Local Topology** tab.

To view or change the configuration settings of a proxy server cluster, in the administrative console click **Servers > Clusters > Proxy server clusters > proxy_server_cluster_name**.

Cluster name

Specifies a logical name for the proxy cluster. The name must be unique among proxy clusters within the containing cell.

Bounding node group name

Specifies the node group that forms the boundaries for this proxy cluster.

A node group is a collection of proxy server nodes. A node is a logical grouping of managed proxy servers, usually on a system that has a distinct IP host address. All proxy servers that are members of a proxy cluster must be on nodes that are members of the same node group. Nodes that are organized into a node group need enough capabilities in common to ensure that proxy clusters formed across the nodes in the node group can host the same application in each proxy cluster member. A node must be a member of at least one node group and can be a member of more than one node group.

Create and manage node groups by clicking **System administration > Node groups** in the administrative console.

Local Topology tab

Use this page to display, in a tree format, a list of all of the application server proxy clusters defined for your environment. The list shows all of the nodes and proxy cluster members that are included in each proxy cluster contained in a cell.

Proxy server cluster member collection

Use this page to view and manage proxy servers that belong to a proxy cluster.

To view this administrative console page, click **Servers > Clusters > Proxy server clusters > proxy_cluster_name > Cluster members**.

Proxy servers that are part of a proxy cluster are referred to as proxy cluster members. A copy of the first proxy cluster member that you create is stored as part of the proxy cluster data and becomes the template for all additional proxy cluster members that you create.

You can use this page to perform the following actions:

- Create a New proxy cluster member. To create a new member, click **New**.

A copy of the first proxy cluster member that you create is stored as part of the proxy cluster data and becomes the template for all additional proxy cluster members that you create. Any individual configuration change that you make to a proxy cluster member does not affect the configuration settings of the proxy cluster member template.

You can use wsadmin commands to modify the proxy cluster member template, or you can click **Servers > Clusters > Proxy server clusters > proxy_cluster_name > Cluster members**, and then click **Templates**. Any change that you make to the template does not affect existing proxy cluster members.

- Delete a proxy cluster member. To delete a proxy cluster member, select the proxy cluster member you want to delete, then click **Delete**.
- Create or edit proxy cluster templates. To work with proxy cluster templates, click **Templates**.
- Start a proxy cluster member. To start a proxy cluster member, select the server that you want to start, then click **Start**.
- Stop a proxy cluster member. To stop a proxy cluster member, select the server that you want to stop, then click **Stop**.

Member name

Specifies the name of the server in the proxy cluster. On most platforms, the name of the server is the process name. The name must match the (object) name of the proxy server.

Node

Specifies the name of the node for the proxy cluster member.

Version





Specifies the version of the product on which the proxy cluster member runs.

Status

This field indicates whether the proxy cluster member is started, stopped, partially stopped, or unavailable. If the status is unavailable, the node agent is not running in that node and you must restart the node agent before you can start the server.

Table 13. Status settings of the proxy server cluster member.

This table lists the status settings of the proxy server cluster member.

	Started	The proxy cluster member is running.
	Partially stopped	The proxy cluster member is in the process of changing from a started state to a stopped state.
	Stopped	The proxy cluster member is not running.
	Unavailable	Status cannot be determined. A proxy cluster member with an unavailable status might, in fact, be running but has an unavailable status because the proxy cluster member that is running the administrative console cannot communicate with this proxy cluster member.

Proxy cluster member settings

Use this page to manage the members of a proxy cluster. A proxy cluster of proxy servers is managed together and participate in workload management.

To view this administrative console page, click **Servers > Clusters > Proxy server clusters > proxy_cluster_name > Cluster members > cluster_member_name**.

Member name

Specifies the name of the proxy server in the proxy cluster. On most platforms, the name of the server is the process name. The member name must match the name of one of the servers that are listed on the proxy servers page.

Run in development mode

Enabling this option may reduce the startup time of an proxy server. This might include Java virtual machine (JVM) settings, such as disabling bytecode verification and reducing Just in Time (JIT) compiler compilation costs. Do not enable this setting on production servers.

This option is not supported in an i5/OS environment.

Specifies that you want to use the JVM settings, **-Xverify** and **-Xquickstart**, on startup. After selecting this option, save the configuration and restart the server to activate development mode.

The default setting for this option is `false`, which indicates that the server is not started in development mode. Setting this option to `true` specifies that the server is started in development mode, using settings that decrease server startup time.

Data type	Boolean
Default	false

Parallel start

Specifies whether to start the server on multiple threads. When you start the server on multiple threads, the server components, services, and applications start in parallel rather than sequentially, which might shorten the startup time.

The default setting for this option is `true`, which indicates that the server uses multiple threads when it starts. Setting this option to `false` specifies that the server uses a single thread when it starts, which might lengthen startup time.

Data type	Boolean
Default	true

Start components as needed

Select this property if you want the proxy server components started as they are needed by an application that is running on this proxy server.

When this property is selected, proxy server components are dynamically started as they are needed. When this property is not selected, all of the proxy server components are started during the startup process. Therefore, selecting this property usually results in improved startup time because fewer components are started during the startup process.

gotcha: If you are running other WebSphere products on top of the Application Server, make sure that those other products support this functionality before you select this property.

Proxy cluster member templates collection

Use this page to view the list of proxy cluster member templates that exist for this proxy cluster.

To view the proxy cluster member templates that are available for creating a new member of a proxy cluster, in the administrative console, click **Servers > Clusters > Proxy server clusters > proxy_cluster_name > Cluster members > Templates**.

To edit the attributes of an existing proxy cluster member template, click the name of the template.

Usually, only one template exists that you can use to create additional members for a proxy cluster. However, if a proxy cluster includes nodes that are at different versions of the product, a different template exists for each of these versions. For example, if a proxy cluster has proxy cluster members residing on both a Version 6.1 node and a Version 7.0 node, the proxy cluster has two templates. The Version 6.1

template is used when you create an additional proxy cluster member on the Version 6.1 node, and the Version 7.0 template is used when you create an additional proxy cluster member on the Version 7.0 node.

If you modify a template, all new proxy cluster members are created with the server property settings of the modified template. However, the property settings of existing proxy cluster members do not change. If you make any change to a proxy cluster member template, you should make the same change to all of the existing proxy cluster members.

Name

Specifies the name of the proxy cluster member template.

Platform

Specifies the operating system platform to which this template applies.

Version

Specifies the version of the product to which the template applies.

Description

Specifies a description of this proxy cluster member template. This field is optional and might be blank.

Proxy cluster member template settings

Use this page to modify proxy cluster member template attributes.

To view this administrative console page, click **Servers > Clusters > Proxy server clusters > proxy_cluster_name > Cluster members > Templates > cluster_member_template_name**. The following attributes are displayed:

Name

Displays the name of the proxy cluster member template.

Run in development mode

Enabling this option may reduce the startup time of a proxy server. This might include Java virtual machine (JVM) settings, such as disabling bytecode verification and reducing Just in Time (JIT) compiler compilation costs. Do not enable this setting on production servers.

This option is not supported in an i5/OS environment.

Specifies that you want to use the JVM settings, **-Xverify** and **-Xquickstart**, on startup. After selecting this option, save the configuration and restart the server to activate development mode.

The default setting for this option is `false`, which indicates that the server is not started in development mode. Setting this option to `true` specifies that the server is started in development mode, using settings that decrease server startup time.

Data type

Boolean

Default

false

Parallel start

Specifies whether to start the proxy server on multiple threads. When you start the proxy server on multiple threads, the proxy server components, services, and applications start in parallel rather than sequentially, which might shorten the startup time.

The default setting for this option is `true`, which indicates that the proxy server uses multiple threads when it starts. Setting this option to `false` specifies that the proxy server uses a single thread when it starts, which might lengthen startup time.

Data type	Boolean
Default	true

Start components as needed

Select this property if you want the proxy server components started as they are needed by an application that is running on this proxy server.

Note: When this property is selected, proxy server components are dynamically started as they are needed. When this property is not selected, all of the proxy server components are started during the startup process. Therefore, selecting this property usually results in improved startup time because fewer components are started during the startup process.

Avoid trouble: If you are running other WebSphere products on top of the Application Server, make sure that those other products support this functionality before you select this property.

Creating a proxy cluster: Basic proxy cluster settings

Use this page to enter the basic settings for a proxy cluster.

To view this administrative console page, click **Servers > Clusters > Proxy server clusters > New**.

Proxy cluster name

Specifies the name of the proxy cluster. The proxy cluster name must be unique within the cell.

Supported Protocols

Indicates the protocol or protocols that the proxy server is configured to handle.

This information is based on the types of transport channels that are included in the transport chains that are configured for the proxy server. For example, if a transport chain includes an HTTP channel, HTTP displays in this field. If a transport chain includes both a SIP and an HTTP channel, SIP, HTTP displays in this field.

Creating a proxy cluster: Create first proxy cluster member

Use this page to specify settings for the first proxy cluster member.

There are two ways to create the first member of a proxy cluster:

- You can create the first member when you create a new proxy cluster.
To create a new proxy cluster, in the administrative console, click **Servers > Clusters > Proxy server clusters > New**.
- You can create an empty proxy cluster and then add a first member after you finish creating the proxy cluster.
To create a proxy cluster member for an existing proxy cluster, in the administrative console, click **Servers > Clusters > Proxy server clusters > *proxy_cluster_name* > Cluster members > New**.

When you create the first proxy cluster member, a copy of that member is stored as part of the proxy cluster data and becomes the template for all additional proxy cluster members that you create.

When adding servers to a proxy cluster, note that you can either remove a proxy server from a proxy cluster by deleting the proxy server from the list of proxy cluster members, or by deleting the server from the Proxy Servers collection.

Member name

Specifies the name of the proxy server that is created for the proxy cluster.

The member name must be unique on the selected node.

Select node

Specifies the node on which the proxy server resides.

Generate unique HTTP ports

Specifies that a unique HTTP port is generated for the proxy server. By generating unique HTTP ports for the proxy server, you avoid potential port collisions and configurations that are not valid.

Select basis for first proxy cluster member:

Specifies the basis you want to use for the first proxy cluster member.

- If you select **Create the member using a proxy server template**, the settings for the new proxy server are identical to the settings of the proxy server template you select from the list of available templates.
- If you select **Create the member using an existing proxy server as a template**, the settings for the new proxy server are identical to the settings of the proxy server you select from the list of existing proxy servers.
- If you select **Create the member by converting an existing proxy server**, the proxy server you select from the list of available proxy servers becomes a member of this proxy cluster.
- If you select **None. Create an empty proxy cluster**, a new proxy cluster is created but it does not contain any proxy cluster members.

Important: The basis options are available only for the first proxy cluster member. All other members of a proxy cluster are based on the proxy cluster member template, which is created from the first proxy cluster member.

Creating a proxy cluster: Create additional proxy cluster members

Use this page to create additional members for a proxy cluster. You can add a member to a proxy cluster when you create the proxy cluster or after you create the proxy cluster. A copy of the first proxy cluster member that you create is stored as part of the proxy cluster data and becomes the template for all additional proxy cluster members that you create.

To add members to a proxy cluster, in the administrative console, click **Servers > Clusters > Proxy server clusters > New > proxy_cluster_name > Cluster members > New**. After you enter the required information about the new proxy cluster member, click **Add Member** to add this member to the proxy cluster member list.

After adding a proxy cluster member, you might need to change one or more of the property settings for this proxy cluster member, or another proxy cluster member that you just added. To change one or more of the editable property settings (Member name, Node, and Generate unique ports) for any proxy cluster member that you just added, other than the first proxy cluster member, select that proxy cluster member, and then click **Edit**. When you finish changing the property settings, click **Update Member** to save your changes.

If you decide not to create a particular proxy cluster member, select the member and then click **Delete**.

You cannot edit or delete the first proxy cluster member or an already existing proxy cluster member.

If you create additional proxy cluster members immediately after you create the first proxy cluster member, the list of proxy cluster members includes a checklist in front of the names of these additional proxy cluster members. However, a check box does not appear in front of the name of the first proxy cluster member because you cannot delete this member or edit its settings. To modify the first proxy cluster member, click **Previous**.

Similarly, if you are adding proxy cluster members to a proxy cluster that already has existing members, the existing members appear in the list of proxy cluster members but a check box does not appear in front of the names of these proxy cluster members. To delete one of these existing members or to change the settings of one of these proxy cluster members, in the administrative console click **Servers > Clusters > Proxy server clusters > *proxy_cluster_name* > Cluster members**, and then select the member that you want to delete or whose configuration settings you want to change.

Member name

Specifies the name of the proxy server that is created for the proxy cluster.

The member name must be unique on the selected node.

Select node

Specifies the node on which the proxy server resides.

Generate unique HTTP ports

Specifies that a unique HTTP port is generated for the proxy server. By generating unique HTTP ports for the proxy server, you avoid potential port collisions and configurations that are not valid.

Creating a proxy cluster: Summary settings

Use this administrative console page to view and save settings when you create a proxy cluster or proxy cluster member.

You can view this administrative console page whenever you create a new proxy cluster or a new proxy cluster member. This summary page displays your configuration changes before you commit the changes and the new proxy cluster or proxy cluster member is created.

To create a cluster, in the administrative console, click **Servers > Clusters > Proxy server clusters > New**.

To create a proxy cluster member for an existing proxy cluster, in the administrative console, click **Servers > > Clusters > Proxy server clusters > New *proxy_cluster_name* Cluster members > New**. After you enter the required information about the new proxy cluster member, click **Add Member** to add this member to the proxy cluster member list.

The bounding node group of the proxy cluster is based on the first application server that is added as a member of the proxy cluster. The settings for this first member become the settings for the proxy cluster member template that is then used to create additional proxy cluster members.

To select a different bounding node group, in the administrative console, click **Servers > Clusters > Proxy server clusters > New > Cluster members > New**. Then select the appropriate node group for the new proxy cluster member. When you select a different node group, another proxy cluster member template is automatically created for that node group, if one does not already exist.

Review the changes to your configuration. Click Finish to complete and save your work.

Managing a proxy server cluster

You can use either the administrative console, or the wsadmin tool to manage a proxy server cluster .

Before you begin

The main reason for creating a proxy cluster is to make it easier to administer multiple proxy servers. For example, if your proxy servers are members of a proxy server cluster, you can specify configuration

settings for that proxy server cluster, and the settings are automatically applied to all of the proxy servers in that cluster. Creating a proxy server cluster also enables you to simultaneously start and stop all of the proxy servers in that cluster.

gotcha: A proxy server cluster does not have some of the same functionality that an application server cluster has. For example, because there is no data replication among members of a proxy cluster, failover between proxy servers in the cluster is not supported. If a proxy server is down, all active connections owned by the proxy server go away and then incoming requests fail. Both proxy servers and proxy clusters, on the other hand, support the high availability and failover of backend servers, such that the proxy server can detect if a backend server is down and then forward the requests to a server that has the session replicated.

About this task

Complete one or more of the following tasks to use the administrative console to manage your proxy server clusters.

Procedure

1. In the administrative console, click **Servers > Clusters > Proxy server clusters**.
2. Select the proxy server clusters and click either **Start** or **RippleStart** to start one or more proxy server clusters.
 - **Start** launches the server process of each member of the cluster by calling the node agent for each server to start the servers. After all servers are running, the state of the cluster changes to running. If the call to a node agent for a server fails, the server does not start.
 - **RippleStart** combines stopping and starting operations. It first stops and then restarts each member of the cluster. For example, your cluster contains 3 cluster members named server_1, server_2 and server_3. When you click RippleStart, server_1 stops and restarts, then server_2 stops and restarts, and finally server_3 stops and restarts. Use the RippleStart option instead of manually stopping and then starting all of the application servers in the cluster.
3. Select the proxy server clusters and click either **Stop** or **ImmediateStop** to stop one or more proxy server clusters.
 - **Stop** halts each server in a manner that allows the server to finish existing requests and allows failover to another member of the cluster. When the stop operation begins, the cluster state changes to partially stopped. After all servers stop, the cluster state becomes stopped.
 - **ImmediateStop** stops the server quickly without regard to existing requests. The server ignores any current or pending tasks. When the stop operation begins, the cluster state changes to partially stopped. After all servers stop, the cluster state becomes stopped.
4. Click the name of the proxy server cluster to access the Configuration tab to change the configuration settings.
5. Click **New**, and type the name for the cluster in the **Cluster name** field to create a new proxy server cluster.
6. Click **Delete**, and then click **OK** to delete an existing proxy server cluster.
7. To add new members to a proxy server cluster, click the name of an existing proxy server cluster, and click **Cluster members > New**. Type the name for the proxy server in the **Member name** field.

Results

You have successfully modified a proxy server cluster.

Migrating profiles for the proxy server

This topic describes how Version 6.0.2 profiles contain the proxy server feature when migrating to Version 7.0 profiles.

About this task

Complete the following steps to migrate from a Version 6.0.2 profile to a Version 7.0 profile.

Procedure

1. Run the **WASPreUpgrade.bat** or the **WASPreUpgrade.sh** command from the *install_root/bin* directory and point it to the Version 6.0.2 release.
This action makes a copy of all the required Version 6.0.2 files that are needed for the **WASPostUpgrade.bat** or **WASPostUpgrade.sh** command. You can delete these Version 6.0.2 files, but this action is not recommended.
2. Create your corresponding profiles in Version 7.0, if you have not already done so.
3. Run the **WASPostUpgrade.bat** or the **WASPostUpgrade.sh** command from the *install_root/bin* directory and point the commands to the WASPreUpgrade backup directory that you created in step one.

Customizing routing to applications

This topic provides information on disabling routing through the proxy server to applications that are on on-demand configuration (ODC)-compliant application servers.

About this task

Complete these steps to disable routing to ODC-compliant application servers.

Procedure

1. From the administrative console, select **Applications > Enterprise Applications > application_name**.
2. In the Modules section, click **Manage modules**.
3. Click a module name.
4. In the Additional Properties section, click **Web Module Proxy Configuration**.
5. In the General Properties section, deselect **Enable proxy** to disable routing using the proxy server.
6. Optional: Choose a protocol from the **Web Module Transport Protocol** list. A transport protocol, such as HTTP, can be used for the protocol between the proxy server and the application server instead of the protocol that the client uses to communicate with the proxy server.
For example, in order to perform Secure Sockets Layer (SSL) termination, which is also known as SSL offload, for HTTPS traffic for the Web module, select **HTTP** for the transport protocol.
7. Click **Apply**.
8. Click **OK**.

Web module proxy server configuration settings

Use this page to specify proxy server configuration settings for the web module.

To view this administrative console page, click **Applications > Application Types > WebSphere enterprise applications > application_name > Manage Modules > Web_module_name > Web Module Proxy Configuration**.

Name

Specifies the name of the web module.

Enable Proxy

Select **Enable Proxy** to enable proxy server to route requests to this web module. Deselect **Enable Proxy** to disable routing using the proxy server.

Web Module Transport Protocol

Specifies the protocol that the proxy server uses when communicating with this web module.

Choose the protocol in the web module transport protocol field if you want to use a specific transport protocol, such as HTTP, for the protocol between the proxy server and the application server. This is an alternative to using the protocol that is used by the client to communicate with the proxy server. For example, in order to perform Secure Sockets Layer (SSL) termination, which is also known as SSL offload, for HTTPS traffic for the web module, select HTTP for the transport protocol. HTTPS protocol is for advanced configurations and is not commonly used.

Custom Properties

Specifies additional custom properties for this runtime component. Some components use custom configuration properties that are defined by this option.

Routing requests to ODC-compliant application servers in other cells

On Demand Configuration (ODC) enables product components, such as the proxy server, to build application deployment, availability, and accessibility information in order to route requests for these applications without any additional configuration at the proxy server. If you want to isolate proxy servers with firewalls, place them in a cell that is separate from the applications and configure the core group bridge service.

About this task

ODC uses the high availability capabilities of the product to publish and subscribe updates. The deployment manager within a cell and the application servers that have the ODC capabilities typically publish the updates that are subscribed to by intermediaries such as the proxy server.

You can configure the proxy server to route requests to applications that are hosted in other cells. The core group bridge service provides communication between a cell with a proxy server and a cell with a target application. Once the cells are linked with core group bridges, the proxy server will be able to route to the application without additional configuration. To view your core group bridge settings, in the administrative console, click **Servers > Core groups > Core group bridge settings**.

Note: Cross-cell failover is not supported. If the same application is installed on both the local cell and in one or more remote cells, and the application or application servers in the local cell go down, then the ones in the remote cell will not be used. The proxy server will always route to the local cell even if the resource is available in a remote cell.

The basic steps to configure cross-cell routing are configuring and enabling core group bridges in the cell that the proxy server belongs to, and in each of the other cells that are being routed to. The core group bridges need to be configured with the same access point group name.

Procedure

1. Create bridge interfaces, peer access groups and peer ports for cells. The peer access point group name must be the same in the cells.
2. Restart all processes that are now bridge interfaces.

What to do next

If security is enabled, it must be enabled in all cells for the core group bridge service.

Configuring rules to route requests to web servers

This section provides information to configure rules to route requests to web servers or application servers that are not on-demand configuration (ODC)-compliant.

About this task

The proxy server permits explicit configuration of routing rules in order for client requests to route to web servers or application servers that are not ODC-compliant. This involves completing following tasks.

Procedure

1. Create a URI group.
To define the URI patterns that are associated with the web content that is hosted on these servers, in the administrative console click **Environment > URI groups**.
2. Create a generic server cluster definition.
To define the endpoints that define the cluster membership, in the administrative console click **Servers > Clusters > Generic server clusters**.
3. Create routing rules from the detail view of the proxy server panel that associates the inbound virtual host and a defined URI group to a defined generic server cluster.

Modifying the HTTP endpoints that the proxy server listens on

By default, the proxy server listens on the following named endpoints: `PROXY_HTTP_ADDRESS` and `PROXY_HTTPS_ADDRESS`. You can modify the ports and hosts that are associated with these endpoints in the administrative console.

About this task

Modify the ports and hosts that are associated with the proxy server endpoints as follows:

Procedure

1. In the administrative console, click **Servers > Server Types > WebSphere proxy servers > *proxy_server_name* > Communications > Ports**.
2. Select the port you want to modify.
The host and port that are associated with the specified endpoints can be modified to suit the requirements of the deployment. The administrator must ensure for correct routing, the virtual hosts that are associated with applications to be routed to are correctly updated with the appropriate host aliases (host aliases with the modified host and port combinations).
3. Click **Apply**.

What to do next

Restart the server. The server must be restarted for this modification to go into effect.

Adding a new HTTP endpoint for the proxy server

An administrator can use the proxy server to create additional endpoints to listen for HTTP and HTTPS requests.

About this task

The following steps will create a new transport chain:

Procedure

1. Click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Proxy server transports** in the administrative console.
2. Click **New** to launch the Create new transport chain wizard.
3. Determine a name for the transport chain.
4. Choose a template based on whether the endpoint should accept HTTP (proxy template) or HTTPS (proxy-secure template) requests. The wizard prompts for the host and port for the endpoint. Creating a new endpoint for the proxy server requires a restart of the proxy server to be effective.

Setting up caching in the proxy server

This topic provides information on caching static and dynamic content in the proxy server.

About this task

Complete the following steps to configure a proxy server such that it can cache static and dynamic content.

Procedure

1. Configure the object cache instance for size, disk offload location, and other such capabilities, in the administrative console. Click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Proxy cache instance config**. Repeat these steps on any nodes that have a proxy server.
2. Select the proxy cache store instance and enable configuration attributes such as cache size, disk offload, and cache replication. For disk offload, it is recommended that the location be set to a dedicated disk partition.
3. Enable caching at the proxy server, in the administrative console. Click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Proxy settings** page in the administrative console.
4. Select **Enable caching** and choose a cache instance from the drop-down box.
 - a. To enable dynamic content to be cacheable with the proxy server, in the administrative console, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Proxy settings**, and then select **Cache dynamic content**. You enable cacheability and invalidation of dynamic content when you enable servlet caching on the application server, and specifying the cache criteria in a cachespec.xml file that is associated with that application. Invalidation is received by connecting to the cache update URI that is associated with the invalidation servlet hosted on the application server cluster.

Dynamic content is content that an application, that is hosted on an application server, generates. A proxy server caches dynamic content only if the content is identified as edge cacheable in the cachespec.xml file for the application. All of the information that describes the cache, such as the ID to use for the cache, dependency identifiers for invalidation, and expiration times, is also defined in the cachespec.xml file. Proxy Server uses the ESI protocol to obtain this information from the file.

See the *Administering applications and their environment* PDF for more information on how to set up a cachespec.xml file for an application.

Cached dynamic content can be invalidated by events in the application server. The ESI Invalidation Servlet, that is contained in the DynacacheEsi.ear application, propagates these invalidation events from the application server to the proxy server. The DynacacheEsi.ear is shipped with the product, and must be deployed in the cluster with the application that is generating the dynamic content for dynamic caching at the proxy server to function properly.

- b. Static caching is enabled by default when caching is enabled for the proxy server. *Static content* is web content that is public and accompanied by HTTP response headers, such as EXPIRES and LAST_MODIFIED_TIME, that describe how long the response can be cached. The proxy server

uses the HTTP 1.1 RFC (2616), which specifies how content should be treated and includes capabilities such as VARY header support for caching variants of the same resource Uniform Resource Identifier (URI).

Static cache rules collection

This topic lists the static cache rules for a proxy server. From this topic you can create, delete, or modify a static cache rule.

To view this administrative console topic, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP Proxy Server Settings > Static cache rules**.

The security proxy, or the intermediary that is the entry point into the enterprise, is responsible for terminating SSL connections with the client, authenticating the request, propagating the connection characteristics for the client, and any other credentials to the application server in the enterprise.

The proxy server enables security proxies to be identified so that private headers that are set in the request are propagated as they are to the application servers. Identify the list of security proxies that are trusted by the proxy server using the trusted security proxies field. To access this administrative console field, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Proxy settings**. You can find trusted security proxies in the **Security** section of this administrative console page.

URI Groups

The URI group name is a user-specified name.

The name field cannot contain the following characters: # \ / , : ; " * ? < > | = + & % ' .

The name that is defined must be unique among URI groups and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

Disable caching for this URI group

Specifies whether or not caching is disabled.

The default is `false`, which indicates that caching is enabled for the URI group.

Default expiration

The default expiration that you set for the cached response for the URI that is associated with this cache rule.

The default expiration value is in seconds.

Last modified factor

Use this field to derive the cache expiration value for a response if it does not have HTTP expiration headers and when it has a `LastModifiedTime` header in the response.

Name of the virtual host

A virtual host that is configured using the virtual host service. This virtual host is associated with the proxy server. This attribute is one of the elements in a request that is matched by the proxy server to determine if this rule is activated.

Static cache rule settings

Use this topic to configure a cache rule that is associated to a URI group for the proxy server. HTTP 1.1 defines a set of rules for proxy servers to cache content. Static cache rules enable these default rules to be overridden for a given address space. Before the rules have any meaning, you must enable caching on

the **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP Proxy Server Settings > Proxy settings** administrative console page.

To view this administrative console page, click **Servers > Proxy Servers > server_name > HTTP Proxy Server Settings > Static cache rules > URI_group**.

You can edit proxy server setting fields on the Configuration tab.

URI groups

URI groups, along with the virtual host, define the scope of the address space to have cache customizations performed.

The name field cannot contain the following characters: # \ / , : ; " * ? < > | = + & % ' .

The name that is defined must be unique among URI groups and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

Disable caching for this URI group

Disables caching for this address space. A user may wish to disable caching for a set of content servers that are known to contain sensitive or highly-personalized information.

The default is `false`, which indicates that caching is enabled for the URI group.

Default expiration

The default expiration value, in seconds, that is used to determine the validity of a cached response when all other HTTP 1.1 caching-related response headers do not give guidance. The default value is sufficient in most environments.

The default expiration value is in seconds.

Last modified factor

The percentage of a last-modified header for a response that determines the validity of a cached response when the response does not have explicit HTTP expiration headers. The default value is sufficient in most environments.

The default for this field is `0.0`.

Name of the virtual host

A virtual host that is configured using the virtual host service. This virtual host is associated with the proxy server. This attribute is one of the elements in a request that is matched by the proxy server to determine if this rule is activated.

The default for this field is `none`.

Routing requests from a plug-in to a proxy server

This topic provides information on setting up a web server plug-in to route requests to a proxy server.

About this task

An administrator might choose to set up a web server, such as IBM HTTP Server, with the web server plug-in as a front-end to the proxy server. The plug-in configuration file for such a topology cannot use the traditional plug-in configuration generation mechanism if the requests are routed through the proxy server.

To generate the `plugin-cfg.xml` file to use with the web server plug-in to route through the proxy server, complete the following steps:

Procedure

1. From the administrative console, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Proxy settings**.
2. In the **Generate plug-in configuration** drop-down menu, select the appropriate scope.
3. Optional: If you have a script that manually copies the plugin-cfg.xml file from the node to the plug-in installation location, enter the path to the script in the **Plugin config change script** field.
4. In the Trusted Security Proxy field, add the hostname or IP address of the node for the plug-in that serves as the trusted intermediary for the proxy server.
5. Click **OK**.
6. Disable the automatic propagation of the plug-in if you are using IBM HTTP Server with remote administration. From the administrative console, click **Servers > Server Types > Web Servers > web_server_name > Plug-in properties**. Deselect **Automatically propagate plugin configuration file**. This will prevent WebSphere Application Server from copying the traditional plugin-cfg.xml file over the proxy server plugin-cfg.xml file.
7. Save your changes.
8. Stop and restart the proxy server. The plugin-cfg.xml file will be in the {WAS_ROOT}/profiles/*profilename*/etc directory unless your plug-in was generated for the server scope. If you generated the plug-in for the server scope, the plugin-cfg.xml file will be in the {WAS_ROOT}/profiles/*profilename*/etc/*server_name* directory. If you do not have a script in the **Plugin config change script** field, manually copy the plugin-cfg.xml file to the plug-in.

gotcha: During the plugin-cfg.xml generation process temporary plugin-cfg-xxxx.xml files are created. If you notice any of these temporary files in the same directory as the plugin-cfg.xml file, you can either ignore them, or manually delete them.

Results

After a plugin-cfg.xml file is initially generated, it is automatically regenerated whenever the On Demand Configuration (ODC) changes. For example, the plugin-cfg.xml file is regenerated whenever an application is installed or uninstalled, or the weights assigned to one or more proxy server cluster members changes.

What to do next

To verify that the proxy server trusts the web server, add the host name or address of the web server to the Trusted security proxies section on the Proxy Settings page in the administrative console. To reach this page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP proxy server settings > Proxy settings**. This enables the proxy server to honor the private headers that are set by the fronting intermediary server.

Creating a proxy server cluster using the wsadmin command

If you run multiple proxy servers on your system, you might want to create a proxy server cluster to make it easier to administer these proxy servers. You can use either the administrative console or the **wsadmin** command to create a proxy server cluster.

Before you begin

A proxy server cluster includes the machines, and nodes that are going to belong to the proxy server cluster. Before you define your proxy server cluster:

- Determine whether a domain name server (DNS), a load balancer, or a proxy server is going to be used to route requests to the proxy server cluster.
- Verify that Version 7.0 of the product is installed on the nodes that will belong to the proxy server cluster.

gotcha: A proxy server cluster does not have some of the same functionality that an application server cluster has. For example, a proxy cluster does not provide failover, or high availability support. The main reason for creating a proxy cluster is to make it easier to administer multiple proxy servers. For example, if your proxy servers are members of a proxy server cluster, you can specify configuration settings for that proxy server cluster, and the settings are automatically applied to all of the proxy servers in that cluster. Creating a proxy server cluster also enables you to simultaneously start and stop all of the proxy servers in that cluster.

About this task

Complete the following tasks to create a proxy server cluster.

Procedure

1. Start the deployment manager.
2. Start the wsadmin utility.
3. Issue one of the following commands.

The following command creates an empty cluster with no members:

```
$AdminTask createCluster {-clusterConfig {-clusterName <name_of_cluster> -clusterType PROXY_SERVER}}
```

The following command creates a cluster, and add a proxy server to that cluster:

```
$AdminTask createCluster { -clusterConfig {{<name_of_cluster> true PROXY_SERVER}} -convertServer  
  {{<node_name> <name_of_proxy_server> "" "" ""}}
```

The proxy server that you add is used as the template for all subsequent proxy servers that you add to the cluster.

4. Add a member to the cluster:

If no members exist in the cluster, the first proxy server that is added serves as the template for subsequent members that you add to the cluster.

Issue the following command to add a member to the cluster:

```
$AdminTask createClusterMember {-clusterName <name_of_cluster> -memberConfig  
  {-memberNode <node_name> -memberName <name_of_proxy_server>}}
```

When a proxy server is added to a cluster, proxy-specific configuration settings for it can only be configured using the wsadmin scripting client.

5. Issue the \$AdminConfig save command to save the configuration changes.
6. Start the proxy server cluster.
Start the proxy server cluster automatically enables request routing.
7. Configure requests to route to the proxy server.

For DNS-based routing, associate the logical name of the site with the IP addresses of the proxy server cluster members in DNS.

For Load balancer routing, configure the IP addresses of the cluster members as the target of the virtual cluster.

For Edge proxy or IBM HTTP Server with WebSphere Application Server plug-in-based routing, generate the plug-in configuration file for the proxy server cluster, and configure the Edge proxy or the WebSphere Application Server plug-in with this information.

Results

The proxy server cluster is created with the members and is enabled for routing traffic.

What to do next

Monitor the traffic.

Monitoring the proxy server with PMI

You can monitor the traffic of a proxy server using the Performance Monitoring Infrastructure (PMI) function.

Before you begin

The proxy server must be running before performing these steps.

Procedure

1. In the administrative console, click **Monitoring and Tuning > Performance Monitoring Infrastructure (PMI)** in the console navigation tree. The proxy server collection page displays.
2. Select the proxy server from the collection list.
3. Click **Custom**. The Custom monitoring level panel displays.
4. In the navigation tree, expand **Proxy Module**. Select the statistics you want to view, then click **Enable**.

Monitoring traffic through the proxy server

You can monitor traffic, such as requests and connection statistics, through the proxy server.

Before you begin

You should know the machines and nodes that will belong to the proxy server cluster before completing these steps, because the product must be installed on those machines.

Procedure

1. Ensure that the proxy server is running and there is some traffic flowing through the proxy server.
2. Obtain the proxy server MBean and invoke the operation to get the route statistics as follows:
 - a. Start the wsadmin scripting tool.
 - b. Get all of the traffic statistics through the proxy server using one of the following commands.

Using the JACL command

```
$AdminControl queryNames type=ProxyServer,*  
set proxymbean <cut and paste the MBean identifier from the previous command output>  
$AdminControl getAttribute $proxymbean stats
```

Using the Jython command

```
print AdminControl.getAttribute((AdminControl.queryNames("type=ProxyServer,*")), "stats")
```

The **\$AdminControl queryName** command lists all of the proxy server MBeans. There will be one per active proxy server in the cell. Set the *proxymbean* variable to the appropriate proxy server MBean from the output of the previous command.

Results

The traffic that flows through the proxy server can now be monitored.

Overview of the custom error page policy

The custom error page policy is a feature that enables the proxy server to use an application to generate an HTTP error response. With this capability, the administrator can return a polished error page when the proxy server generates an error, or when a content server returns an unsuccessful response.

The following action describes scenarios for how the error page policy is used when it is configured:

- **Internal error**

1. The client sends the following request to the proxy server: GET /house/rooms/kitchen.jpg HTTP/1.1.
2. The proxy server generates an internal error because no servers map to the request (HTTP 404 – File not found).
3. The error policy is configured to handle HTTP 404 responses, so it sends a request to the error page application to retrieve error content to send to the client. The request URI and HTTP response code are included as query parameters in the request to the error page application. If the configured error page application URI is /ErrorPageApp/ErrorPage, then the request URI to the error page application is: /ErrorPageApp/ErrorPage?responseCode=404&uri=/house/rooms/kitchen.jpg. The query parameters “responseCode” and “uri” are sent to the error page application by default.
4. The proxy server returns the response code and the content that the error page application returned. The error page application can also be set up to return the response code that is passed in the responseCode query parameter.

- **Remote error**

1. The client sends the following request to the proxy server: GET /house/rooms/kitchen.jpg HTTP/1.1
2. The proxy server forwards the request to the homeserver.companyx.com content server.
3. The homeserver.companyx.com content server is unable to locate the /house/rooms/kitchen.jpg file and sends an HTTP 404 response (File not found) to the proxy server.
4. The error policy is configured to handle HTTP 404 responses, so it sends a request to the error page application to retrieve error content to send to the client. The request URI and HTTP response code are included as query parameters in the request to the error page application. If the configured error page application URI is /ErrorPageApp/ErrorPage, then the request URI to the error page application is: /ErrorPageApp/ErrorPage?responseCode=404&uri=/house/rooms/kitchen.jpg. The query parameters “responseCode” and “uri” are sent to the error page application by default.
5. The proxy server returns the response code and the content that the error page application returned. The error page application can also be set up to return the response code that is passed in the responseCode query parameter.

A sample error application is available in the `<WAS_INSTALL_ROOT>/installableApps/HttpErrorHandler.ear` file.

Request mapping

This topic provides an overview of how the proxy server matches an HTTP request that is received to an application that is deployed in the cell or routing rule.

Unlike the Apache Web Server or Caching Proxy, which have flat configuration files with routing precedence that is inherent to the ordering of directives, the proxy server uses a best match mechanism to determine the installed application or routing rule that corresponds to a request. The virtual host or URI patterns determine the best match for a web module or routing rule. For applications that are deployed in clusters, the proxy server maintains affinity (Secure Sockets Layer ID, cookie, and URL rewriting), otherwise, a weighted round-robin approach is used to select the target server. The following examples address various routing scenarios for when routing rules and applications are deployed within the same cell.

Proxy environment

A WebSphere proxy server called proxy1 is active in the same cell as the applications and routing rules. All of the applications and routing rules are enabled in the cell for proxy1, and PROXY_HTTP_ADDRESS for proxy1 is set to 80.

Virtual host	Host name	Port
default_host	host1.company.com	80
	host1.company.com	9080

Virtual host	Host name	Port
	*	80
proxy_host	host2.company.com	80
	*	443
	*	80
server_host	host3.company.com	80

URI group name	URI patterns
ALL	/*
ROOMS	/kitchen/*, /bathroom/*, /bedroom/*
CONFLICT	/WM2C/*

Generic server cluster name	Protocol	Host	Port
CLUSTER1	HTTP	webserver1.company.com	9081
		webserver2.company.com	9083
CLUSTER2	HTTP	host47.company.com	8088
		host48.company.com	8088
CLUSTER2-SSL	HTTPS	host47.company.com	8443
		host48.company.com	8443

Routing rule name	Virtual host	URI group	Action
ALLTOCLUSTER1	proxy_host	ALL	Generic server cluster - CLUSTER1
ROOMTOCLUSTER2	proxy_host	ROOMS	Generic server cluster - CLUSTER2
ALLTOCLUSTER2	server_host	ALL	Generic server cluster - CLUSTER2
REDIRECTTOCONFLICT	default_host	CONFLICT	Redirect - http://www.conflict.com

Application name	Context root	Web module name	Virtual host	Web module URI patterns
App1	/WM1A/	Web Mod A	default_host	wm1a.jsp
	/WM1B/	Web Mod B	default_host	wm1b.jsp
App2	/WM2C/	Web Mod C	default_host	/*, wm2c.jsp
	/WM2D/	Web Mod D	default_host	/*, wm2d.jsp

Example 1: Basic request

The proxy1 proxy receives the following request:

```
GET /WM1A/wm1a.jsp HTTP/1.1
Host: host1.company.com
```

Result

The `wm1a.jsp` file is sent as the response. The `ALLTOCLUSTER1` routing rule is a possible match, but Web Mod A is chosen as the best match by `proxy1` because the combination of its context root and URI pattern `/WM1A/wm1a.jsp` is a better match than `/*`. Web Mod A is also chosen as the best match because its virtual host contains the `host1.company.com:80` alias, which is a more specific match than the `*:80` wild card alias.

Example 2: Routing rules that use the same URI group and different virtual hosts

The `proxy1` proxy receives the following request:

```
GET /index.html HTTP/1.1
Host: host3.company.com
```

Result

The `proxy1` proxy maps the request to the `ALLTOCLUSTER2` routing rule, and a response is received from a server in `CLUSTER2`. The `ALLTOCLUSTER1` routing rule is a possible match and can handle the request if the `ALLTOCLUSTER2` routing rule did not exist. However, the `ALLTOCLUSTER2` rule is the best match because its virtual host (`server_host`) explicitly lists `host3.company.com`.

Example 3: Routing rules that use same virtual host and different URI groups

The `proxy1` proxy receives the following request:

```
GET /kitchen/sink.gif HTTP/1.1
Host: host2.company.com
```

Result

The `proxy1` proxy maps the request to the `ROOMSTOCLUSTER2` routing rule and a server from the `CLUSTER2` cluster sends a response. The `ALLTOCLUSTER1` routing rule is a possible match, but the `ROOMSTOCLUSTER2` rule is the best match because its URI group contains a pattern `/kitchen/*` that is a better match for the request URI `/kitchen/sink.gif`.

Example 4: Routing rule URI group conflicts with URI pattern of a web module that uses the same virtual host

The `proxy1` proxy receives the following request:

```
GET /WM2C/index.html HTTP/1.1
Host: host1.company.com
```

Result

The result is indeterminate. It is unknown whether Web Mod C or the `REDIRECTTOCONFLICT` routing rule handles the request because they use the same virtual host and have the same URI pattern. In such cases, the `ID DWCT0007E` message is displayed in `SystemOut.log` file for the `proxy1` proxy. In this example, changing the `REDIRECTTOCONFLICT` routing rule to use a different virtual host resolves the problem.

Note: This topic references one or more of the application server log files. Beginning in WebSphere Application Server Version 8.0 you can configure the server to use the High Performance Extensible Logging (HPEL) log and trace infrastructure instead of using `SystemOut.log`, `SystemErr.log`, `trace.log`, and `activity.log` files or native z/OS logging facilities. If you are using HPEL, you can access all of your log and trace information using the LogViewer command-line tool from your server profile bin directory. See the information about using HPEL to troubleshoot applications for more information on using HPEL.

Example 5: The `PROXY_HTTP_ADDRESS` address is not in the virtual host

Assume that the `proxy1` proxy address, `PROXY_HTTP_ADDRESS`, is changed to 81, while all of the other configuration information remains the same. The `proxy1` proxy receives the following request:

```
GET /index.html HTTP/1.1
Host: host1.company.com:81
```

Result

The proxy1 proxy is unable to handle the request because the PROXY_HTTP_ADDRESS address is not available in a virtual host and will send an HTTP 404 response back to the client.

Session failover in the proxy server

This article describes how the proxy server handles session failover.

You can enable memory-to-memory replication on an application server to maintain session state in multiple servers. In this case, a private header is added to the response which identifies the backup servers for the session. The proxy server reads this header and maintains a list of backup servers for a session. If the proxy server fails to route to the primary server, it tries to route to the backup servers. If none of the backup servers are available, a deterministic algorithm selects one of the available servers; consequently, multiple proxy servers will route to the same server.

If the set of servers that are hosting a session changes, the private response header causes the proxy server to update its list of servers for the session. It is possible that the set of servers is updated, but the proxy server has not yet received an updated response header. In this case, the proxy server routes to a server that does not contain the session data. If this occurs, the backend server obtains the session data from a server that contains the session data. There is no functional difference in this case; however, there is a performance difference due to the cost of obtaining the session data from another server.

Installing a Session Initiation Protocol proxy server

The Session Initiation Protocol (SIP) proxy server initiates communication and data sessions between users. It delivers a high performance SIP proxy capability that you can use at the edge of the network to route, load balance, and improve response times for SIP dialogs to backend SIP resources. The SIP proxy provides a mechanism for other components to extend the base function and support additional deployment scenarios. This topic provides information to install a Session Initiation Protocol (SIP) proxy server.

Before you begin

Ensure that you have a SIP application installed. The SIP container will not listen on a port without a SIP application installed. For a proxy server to be useful, you should have a cluster of SIP application servers.

About this task

The SIP proxy design is based on the HTTP proxy architecture and can be considered a peer to the HTTP proxy. Both the SIP and the HTTP proxy are designed to run within the same proxy server and both rely on a similar filter-based architecture for message processing and routing.

A SIP proxy serves as the initial point of entry, after the firewall, for SIP messages that flow into and out of the enterprise. The SIP proxy acts as a surrogate for SIP application servers within the enterprise. In fact, the nodes that host the SIP proxy servers host the public SIP domain of the enterprise. As a surrogate, you can configure the SIP proxy with rules to route to and load balance the clusters of SIP containers. The SIP proxy is capable of securing the transport, using secure sockets layer (SSL), and the content, using various authentication and authorization schemes.

The SIP proxy is also responsible for establishing outbound connections to remote domains on behalf of the back-end SIP containers and clients that reside within the domain that is hosted by the proxy. Another important feature of the SIP proxy is its capability to protect the identity of the back-end SIP containers from the SIP clients.

gotcha: You must first have created a cell, deployment manager, and node when you installed WebSphere Application Server.

Procedure

Create a proxy server on the node that you just federated, or on another node in the cell that contains the cluster that the proxy will sit in front of by clicking **Servers > Server Types > WebSphere proxy servers > New**.

gotcha: You must select the SIP protocol.

You do not have to install the proxy server on a machine that also includes one of the servers in the cluster.

Results

After you choose a default cluster, your SIP proxy server will be functional. However, if the SIP proxy server is fronted by an IP sprayer, you must set up the loopback address and modify the inbound channel chains to make the SIP proxy server functional. See the load balancer documentation for information about setting up the loopback address.

gotcha: The virtual host for your SIP container ports must be defined, and the SIP container(s) must be restarted after adding the new virtual host.

Trusting SIP messages from external domains

The general approach for providing secure communications between two independent domains or communities (each maintaining distinct directories) relies on *identity assertion*, where a trust relationship is established between two distinct domains using a certificate exchange during the setup of the physical Secure Sockets Layer (SSL) connection between the two domains.

About this task

Authentication of Session Initiation Protocol (SIP) messages that are sent by end users needs to occur only in the local domain for the user. All user messages pass through the SIP container local domain before being sent on to the external domain. If a message is received from an external domain over a secured connection that is mutually authenticated in the manner described as follows, it is assumed that the message is authenticated by the external domain because of the trust relationship. An administrator can enable support for external domains in the SIP proxy as follows:

Procedure

1. Enable client authentication within the SSL repertoire that is assigned to all the inbound channel chains (or endpoints) that are to receive inbound connections from external domains.
2. Ensure that all trusted certificate authorities are set up in the trust store that is assigned to the SSL repertoires mentioned in the previous step. Set up the asymmetric key pair (public and private keys) for the local domain, with the proper chain of certificates that is associated with the local domain.
3. Configure the distinguished names (DNs) that are associated with the external domains to support. The DN is part of the X.509 certificate that is sent by the external domain server when the SSL connection is set up. Within the configuration model, each SIP external domain entry includes a field for the external DN.
4. Assuming that the SIP infrastructure is deployed within each domain, provide the DN to the external domain administrator that is included in the local domain's public certificate. With this action, the external domain administrator can configure the proper external DN.

With this approach, the Java Secure Socket Extension (JSSE) is responsible for authorizing the certificate that is received over a new inbound connection from an external domain. This authorization is based on the agreed upon certificate authorities whose certificates are set up in the local trust store. If

the external domain certificate is authorized, it is then the responsibility of the SIP proxy to filter the connections, based on the DN that is associated with the external domain certificate. The proxy also validates outbound connections by ensuring that the DN that is received in the remote server certificate matches the DN configured for the external domain.

The SIP proxy must recognize when identity assertion is in use so that it can inform the SIP container that no message authentication is required over this mutually authenticated connection. This communication is done by adding the P-Preferred-Identity SIP header, which is described in RFC 3325, in all SIP messages that are sent from the proxy to the SIP container that arrive over the authenticated connection. The SIP container only recognizes this header when it is received from a device that resides in the trusted domain, specifically the SIP proxy. It is up to the SIP proxy to remove this header from any inbound messages that are received over any connections to remote devices that are not considered part of the trusted domain. You can also use this header to support the addition of proxy authentication.

Tracing a Session Initiation Protocol proxy server

You can trace a Session Initiation Protocol (SIP) proxy server, starting either immediately or after the next server startup.

About this task

By default, the trace messages do not include the Authorization and Proxy-Authorization headers. If you also do not want the other SIP message headers to appear in the trace log, add the SIP UDP transport channel custom property `hideMessageHeaders` custom property to the settings for the SIP inbound channel (SIP 1) and set the property to `true`. You can also add the `hideMessageBody` custom property to the settings for this channel and set it to `true` if you do not want the message body included in the trace messages.

Note: This topic references one or more of the application server log files. Beginning in WebSphere Application Server Version 8.0 you can configure the server to use the High Performance Extensible Logging (HPEL) log and trace infrastructure instead of using `SystemOut.log`, `SystemErr.log`, `trace.log`, and `activity.log` files or native z/OS logging facilities. If you are using HPEL, you can access all of your log and trace information using the LogViewer command-line tool from your server profile bin directory. See the information about using HPEL to troubleshoot applications for more information on using HPEL.

To trace a SIP proxy server, complete the following steps:

Procedure

1. Start the product, and open the administrative console.
2. In the administrative console, click **Troubleshooting > Logs and trace**.
3. Select the name of the server for the SIP proxy server.
4. From the General Properties section, click **Diagnostic Trace Service**.
5. Select one of the following options:

Option	Description
Configuration	To start tracing after the next server startup
Runtime	To start tracing immediately

6. Replace the content of the trace specification with the following code:
`*=info:com.ibm.ws.sip.*=all:com.ibm.ws.proxy.*=all`
7. Make sure that the **Enable trace with following specification** check box is checked.
8. Click **Apply > Save**.

What to do next

When the changes take effect, SIP proxy server tracing messages display in *WASProductDir/logs/serverName/trace.log* on the SIP proxy server node, where *WASProductDir* is the fully-qualified path name of the directory where the product is installed and *serverName* is the name of the specific instance of the application server that is running the SIP proxy server to be traced.

High availability and workload management with Session Initiation Protocol proxy server

The Session Initiation Protocol (SIP) high availability solution assumes that all messages that belong to the same dialog are handled by the same container. If a container fails, all of the sessions that were handled by that container are picked up by the other servers in that container replication domain, and are activated immediately. All subsequent messages that belong to a session from the failed container are sent to the new container in charge of that session.

gotcha: The SIP proxy server does not administer transaction-level failover, which are calls that are made in the middle of a transaction. The SIP proxy server administers failover of stable calls, which are calls that are not made in the middle of a transaction.

High availability manages the following:

- Scalability – The ability to add more servers to the cluster to handle increased loads.
- Load balancing – The ability to distribute the load across all of the servers in the cluster so no server is overloaded while there are other servers that are not utilized.
- Fail over – The ability to recover from a failure in one or more of the components in the solution.

The SIP high availability solution uses the following components:

- SIP container - Maintains all of the sessions and launches all of the applications.
- SIP proxy server - Manages a large number of client connections, routes incoming messages to the appropriate SIP container, and creates outbound connections to clients and other domains.
- Network Dispatcher - Provides a single IP for the cluster and round-robins between proxies.
- Unified Clustering Framework (UCF) - Communicates routing information between the SIP container and the SIP proxy. Using UCF, the SIP proxy routes messages to the least-loaded SIP container or to a container that is taking over sessions for a failed server.

Note: If you add SIP containers to a cluster while traffic is flowing, you should add them one container at a time so that the system can go through the bootstrap process for the container without draining resources from the entire cluster. If you add one container at a time, only the added container goes through the bootstrap process as opposed to all of the containers in the cluster.

Manage failover in the SIP proxy by:

1. Replicating the data in the sessions between SIP containers so that other containers are able to activate the failed sessions in case of a server failure.
2. Activating the failed sessions on the rest of the servers immediately when a failure is detected because the SIP sessions might have timers associated with them.
3. Routing incoming messages that belong to failed sessions to the new server that is handling the session.

Load balancing with the Session Initiation Protocol proxy server

Load Balancer for IBM® WebSphere® Application Server can help maximize the potential of your Web site by providing a powerful, flexible, and scalable solution to peak-demand problems. Configuration of a load balancer is critical to prevent any single points of failure at Session Initiation Protocol (SIP) proxy. Configuration of a load balancer is required when more than one SIP proxy is deployed.

Before you begin

Before you begin, complete these tasks:

1. Install Load Balancer for IBM WebSphere Application Server. See the information provided in the Edge Components Information Center. This information center is available on the WebSphere Application Server Library page.
2. From the Load Balancer for IBM WebSphere Application Server, complete the steps for setting up server machines for load balancing. Ensure that you set up a loopback address for your operating system. See the Load Balancer Administration Guide in the Edge Components Information Center.
3. Start the Session Initiation Protocol (SIP) proxy server.

About this task

Complete these steps to integrate the SIP proxy server with the Load Balancer.

Procedure

1. Start the Load Balancer.
 - a. From the command prompt, type `dsserver start`
 - b. Then type `lbadmin` to start the administrative console for the Load Balancer.
 - c. From the administrative console, right click **Dispatcher**, and then select **Connect to Host**
 - d. Right click the host name, and select **Start Executor**.
2. Start the configuration wizard for the Load Balancer.
 - a. Select default host.
 - b. Type a cluster address. You cannot ping the cluster address before the Executor starts.
 - c. Define your SIP traffic port. Type a port number, such as 5060. You must specify this same value for port when you create a user-defined port in on your proxy server.
 - d. Add each server to which the Load Balancer proxies traffic. In your configuration, the load balanced server is the proxy server for your configuration.
 - e. Start an advisor by typing the name of the advisor. For example, start the HTTP advisor for HTTP traffic. For SIP traffic, start the SIP advisor. The advisor tells the manager if a specific port is accepting traffic.
3. Set up a loopback address on the physical proxy server host that represents the Virtual IP address for the cluster that is defined on the load balancer. Refer to the topic on configuring the server machines in the information center for Load Balancer.
4. Configure an IP sprayer from the application server's administrative console
 - a. From the administrative console, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP proxy server settings > SIP proxy settings**.
 - b. Scroll down to the health checking setting for Load Balancer, and specify the physical IP address of the host on which Load Balancer is installed.
 - c. Specify the SIP health check method name. The IBM Load Balancer uses OPTIONS as its method name.
 - d. Click on **Apply**, and save your actions.
5. Optional: From the administrative console, define custom properties for the SIP proxy server. These custom properties can be used for defining SIP Proxy Load Balancer Health checking.
 - a. In the Additional Properties section, click **Custom properties**.
 - b. Ensure that Proxy servers have both the LBIPAddr and SIPAdvisorMethodName custom properties defined. The information for these custom properties is:

Name	Value
LBIPAddr	Physical IP address of the machine where the IBM Load Balancer is installed
SIPAdvisorMethodName	OPTIONS

Specify a value for these SIP proxy custom properties, and click **OK**.

Attention: These settings are now available from the SIP proxy settings page in the administrative console, and they do not require that a custom property be set, but defining the custom properties is supported. If the custom property is set, the value of the custom property takes precedence over the value that you set in the administrative console.

6. Create a user-defined port from the application server's administrative console.
 - a. From the administrative console, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Ports > New**.
 - b. Select **User-defined port**.
 - c. Enter SIP_LB_Address for the Port Name field.
 - d. Enter a value for the Host field. This is the virtual IP (cluster address) that is configured on your load balancer.
 - e. Enter a value for the Port field. This value corresponds to the port through which the load balanced servers are configured to accept traffic from the load balancer machine. Consider the load balanced servers to be your proxy servers for this configuration.
 - f. Click **Apply**, and then click **Save**.
7. Modify the SIP proxy transports from the administrative console.
 - a. From the administrative console, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP container transport chains > UDP_SIP_PROXY_CHAIN > UDP Inbound Channel**.
 - b. Under the SIP proxy transports section, modify UDP_SIP_PROXY_CHAIN.
 - c. From the Port menu, select SIP_LB_Address.
 - d. Click **Apply**, and click **Save**.
8. Restart the proxy server to save your changes.

SIP proxy settings

The SIP proxy settings page contains general configuration items that affect outbound transport configuration, toleration of IP Sprayer devices, and access logging configuration.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP proxy settings**.

The **SIP proxy settings** panel allows you to define attributes and policies that control the behavior of the SIP proxy server.

Default cluster

Specifies the default cluster name.

The **Default cluster** field must be set to a valid cluster before any SIP messages are routed through the proxy server. The default cluster indicates which cluster of application servers should receive SIP traffic when there are no cluster selection rules defined, or when none of the existing cluster selection rules match.

Data type	Valid cluster name
Default	None

Retry-after header value

Specifies the amount of time, in seconds, that the SIP proxy waits before it returns the SIP request because the SIP containers are overloaded, or the SIP proxy cannot locate available servers to which it can route the request.

Range	1 to 1000
Data type	Integer
Default	5

Logging

Specifies whether to enable or disable access logging.

When **Enable access logging** is checked, specifies the access log maximum size and proxy access log path name. When this control is unchecked, access log maximum size and proxy access log settings are disabled.

Data type	Boolean
Default	Unchecked

Access log maximum size

Specifies the maximum size, in megabytes (MB), of the access log before it rolls over.

Range	1 to 65535
Data type	Integer
Default	20

Proxy access log

Specifies the location of the SIP proxy access log.

Range	Valid path name
Data type	String
Default	<code>\$(SERVER_LOG_ROOT)/sipproxy.log</code>

Container facing network interface

This section contains fields that configure the container-facing network interfaces.

Note: The value asterisk (*) means let the OS decide which interface to use.

UDP interface

Specifies the network interface for all User Datagram Protocol (UDP) data that goes to and from the SIP container. The value for this setting is the hostname or IP address to use for all communications between the SIP proxy and the SIP containers when the network is segmented.

Note: If a value is specified for this setting, you must also specify a value for the UDP port setting.

Data type	String
Default	*

UDP port

Specifies the UDP port for SIP container communications, such as the specific port required to pass through a firewall that separates the SIP proxy and the SIP containers.

Note: If a value is specified for this setting, you must also specify a value for the UDP interface.

Range	1 to 65535
--------------	------------

Data type Integer
Default *

TCP interface

Specifies the network interface for all Transmission Control Protocol (TCP) data that goes to and from the SIP container or containers.

Data type String
Default *

TLS interface

Specifies the network interface for all Transport Layer Security (TLS) data that goes to and from the SIP container or containers.

Data type String
Default *

Load balancer health checking

This section contains fields that configure the load balancer used to load balance the SIP proxy server and perform health checks.

Load balancer members (IP address 1 and 2)

Specifies the IP addresses of the load balancers that source the SIP health checks. The IP addresses (1 and 2) ensure that the message is an actual SIP advisor request before sending a response back to it.

Data type String
Default None

SIP health check method name

Specifies the health check method name sent to the SIP proxy from the load balancer.

Data type String
Default None

Tolerate a specific number of negative health checks

Specifies whether to allow negative health checks.

Data type Boolean
Default False

Maximum negative health checks

Specifies the number of SIP health checks that the load balancer can perform that return negative results, indicating that there is a communication problem between the load balancer and the SIP proxy, before this SIP proxy informs the other SIP proxies that it is no longer processing data.

Range 1 through 10
Data type Integer
Default 3

SIP network outage detection

Specifies whether to enable or disable outage detection.

When **Enable SIP network outage detection** is checked, specifies the KEEPALIVE interval and maximum KEEPALIVE failures. When this control is unchecked, network outage detection is disabled.

Data type	Boolean
Default	Unchecked

Keep alive interval

Specifies the interval, in milliseconds, at which the KEEPALIVE packets are sent to the SIP containers.

Range	1 through 1000
Data type	Integer
Default	3000

Maximum keep alive failures

Specifies the number of KEEPALIVE requests that are sent without getting a response before considering this server down.

Range	1 through 10
Data type	Integer
Default	3

Overload protection

Specifies whether to enable or disable overload protection.

When **Enable proxy managed overload protection** is checked, specifies the maximum throughput allowed and overload error response. When this control is unchecked, maximum throughput and overload error response fields are disabled.

Data type	Boolean
Default	False

Max throughput factor

Specifies the degree of overload protection at the proxy and is a percentage of the maximum messages per averaging period for the SIP container.

Range	1 through 100
Data type	Integer
Default	90

Overload response code

Specifies the overload response code. When the proxy detects an overload condition, it will respond to the request with the overload response code, if it is set.

Data type	Integer
Default	503

Overload response reason

Specifies the overload response reason phrase. When the proxy detects an overload condition, it will respond to the request with the overload response phrase, if it is set.

Data type	String
Default	Service unavailable

SIP external domains collection

The external domain collection panel provides create, remove and update capabilities for the external domain routing configuration.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP proxy settings > External Domains**.

New

Create a new external domain entry. Clicking **New** launches the External Domain Detail panel.

Delete

Used to remove an external domain entry.

Domain

The domain string that is mapped to the associated protocol, host, and port configuration.

Distinguished name

The name that is associated with the external domain. It is used when SSL client authentication is enabled to limit connections from an external domain.

Protocol

This field contains the host name that the SIP Proxy will write to outbound requests so that the receiving agent will connect back to the IP Sprayer.

Host

The host used to make the SIP connection associated with the domain.

Port

The port used to make the SIP connection associated with the domain.

SIP external domains

The external domain detail panel configures the properties for external domain routing.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP proxy settings > External Domains > New**.

Domain

The SIP domain that is mapped to the protocol, host, and port that is specified in the fields on this panel. The SIP proxy server matches the domain that is found in the TO header of a SIP message to this value and uses the related information to connect to the specified SIP service.

Range	Valid SIP domain name, with the addition of an optional preceding * as a wildcard.
Setting recommendations	None

Protocol

The protocol that the SIP proxy server uses to connect to the SIP service.

Range	TCP, SSL, and UDP
Default	TCP
Setting recommendations	None

Distinguished name

The name that is associated with the external domain. Used when SSL client authentication is enabled to limit connections from an external domain.

Range	Any string
Default	blank
Setting recommendations	None

Host

The host that the SIP proxy server uses to connect to the SIP service.

Range	Valid host name or IP address
Default	blank
Setting recommendations	None

Port

The port that the SIP proxy server uses to connect to the SIP service.

Range	1 to 65535
Default	blank
Setting recommendations	None

SIP routing rules collection

Routing rules enable an administrator to direct Session Initiation Protocol (SIP) traffic to a specific cluster when there is more than one cluster running SIP applications in a WebSphere Application Server Network Deployment cell.

Routing rules are not needed in cases where there is one cluster running SIP. Rules are only applied to the initial message of a SIP conversation and not all SIP traffic. To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP proxy settings > Routing rules**.

New

Clicking **New** launches the Routing Rule Detail Panel for creating a new rule.

Delete

Deletes selected rules.

Enable

Sets the enabled attribute of the selected rules to true.

Disable

Sets the enabled attribute of the selected rules to false.

Set order

Launches the Set Order panel.

Select

Allows the user to select multiple rows to be affected by the Delete, Enable and Disable actions.

Order

The order column represents the order in which the rules are evaluated. This is critical since a SIP message may match more than one rule.

Cluster

The name of the cluster to which the rule will route SIP traffic.

Condition

A concatenation of the list of conditions associated with the rule. Condition is not sorted.

Enabled/Disabled

Indicates whether the rule is enabled, and thus considered for evaluation.

SIP routing rules set order

It is possible that a SIP message can match more than one routing rule but the SIP proxy will stop evaluating at the first match. Routing rules are evaluated in the order that they appear in the configuration file. The set order routing rule panel enables the administrator to change this ordering.

Routing rules are not needed in cases where there is one cluster running SIP. Rules are only applied to the initial message of a SIP conversation and not all SIP traffic. To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > *proxy_server_name* > SIP proxy settings > Routing rules > Set Order.**

Move Up

Clicking **Move Up** moves the selected rule up one row.

Move Down

Clicking **Move Down** moves the selected rule down one row.

Select

Enables the user to select one row that will be acted on by the Move Up and Move Down actions.

Cluster

The name of the cluster that the rule will direct SIP requests to.

Condition

A concatenation of the list of conditions that are associated with the rule.

Enabled

Indicates whether the rule is enabled and thus considered for evaluation.

SIP routing rules detail

The routing rule detail panel provides the ability to create and modify individual rules. Since the structure of conditions is complex, the user will need to utilize a different set of panels to change the conditions associated with a rule.

Routing rules are not needed in cases where there is one cluster running SIP. Rules are only applied to the initial message of a SIP conversation and not all SIP traffic. To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > *proxy_server_name* > SIP proxy settings > Routing rules > New.**

Enabled

Enables a rule to be removed from consideration without requiring that it be deleted. This field is checked by default.

Data type	Boolean
Default	true
Setting recommendations	none
Setting dependencies	none

Target Cluster

The name of the cluster that the SIP message will be routed to if the message attributes match the conditions.

Data type	String
Default	First cluster in the list.
Range	List of existing clusters or "null cluster" to indicate that a request should be rejected.

Setting recommendations	None
Setting dependencies	None

SIP rule condition collection

Each rule contains a list of conditions that are combined using a logical AND operator. This means that all of the conditions need to be true for the rule to apply. This panel enables the user to manage the set of conditions.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP Proxy Server Settings > Routing rules > target_cluster > Conditions**.

New

Create a new condition. Clicking **New** launches the Rule Condition Detail panel.

Delete

Removes a condition from the collection.

Type

Indicates which aspect of a SIP message the condition applies to.

Value

The value that will be compared to the aspect of the SIP message indicated by type.

SIP rule condition detail

Routing rules direct SIP requests that match the condition to the selected cluster. The condition setting specifies which SIP messages match the rule. Rules only apply to the initial message of a SIP conversation and not all SIP traffic. Use this panel to create or modify a rule.

Note: Routing rules are not needed in cases where there is only one cluster running SIP.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > SIP Proxy Server Settings > Routing rules > target_cluster > Conditions > New**.

Condition type: Method

Select this option to use **Condition type: Method**. Selecting this condition type activates the Condition value field.

Default	Selected
----------------	----------

Condition value

Specifies a fixed list of predefined method types when **Condition type: Method** is selected.

Range	INVITE, REGISTER, REFER, SUBSCRIBE, UNSUBSCRIBE, PUBLISH, MESSAGE, OPTIONS, INFO
Default	INVITE

Condition type: Defaults

Select this option to use **Condition type: Defaults**. Selecting this condition type activates the Type and Condition value fields. You can select between the fixed condition list, **Type**, and free form entry, **Condition value**, for this condition type.

Default	Not selected
----------------	--------------

Type

Specifies a fixed list of predefined attributes when **Condition type: Defaults** is selected.

Range

TO, FROM, REQUEST URI, SOURCE ADDRESS, DESTINATION ADDRESS

Default

TO

Condition value

Specifies a generic SIP message condition when **Condition type: Defaults** is selected.

Default

Empty string

Condition type: Header

Specifies whether to enable the header for a condition rule. You must specify a header name and header value pair if this setting is enabled.

Default

Not selected

Header name

Specifies the header name for the condition rule. If the value specified for this setting is *Header1*, then a packet sent to the proxy with this name specified as the header name satisfies the condition for the defined rule.

Default

Empty string

Header value

Specifies the header value for the condition rule. If the value specified for this setting is *Value1*, then a packet sent to the proxy with this value specified as the header value satisfies the condition for the defined rule.

Default

Empty string

SIP proxy inbound channel detail

This panel displays the configuration details of the SIP proxy inbound channel.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Transport chain > SIP proxy inbound channel**.

Transport channel name

Specifies the name of the SIP proxy inbound channel.

The name field cannot contain the following characters: # \ / , : ; " * ? < > | = + & % ' .

This name must be unique across all channels in a WebSphere Application Server environment. For example, a SIP proxy inbound channel and a TCP transport channel cannot have the same name if they reside within the same system.

Data type

String

Discrimination weight

Specifies the priority this channel has in relation to the other channels in this transport chain. This property is only used when port sharing is enabled and the channel chain includes multiple channels to which it might forward data. The channel in the chain with the lowest discrimination weight is the first one given the opportunity to look at incoming data and determine whether or not it owns that data.

Data type
Default

Positive integer
0

Troubleshooting the proxy server

This topic helps you to solve problems that you might encounter with your proxy server.

About this task

Proxy server errors are logged in the SystemOut.log, proxy.log, or local.log files. Consult the following list if you are having problems with your proxy server.

Note: This topic references one or more of the application server log files. Beginning in WebSphere Application Server Version 8.0 you can configure the server to use the High Performance Extensible Logging (HPEL) log and trace infrastructure instead of using SystemOut.log, SystemErr.log, trace.log, and activity.log files or native z/OS logging facilities. If you are using HPEL, you can access all of your log and trace information using the LogViewer command-line tool from your server profile bin directory. See the information about using HPEL to troubleshoot applications for more information on using HPEL.

Procedure

- **The proxy server was created successfully, but I am unable to start it.** Check the SYSOUT file for port conflicts. Use the `netstat -a` command to see if any of the endpoints that are associated with the proxy server are already being used. You can find the ports in the administrative console by clicking **Servers > Proxy servers > <server_name> > Ports**.

If the proxy server fails to start when attempting to start it as a non-privileged user on UNIX systems, check for the following message in the logs:

```
ChannelFramew E   CHF0029E: Error initializing chain HTTPS_PROXY_CHAIN because of
exception
com.ibm.wsspi.channel.framework.exception.RetryableChannelException: Permission
denied
TCPPEndpoint  E   TCPC0003E: TCP Channel TCP_7 initialization failed. The socket
bind failed for host * and port 80. The port may already be in use.
```

Change the ports of the PROXY_HTTP_ADDRESS and PROXY_HTTPS_ADDRESS transport chains to values greater than 1024.

- **The proxy server routes requests to the web container over an administration port.** The proxy server is located in front of several web containers. The configuration requires that the web containers listen to the non-default ports such as 9061, 9081, and so on. This scenario is the default case when multiple application servers are on the same machine, which forces new and different ports to be used in the configuration. In this scenario, the proxy server might route an application request to the web container over the administration port of 9061, instead of using the expected port of 9081. Add the listening port numbers of the web container to the virtual host that is associated with the target application. This process will ensure that the proxy server routes the request to the web container over the correct port number.
- **The proxy server started, but I am unable to access the application resources through the endpoints for the proxy server.** Ensure that the endpoints for the proxy server are among the host aliases in the virtual host that are associated with the application.
- **The proxy server routes to another core group.** Verify that core group bridges exist between the core groups in the cell, and that the processes that are chosen to be bridges are restarted. If there is a firewall between the core group, verify that the correct ports are open for core group bridge traffic.
- **The proxy server is unable to route requests to another cell.** Review the core group bridge settings. If the HMGR0149E error message is logged on any server, usually on a server acting as a core group bridge, then the security settings for the cell need to be modified to allow communication.

See the topic entitled *Exporting Lightweight Third Party Authentication keys* for more information about configuring cell security between multiple cells.

- **Receiving a blank page when making a request to the proxy.** Consider the following actions:
 - Update the virtual host. Ensure that the target application and routing rule are assigned to a virtual host that includes the proxy server listening ports (default: HTTP 80, HTTPS 443). Add the proxy server listening ports to the application, or routing rule virtual host, or use the proxy_host virtual host.
 - Stop the conflicting process. Check your system to ensure that no other process (for example, Apache, IBM HTTP Server, and so on) is running that uses the proxy server ports (default: HTTP 80, HTTPS 443). If this problem occurs, the proxy server seems to start normally, but is unable to receive requests on the affected listening port. Check your system as follows:
 1. Stop the proxy server.
 2. Query your system using **netstat** and **ps** commands to determine if an offending process is using the port on which the proxy server is listening.
 3. If an offending process is found, stop the process and configure your system so that the process is not started during system startup.
 - Enable proxy routing. Ensure that proxy routing is enabled for the web module of the application. Proxy routing is enabled by default, so if no proxy properties are modified, disregard this solution. Otherwise, see “Customizing routing to applications” on page 191 for instructions on modifying the proxy properties.
 - Test direct request. Ensure that the target application is installed by making a request directly to the application server. If a response is not received, then the problem is with the application server and not the proxy server. Verify this case by going through the proxy server after you can receive a response directly from the application server.
- **HTTP 404 (File not found) error received from the proxy server.** Consider the following actions:
 - Update the virtual host. Ensure that the target application and routing rule are assigned to a virtual host that includes the proxy server listening ports (default: HTTP 80, HTTPS 443). Add the proxy server listening ports to the application, or routing rule virtual host, or use the proxy_host virtual host.
 - Enable proxy routing. Ensure that proxy routing is enabled for the web module of the application. Proxy routing is enabled by default, so if no proxy properties are modified, disregard this solution. Otherwise, see “Customizing routing to applications” on page 191 for instructions on modifying the proxy properties.
 - Test direct request. Ensure that the target application is installed by making a request directly to the application server. If a response is not received, then the problem is with the application server and not the proxy server. Verify this case by going through the proxy server when you can receive a response directly from the application server.
- **Unable to make Secure Sockets Layer (SSL) requests to application or routing rule.** Ensure that the virtual host of the application or routing rule includes a host alias for the proxy server SSL port (default: 443).
- **Unable to connect to the proxy server...request times out.** Stop the conflicting process. Check your system to ensure that no other process (for example, Apache, IBM HTTP Server, and so on) is running that uses the proxy server ports (default: HTTP 80, HTTPS 443). If this situation occurs, the proxy server seems to start normally, but is unable to receive requests on the affected listening port. Check your system, as follows:
 1. Stop the proxy server.
 2. Query your system using **netstat** and **ps** commands to determine if an offending process is using a port on which the proxy server is listening.
 3. If an offending process is found, stop the process and configure your system so that the process is not started during system startup.
- **Did not receive a response from the error page application when the HTTP error occurred (for example, 404).** Ensure that the error page URI is entered correctly. Also, make sure that the Handle remote errors option is selected if you are handling HTTP error responses from back-end servers. For

more detailed information, refer to “Overview of the custom error page policy” on page 199 and the custom error page policy section of “Proxy server settings” on page 140.

- **What packages do I enable when tracing the proxy server?** All of the following packages are not needed for every trace, but if unsure, use all of them:
 - *=info
 - WebSphere Proxy=all
 - GenericBNF=all
 - HAManager=all
 - HTTPChannel=all
 - TCPChannel=all
 - WLM*=all
 - DCS=all
 - ChannelFrameworkService=all
 - com.ibm.ws.dwlm.*=all
 - com.ibm.ws.odc.*=all
- **How do I enable SSL on/off load?** SSL on/off load is referred to as the transport protocol in the administrative console, and transport protocol is a web module property. Refer to “Customizing routing to applications” on page 191 to see how to configure web module properties. No SSL on/off load or transport protocol properties exist for routing rules because the transport protocol is inherent to the generic server cluster that is specified in the routing rule.
- **When fronted by IBM HTTP Server or a web server plug-in, how do I configure the proxy server so I do not have to add a port for it to the virtual host?** For the proxy server to trust the security-related information that is included in a request, such as private headers that the product adds, add the originator of the request to the proxy server trusted security proxies list. For example, add an IBM HTTP Server or a web server plug-in that sends requests to the proxy server, to the proxy server trusted security proxies list. The web server plug-in can then send product added private header information that, contains the virtual host information of a request. If the proxy does not trust these private headers from the web server plug-in, or from any client, the proxy server adds its own private headers, which requires the addition of proxy server HTTP and HTTPS ports to the virtual host. Typically, when a web server plug-in is used with the proxy server, the intent is to use the proxy server as a back-end server. Therefore, you must add the plug-in as a trusted security proxy to avoid having to expose the proxy server ports. “Routing requests from a plug-in to a proxy server” on page 196 provides more information about configuring a web server plug-in to use with the proxy server. “Proxy server settings” on page 140 provides more information about setting up trusted security proxies.
- **The proxy server seems to hang under stress, or Too Many Files Open exceptions display in ffdc or SystemErr.log.** Under high connection loads, the number of file system descriptors might become exhausted and the proxy server may seem to hang and drop Too Many Files Open exceptions in the ffdc directory or in the SystemError.log file because it is unable to open a socket. To alleviate this problem, modify one or more of the following parameters at the operating system level, and at the proxy server level to optimize the use of connections for the proxy server:
 - **Proxy server tuning**
 - Persistent requests - A persistent request is one that is sent over an existing TCP connection. You can maximize performance by increasing the number of requests that are received over a TCP connection from a client. The value should represent the maximum number of embedded objects, for instance GIF and so on, in a web page +1.
View or set this value in the WebSphere Application Server administrative console by clicking **Servers > Proxy Servers > server_name > Proxy server transports > HTTP_PROXY_CHAIN/HTTPS_PROXY_CHAIN**

Default value	100
---------------	-----

Recommended value	A value that represents the maximum number of embedded objects in a web page + 1.
-------------------	---

- Outbound connection pool size - The proxy server pools outbound connections to target servers and the number of connections that resides in the pool is configurable. If the connection pool is depleted or empty, the proxy server creates a new connection to the target server. Under high concurrent loads, increase the connection pool size should to a value of the expected concurrent client load to achieve optimal performance.

View or set this value in the WebSphere Application Server administrative console by clicking **Servers > Proxy Servers > server_name > HTTP Proxy Server Settings**. In the Content Server Connection section, increase the maximum connections per server field to a value that is equal to or greater than the expected maximum number of connected clients. Save your changes, synchronize the changes to the proxy server node, and restart the proxy server.

Recommended value	Value consistent to the expected concurrent client load.
-------------------	--

- Outbound request time-out - Often times, the back-end application servers that are fronted by the proxy server may be under high load and may not respond in an adequate amount of time, therefore the connections on the proxy server may be tied up from waiting for the back-end application server to respond. Alleviate this by configuring the amount of time the proxy server waits for a response from the target server. This is the Outbound Request Time-out value. By managing the amount of time the proxy server waits for a slow back-end application server, connections are freed up faster and used for other request work.

View or set this value in the administrative console by clicking **Servers > Server Types > WebSphere proxy servers > proxy_server_name > HTTP Proxy Server Settings**. In the Content Server Connection section, set Outbound Request Time-out to a value that represents the acceptable response time from the point of view of the client.

Default value	120
Recommended value	A value that represents the acceptable response time from the point of view of the client.

Troubleshooting request routing and workload management through the proxy server

This section provides information for how to troubleshoot request traffic that flows through the proxy server.

Before you begin

You will need to know the machines and nodes that will belong to the proxy server cluster, because the product needs to be installed on those machines. You will also need to know the URL for the applications, application deployment, and cluster definition details. The proxy server should be started.

About this task

You can use the proxy server MBean to determine how requests are routed to applications, and subsequently, to a particular application server. If the request is being routed incorrectly, you can disable routing to specific applications or reconfigure the routing rules.

Note: This topic references one or more of the application server log files. Beginning in WebSphere Application Server Version 8.0 you can configure the server to use the High Performance Extensible Logging (HPEL) log and trace infrastructure instead of using SystemOut.log , SystemErr.log, trace.log, and activity.log files or native z/OS logging facilities. If you are using

HPEL, you can access all of your log and trace information using the LogViewer command-line tool from your server profile bin directory. See the information about using HPEL to troubleshoot applications for more information on using HPEL.

Procedure

1. Obtain the Dynamic Route MBean for the proxy server and invoke the operation to generate routing information for the URI. Start **wsadmin** and get all of the Dynamic Route MBeans as follows:

```
$AdminControl queryNames  
type=DynamicRoute,*
```

```
set routembean <cut and paste the MBean Identifier from the previous command output>
```

```
$AdminControl invoke $routembean debugRouting {http://*/urlpattern all}
```

Use an asterisk (*) to match all of the virtual hosts, or explicitly specify a virtual host. For example, `http://proxy_name:80/urlpattern`. The **set routembean** command should correspond to the MBean from the output of the previous command.

The proxy server will start generating routing-related information for all subsequent HTTP requests that match the specified virtual host and URL pattern to the `SystemOut.log` file.

2. Send representative workload traffic through the proxy server.
3. Analyze the routing information in the proxy server `SystemOut.log` file.
4. Make required changes to application routing to enable or disable routing through the proxy server, using the administrative console, by clicking **Applications > Enterprise Applications**.
5. Repeat steps two through four until the routing of all requests are satisfied.
6. Disable gathering routing information using **wsadmin** as follows:

```
$AdminControl invoke $routembean  
stopDebugRouting
```

Results

The proxy server and the applications are correctly configured for external access.

Session Initiation Protocol overload protection

Session Initiation Protocol (SIP) overload protects the system from two overload conditions: memory overload and CPU overload. Container managed overload protection (CMOP) and proxy managed overload protection (PMOP) allow for real-time protection based on the overload settings information.

SIP container managed overload protection

In a stand-alone server deployment, SIP container managed overload protection (CMOP) provides the only defense against both memory and CPU overload conditions. An administrator can set up several static thresholds using SIP container settings. When these thresholds are exceeded, the container begins to drop new requests by responding to any requests that initiate new dialogs with a 503 response until the container is no longer overloaded. This includes settings that affect memory and CPU usage.

In an ND deployment, CMOP allows the container to use the same SIP container settings to notify the proxy server when the container is in an overloaded state. After the proxy server receives this notification, it begins to drop new requests instead of forwarding them to the containers. All memory overload conditions in ND are prevented by CMOP regardless of the configuration.

Overload protection is calculated based on the virtual memory settings and the maximum throughput that a container can handle. You can specify a value for the following SIP container settings from the administrative console for CMOP.

- Maximum application sessions

- Maximum messages per averaging period
- Maximum response time
- Maximum dispatch queue size

You can also specify a value for these SIP container custom properties for CMOP.

- `thread.message.queue.max.size`
- `weight.overload.watermark`

SIP proxy managed overload protection

SIP Proxy Managed overload protection (PMOP) is the best line of defense against container overload. In a typical deployment, CMOP alone does not provide optimal results. The following conditions might occur if CMOP is deployed without deploying PMOP at the proxy server.

- The on or off mechanism might become too granular
- Admission rates might fluctuate
- An absolute cap on load might be difficult to establish
- Unstable loads might be sent to the containers

When PMOP is deployed, the proxy server utilizes admission rate controllers for each container. When a container is overloaded, instead of either accepting or rejecting new load for a period of time, new workload can be sent to the backend containers without completely shutting down the flow of new traffic. This allows the proxy server to offer a consistent load to the containers without exceeding the maximum values for the container settings.

The SIP proxy server calculates a maximum value for message throughput to each backend container based on a percentage of the configured Maximum Messages per Averaging Period (MMAP) setting specified for the container. The maximum value for message throughput is called the Maximum Throughput Factor (MTF).

MTF is disabled by default and can only be enabled by specifying a value for the `maxThroughputFactor` custom property. The value specified for the MTF custom property should be less than 100 percent to prevent CPU overload at the container. For example, you might set this value to 90 percent.

When the value of the MTF custom property is set to less than 100 percent, the total throughput to the container should never exceed the maximum value specified for the MMAP container setting. This process protects the container from handling excessive loads when coming out of an overloaded condition.

The MTF value should always be specified when stable and accurate overload protection is required. Specifying the MTF setting provides the best results for loads that range up to twice the capacity of the system. You should consider your system capacity when configuring for overload protection.

The algorithm utilized by the SIP proxy server relies on several features to provide stable and accurate loads to the backend container.

- Per-server rate control managed at the proxy server
- Auto-adjusting, per second admission rate controller
 - Ratio of in-dialog to non-dialog averages used to control rate
 - Auto-rate reduction when in an overloaded state
- Ability to absorb fast load transitions
- Burst tolerance to allow for short occasional load burst without triggering overload
- Stabilization control to prevent excessive overload when there is a transition in the cluster

You can specify a value for the following SIP proxy server custom properties for PMOP.

- burstResetFactor
- deflatorRatio
- dropOverloadPackets
- inDialogAveragingPeriod
- maxThroughputFactor
- outDialogAveragingPeriod
- perSecondBurstFactor
- proxyTransitionPeriod
- sipProxyStartupDelay

Configuring SIP quorum support using the default core group

You can configure quorum to avoid inconsistency among Session Initiation Protocol (SIP) containers, or repeated errors from a proxy server. If quorum is enabled before a network partition occurs, the correct routing decisions can be made. A network partition can occur when a set of SIP containers are disconnected from the network and then reconnected.

Before you begin

Determine whether you want to configure the quorum feature for an entire core group, or for specific clusters within a core group. The topic *Implications of high availability group policy settings* provides additional information about quorum functionality.

About this task

All SIP containers publish a set of unique identifiers (IDs) to the SIP proxy server. Each ID represents a set of SIP sessions. The SIP proxy server is able to make the correct routing decisions based on the one-to-one mapping of these IDs to the SIP containers.

A network partition occurs whenever a network device within the topology of the cell fails. As a result, some portion, or partition, of the cell disconnects from the other portion, or partition.

gotcha: If a network partition evenly splits the cluster members, half of the cluster members are arbitrarily selected to be in the quorum. This split might cause a restart of the partition while it is still connected to clients. Therefore, you should configure your system to minimize evenly split partitions. You should create a set of three groupings: three data centers, three blade centers, and three groupings of cluster members.

Whenever network connectivity is interrupted, a backup SIP container takes ownership of all IDs that were managed by the disconnected SIP container. The backup container then publishes ownership of these IDs to the SIP proxy server so that the proxy server can make the correct routing decisions.

When the network connection for the primary container is restored, the primary container begins publishing ID ownership to the SIP proxy server to indicate that it owns the same IDs as the backup container. If the SIP proxy server has two destinations for each ID, it is impossible for the SIP proxy server to consistently make the correct routing decisions. To avoid this problem, you must configure the SIP quorum feature for your proxy servers before a network partition occurs.

The SIP quorum feature can be enabled for an entire core group, such as DefaultCoreGroup, or for specific clusters within a core group. When the quorum feature is enabled on the Default SIP Quorum core group policy for a core group, the feature is enabled for all clusters in the core group. If the SIP quorum feature is only enabled for some of the clusters in a core group, then you must modify the default policy, and create a duplicate core group policy setting to enable quorum support for those clusters.

You must enable the Default SIP Quorum core group policy, or configure a duplicate core group policy with quorum enabled for each core group that requires quorum support. The purpose of the high availability group that uses the core group policy is to track quorum between the SIP containers, or SIP proxy servers, in a cluster.

Complete these steps to configure the quorum feature using an additional SIP quorum core group policy.

Note: Only one cluster name can be applied to a policy. Repeat this procedure for each cluster that requires the SIP quorum feature to create a new policy with the appropriate match criteria. Each SIP quorum policy should have at the most three match criteria.

Procedure

1. In the administrative console, click **Servers > Core Groups > Core group settings > *core_group_name***.
2. Click **Policies > New**.
3. Select **All active policy**, and then click **Next**.
4. Specify a unique name for the policy in the **Name** field, and then enter a description in the **Description** field.
5. Select **Quorum**, and then click **OK**. You will receive a warning message that indicates that you must define at least one match criteria for this policy.
6. In the Additional Properties section, click **Match criteria > New**.
7. Specify *policy* in the **Name** field, and `AllActiveQuorumPolicy` in the **Value** field. Both of these fields are case sensitive, and both values must be entered as shown in this step.
8. Click **Apply**.
9. Click the name of your policy in the navigation breadcrumb on this administrative console page, and then, in the Additional Properties section, click **Match criteria > New** again.
10. This time, specify *type* in the **Name** field, and `SIP_QUORUM` in the **Value** field. As previously mentioned, both of these fields are case sensitive, and both values must be entered as shown in this step.
11. Click **Apply**.
12. Perform the following actions if you only want this new policy to apply to a specific cluster within the core group. Skip this step if you want this new policy to apply for the entire core group.
 - a. Click the name of your policy in the navigation breadcrumb on this administrative console page, and then, in the Additional Properties section, click **Match criteria > New** again.
 - b. This time, specify `IBM_hc` in the **Name** field, and the name of a cluster, to which you want to apply this policy, in the **Value** field. Both of these fields are case sensitive. Therefore, make sure that you enter the cluster name exactly as it is defined in the core group.
 - c. Click **Apply**.
13. Click **Save** to save your configuration changes.
14. Restart the affected servers.

If the new SIP quorum core group policy applies to the entire core group, you must restart every server that is part of that core group.

If the new SIP quorum core group policy only applies to a specific cluster within the core group, you must restart all of the members of that cluster.
15. Repeat these steps if you are only enabling SIP quorum for specific clusters in the core group.

Only one cluster name can be associated with a policy. If you have multiple clusters in this core group, for which you want to enable SIP quorum, but you are not enabling SIP quorum for the entire core group, you must create an entirely new policy for each cluster for which you are enabling SIP quorum. For each new policy, you must specify the three match criterias `type=SIP_QUORUM`, `policy=AllActiveQuorumPolicy`, and `IBM_hc=cluster_name`.

Results

The majority of the members that are included in a SIP container or a proxy server cluster must be started before quorum is achieved. The members of a proxy server cluster do not start to listen for SIP requests until quorum is achieved.

When a SIP proxy server is disconnected from the network, a SIP proxy server in the minority partition of the cell continues to handle SIP requests. The minority partition of a cell is the partition that has connectivity to the fewest cluster members.

When a SIP container is disconnected from the network, the SIP container in the minority partition is automatically restarted to clear all information about the logical partitions that were previously managed. The SIP containers in the majority partition take ownership of the logical partitions from the disconnected SIP container and publish these IDs to the SIP proxy servers.

Configuring the SIP proxy for network outage detection

When SIP traffic and the high availability (HA) manager traffic are not on the same network, failures that affect SIP traffic might not be detected by the HA manager, resulting in loss of SIP traffic. You can configure network outage detection on the same network as the SIP traffic to ensure that failures that affect SIP traffic can be detected by the HA manager.

About this task

Define these settings for network outage detection to ensure that SIP network failures are detected by the HA manager.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > *proxy_server_name* > SIP proxy settings**. Scroll to the SIP network outage detection settings on this page.
2. Select **Enable SIP network outage detection** and enter the **Keep alive** interval. The proxy will send keep alive messages to the server at the configured keep alive interval.
3. Specify the **Maximum keep alive failures** to send before a server failure response is sent.
4. Optional: Set the `numFailuresSipAdvisorRequests` custom property so that the SIP proxy notices the failure to receive load balancer advisor requests.

Results

If the proxy misses the number of responses configured as `keepAliveFailures`, or the server misses that number of keep alive requests, it will determine that SIP traffic should no longer be sent between the proxy and the server. The proxy will stop sending SIP messages to that server, and the server will restart and wait for connectivity to be restored before resuming operation.

Administering proxy actions

You can create new proxy actions or you can administer an existing proxy action. A proxy server action is an event that is performed when an HTTP request or an HTTP response is received by the a proxy virtual host. Some examples of proxy server actions include caching actions, rewriting actions, compression actions, header modification actions, and routing actions.

Before you begin

A proxy action cannot be performed unless it is associated with a proxy rule expression. A proxy rule expression is only evaluated when it is associated with a proxy virtual host. A proxy action can be created

or administered without a proxy rule expression or a proxy virtual host, but it cannot be used without them.

About this task

Proxy actions are associated with proxy rule expressions. If a proxy rule expression evaluates to true, then all of the proxy actions specified in the proxy rule expression configuration are performed. Complete these steps to create a new proxy action or to administer an existing proxy action for the proxy server.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions**.
2. Optional: Manage an existing proxy action configuration.
 - a. Click *proxy_action_name* if you want to view or modify the settings for an existing proxy action. If you have made changes to the proxy action configuration, click **OK** to save the changes.
 - b. Click **Delete** to remove an existing proxy action that has been selected.
3. If you want to create a caching proxy action, then click **New Caching Action**.
 - a. Enter the name of the proxy action in the Action name field. The Action name is used as the unique identifier for this proxy action configuration. The Action name must be unique with the cell and cannot include any of the following characters: # \ / , ; ; " * ? < > | = + & % '.
 - b. Select the **Enable caching** check box to enable caching.
 - c. Enter the value in seconds for the **Default expiration** field. The Default expiration field specifies the amount of time, in seconds, before a cached response expires.
 - d. Enter the value in seconds for the **Last modified** factor. The Last modified factor field specifies the amount of time before a response is cached if the response does not have explicit HTTP expiration headers.
 - e. Click **OK** to save the proxy action configuration.
4. If you want to create a compression action, then click **New HTTP Request Compression Action** to create an action for requests, or click **New HTTP Response Compression Action** to create an action for responses.
 - a. Enter the name of the proxy action in the **Action name** field. The Action name is used as the unique identifier for this proxy action configuration. The Action name must be unique with the cell and cannot include any of the following characters: # \ / , ; ; " * ? < > | = + & % '.
 - b. Select the appropriate compression type from the Compression type menu.
 - c. Select the content type for which compression should occur. You can select multiple content types to be compressed. Click **New** to add a new content type to the list. If you want to remove a content type from the list, then select the content type to be removed, then click **Delete**.
 - d. Click **OK** to save the proxy action configuration.
5. If you want to create a header action, click **New HTTP Request Header Action** to create an action for requests, or click **New HTTP Response Header Action** to create an action for responses.
 - a. Enter the name of the proxy action in the **Action name** field. The Action name is used as the unique identifier for this proxy action configuration. The Action name must be unique with the cell and cannot include any of the following characters: # \ / , ; ; " * ? < > | = + & % '.
 - b. Enter the name of the HTTP header to be modified in the **Header name** field.
 - c. Select the appropriate action from the **Header modify action** menu. The available header modify actions include:
 - Set
 - Append
 - Edit
 - Remove
 - d. Enter the value to be used for the Header modify action in the **Header value** field.

- e. Enter an expression to be performed on the header value in the **Header value expression** field. The Header value expression is evaluated and the modify action is performed if the evaluation returned a match.
 - f. If you are creating a HTTP Request Header action, then select the appropriate methods for the Header modify action being performed. You can select multiple methods. Click **New** to add a new method to the list. If you want to remove a method from the list, then select the method to be removed and click **Delete**.
 - g. If you are creating a HTTP Response Header action, then select the appropriate status codes for the Header modify action being performed. You can select multiple status codes to be included. Click **New** to add a new status code to the list. If you want to remove a status code from the list, select the status code to be removed and click **Delete**.
 - h. Click **OK** to save the proxy action configuration.
6. If you want to create a rewriting action proxy action, then click **New Rewriting Action**.
- a. Enter the name of the proxy action in the **Action name** field. The Action name is used as the unique identifier for this proxy action configuration. The Action name must be unique with the cell and cannot include any of the following characters: # \ / , ; " * ? < > | = + & % '.
 - b. Select the type of rewriting action to be performed in the Rewriting action types menu. The following elements can be rewritten using this type of proxy action:
 - Absolute URL response
 - Redirect location header
 - Redirect status code
 - Relative URL response
 - Set cookie domain
 - Set cookie path
 - c. Enter the subject URL pattern to be rewritten in the **From pattern** field.
 - d. Enter the resulting URL pattern after the rewrite has occurred in the **To pattern** field.
 - e. Optional: Select **Enable passive rewrite** to defer the rewriting of the URI until the subsequent request for that URI is sent by the client.
 - f. Optional: In the **Cookie name** field, enter the name of the cookie for which the domain or the path are to be rewritten. This field is only valid for the Set-Cookie type of rewriting actions.
 - g. Optional: In the **Limit URL pattern** field, specify a constraint on the URL patterns to rewrite in the response message. Limiting the URL pattern prevents the proxy server from rewriting all URL patterns in the response message of a certain page. This field is only valid for the absolute URL response action type or the relative URL response action type.
 - h. Optional: In the **Limit Cookie domain** field, specify a constraint to limit the rewriting of the cookie domain to only a set of specified domains. If no domains are specified, then all domains are rewritten. This field is only valid for the Set-Cookie type of rewriting action.
 - i. Optional: In the **Limit Cookie path** field, specify a constraint to limit the rewriting of the cookie path to only a set of specified paths. If no paths are specified, then all the paths are rewritten. This field is only valid for the Set-Cookie type of rewriting action.
 - j. Click **OK** to save the proxy action configuration.
7. If you want to create a routing proxy action, then click one of the following: **New Application Server Route**, **New Generic Server Cluster Route**, **New Fail Route**, **New Redirect Route**, or **New Local Route**.
- a. Enter the name of the proxy action in the **Action name** field. The Action name is used as the unique identifier for this proxy action configuration. The Action name must be unique with the cell and cannot include any of the following characters: # \ / , ; " * ? < > | = + & % '.
 - b. If you are creating a new application server route, then follow these additional steps:

- 1) Enter the beginning time for this routing rule in the **Start time** field. If the start time is specified using a 12-hour clock, then click **AM** or **PM**. If the start time is specified using a 24-hour clock, then click **24-hour**.
 - 2) Enter the finishing time for this routing rule in the **End time** field. If the end time is specified using a 12-hour clock, then click **AM** or **PM**. If the end time is specified using a 24-hour clock, then click **24-hour**.
 - 3) Select **Include** or **Exclude** from the Action menu to specify the type of rule being configured.
 - 4) Select the applications servers that will follow this rule from the Available application servers menu.
 - 5) Click **>**.
 - 6) If you want to remove an application server from the Enabled application servers menu, then select that server from the Enabled application servers menu and click **<**.
- c. If you are creating a new generic server cluster route, then follow these additional steps:
- 1) Select the Generic server cluster that will follow this rule from the **Generic server cluster name** menu.
 - 2) Select either **Active Affinity** or **Passive Affinity** for the affinity type.
 - 3) If you selected Active Affinity, then in the **Default expiration** field, enter the expiration time in seconds.
 - 4) If you selected Passive Affinity, then in the **Cookie name** field, enter the name of the cookie to be used by the proxy server to manage affinity.
 - 5) If you selected Passive Affinity, then select the generic server mappings for which this cookie will be used to manage affinity. If you need to create any additional mappings, click **New**. If you need to remove existing cookie mappings, select the appropriate mapping and click **Delete**.
 - 6) Click **New Time Mapping**.
 - 7) Enter the beginning time for this routing rule in the **Start time** field. If this rule should be applied all the time, then selected **24-hour**.
 - 8) Enter the finishing time for this routing rule in the **End time** field. If this rule should be applied all the time, then selected **24-hour**.
 - 9) Select **Include** or **Exclude** from the Action menu to specify the type of rule being configured.
 - 10) Select the cluster members that will follow this rule from the Available generic server cluster members menu.
 - 11) Click **>**.
 - 12) If you want to remove cluster member from the Enabled generic server cluster members menu, then selected that cluster member from the Enabled generic server cluster members menu and click **<**.
 - 13) Click **OK** to return to set the time-of-day rules and continue creating your generic server cluster route configuration.
- d. If you are creating a failure route, follow this additional step: In the **Fail status code** field, Enter the status code that must be used to indicate a request was not successful.
- e. If you are creating a redirection route, follow this additional step: In the **Redirect URL** field, enter the URL that must be used to redirect the inbound request.
- f. If you are creating a local route, follow this additional step: Confirm that the static file document root is correct. If the value that is listed is not the document root that you want, click **Edit**. See “Administering proxy virtual hosts” on page 247 for more information on changing the static file document root.
8. Click **OK** to finish creating your proxy action rule.

Proxy server actions

Proxy server actions are used in association with proxy rule expressions. If a proxy rule expression evaluates to true, then all the proxy actions associated with the rule expression are performed. Some examples of proxy server actions include caching actions, rewriting actions, compression actions, header modification actions, and routing actions.

Caching actions

Caching actions are set to determine whether a response is cached. A caching action specifies the last modified factor and the default expiration to define how a response is cached.

Rewriting actions

Rewriting actions define how the proxy server rewrites uniform resource locators (URL). A rewriting action is used to rewrite elements of a response message. This is often done to mask the back-end server identity with that of the proxy server. The follow elements can be rewritten using this type of proxy action:

- Absolute URL response
- Redirect location header
- Redirect status code
- Relative URL response
- Set-Cookie

Compression actions

HTTP Compression actions are set to compress the request message body to the server or response message body to the client. The supported compression type standards for these proxy actions are Deflate and Gzip.

Header modification actions

Header modification actions are implemented to perform a header modify action on a specified HTTP header. The available header modify actions include:

- Set
- Append
- Edit
- Remove

The header modify action is performed only if the expression matches when the specified value is applied. For HTTP requests, the header modify action is performed on the HTTP methods you specify. For HTTP responses, the header modify action is performed on the HTTP status codes you specify.

Routing actions

Routing actions are used to route requests when a given rule expression is matched. The following types of routing actions are available:

- Application server routes

Application server routing actions allow you to specify time of day mappings for your application servers. These mappings include or exclude an application server for the routing of requests during a specified time of day. If multiple time of day mappings are configured, the order they are matched is the same as they appear in the application server route configuration.

- Generic server cluster routes

Generic server cluster routing actions work similar to application server routes but apply to generic server clusters instead of application servers.

- **Fail routes**

Fail routing actions are used to return a failure status code to an inbound request. The value of the failure status code is specified in the fail routing action configuration.

- **Redirect routes**

Redirect routing actions are used to redirect an inbound request to a different URL. The URL the request is being redirected to is specified in the redirection routing action configuration.

- **Local routes**

Local routing actions are used to pass an inbound request to be served by the local web applications deployed for the cell.

Proxy actions collection

Use this page to administer actions for the proxy server. Proxy actions include creating, modifying, or deleting rules that affect caching, compression, headers, rewriting, and routing for the proxy server. The Proxy actions collection panel allows you to configure proxy actions from one interface.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions**.

Caching actions

The Caching actions table contains the following fields. Caching actions are set to determine whether a response is cached.

Action name

Specifies the name of the caching action. A proxy action name must be unique within a cell and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Enable caching

Specifies to enable or disable caching.

Default expiration

Specifies the default expiration, in seconds, that is used to determine the validity of cached responses for the URI that is associated with the cache rule.

Last modified factor

Specifies the period of time since the last modification.

Compression actions

Compression actions are set to compress the request message to the server or response message to the client. The Compression actions table contains the following fields.

Action name

Specifies the name of the compression action. A proxy action name must be unique within a cell and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Compression action type

Specifies whether the action type is a request or a response compression action.

Compression type

Specifies the compression type standard to apply to the outbound request sent to the target server or the compression type standard to apply to the response sent to the client.

Header actions

Header actions allow you to add, modify, or delete request and response headers. The Header actions table contains the following fields.

Action name

Specifies the name of the header action. A proxy action name must be unique within a cell and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Header action type

Specifies whether the action type is a request or a response header action.

Header modify action

Specifies the action to be taken on a request or response header, such as set, append, edit, or remove.

Header name

Specifies the header name to be sent in the request.

Header value

Specifies a user-defined value for a request or response header.

Rewriting actions

A rewrite action can modify inbound requests handled by the proxy server. Rewriting actions define how the proxy server rewrites the URL of a response message; for example, to mask the back-end server identity with that of the proxy server. The Rewriting actions table contains the following fields.

Action name

Specifies the name of the rewriting action. A proxy action name must be unique within a cell and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Rewriting action type

Specifies a rewriting action type from a predefined list. See the following table for details.

Rewriting action type	Description
Absolute URL response	Rewrites an absolute URL from matching attributes in a response.
Redirect location header	Rewrites the URL in the relocation header in the HTTP response.
Redirect status code	Specifies the redirect status code in the first line of a response message.
Relative URL response	Rewrites a relative URL in tag attributes a response.
Set cookie domain	Rewrites the domain attribute of the set cookie header.
Set cookie path	Rewrites the path attribute of the set cookie header.

From pattern

Specifies the original URL pattern in the 302 response header from the target server. The pattern can include the asterisk (*) as a wild card symbol. A URL pattern can have one or more asterisks.

To pattern

Specifies the resulting pattern after the rewrite. The pattern can include the asterisk (*) as a wild card symbol. A URL pattern can have one or more asterisks.

Routing action

Routing actions define routes to local file system resources for static file serving. The Routing actions table contains the following fields.

Action name

Specifies the name of the routing action. A proxy action name must be unique within a cell and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Routing type

Specifies a routing type from a predefined list: Application server route, Generic server route, Fail route, Redirect route, and Local route.

Note: For more detailed configuration information, see the individual proxy action settings topics.

Caching action settings

You can configure caching action settings for a proxy server. Caching actions are set to determine whether a response is cached. A caching action specifies the last modified factor and the default expiration to define how a response is cached.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions > action_name**.

Name

Specifies a user-defined symbolic name for a caching action.

A caching action name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Enable caching

Specifies whether or not to enable caching for the proxy server.

You must enable caching before you can provide a value for Default expiration or Last modified factor. If a value is specified for Last modified factor, then the value for Default expiration is not used.

gotcha: If caching is disabled, the proxy server does not cache the uniform resource identifier (URI) that is associated with the proxy rule expression. For example, if a request comes in and it matches the rule expression for a proxy virtual host, then the actions associated with the rule expression, including the caching action, are executed. The rule expression may or may not include an explicit URI or URIgroup. If a request matches a rule expression with an action of caching disabled, the proxy server does not cache the response for that request.

Default expiration

Specifies the amount of time, in seconds, before a cached response expires. The default expiration determines the validity of cached responses for the URI that is associated with the cache rule.

Last modified factor

Specifies the amount of time, in seconds, before a response is cached if the response does not have explicit HTTP expiration headers. The last modified time header must be specified in the response. The value is determined based on when an HTML file was last changed to prevent caching frequently modified files for long periods of time.

HTTP compression action settings

You can configure settings for an HTTP request compression action or an HTTP response compression action for a proxy server. Compression actions are set to compress the request message to the server or response message to the client.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions > action_name**.

Name

Specifies a user-defined symbolic name for an HTTP compression action.

An HTTP compression action name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Compression type

For requests, a compression type specifies the compression type standard to apply to the outbound request body sent to the target server. For responses, compression type specifies the compression type standard to apply to the response body sent to the client.

The following standards are supported: Gzip and Deflate. If you specify Any, either standard can be used.

Gzip

Deflate

Any

Content types

Specifies the content types for which compression is applied.

HTTP header action settings

You can configure settings for an HTTP request header action or an HTTP response header action for a proxy server. Use header modification actions to add, modify, or delete request and response headers.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions**.

Action name

Specifies a user-defined symbolic name for an HTTP header action.

An HTTP header action name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Header name

Specifies the name of the HTTP header to set, append, edit, or remove from a request header or a response header.

Header modify action

Specifies the action to be taken on a request or response header, such as set, append, edit, or remove.

Table 14. Header actions.

This table lists the types of header modification actions.

Types of actions	Description
Set	Adds a new value for a request or response header. If a value does not exist, this value is added. If a value does exist, this value replaces the current value.
Append	Adds a value to the current value for a request or response header. If a value does not exist for the header, then this value is added. If a value does exist for the header, then this value is added to the end of the current value.
Edit	Changes the current value to a different value for a request or response header. If a value exists for the header, then this value is changed equivalent to a regular expression search and replace.

Table 14. Header actions (continued).

This table lists the types of header modification actions.

Types of actions	Description
Remove	Removes the specified header. If the header exists, then the header is removed. If the header does not exist, then no action is taken.

Header value

Specifies a user-defined value for a request or response header.

Header value expression

Specifies a regular expression applied to the value of the Header name field. If a match exists, then the value specified for the header value field replaces the current value of the header name field.

Method names (HTTP header request action)

Specifies the HTTP method to which the action applies, such as GET or POST. If a value is not specified, then the action is applied for all method names.

Method names apply to HTTP header request actions only.

Status codes (HTTP header response action)

Specifies the return status codes to which the action applies, such as 200 or 503. If a value is not specified, then the action is applied for all status codes.

Status codes apply to HTTP header response actions only.

Rewrite action settings

You can configure settings to implement a rewrite action for outbound responses handled by the proxy server. Rewriting actions define how the proxy server rewrites elements of the uniform resource locators, such as URLs in an HTML page or the redirect link in the response. Rewrite actions are often done to mask the back-end server identity with that of the proxy server.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions > action_name**.

Action name

Specifies a user-defined symbolic name for a rewriting action.

A rewriting action name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Rewriting action type

Specifies the type of rewriting action to perform. You can specify the following rewriting action types: Absolute URL response, Redirect location header, Redirect status code, Relative URL response, Set-Cookie.

Table 15. Rewriting action types.

This table lists the rewriting action types.

Action type	Description
Absolute URL response	<p>Rewrites the absolute URI in the tag attribute in the HTTP response. The proxy server scans the response for an attribute matching the From pattern. If a match of the From pattern occurs, then the proxy rewrites the response based on the To pattern. For example:</p> <pre>frPattern = '/(.*)' toPattern = '/prefix/\$1'</pre> <p>The tag <code></code> is changed to <code></code>.</p>
Redirect location header	<p>Rewrites the URI in the relocation header in the HTTP response. For example:</p> <pre>fromPattern = 'http:(.*)' toPattern = 'https:\$1'</pre> <p>The location header: "Location: http://www.ibm.com" is changed to "Location: https://www.ibm.com."</p>
Redirect status code	<p>Specifies the redirect status code in the first line of a response message, such as 301 or 302.</p>
Relative URL response	<p>Rewrites an Relative URL in tag attributes a response. The proxy server scans the response for an attribute matching the From pattern. If a match of the From pattern occurs, then the proxy will rewrite the response based on the To pattern. For example:</p> <pre>fromPattern = '/(.*)' toPattern = '/prefix/\$1'</pre> <p>The tag <code></code> is changed to <code></code>.</p>
Relative URL response:Passive	<p>Instead of rewriting the response directly, the proxy server will inject a cookie in the response header. For example: If a request for <code>"myimages/1.jpg"</code> is resent from the browser with the cookie, then the proxy server will recreate the request URI as <code>"prefix/myimages/1.jpg"</code>. This feature requires a browser that supports cookies and for each session, only one passive rule can be defined.</p>
Set-Cookie_Domain	<p>Rewrites the domain attribute of the set cookie header. For example:</p> <pre>fromPattern = '(.*)' toPattern = '\$1.cn'</pre> <p>The set cookie header: "Set-Cookie: JSESSIONID: abcdefg; domain="www.ibm.com"" is changed to be "Set-Cookie: JSESSIONID: abcdefg; domain="www.ibm.com.cn""</p>

Table 15. Rewriting action types (continued).

This table lists the rewriting action types.

Action type	Description
Set-Cookie_Path	<p>Rewrites the path attribute of the set cookie header. For example:</p> <pre>frPattern = '(.*)' toPattern = '/prefix\$1'</pre> <p>The set cookie header: "Set-Cookie: JSESSIONID: abcdefg; domain="www.ibm.com"; path=/" is changed to "Set-Cookie: JSESSIONID: abcdefg; domain="www.ibm.com"; path="/prefix/".</p>

From pattern

Specifies the original URL pattern in the response from the target server. The pattern can include the following wild card symbol: * . A URL pattern can have one or more asterisks (*).

To pattern

Specifies the resulting pattern after the rewrite. The pattern can include the following wild card symbol: * . A URL pattern can have one or more asterisks (*).

Enable passive rewrite

Specifies whether or not to defer the rewriting of the URI until the subsequent request for that URI is sent by the client. Enabling passive rewrite prevents the proxy server from rewriting all the links in the response before sending the response back to the client.

Cookie name

Specifies the cookie for which path or domain attributes are rewritten. This setting is only valid when the action type is Set-Cookie path or Set-Cookie domain.

Limit URL pattern

Specifies to match a request URL to rewrite in the response message. Limiting the URL pattern prevents the proxy server from rewriting all URL patterns in the response message of a certain page, allowing the proxy server to skip parsing responses for other pages if there are multiple pages. This setting is only valid when the action type is absolute URL response or relative URL response.

Limit cookie domain

Specifies a constraint to limit the rewriting of the cookie domain to only a set of specified domains. If no domains are specified, then all domains are rewritten. This field is only valid when the rewriting action type specified is Set cookie domain.

Limit cookie path

Specifies a constraint which limits rewriting the cookie path to the specified paths. If no paths are specified, then all paths are rewritten. This field is only valid when the rewriting action type specified is Set cookie path.

Route action settings

You can configure settings for a route action for a proxy server. Add a route action to define routes to local file system resources for static file serving.

This topic is for local route actions, fail route actions, redirect route actions, and application server route actions. Some settings only apply to a specific type of route action. See the topic about generic server route actions for information about generic server route actions.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions > action_name**.

Action name

Specifies a user-defined symbolic name for a route action.

A route action name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Static file document root: /home/action1 (local route action)

Specifies the root directory on the file system where static files are located. Click **Edit** to access the Proxy Settings page to set the static file document root for a proxy server or an individual proxy server virtual host.

Static file document root applies to local route actions only.

Fail status code (fail route action)

Specifies the HTTP status code to send to the client indicating that the request failed. Possible values are integers with a value greater than zero.

Fail status code applies to fail route actions only.

Redirect URL (redirect route action)

Specifies the URL to send to the client in a 302 redirect response.

Redirect URL applies to redirect route actions only.

Time of day rules (application server and generic server cluster routes)

Specifies a time rule, which is typically used to configure a maintenance window. You can specify a start time and an end time to include or exclude routing to a particular cluster member.

Click **New Time Mapping** to access the Time Mapping settings page to specify a time interval for the time mapping. You can create, delete, or edit time mappings.

Table 16. Time mapping settings.

This table lists the time mapping settings.

Setting	Description
Time	Specifies the start time and end time for the time mapping.
Action	If the action is set to include, then the server routes actions to the cluster members specified in the time mapping. If the action is set to exclude, the server does not route actions to the specified cluster members during this time interval.

Generic server cluster route action settings

You can configure a generic server cluster route action for a proxy server. Add a generic server cluster route action to define routes for inbound requests to specific generic server clusters.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions > action_name**.

Action name

Specifies a user-defined symbolic name for a generic server cluster route action.

A generic server cluster route action name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Generic server cluster name

Specifies the generic server cluster name provided when the generic server cluster was created. This is a user-defined field. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

The name specified must be unique among generic server clusters and cannot begin with a period or a space. A space does not generate an error, but leading and trailing spaces are automatically deleted.

Active affinity

Specifies whether the proxy server manages the application affinity to the target generic server. Active affinity is used when a generic server application cannot manage active affinity.

A cookie is used to maintain affinity and ensure that a request is returned to the correct server within the configured time. The Default expiration field specifies the amount of time, in seconds, that the active affinity set by the proxy server is valid. The cookie is automatically set to expire 24 hours after the affinity is no longer valid.

Passive affinity

Specifies whether the proxy server maintains application affinity based on a specified cookie that is set by the target generic server. Passive affinity is used when a generic server sets an affinity cookie that the proxy can use to manage affinity to a generic server.

The administrator specifies a cookie name and then maps the cookie values to each generic server.

Cookie name

Specifies the cookie that is sent by the server and used by the proxy to determine affinity.

Cookie mapping

Specifies the cookie settings to use for a particular generic server.

Table 17. Cookie mapping settings. This table lists the cookie mapping settings to use for a particular generic server.

Action type	Description
Cookie value	Specifies the value for the cookie that is set by the server. The cookie value is mapped to the server defined by the host and port.
Host	Specifies the host name for the target server.
Port	Specifies the port for the target server.

Time of day rules

Specifies a time rule, which is typically used to configure a maintenance window, for generic server cluster routes. You can specify a start time and an end time to include or exclude routing to a particular cluster member.

Click **New Time Mapping** to access the settings page to specify a time interval for the time mapping. You can create, delete, or edit time mappings.

Table 18. Time mapping settings. This table lists the time of day rules mapping settings to use for a particular generic server.

Setting	Description
Time	Specifies the start time and end time for the time mapping.

Table 18. Time mapping settings (continued). This table lists the time of day rules mapping settings to use for a particular generic server.

Setting	Description
Action	If the action is set to include, then the server routes actions to the cluster members specified in the time mapping. If the action is set to exclude, the server does not route actions to the specified cluster members during this time interval.

Time mapping settings

You can configure time mapping settings for the proxy server that set routing rules to be in effect during specific time intervals. These settings can be specified for application server members or for generic server cluster members.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy actions > routing_action_name > time_mapping**.

Note: Select **Proxy Virtual Host Configuration** under Proxy Actions and create a new routing action name if you have not already configured one.

With the time mapping panel, you can make specific servers active or inactive during specified time intervals.

Start time

Specifies the start time, in hours and minutes, for when the routing action being created is valid. The time entered for this field uses a 24-hour clock.

End time

Specifies the end time, in hours and minutes, for when the routing action being created is no longer valid. The time entered for this field uses a 24-hour clock.

Action

Specifies to include or exclude the application server or generic server cluster members when a routing request is sent during the specified Start time and End time.

Include

Specifies the servers to include in routing decisions during the specified time period.

Exclude

Specifies the servers to exclude from routing decisions during the specified time period.

Application server members

Specifies the available application servers that can use the specified time mappings. You can add or remove application servers. The servers listed in the Enabled list are included or excluded from routing requests as selected.

Note: This field only displays if you configured an application server member.

Generic server cluster members

Specifies the available generic server clusters that can use the specified time mappings. You can add or remove generic cluster members. The servers listed in the Enabled list are included or excluded from routing requests as selected.

Note: This field only displays if you configured a generic server cluster member.

Administering custom advisors for the proxy server

You can administer custom advisors for the proxy server. Custom advisors allow for more specific determination of target application server availability by sending protocol level requests to back-end servers. Custom advisors are unique based on the combination of the business level application ID and the composition unit ID.

About this task

Complete these steps to administer actions for the proxy server.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisor policies**.
2. Click the name of a custom advisor to change settings.
3. Specify the business level application ID.
4. Specify the composition unit ID.
5. Specify the poll interval using seconds in the Poll interval field..
6. Specify the connection timeout using seconds in the Connect timeout field.
7. Specify the input/output timeout using seconds in the I/O timeout field.
8. Optional: Select **Enable logging** if you would like to use logging for this custom advisor. If you enable logging, then follow these steps:
 - a. Select **Enable log file wrapping** if you would like wrapping turned on.
 - b. Specify the maximum size of the log file using megabytes in the Log file size field.
9. Create mappings to be used by your custom advisor using one of the following sub-steps:
 - a. "Configuring stand-alone application server mappings" on page 242
 - b. "Configuring application server cluster mappings" on page 243
 - c. "Configuring generic server cluster mappings" on page 245
10. Optional: Click **Delete** to remove a selected mapping from the collection.

Custom advisor policies

Custom advisor policies help to determine target application server availability. Custom advisors are Java code modules that work within the proxy server to provide information about the application's availability to the proxy server selection code.

Custom advisor policies provide a mechanism to interpret an application protocol response message to determine if an application server, a cluster, or a generic server cluster should be used by the proxy server when requests are made. A custom advisor is able to verify that the application is available, functioning properly, and has access to all required resources.

The proxy server periodically performs an advisor cycle. During an advisor cycle it will call the `isUsable()` method defined on the custom advisor for each available application server, cluster, and generic server cluster targeted by that custom advisor. The `isUsable()` method passes an `AdvisableServer` object, which is used to determine the address, port, and protocol for the targeted application servers, clusters, and generic server clusters.

The custom advisor sends a request to the targets and if communication is successful, then receives their responses. Using the responses, the custom advisor determines if the target is usable or is not usable. If the target is not usable, then the target will be marked as unavailable and will not be used for selection. A target that is marked as unavailable will not be used for selection for this application again, until it is determined to be available by a future advisor cycle. If the target is determined to be usable, a value of `true` is returned, and the target will continue to be used for selection.

Custom advisors collection

Use this page to administer custom adviser policies. With custom advisors, you can determine the availability of a specific target application server by sending protocol level requests to back-end servers. Custom advisor policies are unique based on the combination of the business-level application ID and the composition unit ID.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisor policies**.

Business-level application ID

Specifies a unique identifier for a business level application. A business level application is a configuration that is stored in the product configuration repository.

Composition unit ID

Specifies a unique identifier for a composition unit. A composition unit is a registered custom adviser asset that has additional configuration information, which you specified when adding the asset to the application.

Custom advisor policy settings

You can configure settings for a custom advisor policy. Custom advisor policies allow for more specific determination of target application server availability by sending protocol level requests to back-end servers. Custom advisor policies are unique based on the combination of the business-level application ID and the composition unit ID.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisor policies > bla_id**.

Business-level application ID

Specifies a unique identifier for a business level application. A business-level application is a configuration that is stored in the product configuration repository.

Composition unit ID

Specifies a unique identifier for a composition unit. A composition unit is a registered custom adviser asset that has additional configuration information, which you specified when adding the asset to the application.

Poll interval

Specifies the amount of time, in seconds, between requests for custom advisors.

Connect timeout

Specifies the amount of time, in seconds, to wait before a connection attempt fails.

I/O timeout

Specifies the amount of time, in seconds, for a custom advisor to wait before read and write operations succeed. If the timeout is reached, then the server stops.

Enable logging

Specifies whether or not logging is enabled. By default, the check box is cleared.

If logging is enabled, then the proxy server logs error messages to a log file. If logging is not enabled, log messages are not added to a log file.

Enable log file wrapping

Specifies whether information at the beginning of the log file is overwritten when the maximum log file size is reached. The default value is True.

Log file size

Specifies the size, in megabytes, of the log file.

Custom advisor mappings

Specifies the application servers, application server clusters, or generic server clusters the custom advisor monitors.

Click **New custom advisor mapping** to access the Custom advisor settings page to create a new custom advisor mapping for a custom advisor.

Configuring stand-alone application server mappings

You can configure a stand-alone application server mapping. Stand-alone application server mappings specify that a stand-alone application server is mapped to a custom advisor.

Before you begin

Stand-alone application server mappings cannot be configured until a proxy server has been configured and a custom advisor has been deployed.

About this task

Complete these steps to configure a stand-alone application server mapping.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisors policies > custom_advisor_namestandalone_application_server_mapping_name**.
2. Click **New Stand-alone Application Server Mapping** to begin configuring a new stand-alone application server mapping.
3. In the Cell name menu, select the cell where the server is located that the custom advisor will monitor.
4. In the Node name menu, select the node where the server is located that the custom advisor will monitor. Only the nodes contained within the cell you selected will be available in the Node name menu.
5. In the Server name menu, select the server the custom advisor will monitor. Only the server located on the node you selected will be available in the Server name menu.
6. Specify the application to be monitored. Only the applications deployed on the server you selected will be available in the Application name menu.
7. From the menu, choose a transport chain.
8. Click **OK**.

Stand-alone application server cluster mapping settings

You can configure settings for a stand-alone application server cluster mapping. Stand-alone application server cluster mappings are specified only for a stand-alone application server cluster custom advisor.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisors > custom_advisor_name > standalone_application_server_cluster_mapping**.

Cell name:

Specifies a logical name for the cell.

A cell name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % ' .

Node name:

Specifies the name of the node. A node is a logical grouping of managed servers.

A node name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Server name:

Specifies the display name for the server.

A server name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Application name:

Specifies the name of the application.

An application name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Transport chain:

A transport chain consists of one or more types of channels, each of which supports a different type of I/O protocol, such as TCP, HTTP, or DCS.

Transport chains enable communication through transport channels, or protocol stacks, which are usually socket based.

Configuring application server cluster mappings

You can configure an application server cluster mapping to specify which application server clusters a custom advisor will monitor.

Before you begin

Application server cluster mappings cannot be configured until a proxy server has been configured and a custom advisor has been deployed.

About this task

Complete these steps to configure an application server cluster mapping.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisors policies > custom_advisor_nameapplication_server_cluster_mapping_name**.
2. Optional: Click **New Application Server Cluster Mapping** to begin configuring a new application server cluster mapping.
3. In the Cell name menu, select the cell of the server that the custom advisor will monitor.
4. In the Cluster name menu, select the cluster of the server that the custom advisor will monitor. Only the available clusters within the cell you selected are available in the Cluster name menu.
5. Specify the application to be monitored. Only the applications that are deployed on the cluster you selected are available in the Application name menu.
6. From the menu, choose a transport chain.
7. Select the cluster members that the custom advisor will monitor from the Available application server cluster members menu.

8. Click > to add the selected cluster members to be monitored by the custom advisor.
9. Optional: If you want to remove a cluster member from the Selected application server cluster members menu, select the cluster members to remove and click <.
10. Click **OK**.

Application server cluster mapping settings

You can configure settings for an application server cluster mapping. Application server cluster mappings are specified only for an application server cluster custom advisor.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisors** *custom_advisor_name > application_server_cluster_mapping*.

Cell name:

Specifies a logical name for the cell.

A cell name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Cluster name:

Specifies a logical name for the proxy cluster.

A cluster name must be unique among proxy clusters within the containing cell and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Application name:

Specifies the name of the application.

An application name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Transport chain:

A transport chain consists of one or more types of channels, each of which supports a different type of I/O protocol, such as TCP, HTTP, or DCS.

Transport chains enable communication through transport channels, or protocol stacks, which are usually socket based.

Application server cluster members:

Specifies the application server clusters that use the specified cluster mapping. You can add or remove application server cluster members.

An application server cluster is a cluster of application servers. Application servers host a common set of resources and can receive routing actions as a unit.

Node name

Specifies the name of the node. A node is a logical grouping of managed servers. A node name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Server name

Specifies the display name for the server. A server name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Configuring generic server cluster mappings

You can configure a generic server cluster mapping. A generic server cluster allows you to configure external servers into a logical cluster that can be used by the proxy server to route requests. Generic servers host a common set of resources and can receive routing actions as a unit. Generic server cluster mappings are configured to specify which generic server clusters a custom advisor will monitor.

Before you begin

Generic server cluster mappings cannot be configured until a proxy server has been configured and a custom advisor has been deployed.

About this task

Complete these steps to configure a generic server cluster mapping.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisors policies > custom_advisor_namegeneric_server_cluster_mapping_name**.
2. Optional: Click **New Generic Server Cluster Mapping** to begin configuring a new generic server cluster mapping.
3. In the Cluster name menu, select the generic server cluster the custom advisor will monitor is located.
4. Select the generic cluster members the custom advisor will monitor from the Available generic server cluster members menu.
5. Click > to add the generic server cluster members to be monitored by the custom advisor.
6. Optional: If you want to remove a generic cluster member from the Selected generic server cluster members menu, then select the generic cluster member to remove and click <.
7. Click **OK**.

Generic server cluster mapping settings

You can configure settings for a generic server cluster mapping. Generic server cluster mappings are specified only for a generic server cluster custom advisor.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Custom advisors > custom_advisor_name > generic_server_cluster_mapping**.

Cluster name:

Specifies a logical name for the proxy cluster.

A cluster name must be unique among proxy clusters within the containing cell and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Generic server cluster members:

Specifies the generic server clusters that use the specified time mappings. You can add or remove generic server cluster members.

A generic server cluster is a cluster of generic servers. Generic servers host a common set of resources and can receive routing actions as a unit. Generic servers, such as web servers, are not managed by the application server.

Host name

Specifies the IP address, domain name system (DNS) host name with domain name suffix, or the DNS host name for the generic server cluster.

Port Specifies the port where the generic server cluster accepts client requests. Specify a port value in conjunction with the host name.

Creating custom advisors for the proxy server

Use the following steps to create and deploy a custom advisor to a proxy server. Custom advisor policies allow for more specific determination of target application server availability. Custom advisors are Java code modules written that work within the proxy server to provide information about application server availability to the proxy server selection code.

About this task

Complete these steps to create and deploy a custom advisor for the proxy server.

Procedure

1. Create the custom advisor code.

Custom advisors are written in the Java language. A custom advisor extends the `com.ibm.wsspi.advisor.AbstractCustomAdvisor` class in the `proxy.jar` file that is included with WebSphere Application Server. Custom advisors use the defined methods of the `AbstractCustomAdvisor` class to obtain the information about the advisor. A custom advisor also must implement the following elements:

- A constructor method that takes a `CustomAdvisorConfigObject` object and calls the `super(caConfigObject)` method, for example

```
public AbstractHttpProxyCustomAdvisor(CustomAdvisorConfigObject caConfigObject) {  
    super(caConfigObject);  
}
```

- An `isUsable()` method that takes an `AdvisableServer` object; for example

```
public boolean isUsable(AdvisableServer aServer) throws CustomAdvisorException;
```

The `initialize` method is called after the `AbstractCustomAdvisor` construction, but before the `isUsable` method is called. This process allows the custom advisor to perform any additional steps after the base class completes initialization, but before the `isUsable` method is called, which ensures that the `initialize` method is only called once. If overridden, then the `initialize()` method must call the `super.initialize` method, for example:

```
protected void initialize() {  
    super.initialize();  
}
```

For more information about the required routines and the other methods available to a custom advisor, see the application programming interface (API) reference section of the information center. From the information center navigation, scroll to the Reference section and click APIs - Application Programming Interfaces. A list of the product API specifications displays in alphabetic order.

There are two exception classes that need to be considered when creating the custom advisor:

- The `CustomAdvisorException` can be created by the `isUsable` method of the custom advisor to tell the `AbstractCustomAdvisor` that the custom advisor must not call the `isUsable` method again until the next advisor cycle.
- The `NoLogConfiguredException` is created by the `AbstractCustomAdvisor` if the no logging file has been configured for the custom advisor, but logging is enabled.

The `httpcustomadvisor.jar` file can be used as a sample of a custom advisor. This file contains an `AbstractHttpProxyCustomAdvisor.java` class that extends the `com.ibm.wsspi.advisor.AbstractCustomAdvisor` and implements the `isUsable()` and `initialize()` methods.

Sample `httpcustomadvisor.jar` file:

```
<advisor-context>
<description>Webbsphere Proxy Demo HTTP Advisor Context</description>
<display-name>Webbsphere Proxy Demo HTTP Advisor Context</display-name>
?
<advisor>
<advisor-name>WebSphereProxyDemoHttpAdvisor</advisor-name>
?
<advisor-class>
com.ibm.ws.proxy.demo.customadvisor.http.HttpProxyCustomAdvisor
</advisor-class>
<description>Demo Websphere Proxy Http Advisor
Implementation</description>
<display-name>Demo Websphere Proxy Http Advisor</display-name>
</advisor>
</advisor-context>
```

2. Compile your custom advisor code. After you have created the Java source code for your custom advisor, you must compile it using the `AbstractCustomAdvisor` code that is included with WebSphere Application Server. To access the abstract custom advisor classes in the `com.ibm.wsspi.advisor` package, add the `proxy.jar` file to your Java class path. The `proxy.jar` file is located in the `#{WAS_INSTALL_ROOT}/plugins` directory.

3. Create the `advisor-context.xml` file.

After compiling the custom advisor code, you will need create the `advisor-context.xml` file. This file is used to identify the code as a custom advisor Java archive (JAR) file when it is imported as an asset and then added as a compilation unit to a business-level application (BLA). When the custom advisor JAR asset is added to a BLA and then targeted to a proxy server, the Content DistributionFramework (CDF) support will distribute and copy all the BLA artifacts of the custom advisor to the appropriate configuration information on the targets specified.

The `advisor-context.xml` contains the class name for the custom advisor to be run and the custom advisor name. The format of the `advisor-context.xml` file must follow the `advisor-context.xsd` schema in the `proxy.jar` file. You can use an XML schema tool to assist in creating and setting the appropriate information. The required configuration information is defined as follows:

```
<advisor-name> SomeCustomAdvisor </advisor-name>
<advisor-class> com.ibm.wlm.test.customadvisor.SomeCustomAdvisor </advisor-class>
<description> Some Custom Advisor Description </description>
<display-name> Some display name </display-name>
```

4. Create the custom advisor BLA. Package your compiled custom advisor class files and the `advisor-context.xml` into a JAR file. This JAR file is then used when creating the custom advisor BLA to be installed and deployed to the proxy server. The following example shows the commands to use to install a custom advisor as a BLA.

```
$AdminTask importAsset {-source C:/proxy/testadvisor.jar -storageType FULL}
$AdminTask createEmptyBLA {-name myBLA}
$AdminTask addCompUnit {-blaid myBLA -cuSourceID assetname=testadvisor.jar,assetversion=1.0 -MapTargets {{.* ProxyServer}} -CustomAdvisorCUOptions
{{"type=Cluster,cellName=yourCellName,clusterName=yourClusterName
,applicationName=myBLA" default default default 1000}}}
$AdminConfig save
```

5. Configure your deployed custom advisor. See “Administering custom advisors for the proxy server” on page 240 for additional details.

Administering proxy virtual hosts

Virtual hosting allows a single proxy server to host multiple domains and ports on a single IP address and port. A proxy virtual host can be created for each Web domain the proxy server is hosting, or wild card characters can be used to host multiple Web domains with a single proxy virtual host.

About this task

Note: A proxy virtual host allows a single proxy server to host multiple domains and ports on a single IP address and port. A proxy virtual host consists of the name and the port representing the Web domain and a set of proxy rule expressions to perform specified proxy actions when a defined criteria exists. Additionally, each proxy virtual host can override the server scope configuration of the proxy server to have configuration elements defined specifically for that virtual host. Proxy virtual hosts use a set of proxy server actions and proxy rule expressions. Proxy rules expressions are evaluated when inbound requests are received by the proxy virtual host. If the expression is evaluated to be true, any proxy server actions specified by the proxy rule expression are performed

Complete these steps to administer or create a new proxy virtual host.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Virtual hosts > virtual_host_name**.
2. Optional: Click **New** to access the virtual hosts settings page to configure settings for a new virtual host.
3. Specify a name for the virtual host. The name of the virtual host must match the Web domain it represents. If the web domain is `www.proxy1.com`, the name of the proxy server host must be `www.proxy1.com`. The asterisk symbol, `*`, can be used as a wild card character to represent all Web domains. If the proxy virtual host is `*:80`, then all inbound requests on port 80 are handled by that proxy virtual host regardless of what Web domain is being requested.
4. Specify the port for the virtual host. The port of the virtual host must match the port used by the web domain it represents. If the Web domain uses port 80, then the port of the proxy virtual host must also be 80. The asterisk symbol, `*`, can be used as a wild card character to represent all ports. If the proxy virtual host is `www.proxy1.com:*`, then all inbound requests to `www.proxy1.com` are handled by that proxy virtual host regardless of what port is being used.
5. Choose one or more proxy rule expressions for the virtual host. Proxy rule expressions allow for proxy actions to be performed when the expression evaluates to true. See “Proxy rule expressions” on page 253 and “Proxy server actions” on page 229 for more information on proxy rule expressions and proxy server actions.
6. Optional: Move a proxy virtual host up or down in the list to ensure the correct proxy virtual host is used. The usage of wild card characters for virtual proxy hosts creates a situation where an inbound request might match multiple proxy virtual hosts. In this scenario, the request will be handled by the first proxy virtual host that matches the request.
7. Optional: Click **Edit** to change the selected proxy rule expression.
8. Optional: Click **Proxy Virtual Host Settings** to override the server scoped settings for static file serving, logging, or error page policy.
 - a. If you want to override the static file serving settings for this proxy virtual host, click **Static File Serving**, select **Customize for this virtual host**, and then specify a new value for the **Static file document root** field.
 - b. If you want to override the logging settings for this proxy virtual host, click **Logging**, select **Customize for this virtual host**, and then specify new values for one or more of the following fields:
 - **Enable access logging**
 - **Access log maximum size**
 - **Proxy access log**
 - **Cache access log**
 - **Local access log**

- c. If you want to override the error page policy settings for this proxy virtual host, click **Error Page Policy**, and then select **Customize for this virtual host**, and then specify new values for one or more of the following fields:
 - **Error page generation application URI**
 - **Handle errors generated by the proxy server**
 - **Handle errors generated by the application server**
 - **Headers to forward to error page application**
 - **HTTP status codes that are to be recognized as errors**
 - d. Click **OK** to save your proxy virtual host settings, and return to the previous administrative console page.
9. Click **OK** to save all of your other changes.

Proxy virtual hosts

Virtual hosting allows a single proxy server to host multiple domains and ports on a single IP address and port.

A proxy virtual host consists of the name and port of a web domain and a set of proxy rule expressions that perform proxy actions for specific criteria. Additionally, each proxy virtual host can override the proxy server configuration to have configuration elements defined specifically for that virtual host. The following settings can specify virtual host settings in place of the server scope settings:

- Logging
- Custom error pages
- Static file serving

Proxy virtual hosts use proxy server actions and proxy rule expressions. Proxy rule expressions and proxy server actions are only used for proxy virtual hosts. When the proxy virtual host receives inbound requests, the proxy rule expressions are evaluated. If the expression is evaluated to be true, any proxy server actions that are specified by the proxy rule expression are performed. The following proxy server actions can be specified when an expression evaluates to true:

- Routing rules
- Caching rules
- URL rewriting rules
- Header modification rules
- Compression rules

A different proxy virtual host can be created for the proxy server to represent each web domain that the proxy server is hosting. For example, a request for `www.proxy1.com` on port 80 uses the configuration specified for `www.proxy1.com:80`. A request for `www.proxy2.com` on port 80 uses the configuration specified for `www.proxy2.com:80`. You can use a wild card character to specify that a proxy virtual host can be used for all web domains or all ports. For example, `www.proxy1.com:*` specifies that a proxy virtual host can be used for all requests for the web domain `www.proxy1.com` regardless of the port. A proxy virtual host for `*:80` specifies that it can be used for all requests on port 80 regardless of the web domain.

After creating a proxy server with the needed proxy virtual hosts, the HTTP protocol allows multiple web domains to be hosted by a single server process. When an inbound request is received by the proxy server, it matches the proxy virtual host located in the inbound request message to the appropriate configuration for that proxy virtual host. If a request matches multiple proxy virtual hosts because wild card characters were used, the proxy virtual host that is first in the list of proxy virtual hosts is used.

Proxy virtual hosts collection

Use this page to administer proxy virtual hosts. A proxy virtual host allows a single proxy server to host multiple domains or ports on a single IP or port. Each proxy virtual host consists of a domain name and a port.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Proxy virtual hosts**.

Virtual host name

Specifies a user-defined symbolic name for a proxy virtual host.

A virtual host name must be unique and cannot contain an invalid character. The virtual host name is a reflection of the web domain it represents. For example, use a virtual host name of www.proxy1.com to represent the www.proxy1.com web domain. The asterisk symbol, *, can be used in the name field to indicate that this proxy virtual host matches all web domains. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % ' .

Proxy rule expressions

Specifies a rule expression for a proxy virtual host. A proxy rule expression consists of operands and operators that is defined by an administrator. If a proxy rule expression evaluates to true, then the proxy actions that are configured for the rule are run.

Enabled

Specifies whether or not a proxy virtual host is enabled.

If a proxy virtual host is enabled, then the configuration for the proxy virtual host is used when a user makes a request for the proxy virtual host. Otherwise, another matching proxy virtual host configuration is used. If no other proxy virtual host configuration matches the configuration for the requested proxy virtual host, then the server-scoped configuration is used.

Proxy virtual host settings

You can configure settings for a proxy virtual host. A proxy virtual host allows a single proxy server to host multiple domains or ports on a single IP or port. Each proxy virtual host consists of a domain name and a port.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Virtual hosts > virtual_host_name**.

Virtual host name

Specifies a user-defined symbolic name for a proxy virtual host.

A virtual host name must be unique and cannot contain an invalid character. The virtual host name is a reflection of the web domain it represents. For example, use a virtual host name of www.proxy1.com to represent the www.proxy1.com web domain. The asterisk symbol, *, can be used in the name field to indicate that this proxy virtual host matches all web domains. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % ' .

Virtual host port

Specifies the port number associated with the web domain that the proxy virtual host represents. The asterisk symbol, *, can be used in the virtual host port field to indicate that this proxy virtual host matches requests for all ports of the web domain that are specified by the Virtual host name field..

Proxy rule expressions

Specifies one or more rule expressions for a proxy virtual host. At run time, the proxy host evaluates the expressions according to the order that they are defined. If the value of a proxy rule expression is true,

the actions associated with the expression is performed by the proxy virtual hosts. Click **Edit** to change a proxy rule expression. Proxy rule expressions are only available for proxy virtual hosts.

You can enable proxy rule expressions to complete certain proxy actions for a proxy virtual host. Click the arrows to include or exclude proxy rule expressions. Proxy rule expressions are evaluated in the order that they are listed. You can move a proxy rule expression up or down in the list to determine when the rule expression is evaluated.

Available proxy rule expressions

Specifies the rule expressions that can be added to a virtual host.

Proxy rule expressions

Specifies the rule expressions that were added to the virtual host.

Proxy virtual host settings details

Use this panel to override some proxy server scoped settings with values to be used for the proxy virtual host.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_name > Virtual hosts > virtual_host_name > Proxy virtual host settings**.

General Properties

The three types of configurations available on this page are static file serving, logging, and error page policy. For each of these types, you can choose to use the server scoped value for this setting or you can override the settings with new values that are used only for this proxy virtual host.

- If you choose **Use global server settings**, the server scoped values for that type are displayed and those values will be used for the proxy virtual host.
- If you choose **Customize for the virtual host**, the values that you enter in the fields for that type are used for the proxy virtual host instead of the server scoped values.

Static file serving

This type of configuration specifies the information needed for the proxy server to perform static file serving.

- **Static file document route:** The location on the file system of the static files to be served

Logging

This type of configuration specifies the logging options for proxied requests and stored cache requests.

- **Enable access logging:** Specifies whether or not access logging is used.
- **Access log maximum size:** Specifies the maximum size of each access in megabytes.
- **Proxy access log:** Specifies the log that is used used to log responses that are received from remote servers.
- **Cache access log:** Logs responses that are served from the local cache.
- **Local access log:** Logs all non-cache local responses, for example, redirects and internal errors.

Error page policy

This type of configuration specifies settings to support the use of customized error pages to be displayed when errors occur during the processing of requests.

- **Error page generation application URI:** If a valid URI to an installed application is not provided, the custom error page policy does not handle requests.
- **Handle errors generated by the proxy server:** Specifies if errors generated by the proxy server are handled with the custom static error pages stored on the local file system. If this is not selected, then the default error messages are used instead of any customer error pages.

- **Handle errors generated by the application server:** Specifies if errors generated by the application are handled with the custom static error pages stored on the local file system. If this is not selected, then the default error messages are used instead of any customer error pages.
- **Headers to forward to error page application:** Specifies a list of the headers from the original request to forward to the error page generation application.
- **HTTP status codes that are to be recognized as errors:** Specifies a list of the status codes in a response to direct to the error page generation application.

Administering proxy rule expressions

You can administer proxy rule expressions to make proxy actions more granular in scope. Proxy rule expressions are configurations assigned to a proxy virtual host.

About this task

A proxy rule expression consists of operands and operators that are defined by an administrator. When an expression evaluates to true, the proxy action rules associated with that proxy rule expression are performed.

Complete these steps to create a new proxy rule expression or to administer an existing proxy rule expression.

Procedure

1. From the administrative console, select **Servers > Server Types > WebSphere proxy servers > *proxy_server_name* > Proxy Virtual Host Configuration > Proxy rule expressions**.
2. Click **New** to create a new proxy rule expression. To administer an existing proxy rule expression, Click ***rule_expression_name***.
3. Specify the name for the rule expression.
4. Click **Subexpression builder** to add an expression. You can also create the expression by entering the expression manually. The Subexpression builder is only designed to generate a subset of the available options when creating an expression. For example the Subexpression builder does not allow the usage of parenthesis in an expression. If a complex expression is needed, then type the expression into the field instead of using the Subexpression builder. For some examples of valid expressions, see “Proxy rule expressions” on page 253. To use the Subexpression builder to create your expression, repeat these steps for each subexpression that you want to create.
 - a. From the **Logical operator** menu, choose a logical operator. If this the first subexpression in this field, then the logical operator will be removed when it is generated.
 - b. From the **Select operand** menu, choose an operand.
 - c. From the **Operator** menu, choose an operator.
 - d. From the **Select <operand_name>** menu, choose the name of the operand to be used. The name and available selections for this menu is dependant on the operand specified in step b. For example, if you selected **cell** in step b, then the name of this menu will **Select cell** and the menu will list the available cells as menu options.
 - e. Click **Generate subexpression** to add the new expression to the Subexpressions list.
 - f. Click **OK**.
5. Enable a proxy action for the proxy rule expression. You can enable multiple proxy actions. All the enabled proxy actions will be performed when the proxy rule expression evaluates to true.
6. Optional: If the a proxy action needs to be modified, select that proxy action, and click **Edit**.
7. Optional: Move a proxy action up or down in the list to change the order in which the proxy actions will be performed. If the sequence the proxy actions are performed is important for the rules you specified, ensure that the order of the proxy actions in the list corresponds to the order they must be performed.
8. Click **OK**.

Proxy rule expressions

Use proxy rule expressions to make configuration rules more granular in scope by specifying information within the rule. Proxy rule expressions are assigned to a proxy virtual host. When a request is handled by the proxy virtual host, the proxy rule expressions associated with that proxy virtual host are evaluated. If any of the proxy rule expressions evaluates to true, then all the proxy actions specified in the proxy rule expression configuration are performed.

Proxy rule expressions have operands and operators that are created and managed by an administrator. With operands, you can configure proxy rule expressions based on the following criteria:

- cell
- application
- module
- uri
- urigroup

Operands are combined with operators to define the proxy rule expressions. Operators can be applied with words or symbols.

Word	Symbol
AND	&&
OR	

Example 1

In the following example, the expression evaluates to true if the target cell name is *mycell*. Otherwise, the expression evaluates to false.

```
cell=mycell
```

Example 2

In the following example, the expression evaluates to true if the target cell name is *mycell*, and the application name is *myapp*. Otherwise, the expression evaluates to false.

```
cell=mycell AND application="myapp"
```

Example 3

In the following example, the expression evaluates to true if the target cell name is *mycell*, and the target application name is *myapp1* or *myapp2*. Otherwise, the expression evaluates to false.

```
cell=mycell && (application="myapp1" || application="myapp2")
```

Example 4

In the following example, the expression evaluates to true if the target cell name is *mycell*, and the target application is not named *myapp*. Otherwise, the expression evaluates to false.

```
cell=mycell AND application!=myapp
```

Example 5

In the following example, the expression evaluates to true if the request URI matches the pattern */proxy1/**. Otherwise, the expression evaluates to false.

```
uri="/proxy1/*"
```

Proxy rule expressions collection

Use this page to administer proxy rule expressions for the proxy server. Proxy rule expressions allow you to make configuration rules more granular in scope by specifying information within the rule. A proxy rule expression is associated with a virtual proxy host and consists of operands and operators that are defined by an administrator. When an expression evaluates to true, the proxy action rules associated with that proxy rule expression are performed.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > server_name > Proxy Virtual Host Configuration > Proxy rule expressions**.

Expression name

Specifies a user-defined symbolic name for a proxy rule expression.

An expression name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Expression

Specifies the expression that is evaluated when an inbound request is made to the proxy virtual host.

An expression evaluates to true or false and consists of operands and operators. Expressions can be entered manually on the Proxy rule expressions settings page. The **Subexpression builder** can also be used on that page to generate the expressions.

Table 19. Rule expression operands.

This table lists the rule expression operands.

Operands	Description
Cell	Specifies the cell that contains the back end server to which the request is mapped.
Application	Specifies the Java Platform, Enterprise Edition (Java EE) application that a given request maps to on the back end server.
Module	Specifies the J2EE application module to which a given request is mapped.
URI	Specifies the URI for an inbound request.
URIgroup	Specifies a group of URIs to match against the URI. If the inbound request is in the URI group, then the expression evaluates to true.

Proxy actions

Specifies the proxy actions configured for the rule expression. Proxy actions are performed when the proxy rule expression evaluates to true.

You can configure the following proxy actions for a proxy rule expression:

- header actions
- caching action
- compression actions
- rewriting actions
- routing actions

Proxy rule expression settings

You can configure settings for a proxy rule expression. A proxy rule expression consists of operands and operators that are defined by an administrator. If a proxy rule expression evaluates to true, then all proxy actions configured for that rule expression are run.

To view this administrative console page, click **Servers > Server Types > WebSphere proxy servers > proxy_server_nameProxy Virtual Host Configuration > Proxy rule expressions > expression_name**.

Expression name

Specifies a user-defined symbolic name for a proxy rule expression.

An expression name must be unique and cannot contain an invalid character. The name field cannot contain the following characters: # \ / , ; " * ? < > | = + & % '.

Expression

Specifies the expression that is evaluated when an inbound request is made to the proxy virtual host. You can create expressions manually by entering the text into this field, or you can use the **Subexpression builder** to generate a new expression.

Specify the following settings for the **Subexpression builder**. You can use the following operands in your expression:

Table 20. Rule expression operands.

This table lists the rule expression operands.

Operands	Description
Cell	Specifies the cell that contains the server to which the request is mapped.
Application	Specifies the J2EE application that a given request maps to on the back end server.
Module	Specifies the J2EE application module to which a given request is mapped.
URI	Specifies the URI for an inbound request.
URIgroup	Specifies a group of URIs to match against the URI. If the inbound request is in the URI group, then the expression evaluates to true.

Proxy actions

Specifies the proxy actions configured for the rule expression.

You can configure the following proxy actions for a proxy rule expression:

- header actions
- caching action
- compression actions
- rewriting actions
- routing actions

Click **Edit** to modify a proxy action from this panel. Click the arrows to include or exclude proxy actions. You can move a proxy action up or down in the list to determine when the proxy action is performed.

Creating a custom filter and deploying it to a proxy server

You can create a custom filter for your proxy server if you need to have the proxy server perform a function, such as customized logging, that is not provided through normal product settings.

Before you begin

- Determine where you are going to store the artifact that contains the filter you create. You can import this artifact from either a local or remote file system.
- You must know the name of the proxy server on which you want to install the custom filter.
- You must start the administrative console that is used to control this proxy server, it is not already started.

About this task

A filter provides an optional, secondary control over a function, that is beyond the control that is normally provided through typical product settings. For example, an applications might use a logging filter mechanism to suppress all of the events that have a particular message key.

Procedure

1. Create a custom filter.
 - a. Create a class that extends `com.ibm.wsspi.HttpDefaultFilter`.
 - b. Override the abstract `doFilter` method, and, optionally, the `init` and `destroy` methods. If you override the `init` and `destroy` methods, you must call the super versions of these methods to preserve filter lifecycle functionality.
 - c. Write a new `doFilter` method, that uses the `HttpProxyServiceContext` interface.

This new `doFilter` method can be written such that it:

- Changes any artifacts that are associated with the request or the response, such as the response itself, the response code, or the headers.
- Changes any artifacts that are associated with both the request and the response.
- Obtains information about either the request or the response.
- Obtains information about both the request and the response.

- d. Use the proxy server filter managed bean (MBean), `proxyFilterMbean`, to determine the correct ordinal for the filter.

```
proxyFilterMbean = AdminControl.queryNames('type=ProxyServerFilterBean,*')
AdminControl.invoke(proxyFilterMbean, 'viewAllFilters')
```

The order, in which all of the filters on the proxy server are processed, displays.

- e. Create the filter descriptor file, `filter-context.xml`

This file is used to define all of the filters that have this descriptor. The following example illustrates a basic version of a `filter-context.xml` file.

In this example, the descriptor determines where and when the given filter is executed on both the request and the response. The filter point determines where the filter is executed. In this example, the filter executes after the request is received. The ordinal determines when the filter gets processed relative to other filters at the same filter point. The higher the ordinal, the higher the filter is in the processing queue.

```
<?xml version="1.0" encoding="UTF-8">
<filter-context xmlns="http://www.ibm.com/2003/FilterContextSchema">
  <description>Proxy Filter Sample descriptor</description>
  <display-name>Proxy Sample Filter</display-name>

  <filter>
    <filter-name>HttpRequestFilter</filter-name>
    <filter-class>com.ibm.ws.proxy.sample.HttpRequestFilter</filter-class>
    <description>HTTP sample filter to execute at REQUEST filter point</description>
```

```

        <display-name>HTTP Request Sample</display-name>
        <protocol-name>HTTP</protocol-name>
        <filter-point>RequestReceived</filter-point>
        <ordinal>1000</ordinal>
    </filter>
</filter-context>

```

- f. Bundle the compiled .class files for the filter, and the filter descriptor into a JAR file.
2. Import the artifact (JAR file) that contains the custom filter.
 - a. In the administrative console, click **Applications > Application Types > Assets > Import**.
 - b. Select either **Local file system** or **Remote file system** to indicate where the JAR file is located.
 - c. Specify the fully qualified name of the JAR file.
The fully qualified name of the JAR file includes the directory path to where the file is located, and the file name. If you do not know the fully qualified name of the JAR file, you can use the browse function to locate the file.
3. Create a business level application (BLA) that includes this artifact.
 - a. In the administrative console, click **Applications > New Application > New Business-level application**.
 - b. In the **Name** field, specify a name for the new application that you are creating.
You can also specify a description of the application in the **Description** field.
 - c. Click **Apply**.
4. Create a BLA composition unit (CU) from the artifact.
 - a. In the **Deployed assets** table, click **Add > Add asset**.
 - b. Select the name of the artifact that you imported in the first step, and then click **Continue**.
 - c. Change the composition unit settings as needed, and then click **Modify target**.
 - d. Select the proxy server on which you want to deploy this CU from the list of available deployment targets, and then click **OK**.
When you click **OK** the product maps the composition unit to the selected proxy server.
 - e. Specify the relationship options for this composition unit.
 - f. Click **Finish**.
To verify that the product successfully added the created this CU, click **Applications > Business-level applications > application_name**. If the product successfully adds the CU, the name of the CU is shown in the list of deployed assets for this BLA.
5. Start the proxy server.
6. Start the BLA that contains the filter.

Results

The filter is running on the proxy server.

What to do next

Use the proxy server filter MBean, proxyFilterMbean, to verify that the filter is installed on the proxy server and that it is being processed in the correct order relative to the other filters that are deployed on the proxy server. If you need to change the order in which this filter is processed, run the modifyOrdinal command against the proxyFilterMbean MBean.

Configuring denial of service protection for the proxy server

You can configure a pair of properties on your proxy server or DMZ Secure Proxy Server for IBM WebSphere Application Server to limit your risk against denial of service attacks involving the buffering of large HTTP payloads.

Before you begin

Denial of service protection for the proxy server or the DMZ Secure Proxy Server for IBM WebSphere Application Server is not done during the creation of these servers. The proxy server or the DMZ Secure Proxy Server for IBM WebSphere Application Server that will include denial of service protection must already exist before following these steps.

About this task

Note:

Protection is now included to guard against a type of security breach known as a denial of service attack. This type of attack can typically send more traffic to a network address than the data buffers were designed to accommodate. The proxy server and DMZ Secure Proxy Server for IBM WebSphere Application Server have several properties that can be configured to limit your risk against denial of service attacks involving the buffering of large HTTP payloads.

A denial of service attack is a malicious type of security breach to a computer system that does not usually result in the theft of information or other security loss. This type of attack can typically send more traffic to a network address than the data buffers were designed to accommodate resulting in a loss of memory. HTTP allows for the body of a message to be sent to an HTTP server as an HTTP request or an HTTP response. The body can be sent to the HTTP server in a series of sequential network writes instead of being sent in one large network write. This process is known as Transfer-Encoding chunking. The maximum size of a Transfer-Encoding: chunked response body and a Transfer-Encoding: chunked request body can be set to determine how much data is buffered before a network write is performed.

Procedure

1. Click **Servers>Proxy Servers>***proxy_server_name*.
2. Under Proxy Settings, expand **HTTP Proxy Server Settings** and click **Denial of service protection**
3. Set the appropriate buffer size in kilobytes for **Maximum request body buffer size**. Buffering can lead to better performance because it will decrease the number of network writes for large payloads. The size of the buffer must not be configured too high or memory exhaustion can occur. To determine the optimal values for your environment, gradually increase the size of the buffer until the proper balance has been achieved.
4. Set the appropriate buffer size in kilobytes for **Maximum response body buffer size**. The same precaution must be taken when setting Maximum response body buffer size as were indicated for Maximum request body buffer size.

Results

After these steps have been properly complete, denial of service protection will be in place for your proxy server or DMZ Secure Proxy Server for IBM WebSphere Application Server.

Denial of Service Protection

Use these settings to define denial of service protection for the proxy server. The buffer chunk sizes are used to provide protection against denial of service attacks. It is very important to tune these settings to balance the level of protection with the performance impacts that can be experienced.

To view this administrative console page, click **Servers > Proxy Servers > <server_name> > HTTP Proxy Server Settings > Denial of Service Protection**.

Maximum request body buffer chunk size

This field sets the maximum amount of the request body data that is buffered in memory before it is sent. The proxy server and secured proxy server can buffer multiple network reads of a Transfer-Encoding: chunked request body before performing a network write. This can improve performance because buffering

the data will decrease the number of network writes required for large payloads. This field should be adjusted with caution. If the buffer size is set too high, memory exhaustion, which is a common intent of denial of service attacks, might be experienced. You will need to test different buffer sizes to find the optimal level of balance between protection and performance for your system. The default value of this field is 32 kilobytes.

Maximum response body buffer chunk size

This field sets the maximum amount of the response body data that is buffered in memory before it is sent. The proxy server and secured proxy server can buffer multiple network reads of a Transfer-Encoding: chunked response body before performing a network write. This can improve performance because buffering the data will decrease the number of network writes required for large payloads. This field should be adjusted with caution. If the buffer size is set too high, memory exhaustion, which is a common intent of denial of service attacks, might be experienced. You will need to test different buffer sizes to find the optimal level of balance between protection and performance for your system. The default value of this field is 32 kilobytes.

Tuning the security properties for the DMZ Secure Proxy Server for IBM WebSphere Application Server

When creating a DMZ Secure Proxy Server for IBM WebSphere Application Server, default security levels of high, medium and low are available. In addition to the predefined configuration levels, you can modify the security settings for your DMZ Secure Proxy Server for IBM WebSphere Application Server. When you choose to customize the settings, a qualitative value of high, medium or low is still assigned to inform you of the overall security level of your DMZ Secure Proxy Server for IBM WebSphere Application Server.

Before you begin

A DMZ Secure Proxy Server for IBM WebSphere Application Server must be installed before these steps can be completed. The DMZ Secure Proxy Server for IBM WebSphere Application Server profile must be registered with the AdminAgent for this panel to be available.

About this task

Installing the DMZ Secure Proxy Server for IBM WebSphere Application Server in the DMZ rather than the secured zone presents new security challenges. The DMZ Secure Proxy Server for IBM WebSphere Application Server has been equipped with various capabilities to provide protection for meeting these challenges. In addition to the predefined security configurations for your DMZ Secure Proxy Server for IBM WebSphere Application Server you can also tune the settings to customize the protection.

Procedure

1. Click **Servers > Proxy Servers > <secured_proxy_server_name> > Custom security settings** to open up the Proxy security settings panel.
2. Choose your administration option for your DMZ Secure Proxy Server for IBM WebSphere Application Server.
 - Local Administration - Security level: medium and high.
This option allows two different types of administration. Managing the DMZ Secure Proxy Server for IBM WebSphere Application Server entirely using the wsadmin tool and loading updated profiles imported from inside the cell using the wsadmin tool are both considered Local Administration.
 - Remote Administration- Security level: low
3. Choose your routing option for your DMZ Secure Proxy Server for IBM WebSphere Application Server.
 - Static routing - Security level: high
 - Dynamic routing - Security level: low and medium

4. Choose your startup permission option for your DMZ Secure Proxy Server for IBM WebSphere Application Server.
 - Run as an unprivileged user - Security level: medium and high
 - Run as privileged user - Security level: low
5. Optional: If Run as an unprivileged user is selected, enter the user name or the user group whose identity the server should assume after startup has completed.
6. Choose your custom error page policy option for your DMZ Secure Proxy Server for IBM WebSphere Application Server.
 - Local error page handling - Security level: high

If you choose to use local error page handling, you need to select which error responses should use custom error messages. Select Handle local errors for responses generated by the proxy server and select Handle remote errors for responses generated by the backend server. Both options may be selected to use custom error messages for local and remote errors. Manage your error code mappings to determine the custom error pages to be used for specific responses.
 - Remote error page handling - Security level: low and medium

If you choose to use remote error page handling to include custom errors, you need to select which error responses should be customized. Select Handle local errors for responses generated by the proxy server and select Handle remote errors for responses generated by the backend server. Both options may be selected to use custom error messages for both local and remote errors. Manage the headers that should be sent to the custom error application and what status codes are to be recognized as errors.

Results

You have finished customizing the security settings for your DMZ Secure Proxy Server for IBM WebSphere Application Server. A qualitative value of high, medium or low has been calculated based on the settings you have chosen to demonstrate the Current DMZ Security level.

DMZ Secure Proxy Server for IBM WebSphere Application Server start up user permissions

The overall security level of the DMZ Secure Proxy Server for IBM WebSphere Application Server can be hardened by reverting the server process to run as an unprivileged user after startup. Although the DMZ Secure Proxy Server for IBM WebSphere Application Server must be started as a privileged user, changing the server process to run as an unprivileged user provides additional protection for local operating resources.

Like the proxy server, the DMZ Secure Proxy Server for IBM WebSphere Application Server must start under a privileged user because it requires authorization to initialize privileged ports. Ports lower than 1024 are considered privileged ports. After these ports are initialized and access to the protected ports is no longer required, it is possible to change the user association of the DMZ Secure Proxy Server for IBM WebSphere Application Server process. Altering the server process to run using the privileges of a user or a group that does not have authority to access the local operation system resources adds a layer of protection to those resources. The firewall helps protect local operating system resources for the proxy server, but as the DMZ Secure Proxy Server for IBM WebSphere Application Server is installed in the DMZ, this type of protection becomes a higher priority. Although changing the user association of the server process for the DMZ Secure Proxy Server for IBM WebSphere Application Server is not required, continuing to run as a privileged user does not use the extra layer of protection for local operation resources that is provided when the server process is changed to run as an unprivileged user.

Table 21. Start up options. This table describes the proxy server start up options.

Run as unprivileged user	This is considered a high and medium security level setting.
Run as privileged user	This is considered a low security level setting.

DMZ Secure Proxy Server for IBM WebSphere Application Server routing considerations

This topic summarizes some of the security implications that must be considered when choosing how your DMZ Secure Proxy Server for IBM WebSphere Application Server will match incoming HTTP requests to an application or routing rule.

The DMZ Secure Proxy Server for IBM WebSphere Application Server can be configured to route requests either statically or dynamically. Using static routing specifies routing is performed using a flat configuration file using routing precedence that is inherent to the ordering of the directives. Requests can also be routed dynamically using a best match mechanism that determines the installed application or routing rule that corresponds to a specific request. The DMZ Secure Proxy Server for IBM WebSphere Application Server will dynamically discover the best route to a destination and distribute to servers with like protocols. It is considered more secure to use static routing than dynamic routing. This is because dynamic routing requires the secured proxy server to communicate with the application server to map requests, whereas static routing is self-contained by the secure proxy server and requires no additional communication.

Table 22. Routing options. This table lists the proxy routing options.

Static Routing	This is considered a high security level setting.
Dynamic Routing	This is considered a low and medium security level setting.

DMZ Secure Proxy Server for IBM WebSphere Application Server administration options

The DMZ Secure Proxy Server for IBM WebSphere Application Server is administered differently than the WebSphere proxy server. The DMZ Secure Proxy Server for IBM WebSphere Application Server is a separate binary installed in the DMZ. Installing the DMZ Secure Proxy Server for IBM WebSphere Application Server in the DMZ requires that administration be managed differently for security reasons. Several administrative options are available for administering the DMZ Secure Proxy Server for IBM WebSphere Application Server to provide different levels of balance between security and usability.

The most secure way to administer the DMZ Secure Proxy Server for IBM WebSphere Application Server is locally using the wsadmin tool. The DMZ Secure Proxy Server for IBM WebSphere Application Server does not have web container. Therefore, local administration can only be done via the command line. Using the wsadmin commands locally to manage the DMZ Secure Proxy Server for IBM WebSphere Application Server is the most secure option available because it does not require any external listening ports to be opened.

The DMZ Secure Proxy Server for IBM WebSphere Application Server configurations can also be managed within the network deployment application server cell and then imported locally using the wsadmin commands. The configurations are maintained inside the cell as configuration only profiles. The profiles are registered with the Admin Agent and are then managed using the administrative console. After you implement any changes to the profile, you export the configuration to a configuration archive (CAR) file using the exportProxyProfile or exportProxyServer wsadmin commands. After you transmit the CAR file to the local DMZ Secure Proxy Server for IBM WebSphere Application Server installation using ftp, the CAR file is imported using the importProxyProfile or importProxyServer wsadmin commands. This option is also considered to be local administration.

Note: Due to security reasons, the number of listening ports on the secure proxy is minimized. You might not be able to manage, start, stop the secure proxy from the admin agent or the job manager remotely when admin security is enabled.

Error handling security considerations for the DMZ Secure Proxy Server for IBM WebSphere Application Server

The overall security level of the DMZ Secure Proxy Server for IBM WebSphere Application Server is partially determined by the choices made regarding the handling of custom errors.

You can define a custom error page for each error code or a group of error codes on errors generated by the proxy server or the application server. This is done using HTTP status codes in responses to generate uniform customized error pages for the application. For security reasons, you can ensure that the error pages are read from the local file system instead of being forwarded to a custom remote application. Choosing this option limits the code path and eliminates the need for a potentially unauthorized application to be run as the error message is generated based on a flat file. For more information about the error handling for the secured proxy server, see “Overview of the custom error page policy” on page 199.

The following security level settings are used when evaluating a custom security level. Local error page handling is used for all of the predefined security levels.

Table 23. Error handling options. This table lists the security level settings that are used when evaluating a custom security level.

Local error page handling	This is considered a high security level setting.
Remote error page handling	This is considered a medium and low security level setting.

Proxy security level properties

These settings describe the attributes and policies that define the security level of a secured proxy server. The overall security level of the secured proxy server is set to the weakest level of security assigned to any of the individual settings.

To view this administrative console page, click **Servers > Proxy Servers > server_name > Custom security settings**. This panel will only be available for a secure proxy server profile that has been registered with the AdminAgent.

Current security level

A qualitative security level based on an evaluation of the current security related configuration values.

The possible values for Current DMZ Security are high, medium, low. During creation of the secured proxy server, default configurations of high, medium and low are available. You are also able to customize these security settings resulting in the Current DMZ Security level being calculated by the system. Each custom setting has an assigned value of high, medium or low. The overall security level is equal to value of the setting that is considered the least secure. For example, to have an overall security level of high, all settings must be configured to the values associated with a high level of security. If any of the settings are configured with a less secure value, the overall security level is the value of that setting.

Administration

Table 24. Administration options. This table lists the proxy administration options.

Option	Used as the default value in the predefined security levels	Description
Local administration	The default value for the Medium and the High security levels	Specifies that administration of the secure proxy server can only be performed using wsadmin commands performed locally on the system.
Remote administration	The default value for the Low security level	Specifies that remote administration of the secure proxy server is permitted.

Routing

Table 25. Routing options. This table lists the proxy routing options.

Option	Used as the default value in the predefined security levels	Description
Static routing	The default value for the High security level	Specifies that the proxy server will make routing determinations from routing information based on flat files on the file system. This is for Hypertext Transfer Protocol (HTTP) only
Dynamic routing	The default value for the Low and the Medium security levels	Specifies that the proxy server will dynamically discover the best route to a destination and distribute to servers with like protocols.

Start-up permissions

Table 26. Start-up permission options. This table lists the proxy start-up permission options.

Option	Used as the default value in the predefined security levels	Description
Run as an unprivileged user	The default value for the Medium and the High security levels	Specifies that the server process will revert to a predefined unprivileged user after start-up has completed.
Run as a privileged user	The default value for the Low security level	Specifies that the server process does not revert to an unprivileged user after startup. It is a requirement that the proxy server start under a privileged user as it initializes privileged ports. Ports lower than 1024 are considered privileged ports. Under this setting, the effective user of the server process continues to be the privileged user. This setting does not provide additional hardening to the access of the server process to the local operation system resources. This is considered a low security level setting.

Custom Error Page Policy

Table 27. Error page options. This table lists the proxy error page options.

Option	Used as the default value in the predefined security levels	Description
Local error page handling	The default value for the Low, the Medium and the High security levels	Specifies that error responses will be generated from flat custom error page files stored locally on the local file system.
Remote error page handling	None	Specifies to route error responses to a remote custom application deployed on a back-end server. This application will generate a custom response for the error

Local error page handling

- **Handle errors generated by the proxy server**

Specifies if errors generated by the proxy server should be handled with the custom static error pages stored on the local file system. If this is not selected then the default error messages will be used instead of any custom error pages.

- **Handle errors generated by application servers**

Specifies if errors generated by the backend server should be handled with the custom static error pages stored on the local file system. If this is not selected then the default error messages will be used instead of any custom error pages.

- **Error mappings**

Specifies the error codes to match with specific static error pages stored on the file system. You can use a relative file path under the configured static file document root to assign a custom error file to be used for a specific error code or group of error codes. The wildcard character, *, is used to assign error files to groups of error codes.

Remote error page handling

- **Error page generation application URI**
Specifies the URI for the custom error page generation application.
- **Handle errors generated by the proxy server**
Specifies if errors generated by the proxy server should be handled with the custom error application deployed on the application server. If this is not selected then the default error messages will be used instead of any custom error pages.
- **Handle errors generated by application servers**
Specifies if errors generated by the backend server should be handled with the custom error application deployed on the application server. If this is not selected then the default error messages will be used instead of any custom error pages.
- **Headers to forward to Error page Application**
Specifies a list of the headers from the original request to forward to the error page generation application.
- **HTTP status codes that are to be recognized as errors**
Specifies a list of the status codes in a response that should be directed to the error page generation application.

Configuring a DMZ Secure Proxy Server for IBM WebSphere Application Server using the administrative console

You can create a DMZ Secure Proxy Server for IBM WebSphere Application Server inside of a network deployment cell using the administrative console of an administrative agent. You can then export the secure proxy server to a node in the demilitarized zone (DMZ) into which you can then import the configuration. After the secure proxy server is created on a node in the DMZ, administration can be done locally or it can be done using the Job Manager console.

About this task

The DMZ Secure Proxy Server for IBM WebSphere Application Server does not contain a web container and therefore does not have an administrative console. Secure proxy server configurations can also be managed within a network deployment application server cell and then imported locally into the DMZ Secure Proxy Server for IBM WebSphere Application Server using `wsadmin` commands. The configurations are created and maintained inside the network deployment application server cell as configuration-only profiles. The profiles are registered with the administrative agent and are then managed using the administrative console. You configure the secure proxy server profile in the network deployment application server cell, export the configuration to a configuration archive (CAR) file using the `exportProxyProfile` or `exportProxyServer` `wsadmin` command, transmit the CAR file to the local secure proxy server installation using FTP, and import the configuration into the DMZ Secure Proxy Server for IBM WebSphere Application Server using the `importProxyProfile` or `importProxyServer` `wsadmin` command. You then repeat the process if any changes are made to the secure proxy server configuration.

Procedure

1. Start an administrative agent on a network-deployment installation.
2. Register the secure proxy (configuration-only) profile with the administrative agent using the `registerNode` command.
3. Restart the administrative agent.
4. When the administrative agent prompts you with a list of the nodes that it manages, select the node from the secure proxy (configuration-only) profile.
5. From the administrative console of the administrative agent, select **Servers > Server Types > WebSphere proxy servers**.

6. Click **New** to access the Proxy Server Creation wizard.
7. Select the DMZ Secure Proxy Server for IBM WebSphere Application Server node.
8. Complete the steps in the wizard to create a new secure proxy server.
This new secure proxy server will only be used as a configuration. It cannot be started inside of the cell.
9. Set the **sipClusterCellName** custom property to be the cell name that contains the configured cluster of SIP containers. This step applies to the SIP proxy only, and not to the HTTP server. For more information about how to set this custom property, see the topic "SIP proxy server custom properties" in this information center.
10. Save the configuration.
11. Using the wsadmin tool, connect to the secure proxy server profile.
12. Export your configuration to be used inside of the DMZ; you can export the entire profile or export the server.
 - To export the profile, run the exportProxyProfile command. For example:
`AdminTask.exportProxyProfile(['-archive "c:/myCell.car"'])`
 - To export the server, run the exportProxyServer command. For example:
`AdminTask.exportProxyServer ('[-archive c:\myServer.ear -nodeName node1 -serverName proxy1]')`
13. Using FTP, transfer the configuration archive to the local secure proxy server node.
14. Start the wsadmin tool on the secure proxy server profile.
15. Import the entire profile, or import the server.
 - Use the importProxyProfile command to import the profile. In the following example, the existing secure proxy server in the profile is replaced with the server in the imported proxy profile; for example:
`AdminTask.importProxyProfile(['-archive', '/myCell.car', '-deleteExistingServers', 'true'])`
 - Use the importProxyServer command to import the server. In the following example, the existing secure proxy server is replaced with the imported proxy server; for example:
`AdminTask.importProxyServer(['-archive /myServer.ear -nodeInArchive node1 -serverInArchive proxy1 -deleteExistingServers'])`
16. Save the configuration changes.
Use the following command example to save your configuration changes:
`AdminConfig.save()`

Results

Successful completion of this procedure results in deployment of the DMZ Secure Proxy Server for IBM WebSphere Application Server on a node in the DMZ.

What to do next

You can now start and begin to use your DMZ Secure Proxy Server for IBM WebSphere Application Server.

Configure secure routing for a DMZ Secure Proxy Server for IBM WebSphere Application Server

You can configure the DMZ Secure Proxy Server for IBM WebSphere Application Server to route requests statically or dynamically.

Before you begin

Configure your profiles and security properties before you configure routing. See the topic Tuning the security properties for the DMZ Secure Proxy Server for IBM WebSphere Application Server. Decide

whether you want to configure static or dynamic routing.

About this task

Static routing is performed using a flat configuration file. Static routing is considered more secure than dynamic routing. With dynamic routing, requests are routed through a best match mechanism that determines the installed application or routing rule that corresponds to a specific request. The secure proxy server will dynamically discover the best route to a destination and distribute to servers with like protocols.

The secure routing options are:

- Use static routing with the `exportTargetTree` command.
- Use dynamic routing by setting up a core group bridge tunnel. See the topic *Configuring communication with a core group that resides on a DMZ Secure Proxy Server for IBM WebSphere Application Server*.

gotcha: Because the DMZ secure proxy server resides in a different cell from the application servers, it must be configured to trust the application server cell in order for Secure Sockets Layer (SSL) to work properly. See the third step in this procedure.

Use the following procedure to configure static or dynamic secure routing.

Procedure

- To configure static routing, follow these steps:
 1. Set the secure proxy server to use static routing, which is the default level after installation. You can do this by either setting the overall security level to high or by setting the custom security level for the routing property to `static`.
 2. Use the `wsadmin` tool to query for the `TargetTreeMbean` mbean.

```
mbean=AdminControl.queryNames('*:*,type=TargetTreeMbean,process=dmgr')
```

3. If your application uses Servlet 3.0 dynamic cookies, start the application that uses dynamic cookies.

4. Invoke the `exportTargetTree` method on the `TargetTree` mbean to a specified XML file.

```
AdminControl.invoke(mbean, 'exportTargetTree', '/opt/IBM/WebSphere/AppServer/targetTree.xml')
```

The static routing file is a special type of routing file that the proxy server uses to route a request from the proxy server directly to an application server. It is not used to route requests from the Web server plug-in to an application server.

5. Using the deployment manager command line, transfer the `targetTree.xml` file from the deployment manager to the `profile_root/staticRoutes` directory for the proxy server.

The file is transferred from the deployment manager to the proxy server by FTP or some other protocol.

If your secure proxy server is interfacing with multiple cells, you can add the static routing file for each cell to the `profile_root/staticRoutes` directory. The secure proxy server considers any `xxx.xml` file that is included in the in the `profile_root/staticRoutes` directory a static routing file. The file does not have to be named `targetTree.xml`.

When you add multiple `xxx.xml` files to the `profile_root/staticRoutes` directory for a secure proxy server, the secure proxy server merges the content of all of these files. The result of this merge is a single static routing file that the secure proxy server can use to route requests to servers in any of the cells.

gotcha: The merger process does not include any files in subdirectories of the `profile_root/staticRoutes` directory. Therefore the secure proxy server does not use any content that is contained in files located in any subdirectory when it routes requests to a servers.

Any attribute change that affects the content of the static routing file, such as a virtual host change, addition or deletion of a proxy server cluster member, a change in weight of a proxy server cluster member, or the installation or uninstallation of an application, automatically regenerates the static routing file.

6. Start the proxy server from the system command line:

```
profile_root/startServer proxy_server_name
```

- To configure dynamic routing, follow these steps:

1. Configure the core group bridge in the application server cell. See the topic Configuring communication with a core group that resides on a DMZ Secure Proxy Server for IBM WebSphere Application Server.

2. Export the tunnel template settings to a file. From the wsadmin tool, use the exportTunnelTemplate command to export the settings, as in the following example:

```
AdminTask.exportTunnelTemplate('[-tunnelTemplateName exportedTunnelTemplate  
-outputFileName tunnelTemplate1.props]')
```

3. Import the tunnel template settings into the DMZ proxy configuration, as in the following example:

```
AdminTask.importTunnelTemplate('[-inputFileName tunnelTemplate1.props  
-bridgeInterfaceNodeName DMZNode01 -bridge InterfaceServerName DMZProxyServer01]')
```

4. Start the proxy server from the system command line:

```
profile_root/startServer proxy_server_name
```

- To configure SSL communications, follow these steps:

1. Configure the `ssl.client.props` properties file using the `retrieveSigners` command. See the information center topic on using the `retrieveSigners` command for more details.

2. The `com.ibm.ssl.trustStore` property should be set to point to the secure proxy server `trust.p12` file. For example:

```
${user.root}/config/cells/SecureProxyCell1/nodes/SecureProxyNode1/trust.p12
```

3. Specify the truststore name of the cell in which the application servers reside when running the command. By default, its name is `CellDefaultTrustStore`. The `retrieveSigners` command can then be used to update the secure proxy server to trust the application server cell:

```
retrieveSigners CellDefaultTrustStore AnotherTrustStore -host mybackendDmgr.location.com -port 8879
```

Results

Completing this procedure results in configuring secure routing for a DMZ Secure Proxy Server for IBM WebSphere Application Server.

What to do next

You can now start and begin to use the DMZ Secure Proxy Server for IBM WebSphere Application Server.

WebSphere DMZ Secure Proxy Server for IBM WebSphere Application Server

The DMZ Secure Proxy Server for IBM WebSphere Application Server can be used to provide a secure platform for your proxy server.

The DMZ Secure Proxy Server for IBM WebSphere Application Server installation enables you to install your proxy server in the demilitarized zone (DMZ), while reducing the security risk that might occur if you choose to install an application server in the DMZ to host a proxy server. The risk is reduced by removing any functionality from the application server that is not required to host the proxy servers, but that can pose a security risk. Installing the secure proxy server in the DMZ rather than the secured zone presents new security challenges. However, the secure proxy server is equipped with capabilities to provide protection from these challenges.

The following capabilities are available to harden the security of the DMZ Secure Proxy Server for IBM WebSphere Application Server and to determine the level of security to assign.

- Startup user permissions

The secure proxy server process can be changed to run as an unprivileged user after startup. Although the secure proxy server must be started as a privileged user, changing the server process to run as an unprivileged user provides additional protection for local operating resources.
- Routing considerations

The secure proxy server can be configured to route requests to target servers based on static routing information or dynamic information. Static routing means that the server obtains the routing information from local flat files. Dynamic routing means that the server obtains the routing information from a Hypertext Transfer Protocol (HTTP) tunnel connection from the proxy server to a server in the secure zone. It is more secure to use static routing as the use of dynamic routing requires an additional connection through the inner firewall. Static routing is only applicable to HTTP requests.
- Administration options

The secure proxy server does not contain a web container, and therefore is unable to host the administrative console. It is better to not have a web container on a DMZ Secure Proxy Server for IBM WebSphere Application Server since hosting application artifacts is considered a security risk and adds an unnecessary footprint to the proxy server. The secure proxy server is installed separately and has several different administrative options that have security implications.
- Error handling

Custom error pages can be used by the secure proxy server for specific error codes or groups of error codes. A custom error page application can be used to generate error messages or flat custom error page files can be stored locally on the file system and used during run time. Choosing to use flat custom error pages instead of a custom error application provides a higher level of security. Choosing this option limits the code path and eliminates the need for a potentially unauthorized application to be run when an error page is needed.
- Denial of service protection

Denial of service protection is provided with the inclusion of two properties: Maximum request body buffer chunk size and Maximum response body buffer chunk size. These properties must be tuned to balance the level of protection with the performance overhead that might be experienced if these properties are set incorrectly.

When creating the DMZ Secure Proxy Server for IBM WebSphere Application Server, you can choose any of the default security levels: High, Medium or Low.

- Low DMZ security level

Table 28. Low DMZ security level default values. This table describes the settings and default values for the low DMZ security level.

Setting	Default value
Startup permissions	Run as a privileged user
Routing	Dynamic routing
Administration	Remote Administration
Error handling	Local error page handling

- Medium DMZ security level

Table 29. Medium DMZ security level default values. This table describes the settings and default values for the medium DMZ security level.

Setting	Default value
Startup permissions	Run as an unprivileged user
Routing	Dynamic routing

Table 29. Medium DMZ security level default values (continued). This table describes the settings and default values for the medium DMZ security level.

Setting	Default value
Administration	Local Administration
Error handling	Local error page handling

- High DMZ security level

Table 30. High DMZ security level default values. This table describes the settings and default values for the high DMZ security level.

Setting	Default value
Startup permissions	Run as an unprivileged user
Routing	Static routing
Administration	Local Administration
Error handling	Local error page handling

Important: The High DMZ security level cannot be used for SIP proxy servers, because static routing cannot be used for the SIP proxy server.

In addition to these predefined settings, you can customize the settings to better serve your requirements. If you choose to customize the settings, your DMZ Secure Proxy Server for IBM WebSphere Application Server is assigned a qualitative categorization of your security level called the *current* security level. Each custom setting has been assigned a value of High, Medium or Low. The current security level is equal to the value of the least secure setting being used. To achieve a current security level of High, only settings assigned the high value can be configured. To achieve a current security level of Medium, only settings with values of High or Medium can be used. A current security level of Low is used if any settings that are assigned the value of Low are set.

An additional change to enhance the protection for the DMZ Secure Proxy Server for IBM WebSphere Application Server is the switch from a Java Development Kit (JDK) to a Java Runtime Environment (JRE). Switching from a JDK to a JRE removes the inclusion of a compiler on the installation. This change is beneficial because the compiler can possibly be used for malicious purposes in the event of a security breach.

No JRE currently is available for i5/OS systems; therefore, a JDK is used. For protection against this type of threat, you can manually remove the tools.jar file from the JDK installation root.

Appendix. Directory conventions

References in product information to *app_server_root*, *profile_root*, and other directories imply specific default directory locations. This topic describes the conventions in use for WebSphere Application Server.

Default product locations - IBM i

These file paths are default locations. You can install the product and other components in any directory where you have write access. You can create profiles in any valid directory where you have write access. Multiple installations of WebSphere Application Server products or components require multiple locations.

app_client_root

The default installation root directory for the Application Client for IBM WebSphere Application Server is the /QIBM/ProdData/WebSphere/AppClient/V8/client directory.

app_client_user_data_root

The default Application Client for IBM WebSphere Application Server user data root is the /QIBM/UserData/WebSphere/AppClient/V8/client directory.

app_client_profile_root

The default Application Client for IBM WebSphere Application Server profile root is the /QIBM/UserData/WebSphere/AppClient/V8/client/profiles/*profile_name* directory.

app_server_root

The default installation root directory for WebSphere Application Server Network Deployment is the /QIBM/ProdData/WebSphere/AppServer/V8/ND directory.

java_home

Table 31. Root directories for supported Java Virtual Machines.

This table shows the root directories for all supported Java Virtual Machines (JVMs).

JVM	Directory
32-bit IBM Technology for Java	/QOpenSys/QIBM/ProdData/JavaVM/jdk60/32bit
64-bit IBM Technology for Java	/QOpenSys/QIBM/ProdData/JavaVM/jdk60/64bit

plugins_profile_root

The default Web Server Plug-ins profile root is the /QIBM/UserData/WebSphere/Plugins/V8/webserver/profiles/*profile_name* directory.

plugins_root

The default installation root directory for Web Server Plug-ins is the /QIBM/ProdData/WebSphere/Plugins/V8/webserver directory.

plugins_user_data_root

The default Web Server Plug-ins user data root is the /QIBM/UserData/WebSphere/Plugins/V8/webserver directory.

product_library

product_lib

This is the product library for the installed product. The product library for each Version 8.0 installation on the system contains the program and service program objects (similar to .exe, .dll, .so objects) for the installed product. The product library name is QWAS8x (where x is A, B, C, and so on). The product library for the first WebSphere Application Server Version 8.0 product installed on the system is QWAS8A. The *app_server_root*/properties/product.properties file contains the value for the product library of the installation, was.install.library, and is located under the *app_server_root* directory.

profile_root

The default directory for a profile named *profile_name* for WebSphere Application Server Network Deployment is the `/QIBM/UserData/WebSphere/AppServer/V8/ND/profiles/profile_name` directory.

shared_product_library

The shared product library, which contains all of the objects shared by all installations on the system, is QWAS8. This library contains objects such as the product definition, the subsystem description, the job description, and the job queue.

user_data_root

The default user data directory for WebSphere Application Server Network Deployment is the `/QIBM/UserData/WebSphere/AppServer/V8/ND` directory.

The profiles and profileRegistry subdirectories are created under this directory when you install the product.

web_server_root

The default web server path is `/www/web_server_name`.

Notices

References in this publication to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APACHE INFORMATION. This information may include all or portions of information which IBM obtained under the terms and conditions of the Apache License Version 2.0, January 2004. The information may also consist of voluntary contributions made by many individuals to the Apache Software Foundation. For more information on the Apache Software Foundation, please see <http://www.apache.org>. You may obtain a copy of the Apache License at <http://www.apache.org/licenses/LICENSE-2.0>.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Intellectual Property & Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
USA

Trademarks and service marks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corporation in the United States, other countries, or both. If these and other IBM trademarked terms are marked on their first occurrence in this information with a trademark symbol (® or ™), these symbols indicate U.S. registered or common law trademarks owned by IBM at the time this information was published. Such trademarks may also be registered or common law trademarks in other countries. For a current list of IBM trademarks, visit the IBM Copyright and trademark information Web site (www.ibm.com/legal/copytrade.shtml).

Microsoft and Windows are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Other company, product, or service names may be trademarks or service marks of others.

Index

C

- clusters
 - proxy server 187

D

- DataPower
 - appliance domain
 - history information 129
 - appliance manager 98, 111, 112
 - managed domain versions 128
 - tasks 126
 - appliances 102, 104, 105, 107, 131
 - domains 131
 - managed sets 116, 118, 120, 123
 - configurations
 - appliance manager 125, 126
 - settings
 - appliance firmware 114, 115
 - appliance managed domains 132
 - appliance manager 124
 - appliance manager history 130
 - appliances 104, 107
 - sharable appliances 129
- directory
 - installation
 - conventions 60, 271
- DMZ Secure Proxy Server 267

I

- installation
 - proxy server 203

P

- profiles
 - proxy server 191
- proxy server 137
 - actions 229, 230
 - adding
 - HTTP endpoints 193
 - administering 225
 - rule expressions 252
 - cache 194, 195, 196
 - cluster configuration 146
 - cluster members 147, 183, 185, 186
 - cluster ports 147
 - clusters 181, 182
 - generic server 146
 - mapping 242
 - configuration 139
 - administration console 264
 - cluster mapping 242, 243, 245
 - URI 148
 - creating 136, 187
 - cluster 187

- proxy server (*continued*)
 - creating (*continued*)
 - cluster members 188
 - summary settings 189
 - custom advisors 240, 241, 246
 - custom properties 154
 - deployment
 - custom filter 256
 - DMZ Secure Proxy Server 267
 - failover 203
 - inbound channel 151
 - installation 203
 - managing 189
 - modifying
 - HTTP endpoints 193
 - performance
 - PMI 199
 - traffic 199
 - policies 199
 - profiles 191
 - request mapping 200
 - rewriting rules 150, 151
 - routing
 - customizing 191
 - ODC compliant applications 192
 - requests 193, 196
 - rules 148, 149
 - troubleshooting 220
 - rule expressions 253, 254
 - rules 229
 - security 265
 - settings 140
 - cache actions 232
 - cluster mapping 242, 244, 245
 - cluster member templates 186
 - cluster members 184
 - cluster route actions 237
 - clusters 183
 - HTTP compression actions 232
 - HTTP header actions 233
 - policies 241
 - rewrite actions 234
 - route actions 236
 - rule expressions 255
 - SIP 208
 - static cache rules 196
 - time mapping 239
 - virtual hosts 250, 251
- setup 135
- SIP 204
 - condition 215
 - custom properties 160
 - external domains 212
 - high availability 206
 - inbound channel 216
 - load balancing 207
 - messages 204
 - network outage detection 225

- proxy server *(continued)*
 - SIP *(continued)*
 - overload protection 223
 - routing 213, 214
 - rules 215
 - settings 208
 - trace 205
 - workload management 206
 - starting 152
 - stopping 153
 - troubleshooting 217, 220
 - URI groups 148
 - virtual hosts 249, 250
 - wsadmin commands 197

R

- routing
 - proxy server 191, 192, 220
 - requests 193

S

- security
 - routing 265

SIP

- custom properties 169
- proxy server
 - condition 215
 - custom properties 160
 - external domains 212
 - inbound channel 216
 - load balancing 207
 - messages 204
 - network outage detection 225
 - overload protection 223
 - routing 214, 221
 - rules 215
 - trace 205
 - troubleshooting 217
- settings
 - proxy server 208