

ADSTAR Distributed Storage Manager
for VM



Administrator's Guide

Version 2

Note!

Before using this information and the product it supports, be sure to read the general information under "Notices" on page xiii.

This book is also available in a softcopy form that can be viewed with the IBM BookManager READ licensed program.

First Edition (September 1996)

This edition applies to Version 2 of the ADSTAR Distributed Storage Manager for VM (5654-A02) and to any subsequent releases until otherwise indicated in new editions or technical newsletters. Make sure you are using the correct edition for the level of the product.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

A form for readers' comments is provided at the back of this publication. If the form has been removed, address your comments to:

IBM Corporation
Information Development, Department 61C
9000 South Rita Road
Tucson, AZ 85744-0001, U.S.A.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 1993, 1996. All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

Notices	xiii
Programming Interface	xiii
Trademarks	xv
Preface	xvii
Who Should Read This Publication	xvii
What You Should Know before Reading This Publication	xvii
Conventions Used in This Book	xvii
ADSTAR Distributed Storage Manager Publications	xviii
Related VM System Publications	xix
IBM International Technical Support Center Publications (Redbooks)	xx
Software Developer's Program	xx
Do You Have Comments or Suggestions?	xx
Translations	xx
Summary of Changes for ADSTAR Distributed Storage Manager	xxi
Changes for Version 2—September 1996	xxi

Part 1. ADSM Basics 1

Chapter 1. Introducing ADSTAR Distributed Storage Manager	3
How ADSM Stores Client Data	6
How ADSM Represents Devices	9
Disk and Tape Devices	9
Files on Disk as Logical Devices	9
How ADSM Represents Storage Media	10
What Are the ADSM Storage Objects?	10
Device Class	10
Storage Pools	11
Storage Pool Volumes	11
What Does a Device Class Contain?	11
Device Classes for Random Access Devices	11
Device Classes for Sequential Access Devices	11
Putting It All Together	12
Planning to Configure the ADSM Storage Environment	14
Evaluating Your Storage Environment	14
Mapping Devices to Device Classes	14
Mapping Storage Pools to Device Classes and Devices	15
Configuring Devices	16
Automating Client Operations	16
Chapter 2. Administrator Tasks	19
Interfaces to ADSM	19
Using Magnetic Disk Devices with ADSM	20

Using Tape Devices with ADSM	20
Managing Tape Operations	20
Defining Device Classes	20
Managing Storage Pools	21
Managing Storage Pool Volumes	21
Managing Policies	21
Automating Operations	22
Managing Server Operations	22
Managing the Database and Recovery Log	22
Managing Licensing, Privilege Classes, and Registration	22
Exporting and Importing Data	23
Protecting and Recovering Your Data	23

Part 2. Configuring and Managing Data Storage 25

Chapter 3. Using Magnetic Disk Devices with ADSM	27
Setting Up Storage Pools on Disk Devices	27
Using Random Access Volumes on Disk Devices	27
Using Disk for FILE Logical Devices	28
Notes on Operations	29
Using Cache	29
Freeing Space on Disk	30
FILE Volumes Used for Database Backups and Export Operations	30
Chapter 4. Using Tape Devices with ADSM	31
Overview of Using Devices with ADSM	31
Example of Setting Up Two 3490E Drives	32
Notes on Operations	34
Mount Operations	35
Collocation	35
Maintaining the Volume Inventory	35
Understanding the Server Tape Processing	36
Using the Internal Mounting Facility	37
Using Exit Machines	37
Assigning CP Command Privilege Classes for Server and Exit Machines	38
Understanding How the Server Selects and Handles Tapes	39
Handling Tape Mount Requests and Exit Machines	42
Querying Mount Requests	43
Querying Mounted Tapes	43
Querying the Status of Exit Machines	44
Replying to Mount Requests When Using the Internal Mounting Facility	44
Replying to Mount Requests When Using Exit Machines	45
Readying Exit Machines	45
Canceling Mount Requests When Using the Internal Mounting Facility	45
Canceling Mount Requests When Using Exit Machines	46
Dismounting Tapes	46
Chapter 5. Using Exit Machines	47

Defining the Exit Machines	48
Setting up an Exit Machine	48
Providing Input to an Exit Machine	49
Satisfying a Tape Mount Request	50
DSMMOUNT EXEC Examples	51
Processing a DELETE Request	65
Example of the DSMDELET EXEC	67
Chapter 6. Defining Device Classes	69
Defining and Updating Device Classes for Sequential Media	70
Defining and Updating Device Classes for Tape	70
Defining and Updating FILE Device Classes	75
Requesting Information about a Device Class	77
Deleting a Device Class	78
Filling Volumes to Capacity	78
Tape Volume Capacity and Data Compression	79
Chapter 7. Managing Storage Pools	81
Storage Pools	81
An Example of Server Storage	83
Assigning Volumes to Storage Pools	85
Assigning Random Access Storage Pool Volumes	85
Assigning Sequential Access Storage Pool Volumes	85
Storage Pool Hierarchy	85
How ADSM Stores Files in a Storage Pool Hierarchy	86
How the Storage Hierarchy Affects Planning for Copy Storage Pools	88
Using the Hierarchy to Stage Client Data from Disk to Tape	88
Server Migration of Files	89
Migration Thresholds for Disk Storage Pools	89
Migration Thresholds for Sequential Access Storage Pools	93
Migration and Copy Storage Pools	94
The Use of Cache on Disk Storage Pools	94
Why Use Cache?	95
When Not to Use Cache	95
Collocation on Sequential Access Storage Pools	95
How the Server Selects Volumes with Collocation Enabled	98
How the Server Selects Volumes with Collocation Disabled	98
Turning Collocation On or Off	99
Collocation on Copy Storage Pools	99
Space Reclamation for Sequential Access Storage Pools	100
Choosing a Reclamation Threshold	101
Reclamation for Copy Storage Pools	102
How Collocation Affects Reclamation	104
Reclamation in a Device Class with Only One Mount Point	105
Expiration Processing	105
Delaying Reuse of Sequential Access Volumes	105
How Restore Processing Works	106
Estimating Space Needs for Storage Pools	107

Estimating Space Needs in Random Access Storage Pools	108
Estimating Space Needs in Sequential Access Storage Pools	109
Defining or Updating Storage Pools	110
Defining a Primary Storage Pool	110
Defining a Copy Storage Pool	113
Backing Up Storage Pools	114
Using Copy Storage Pools to Improve Data Availability	116
Example: Simple Hierarchy with One Copy Storage Pool	116
Monitoring the Use of Storage Pools	117
Monitoring the Use of Storage Pool Space	117
Monitoring Migration Processes	118
Monitoring the Use of Cache Space on Disk Storage	122
Requesting Information on Storage Occupancy	123
Deleting a Storage Pool	126
Restoring Storage Pools	127
What Happens When a Storage Pool Is Restored	128
When a Storage Pool Restoration is Incomplete	129
Chapter 8. Managing Storage Pool Volumes	131
Storage Pool Volumes	131
Access Modes for Storage Pool Volumes	132
Adding Random Access Storage Pool Volumes	133
Defining Storage Pool Volumes	133
Updating Storage Pool Volumes	133
Monitoring the Use of Storage Pool Volumes	135
Requesting General Information about Storage Pool Volumes	135
Requesting Detailed Information about Storage Pool Volumes	135
Requesting Information about Storage Pool Volume Contents	137
Auditing a Storage Pool Volume	139
What Happens When You Audit Storage Pool Volumes	140
Auditing a Volume in a Disk Storage Pool	141
Auditing Multiple Volumes in a Sequential Access Storage Pool	142
Auditing a Single Volume in a Sequential Access Storage Pool	143
Moving Files from One Volume to Another Volume	143
Moving Data to Other Volumes in the Same Storage Pool	144
Moving Data to Another Storage Pool	144
Moving Data from an Offsite Volume in a Copy Storage Pool	145
Procedure for Moving Data	145
Deleting Storage Pool Volumes	147
Deleting an Empty Storage Pool Volume	148
Deleting a Storage Pool Volume with Data	148
Restoring Storage Pool Volumes	149
What Happens When a Volume Is Restored	150
When a Volume Restoration is Incomplete	150

Part 3. Policies 153

Chapter 9. Managing Policies 155

Operations Controlled by Policy	156
Backup and Restore	156
Archive and Retrieve	156
Migration and Recall	156
Policy Objects	157
Management Classes	159
Management Class Configuration	159
Default Management Classes	160
The Include-Exclude List	160
How Files Are Associated with a Management Class	161
File Eligibility for Policy Operations	164
Incremental Backup	164
Selective Backup	166
Archive	166
Automatic Migration from a Client Node	167
How Client Migration Works with Backup and Archive	167
Using the Standard Storage Management Policies	168
Creating Your Own Storage Management Policies	169
Defining and Updating a Policy Domain	172
Defining and Updating a Policy Set	173
Defining and Updating a Management Class	174
Defining and Updating a Backup Copy Group	175
Defining and Updating an Archive Copy Group	179
Assigning a Default Management Class	181
Validating and Activating Policy Sets	181
Activating Policy Sets	182
Running Expiration Processing to Delete Expired Files	183
Querying Policy Objects	184
Querying Copy Groups	184
Querying Management Classes	185
Querying Policy Sets	186
Querying Policy Domains	186
Deleting Policy Objects	187
Deleting Copy Groups	187
Deleting Management Classes	187
Deleting Policy Sets	188
Deleting Policy Domains	188

Part 4. Automating Operations 191

Chapter 10. Automating Operations	193
Automating Server Operations	194
Defining the Schedule	194
Verifying the Schedule	195
Automating Client Operations	195
Defining the Client Schedule	196
Associating Client Nodes with Schedules	196
Starting the Scheduler on the Clients	197

Verifying the Schedule	197
Coordinating Client Schedules	198
Setting the Scheduling Mode	199
Specifying the Schedule Period for Incremental Backup Operations	200
Controlling the Server's Scheduled Workload	200
Controlling Contact with the Server	202
Tailoring Schedules	204
Common Schedule Parameters	204
Specifying Administrative Command Schedule Parameters	205
Specifying Client Schedule Parameters	206
Copying Schedules	208
Deleting Schedules	209
Managing Scheduled Event Records	209
Querying Event Records	209
Removing Event Records from the Database	211
Managing Client Associations with Schedules	212
Querying Associations	212
Deleting Associations	213

Part 5. Maintaining the Server 215

Chapter 11. Managing Server Operations	217
Starting, Halting, and Restarting the Server	217
Starting the Server	217
Halting the Server	218
Restarting the Server	219
Managing Client Sessions	219
Requesting Information about Client Sessions	219
Canceling a Client Session	221
Disabling or Enabling Server Access	221
Managing Server Processes	222
Requesting Information about Server Processes	223
Canceling Server Processes	223
Varying Disk Volumes Online or Offline	224
Requesting Information about Server Status	224
Setting the Server Name	225
Querying Server Options	225
Managing the Activity Log	226
Changing the Size of the Activity Log	226
Setting the Activity Log Retention Period	227
Requesting Information from the Activity Log	227
Monitoring ADSM Accounting Records	228
VM Accounting Record Type '01'	228
VM Accounting Record Type '02'	229
VM Accounting Record Type '03'	230
Getting Help on Commands and Error Messages	230
Chapter 12. Managing the Database and Recovery Log	233

Database and Recovery Log	233
How ADSM Processes Transactions	234
How Space is Managed by the Server	234
Estimating and Monitoring Database and Recovery Log Space Requirements	236
Monitoring the Database and Recovery Log	236
Adding Space to the Database or Recovery Log	238
Step 1: Allocating Space for the Database and Recovery Log	238
Step 2: Defining Database or Recovery Log Volumes to ADSM	240
Step 3: Extending the Capacity of the Database or Recovery Log	241
Deleting Space from the Database or Recovery Log	242
Step 1: Determining If Volumes Can Be Deleted	243
Step 2: Reducing the Capacity of the Database or Recovery Log	244
Step 3: Deleting a Volume from the Database or Recovery Log	245
Optimizing the Performance of the Database or Recovery Log	246
Adjusting the Database Buffer Pool	246
Adjusting the Recovery Log Buffer Pool	248
Chapter 13. Managing Licensing, Privilege Classes, and Registration	251
Managing ADSM Licenses	251
Licensed Features	252
License Compliance	254
Monitoring Licenses	254
Ensuring Client/Server Authentication	255
Setting Password Authentication	255
Setting User Password Expiration	255
Registering Administrators or Updating Information	256
Granting Administrative Authority	256
System Privilege	257
Unrestricted Policy Privilege	258
Restricted Policy Privilege	258
Unrestricted Storage Privilege	258
Restricted Storage Privilege	259
Operator Privilege	260
Analyst Privilege	260
Changing Administrative Authority	260
Extending Administrative Privilege	260
Revoking One or More Administrative Privilege Classes	261
Revoking All Administrative Privilege Classes	261
Reducing Privilege Classes	261
Managing Administrator Access	262
Renaming an Administrator	262
Removing Administrators	262
Locking and Unlocking Administrators from the Server	263
Managing Client Nodes	264
Setting Client Node Registration	265
Managing Client Node Access	267
Requesting Information about Client Nodes	268
Requesting Information about File Spaces	269

Deleting File Spaces and Client Nodes	270
Registering an Application Programming Interface to the Server	271
Understanding How the Compression Option is Set	271
Understanding How the File Deletion Option is Set	272
Chapter 14. Exporting and Importing Data	273
Data That Can Be Exported and Imported	274
Preparing to Export or Import Data	274
Using Preview before Exporting or Importing Data	275
Planning for Sequential Media Used to Export Data	275
Monitoring Export and Import Processes	276
Requesting Information about an Export or Import Process	277
Viewing Information from the Server Console	277
Viewing Information from an Administrative Client	278
Querying the Activity Log for Export or Import Information	279
Exporting Data to Sequential Media Volumes	280
Deciding When to Export Data	281
Exporting Server Data	282
Exporting Administrator Information	282
Exporting Client Node Information	283
Exporting Policy Information	284
Importing Data from Sequential Media Volumes	284
Step 1: Previewing Information before You Import Data	285
Step 2: Importing Definitions	287
Step 3: Tailoring Server Storage Definitions on the Target Server	289
Step 4: Importing File Data Information	290
Considerations When Importing Data	292
Recovering from Errors during the Import Process	293

Part 6. Protecting the Server 295

Chapter 15. Protecting and Recovering Your Data	297
Levels of Protection	297
Storage Pool Protection	298
Database and Recovery Log Protection	298
An Overview of the Process	301
Backing Up Storage Pools	302
Mirroring the Database and Recovery Log	303
Allocating Volume Copies to Separate Physical Disks	303
Defining Database or Recovery Log Mirrored Volumes	304
Requesting Information about Mirrored Volumes	305
Backing Up the Database	306
Defining Device Classes for Backups	306
Setting the Recovery Log Mode	306
Scheduling Database Backups	307
Estimating the Size of the Recovery Log	308
Setting a Database Backup Trigger	309
Saving the Volume History File	311

Saving the Device Configuration Backup File	312
Doing Full and Incremental Backups	314
Recovering by Using Mirrored Volumes	314
Recovering by Using Database and Storage Pool Backups	314
Restoring a Database to a Point in Time	316
Restoring a Database to its Most Current State	319
Correcting Damaged Files	319
Maintaining the Integrity of Files	320
Restore Damaged Files	320
Backup and Recovery Scenarios	322
Protecting Your Database and Storage Pool	322
Recovering to a Point in Time from a Disaster	324
Recovering a Lost or Damaged Storage Pool Volume	325

Part 7. Appendix, Glossary, and Index	327
Appendix A. Interface Cross-Reference	329
Glossary	337
Index	355

Notices

References in this publication to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any of the intellectual property rights of IBM may be used instead of the IBM product, program, or service. The evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, are the responsibility of the user.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Licensing, IBM Corporation, 500 Columbus Avenue, Thornwood, New York 10594, U.S.A. Refer to the HONE SALESMANUAL or product announcement letters for the most current product information.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact IBM Corporation, Information Enabling Requests, Dept. M13, 5600 Cottle Road, San Jose, CA 95193, U.S.A. Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

Programming Interface

This publication is intended to help the customer plan for and manage the ADSM server.

This publication also documents General-use Programming Interface and Associated Guidance Information, Product-sensitive Programming Interface and Associated Guidance Information, and Diagnosis, Modification or Tuning Information provided by ADSM.

General-use programming interfaces allow the customer to write programs that obtain the services of ADSM.

General-use Programming Interface and Associated Guidance Information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

_____ General-use programming interface _____

General-use Programming Interface and Associated Guidance Information...

_____ End of General-use programming interface _____

Product-sensitive programming interfaces allow the customer installation to perform such tasks as diagnosing, modifying, monitoring, repairing, tailoring, or tuning of ADSM. Use of such interfaces creates dependencies on the detailed design or implementation of the IBM software product. Product-sensitive programming interfaces should be used only for these specialized purposes. Because of their dependencies on detailed design and implementation, it is to be expected that programs written to such interfaces may need to be changed in order to run with new product releases or versions, or as a result of service.

Product-sensitive Programming Interface and Associated Guidance Information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

_____ Product-sensitive programming interface _____

Product-sensitive Programming Interface and Associated Guidance Information...

_____ End of Product-sensitive programming interface _____

Diagnosis, Modification or Tuning Information is provided to help the customer to do diagnosis of ADSM.

Attention: Do not use this Diagnosis, Modification or Tuning Information as a programming interface.

Diagnosis, Modification or Tuning Information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

_____ Diagnosis, Modification or Tuning Information _____

Diagnosis, Modification or Tuning Information...

_____ End of Diagnosis, Modification or Tuning Information _____

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

ACF/VTAM	DFSMS	Proprinter
AD/Cycle	DFSMS/MVS	PS/2
ADSTAR	DFSMSdss	RACF
Advanced Peer-to-Peer Networking	ESCON	RISC System/6000
AIX	IBM	RS/6000
AIX/6000	IBMLink	SAA
AIXwindows	Language Environment	SP2
Application System/400	Library Reader	System/370
APPN	MVS/DFP	System/390
AS/400	MVS/ESA	Systems Application Architecture
AT	MVS/SP	SystemView
BookManager	MVS/XA	Virtual Machine/Enterprise Systems Architecture
C/370	OpenEdition	Virtual Machine/Extended Architecture
CICS	Operating System/2	VM/ESA
Common User Access	Operating System/400	VM/XA
CUA	OS/2	VSE/ESA
DATABASE 2	OS/400	VTAM
DB2/6000	POWERparallel	WIN-OS/2

The following terms are trademarks of other companies:

Trademark	Company	Trademark	Company
Andataco	Andataco Corporation	NetWare	Novell, Inc.
Apple	Apple Computer, Inc.	NFS	Sun Microsystems, Inc.
Attachmate	Attachmate Corporation	Novell	Novell, Inc.
CompuServe	CompuServe, Inc.	Open Desktop	The Santa Cruz Operation, Inc.
dBASE	Borland International, Inc.	OpenWindows	Sun Microsystems, Inc.
DECstation	Digital Equipment Corporation	PARADOX	Borland International, Inc.
DLT	Quantum Corporation	PC/TCP	FTP Software, Inc.
DPX/20	Groupe Bull	PTX	Sequent Computer Systems
Dynatek	Dynatek Automation Systems	SCO	The Santa Cruz Operation, Inc.
DynaText	Electronic Book Technologies, Inc.	Sequent	Sequent Computer Systems
Exabyte	Exabyte Corporation	SINIX	Siemens Nixdorf Information Systems, Inc.
Extra!	Attachmate Corporation		
FOXPRO	Microsoft Corporation	Solaris	Sun Microsystems, Inc.
Hewlett-Packard	Hewlett-Packard Company	Sony	Sony Corporation
HP-UX	Hewlett-Packard Company	SPARC	SPARC International, Inc.
Ice Box	Software International Microsystems	StorageTek	Storage Technology Corporation
iFOR/LS	Gradient Technologies, Inc.	Sun	Sun Microsystems, Inc.
INGRES	ASK Group, Inc.	Sun Microsystems	Sun Microsystems, Inc.
Intel	Intel Corporation	SunOS	Sun Microsystems, Inc.
Iomega	Iomega Corporation	Sun-3	Sun Microsystems, Inc.
IPX/SPX	Novell, Inc.	Sun-4	Sun Microsystems, Inc.
IRIX	Silicon Graphics, Inc.	SureStore	Hewlett-Packard Company
Jetstore	Hewlett-Packard Company	SyQuest	SyQuest Technology, Inc.
Lotus	Lotus Development Corporation	ULTRIX	Digital Equipment Corporation
Lotus Notes	Lotus Development Corporation	WangDAT	Tecmar Technologies, Inc.
Macintosh	Apple Computer, Inc.	Windows 95	Microsoft Corporation
MacTCP	Apple Computer, Inc.	Windows NT	Microsoft Corporation
Motif	Open Software Foundation, Inc.	X Windows	Massachusetts Institute of Technology

C-bus is a trademark of Corollary, Inc.

Microsoft, Windows, and the Windows 95 logo are trademarks or registered trademarks of Microsoft Corporation.

PC Direct is a trademark of Ziff Communications Company and is used by IBM Corporation under license.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

Other company, product, and service names, which may be denoted by a double asterisk (**), may be trademarks or service marks of others.

Preface

ADSTAR Distributed Storage Manager (ADSM) is a client/server program that provides storage management solutions to customers in a multivendor computer environment. ADSM provides an automated, centrally scheduled, policy-managed backup, archive, and space-management facility for file servers and workstations.

Who Should Read This Publication

This guide is intended for anyone who has been assigned an ADSM administrator user ID and an administrative privilege class. While ADSM can be managed by a single administrator, administrative responsibilities can be divided among several people as an installation requires.

All of the administrator commands you need to operate and maintain ADSM can be invoked from a workstation connected to the server.

What You Should Know before Reading This Publication

You should be familiar with the operating system on which the server resides and the communication protocols required for the client/server environment.

For information on product requirements for ADSM, see *ADSTAR Distributed Storage Manager for VM: Licensed Program Specifications*. For information on installing ADSM, see *ADSTAR Distributed Storage Manager for VM: Quick Start*.

You also need to understand the storage management practices of your organization, such as how you are currently backing up your workstation files and how you are using random access media and sequential access media.

Conventions Used in This Book

To help you recognize where example commands are to be entered, this book uses the following conventions:

- Command to be entered on the VM command line:

```
attach fe8 dsmserv 400
```

- Command to be entered on the command line of an administrative client:

```
query devclass
```

- Command to be entered on the OS/2 command line:

```
> dsmadmc -mountmode
```

ADSTAR Distributed Storage Manager Publications

The ADSM library is available in softcopy on the following CD-ROMs:

Title	Order Number
ADSM Online Library	SK2T-1893
IBM Online VM Collection	SK2T-2067

The following table lists ADSM publications.

Short Title	Publication Title	Order Number
ADSM General Information	<i>ADSTAR Distributed Storage Manager: General Information</i>	GH35-0131
ADSM Messages	<i>ADSTAR Distributed Storage Manager: Messages</i>	SH35-0133
ADSM Licensed Program Specifications	<i>ADSTAR Distributed Storage Manager for VM: Licensed Program Specifications</i>	GC35-0226
ADSM Quick Start	<i>ADSTAR Distributed Storage Manager for VM: Quick Start</i>	GC35-0227
ADSM Administrator's Reference	<i>ADSTAR Distributed Storage Manager for VM: Administrator's Reference</i>	GC35-0229
ADSM Using the UNIX HSM Clients	<i>ADSTAR Distributed Storage Manager: Using the UNIX Hierarchical Storage Management Clients</i>	SH26-4030
ADSM V2 Using the Apple Macintosh Backup-Archive Client	<i>ADSTAR Distributed Storage Manager Version 2: Using the Apple Macintosh Backup-Archive Client</i>	SH26-4051
ADSM Using the UNIX Backup-Archive Clients	<i>ADSTAR Distributed Storage Manager Version 2: Using the UNIX Backup-Archive Clients</i>	SH26-4052
ADSM V2 Using the OS/2 Backup-Archive Client	<i>ADSTAR Distributed Storage Manager Version 2: Using the OS/2 Backup-Archive Client</i>	SH26-4053
ADSM V2 Using the DOS Backup-Archive Client	<i>ADSTAR Distributed Storage Manager Version 2: Using the DOS Backup-Archive Client</i>	SH26-4054

Short Title	Publication Title	Order Number
ADSM V2 Using the Novell NetWare Backup-Archive Client	<i>ADSTAR Distributed Storage Manager Version 2: Using the Novell NetWare Backup-Archive Client</i>	SH26-4055
ADSM V2 Using the Microsoft Windows Backup-Archive Clients	<i>ADSTAR Distributed Storage Manager Version 2: Using the Microsoft Windows Backup-Archive Clients</i>	SH26-4056
ADSM Using the Lotus Notes Backup Agent	<i>ADSTAR Distributed Storage Manager: Using the Lotus Notes Backup Agent</i>	SH26-4047
ADSM Installing the Clients	<i>ADSTAR Distributed Storage Manager: Installing the Clients</i>	SH26-4049
ADSM Client Reference Cards	<i>ADSTAR Distributed Storage Manager: Client Reference Cards</i>	SX26-6013
ADSM Using the Application Programming Interface	<i>ADSTAR Distributed Storage Manager: Using the Application Programming Interface</i>	SH26-4002

Related VM System Publications

The following table lists related VM publications.

Publication Title	Order Number
VM/ESA Version 1	
<i>VM/ESA CP Planning and Administration</i>	SC24-5521
<i>VM/ESA CMS Command Reference</i>	SC24-5461
<i>VM/ESA SFS and CRR Planning, Administration, and Operation</i>	SC24-5649
<i>VM/ESA System Messages and Codes</i>	SC24-5529
VM/ESA Version 2	
<i>VM/ESA CP Planning and Administration</i>	SC24-5750
<i>VM/ESA CMS Command Reference</i>	SC24-5776
<i>VM/ESA CMS File Pool Planning, Administration, and Operation</i>	SC24-5751
<i>VM/ESA System Messages and Codes</i>	SC24-5784

IBM International Technical Support Center Publications (Redbooks)

The International Technical Support Center (ITSC) publishes redbooks, books on specialized topics such as using ADSM to back up databases. You can order publications through your IBM representative or the IBM branch office serving your locality. You can also search for and order books of interest to you by visiting the IBM Redbooks home page on the World Wide Web at this address:

<http://www.redbooks.ibm.com/redbooks>

Software Developer's Program

The IBM Storage Systems Division (SSD) Software Developer's Program provides a range of services to software developers who want to use the ADSM application programming interface (API). Information about the SSD Software Developer's Program is available in:

- IBMSTORAGE forum on CompuServe
- SSD Software Developer's Program Information Package

To obtain the Software Developer's Program Information Package:

1. Call 800-4-IBMSSD (800-442-6773). Outside the U.S.A., call 408-256-0000.
2. Listen for the Storage Systems Division Software Developer's Program prompt.
3. Request the Software Developer's Program Information Package.

Do You Have Comments or Suggestions?

If you have difficulty using this publication or if you have comments and suggestions for improving it, please complete and mail the reader's comment form found in the back of this publication. Your comments and suggestions can contribute to the quality and usability of this publication.

You can send us comments electronically by using these addresses:

- IBMLink from U.S.: STARPUBS at SJSVM28
- IBMLink from Canada: STARPUBS at TORIBM
- IBM Mail Exchange: USIB3VVD at IBMMAIL
- Internet: starpubs@vnet.ibm.com (or [starpubs](mailto:starpubs@vnet.ibm.com) at vnet.ibm.com)
- Fax from U.S. and Canada: 520 799-6487
- Fax from other countries: (1) 520 799-6487

Translations

Selected ADSM publications have been translated into languages other than American English. For a complete list of the available translations and their order numbers, see *ADSM General Information*. Contact your IBM representative for more information about the translated publications and whether these translations are available in your country.

Summary of Changes for ADSTAR Distributed Storage Manager

This section summarizes changes made for this edition of this book.

Changes for Version 2—September 1996

The new functions for ADSM for VM Version 2 are:

Database backup and recovery

You can perform full and incremental backups of the server database to protect against loss or damage. You can use the backup copies to restore the database to its current state or to a specific point in time. You can back up the database while the server is available to clients.

Note: To allow for recovery of the database to its most current state, you may have to extend your recovery log space significantly.

See Chapter 15, “Protecting and Recovering Your Data” on page 297 for details.

Storage pool backup and recovery

You can back up client files stored on storage pools to sequential media. These media can be either onsite, to protect against media loss, or offsite, for disaster recovery purposes.

See Chapter 7, “Managing Storage Pools” on page 81 for details.

Administrative command scheduling

You can define schedules for automatically issuing administrative commands once or periodically.

See Chapter 10, “Automating Operations” on page 193 for details.

Hierarchical storage management

Hierarchical storage management (HSM) provides space management services to HSM clients. HSM clients can automatically migrate user files to storage pools to free up client storage space. A user can access a migrated file as if it were on local storage.

See Chapter 9, “Managing Policies” on page 155 for details.

Part 1. ADSM Basics

Chapter 1. Introducing ADSTAR Distributed Storage Manager

ADSTAR Distributed Storage Manager (ADSM) is an enterprise-wide storage management application for the network. It provides automated storage management services to multivendor workstations, personal computers, and local area network (LAN) file servers. ADSM includes the following components:

Server

Allows a host system to provide backup, archive, and space management services to workstations. The server maintains a database and recovery log for ADSM resources, users, and user data.

The server controls the ADSM server storage, or storage pools. These are groups of random and sequential access media that store backed up, archived, and space-managed files.

Administrative client

Allows administrators to control and monitor server activities, define management policies for client files, and set up schedules to provide services at regular intervals.

Backup-archive client

Allows users to maintain backup versions of their files, which they can restore if the original files are lost or damaged. Users can also archive files for long-term storage and retrieve the archived files when necessary. Users themselves or administrators can register workstations and file servers as client nodes with an ADSM server.

Hierarchical storage management (HSM) client

Provides space management services for workstations on some platforms. ADSM users can free workstation storage by migrating less frequently used files to server storage. These migrated files are also called *space-managed files*. Users can recall space-managed files automatically simply by accessing them as they normally would.

Application programming interface (API)

Allows users to enhance existing applications with back up, archive, restore, and retrieve services. When users install the ADSM application client on their workstations, they can register as client nodes with an ADSM server.

Figure 1 on page 4 shows an example of an ADSM client/server environment. In this example, an administrator monitors the system from a workstation on which the administrative client program has been installed.

The backup-archive client program and HSM client program have been installed on workstations connected through a LAN and registered as client nodes. From these client nodes, users can back up, archive, or migrate files to the server.

Based on ADSM policies assigned to files, the server stores client files on disk or tape volumes in server storage, which can be grouped into storage pools.




Figure 1. Sample Client/Server Environment

The rest of this chapter presents key ADSM concepts and information about storage for ADSM. It describes how ADSM manages client files based on information provided in administrator-defined policies, and manages devices and media based on information provided in administrator-defined ADSM storage objects.

Section	Page
Concepts:	
How ADSM Stores Client Data	6
How ADSM Represents Devices	9
How ADSM Represents Storage Media	10
What Are the ADSM Storage Objects?	10
Putting It All Together	12
Planning to Configure the ADSM Storage Environment	14
Configuring Devices	16
Automating Client Operations	16

How ADSM Stores Client Data

ADSM policy governs storage management including:

Backup

Copying files from client workstations to server storage to ensure against loss of data. Copies of multiple versions of a file can be stored.

Archiving

Copying files from client workstations to server storage for long-term storage.

Space Management

Freeing up client storage space by copying a file from client workstations to server storage. The original file is replaced with a stub file that points to the original in server storage. The process of moving the client file to server storage is also called **migration**.

Policy is defined by administrators in policy objects: policy domains, policy sets, management classes, and backup and archive copy groups. When you install ADSM, you have a set of policy objects named STANDARD. For information about this default policy, see “Using the Standard Storage Management Policies” on page 168.

Figure 2 on page 7 shows an overview of the ADSM process for storing client data. When users back up, archive, or migrate files, ADSM does the following:

1 Determines where to store the file

ADSM checks the management class bound to the file to determine the destination of the file, that is, where the file should be stored. The storage destination is an ADSM storage pool, which can be a group of disk or tape volumes. For backed up and archived files, storage destinations are assigned in the backup and archive copy groups, which are within management classes. For space-managed files, storage destinations are assigned in the management class.

See Chapter 9, “Managing Policies” on page 155 for information on assigning storage destinations in copy groups and management classes, and binding management classes to client files.

2 Stores information about the file in the ADSM database

ADSM saves information in the ADSM database about each file that it backs up, archives, or migrates. This information includes the file name, file size, file owner, management class, copy group, and location of the file in ADSM server storage.

See Chapter 12, “Managing the Database and Recovery Log” on page 233 for information on managing the database.

3 Stores the file in ADSM server storage

ADSM stores backup-archive client files and HSM client files on media that are associated with ADSM storage pools. The media can be disk or tape volumes.

For information about storage pools and storage pool volumes, see Chapter 7, “Managing Storage Pools” on page 81 and “Storage Pool Volumes” on page 131.




Figure 2. Overview of How ADSM Stores Client Data

Figure 3 shows in more detail the interaction between ADSM policy objects and ADSM backup, archive, and migration services.




Figure 3. How ADSM Controls Backup, Archive, and Migration

- 1** An ADSM client initiates a backup, archive, or migration operation. The file involved in the operation is bound to a management class. The management class is either the default or one specified for the file in the client's include-exclude list.
- 2** If the file is a candidate for backup, archive, or migration based on information in the management class, the client sends the file and file information to the server.
- 3** The server checks the management class that is bound to the file to determine where to store the file within ADSM server storage. The storage destination for space-managed files is contained in the management class. The storage destination for backed up and archived files is contained in the copy groups, which are associated with the management class.

4 The server stores the file in the ADSM storage pool identified as the storage destination. Information about the file is stored in the server database.

If server storage is structured in a hierarchy, ADSM can later migrate the file to a different storage pool. For example, server storage may be set up so that ADSM migrates files from a disk storage pool to tape volumes in a tape storage pool.

Files remain in server storage until they expire and expiration processing occurs, or until they are deleted. A file expires because of criteria set in policy or because the file is deleted from the client file system.

How ADSM Represents Devices

ADSM represents physical devices with administrator-defined ADSM storage objects: device classes. The device class, defined when devices are configured for ADSM, contain information for the management of devices and media. Each type of device requires a device class.

Disk and Tape Devices

Magnetic disk devices are the only devices in the random access category so they all share the same ADSM device type: DISK. ADSM predefines the DISK device class.

Tape devices can have a device type of either REEL or CARTRIDGE.




Figure 4. Devices Are Represented by Device Classes

Files on Disk as Logical Devices

ADSM allows administrators to create logical volumes on server disk space with the characteristics of sequential access volumes such as tape. ADSM supports these virtual devices through the FILE device type.

FILE (logical) devices are often useful when transferring data for purposes such as electronic vaulting.

How ADSM Represents Storage Media

ADSM represents storage media with administrator-defined ADSM objects: storage pool volumes and storage pools. Figure 5 shows storage pool volumes grouped into a storage pool. Each storage pool represents only one type of media. For example, a storage pool for cartridge devices represents collections of only cartridge tapes.




Figure 5. Relationships of Storage Pool Volumes, Storage Pools, and Media

What Are the ADSM Storage Objects?

The following ADSM storage objects are collections of information that indicate to ADSM how to communicate with devices and how to manage media:

- Device class
- Storage pool
- Storage volume

Device Class

Each device is associated with an ADSM device class. A device class contains information about the device type and the way the device manages its media. See Chapter 6, “Defining Device Classes” on page 69 for more detailed information about device classes.

For devices that access data randomly, ADSM provides a predefined device class of DISK.

For devices that access data sequentially, the administrator must define the device class. (Devices that access data sequentially include FILE device classes, where data resides in files on the server’s disk storage.)

Storage Pools

A storage pool is a named collection of storage volumes that are associated with one device class. Each storage pool represents a collection of volumes sharing the same media type. For example, a storage pool associated with a device class for cartridge tape contains only cartridge tape volumes. Many of the parameters associated with a storage pool depend on whether the data on storage pool media is accessed randomly or sequentially. These parameters are described in more detail in Chapter 7, “Managing Storage Pools” on page 81.

ADSM supplies default disk storage pools named BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL. To use these default pools, all you must do is format and define volumes to them. For more information, see “Using Random Access Volumes on Disk Devices” on page 27.

Storage Pool Volumes

ADSM represents space on media with an object called a storage pool volume. A storage pool volume is associated with a storage pool and represents a unit of space available for ADSM client data. For example, 3480 cartridges become storage pool volumes when they are assigned to an ADSM storage pool.

See Chapter 8, “Managing Storage Pool Volumes” on page 131 for more information about ADSM storage pool volumes.

What Does a Device Class Contain?

The contents of a device class are determined by whether the device accesses the data on its media randomly or sequentially.

Device Classes for Random Access Devices

Devices that access their media randomly share a common ADSM device type, and they do not require the administrator to define an ADSM library. ADSM provides a single, random-access device class, named DISK. You cannot define other random access device classes.

Random access device types store data in blocks of storage that can be scattered across the available space on a disk. As data becomes deleted by the server, the space occupied by that data can be reused.

Device Classes for Sequential Access Devices

Devices such as tape drives access their data sequentially. A device class for a sequential device contains a device type and media management information.

Sequential access device types store data at the beginning of a volume and append new data after existing data. As data is deleted, the space is not immediately reused. The server can reclaim space later by using the reclamation process (see “Space Reclamation for Sequential Access Storage Pools” on page 100 for details).

Tape devices and FILE type devices are members of the sequential access category of devices.

Device Type

Every sequential access device class requires one of the ADSM device types as part of its definition. A device type identifies a device as a member of a group of devices sharing similar media characteristics. ADSM provides device types for many devices including DISK, CARTRIDGE, REEL, and FILE device types. For example, cartridge tape devices require cartridge tapes; all cartridge tape devices share a device type of CARTRIDGE.

FILE is a special kind of ADSM sequential device type that allows the administrator to create logical tape devices by creating files on the ADSM server that have the characteristics of a tape device.

Media Management Information

Every sequential access device class contains media management information, for example, recording format, estimated capacity, and labeling prefixes. For more information about how ADSM helps to manage media, see “Using Disk for FILE Logical Devices” on page 28 and Chapter 4, “Using Tape Devices with ADSM” on page 31.

Putting It All Together

Figure 6 on page 13 summarizes the relationships among the physical device environment, ADSM storage and policy objects, and ADSM clients. The numbers in the following list correspond to the numbers in the figure.

- 1** When clients are registered, they are associated with a policy domain. Within the policy domain are the other ADSM policy objects.
- 2**, **3** When a file is backed up, archived, or migrated from a client, it is bound to a management class. A management class and the backup and archive copy groups within it specify where files are stored and how they are managed when they are backed up, archived, or migrated from a client (space-managed files).
- 4**, **5** Storage pools are the destinations for backed up, archived, or space-managed files. Copy groups specify storage pools for backed up or archived files. Management classes specify storage pools for space-managed files.

Storage pools are mapped to device classes, which represent devices. The storage pool contains volumes as indicated by the device type associated with the device class. For example, a storage pool that is mapped to a device class with a device type of cartridge contains only cartridge tapes.

All devices require a device class that specifies at least a device type.
- 6** Files that are initially stored on disk storage pools can migrate to tape storage pools if the pools are set up in a storage hierarchy.




Figure 6. Putting It All Together

Planning to Configure the ADSM Storage Environment

Businesses often back up data to a variety of storage devices ranging from high-performance DASD devices to slower and less expensive tape devices. Administrators must balance the data availability requirements of users with the costs of storage devices.

This section discusses how to evaluate your current environment to determine the device classes and storage pools for your ADSM storage environment.

Evaluating Your Storage Environment

Before configuring devices, it is helpful to evaluate the hardware available to ADSM:

1. Determine the storage devices that are available to ADSM. Determine how many tape drives you have that you will allow ADSM to use.
2. Determine the ADSM device type for each of the available devices. Group together similar devices and identify their device classes. For example, create separate categories for 3480 and 3490E cartridge devices.

Note: For sequential access devices, categorize the type of tape cartridge based on capacity. For example, standard cartridge tapes and enhanced capacity cartridge tapes require different device classes.

3. Categorize storage pools by user requirements. Gather users' requirements for data availability. Determine which data needs quick access and which does not.
4. Be prepared to label storage pool volumes. You will need to create a new or use an existing labeling convention for ADSM storage pool volumes.

Mapping Devices to Device Classes

As an example of mapping devices to device classes, assume the following ADSM storage environment:

- Internal disk drives
- 3490 Enhanced Capability models (3490E) in a 3494 tape library
- 3490 Magnetic Tape Subsystems
- 3480 Magnetic Tape Subsystems

You can map storage devices to device classes as shown in Table 1 on page 15.

Table 1. Mapping Storage Devices to Device Class

Device Class	Description
DISK	Storage volumes that reside on the internal disk drive ADSM provides one DISK device class that is already defined, and you cannot define another device class for disk storage.
CARTRIDGE_E	Enhanced Capacity Cartridge System Tape (ECCST) volumes used with 3490E tape devices
CARTRIDGE_B	Standard Cartridge System Tape (CST) volumes used with 3480 or 3490 Base tape devices

You must define any device classes that you need for your tape devices. See Chapter 6, "Defining Device Classes" on page 69 for information on defining tape device classes to support your physical storage environment.

Mapping Storage Pools to Device Classes and Devices

After you have categorized your storage devices, identify availability, space, and performance requirements for user data stored on disk or tape. You can then assign each storage pool as a storage destination for backed up, archived, or space-managed files.

For example, an administrator determines that users in the business department have three requirements:

- Immediate access to all space-managed files and to some backed up files, such as accounts receivable and payroll accounts
- Periodic access to some archived files, such as monthly sales and inventory reports
- Occasional access to backed up or archived files that are rarely modified, such as yearly revenue reports

To match user requirements to storage devices, the administrator defines storage pools and device classes. See Table 2 on page 16.

Table 2. Mapping Storage Pools to Device Classes, Libraries, and Drives

Storage Pool	Device Class	Volume Type	Storage Destination
BACKUPPOOL	DISK	Storage volumes on the internal disk drive	For a backup copy group for files requiring immediate access
SPACEMGPOOL	DISK	Storage volumes on the internal disk drive	For a management class for space-managed files that require immediate access
ARCHTAPEF	CARTRIDGE_E	ECCST volumes	For an archive copy group for files requiring quick, reliable access
BACKTAPE	CARTRIDGE_E	ECCST volumes	For backup copy groups for files not requiring immediate access
ARCHTAPES	CARTRIDGE_B	CST volumes	For archived data not requiring immediate access

Note: ADSM supplies default disk storage pools named BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL. To use these default pools, all you must do is define volumes to them. For more information, see “Using Random Access Volumes on Disk Devices” on page 27.

Configuring Devices

Before a device can be used by ADSM, the device must be configured to the operating system as well as to ADSM. For information on these tasks, see the following:

- Chapter 3, “Using Magnetic Disk Devices with ADSM” on page 27
- Chapter 4, “Using Tape Devices with ADSM” on page 31

Automating Client Operations

You can automate operations such as backup for the ADSM clients. Figure 7 on page 18 shows the ADSM objects that may be involved in automated client operations. The key objects that interact are:

Include-exclude list (file for UNIX clients) on each ADSM client

Determines which files are backed up or space-managed, and determines management classes for files

Management class

Determines where client files are stored and how they are managed

Schedule

Determines when client operations such as backup occur

Association defined between client and schedule

Determines which schedules are run for a client

The client can specify a management class for a file or set of files, or can use the default management class for the policy domain. The client specifies a management class by using an INCLUDE option in the client’s include-exclude list or file. (See **A** in Figure 7 on page 18.)

The management class contains information that determines how ADSM handles files that clients backup, archive, or migrate. For example, the management class contains the backup copy group and the archive copy group. Each copy group points to a

destination, a storage pool where files are stored when they are backed up or archived. (See **E** in Figure 7 on page 18.)

Clients are assigned to a policy domain when they are registered. Schedules that can automate client operations are also associated with a policy domain. (See **C** in Figure 7 on page 18.) To automate client operations, you define schedules for a domain. Then you define associations between schedules and clients in the same domain. (See **B** in Figure 7 on page 18.)

For a schedule to work on a particular client, the client machine must be turned on and must be running the client scheduler.

The scheduled client operations are called *events*, and information about events are stored in the ADSM database. (See **D** in Figure 7 on page 18.) For example, you can query the server to determine which scheduled events completed successfully and which failed.

For how to set up policy domains and management classes, see Chapter 9, “Managing Policies” on page 155. For more details on how to automate client operations, see “Automating Client Operations” on page 195.




Figure 7. Automating Client Operations

Chapter 2. Administrator Tasks

This chapter provides a brief overview of the tasks that ADSM administrators can do. It also points to the sections in this publication that present the details of those tasks and the concepts you need to understand to complete them. The tasks are in the order in which they appear in the chapters of this book:

- Configuring and Managing Server Storage
 - Using magnetic disk devices with ADSM
 - Using tape devices with ADSM
 - Using tape installation-wide exits
 - Defining device classes
 - Managing storage pools
 - Managing storage volumes
- Policies
 - Managing ADSM policies
- Automating Operations
- Maintaining the Server
 - Managing server operations
 - Managing the database and recovery log
 - Managing licensing, privilege classes, and registration
 - Exporting and importing data
- Protecting and recovering your data

Interfaces to ADSM

There are three types of interfaces to ADSM:

- Graphical user interfaces (GUIs). For information about using the GUI, see the online information or refer to *ADSM Quick Start*.
- The command-line interface. For information about using the administrative client command-line interface, refer to *ADSM Administrator's Reference*. For information about using the backup-archive client command-line interface, refer to the ADSM user's guide for that client.
- The application programming interface. For more information, refer to *ADSM Using the Application Programming Interface*.

See Appendix A, "Interface Cross-Reference" on page 329 for a table that relates administrative commands with the administrative GUI.

Using Magnetic Disk Devices with ADSM

Magnetic disk devices can be used with ADSM for two purposes:

- Storage of the database and recovery log
- Storage of client data that is backed up, archived, or migrated from client nodes

ADSM can store data on magnetic disk using random access volumes or logical volumes with a device type of FILE.

For guidance setting up storage pools on disk devices, see Chapter 3, “Using Magnetic Disk Devices with ADSM” on page 27.

Using Tape Devices with ADSM

Tape devices can be used with ADSM for the following purposes:

- Storage of client data that is backed up, archived, or space-managed from client nodes
- Storage of database backups
- Exporting data

For guidance and scenarios on configuring your tape devices, see Chapter 4, “Using Tape Devices with ADSM” on page 31.

Managing Tape Operations

ADSM provides commands and options to help you manage how tapes are used. You can:

- Control tape mount request messages
- Display information about the status of mounted tapes
- Dismount tapes

You can also set up ADSM to work with your tape management system. ADSM provides a deletion installation-wide exit to notify your tape management system when the server deletes a tape from the database.

For more information about these tasks, see “Understanding the Server Tape Processing” on page 36.

Defining Device Classes

A device class represents a set of storage devices with similar availability, performance, and storage characteristics. You must define device classes for the types of drives available to an ADSM server. You specify a device class when you define a storage pool, which is a named collection of volumes for storing user data.

For more information about defining device classes, see Chapter 6, “Defining Device Classes” on page 69.

Managing Storage Pools

Backed up, archived, and space-managed files are stored in groups of volumes called storage pools. The data on these primary storage pools can be backed up to copy storage pools for disaster recovery purposes. Because each storage pool is assigned to a device class, you can logically group your storage devices to meet your storage management needs.

You can establish a hierarchy of storage pools. The hierarchy may be based on the speed or the cost of the devices associated with the pools. ADSM migrates client files through this hierarchy to ensure the most efficient use of a server's storage devices.

When defining or modifying a storage pool, you can specify any or all of the following:

Cache	When files are migrated from disk storage pools, duplicate copies of the files may remain in cache (disk storage) for faster retrieval and are deleted only when space is needed.
Collocation	ADSM keeps each client's files on a minimal number of volumes within a storage pool. Because client files are consolidated, restoring collocated files requires fewer media mounts.
Reclamation	Files on sequential access volumes may expire, move, or be deleted. The reclamation process consolidates the active, unexpired data on many volumes onto fewer volumes. The original volumes can then be reused for new data.

For more information about storage pools and taking advantage of storage pool features, see Chapter 7, "Managing Storage Pools" on page 81.

Managing Storage Pool Volumes

You manage storage volumes by defining, updating, and deleting volumes, and by monitoring the use of server storage. Monitoring volumes can reveal inconsistencies that can be corrected between information in the database and client node files in storage pools. You can also move files within and across storage pools to optimize the use of server storage.

For more information about these tasks, see Chapter 8, "Managing Storage Pool Volumes" on page 131.

Managing Policies

From a client node, files can be backed up or archived to the server. This process ensures that current data can be restored or retrieved if it is accidentally deleted or corrupted on the workstations. Files from an HSM client can also be migrated from local file systems. Recall of migrated files is transparent and automatic when a client accesses a file, or the client can selectively recall files.

You define policies based on user requirements for backing up, archiving, or migrating data. You do this by defining policy objects, which identify backup, archive, and migration criteria, and by scheduling client operations.

For more information about establishing and managing policies for your organization, see Chapter 9, “Managing Policies” on page 155.

Automating Operations

You can define schedules for the automatic processing of most administrative commands and client operations such as backup and restore.

For more information about scheduling ADSM commands and operations, see Chapter 10, “Automating Operations” on page 193.

Managing Server Operations

You can manage server operations such as starting and stopping the server, maintaining and suspending client sessions with the server, and controlling server processes.

ADSM provides you with many sources of information about server and client status and activity, the state of the database, and resource usage. By monitoring this information, you can provide reliable services to users while making the best use of available resources.

For details about the day-to-day tasks involved in administering the server and about reports and information available to you, see Chapter 11, “Managing Server Operations” on page 217.

Managing the Database and Recovery Log

The ADSM database contains information about the client data in storage pools, registered client nodes, ADSM policies, and ADSM schedules. The server recovery log, which records changes made to the database, is used to restore the database to a consistent state.

You manage the database and recovery log space and the buffer pool to tune database and recovery log performance.

For more information about the ADSM database and recovery log and about the tasks associated with administering them, see Chapter 12, “Managing the Database and Recovery Log” on page 233.

Managing Licensing, Privilege Classes, and Registration

You can monitor an installation’s compliance with the terms of its license agreement. ADSM lets you check license compliance and modify the terms.

An organization may name a single administrator or may distribute the workload among a number of administrators and grant them different levels of authority.

You register workstations as client nodes with the server. You can also provide client/server authentication by requiring the use of passwords to ensure that the client and the server are authorized to communicate with each other.

For more information about the preceding concepts and tasks, see Chapter 13, “Managing Licensing, Privilege Classes, and Registration” on page 251.

Exporting and Importing Data

As your storage needs increase, you can move data from one server to another. You can *export* part or all of a server’s data to tape or a flat file so that you can then *import* the data to another server.

For more information about moving data between servers, see Chapter 14, “Exporting and Importing Data” on page 273.

Protecting and Recovering Your Data

ADSM provides a number of ways to protect and recover your data from media failure or from the loss of the ADSM database or storage pools due to a disaster. These recovery methods are based on the following measures:

- Mirroring, by which the server maintains one or more copies of the database or recovery log, allowing the system to continue when one of the mirrored disks fails
- Periodic backup of the database
- Periodic backup of the storage pools
- Recovery of damaged files

For more information about protecting your data and for details about recovering from a disaster, see Chapter 15, “Protecting and Recovering Your Data” on page 297.

Part 2. Configuring and Managing Data Storage

Chapter 3. Using Magnetic Disk Devices with ADSM

With ADSM, magnetic disk devices are used for two main purposes:

- To store the database and the recovery log.

For information on using disk storage for the database and recovery log, see Chapter 12, “Managing the Database and Recovery Log” on page 233.

- To store client data that has been backed up, archived, or migrated from client nodes. The client data is stored in storage pools.

A summary of procedures for using disk storage for client data is in this chapter.

You may also want to use disk storage (in the form of FILE volumes) to store backups of the ADSM database and to export and import ADSM data.

The sections listed in the following table begin at the indicated pages.

Section	Page
Concepts:	
Using cache	29
Freeing space on disk	30
FILE volumes used for database backups and export operations	30
Tasks:	
Using random access volumes on disk devices	27
Using disk for FILE logical devices	28

Setting Up Storage Pools on Disk Devices

ADSM stores data on magnetic disks in two ways:

- In random access volumes, as data is normally stored on disk. See “Using Random Access Volumes on Disk Devices.”
- In files on the disk. Each file is considered a sequential access volume. Within each file, data is stored sequentially, as it is on tape devices. See “Using Disk for FILE Logical Devices” on page 28.

Using Random Access Volumes on Disk Devices

For disk devices, ADSM provides a defined DISK device class that is used with all disk devices.

Do the following to use random access volumes on a disk device:

1. Format a random access volume

Notes:

- a. At ADSM installation, use the DSMINST EXEC.
 - b. After installation, **do not** use the DSMINST EXEC; it will erase your database and recovery log volumes. Instead, use the DSMMDISK EXEC.
2. Define a storage pool that is associated with the DISK device class, or use one of the default storage pools that ADSM provides (ARCHIVEPOOL, BACKUPPOOL, and SPACEMGPOOL). See “Example: Defining a Storage Pool Hierarchy” on page 111 for details.
 3. Define the DISK volumes formatted in step 1 to the storage pool. See “Defining Storage Pool Volumes” on page 133 for details.
 4. Do one of the following:
 - Specify the new storage pool as the destination for client files that are backed up, archived, or migrated, by modifying existing policy or creating new policy. See Chapter 9, “Managing Policies” on page 155 for details.
 - Place the new storage pool in the storage pool migration hierarchy by updating an already defined storage pool. See “Example: Updating a Storage Pool Hierarchy” on page 112.

Using Disk for FILE Logical Devices

Another way to use magnetic disk storage is to use files as logical volumes that store data sequentially (as on tape volumes). You can use FILE (logical) devices to ship data electronically. For example, you can send the results of an export operation or a database backup operation to another location. At the receiving site, the files can be placed on tape or disk. You can define a device class with a device type of FILE for CMS files on a minidisk or in a Shared File System (SFS) directory.

Note: Device classes containing CMS files should not be used for primary storage pools. See Chapter 7, “Managing Storage Pools” on page 81 for details about primary and copy storage pools.

If you use an **SFS directory** for a device class, which is preferred, consider the following:

- Define the directory to only one ADSM server.
- If multiple SFS files will be accessed at the same time, you may need to adjust the USERS SFS Filepool Server startup parameter.
- Ensure that the SFS filespace has enough free space for the creation of CMS files by ADSM.
- When the filespace limit is exceeded, the ADSM process that is using the device class fails, and ADSM issues a write-error message and marks the volume (the CMS file) as read/only.
- Systems using DFSMS/VM ML2 should not allow CMS files created by ADSM and maintained in an SFS directory to be DFSMS/VM-managed to itself (DFSMS/VM ML2 directories should not be used for ADSM CMS files).

If you use a **minidisk** for a device class, consider the following:

- The minidisk should be used by only one copy storage pool.
- If the minidisk is to be used for backup, dump or export, it can be defined to only one server.
- The minidisk should be used only for the device class files and should not be used for other CMS files.
- If the device class is to be used only for export and database backups and dumps, the mount limit must be one.
- If the device class is to be used as a copy storage pool, specify a mount limit of two to allow reclamation.
- CMS does not update the minidisk file directory as soon as an opened file is closed. The file directory is updated only when all opened files on the minidisk are closed.
- Ensure that the minidisk has enough free space for the creation of CMS files by ADSM.
- When a minidisk fills, the ADSM process that is using the minidisk fails, and ADSM issues a write-error message and marks the volume (the CMS file) as read/only.

Do the following to use the FILE device class:

1. Define a device class with device type FILE. See “Defining and Updating FILE Device Classes” on page 75.
2. Define a copy storage pool that is associated with the new FILE device class. See “Defining a Copy Storage Pool” on page 113 for details.

ADSM automatically creates the files to be used as sequential access volumes. Volume names can be defined using the DEFINE VOLUME command, or they can default to scratch.

Notes on Operations

This section contains information to be aware of when using magnetic disk devices for ADSM. The sections give pointers to additional information.

Using Cache

When you define a storage pool that uses disk random access volumes, you can choose to enable or disable cache. Using cache can improve the retrievability of files. When you use cache, a copy of the file remains on disk storage even after the file has been migrated to the next pool in the storage hierarchy, for example to tape. If the file needs to be restored or retrieved, the copy in cache can be used rather than the copy on tape, improving performance. However, using cache increases the space needed for the ADSM database. For more information, see “The Use of Cache on Disk Storage Pools” on page 94.

Freeing Space on Disk

As client files expire, the space they occupy is not freed for other uses until you run ADSM's expiration processing.

Expiration processing deletes from the ADSM database information about any client files that are no longer valid according to the policies you have set. For example, suppose four backup versions of a file exist in ADSM server storage, and only three versions are allowed in the backup policy (the management class) for the file. Expiration processing deletes information about the oldest of the four versions of the file. The space that the file occupied in the storage pool becomes available for reuse.

You can run expiration processing by using one or both of the following methods:

- Use the ADSM command EXPIRE INVENTORY. See "Running Expiration Processing to Delete Expired Files" on page 183.
- Set the server option for the expiration interval, so that expiration processing runs periodically. You can set options through the ADSM Utilities menu or by issuing the CHGSVRADSM command (see *ADSM Administrator's Reference*).

FILE Volumes Used for Database Backups and Export Operations

When you backup the database or export server information, ADSM records information about the volumes used for these operations in the *volume history* file. ADSM will not allow you to reuse these volumes until you delete the volume information from the volume history file. To reuse volumes that have previously been used for database backup or export, use the DELETE VOLHISTORY command. For information about the volume history file, see "Saving the Volume History File" on page 311.

Chapter 4. Using Tape Devices with ADSM

ADSM can use tape devices for storing backed-up, archived, and space-managed client data, for storing backups of its database, and for exporting data.

ADSM provides server options and commands to help administrators with system or operator privilege control how tapes are used. You can also use a tape management system to control how the server uses tapes.

The sections listed in the following table begin at the indicated pages.

Section	Page
Concepts:	
Overview of using devices	31
Notes on operations	34
Tasks:	
Configuring devices	32

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI and the ADSM utilities.

Overview of Using Devices with ADSM

Sequential access devices typically require that the following steps be performed so that ADSM can use the devices. The numbers in the steps correspond to the numbers in Figure 8 on page 32.

1 Define the required ADSM objects.

The administrator defines the storage objects that represent the physical device and media: device class, storage pool, and storage volume. For an introduction to the ADSM storage objects, see "What Are the ADSM Storage Objects?" on page 10.

2 Define ADSM policy that links client data with media for the device.

The administrator defines or updates the ADSM policy objects that will link clients to the pool of storage volumes and to the device. Do this by using the new storage pool as a destination for backed up, archived, or space-managed client data. For an introduction to the ADSM policy objects, see "What Are the ADSM Storage Objects?" on page 10.

An alternative is to simply place the new storage pool in the storage pool migration hierarchy by updating an already defined storage pool.

- 3 Register clients to the policy domain defined or updated in the preceding step. This step links clients and their data with storage volumes and devices.




Figure 8. Overview of Sequential Device Configuration

Example of Setting Up Two 3490E Drives

For the following example, two 3490E drives are attached to VM and configured to the operating system. The example takes you through the steps necessary to get ADSM to use the devices for storing client data.

This example presents the procedure with a minimum of customization. If you want to do more, see the references in the steps for more details.

Define the ADSM Objects

- 1 Classify drives according to type and format by defining ADSM device classes. For example, if you want to use the 3490C recording format, use the following command:

```
define devclass tap3490_class devtype=cartridge -
format=3490c mountlimit=2
```

Key choice: Mount limit (number of drives available in this device class) has a default value of 2. The mount limit should be equal to the number of drives of the same type that are available to ADSM.

- 2** Check the server options MOUNTOP, REPLYOP, EXITVM, and DELETIONEXIT to ensure that mount messages are sent when and where you want. For more information on server options, see *ADSM Administrator's Reference*.
- 3** Set up the storage pool to use the devices in the device class you just defined. For example:

```
define stgpool tap3490_pool tap3490_class maxscratch=20
```

Key choices:

- a. If you do not specify a value for the maximum number of scratch volumes, you must explicitly define each volume to be used in the storage pool. If you allow scratch volumes, ADSM can choose from the scratch volumes available, without action on your part.
- b. Collocation is turned off by default. Collocation is a process by which the server attempts to keep all files belonging to a client file space on a minimal number of volumes. Once clients begin storing data in a storage pool with collocation off, you cannot easily change the data in the storage pool so that it is collocated. To understand the advantages and disadvantages of collocation, see “Collocation on Sequential Access Storage Pools” on page 95 and “How Collocation Affects Reclamation” on page 104.

See “Defining a Primary Storage Pool” on page 110.

Update ADSM Policy

You can do one or both of the following:

- Have clients back up data directly to tape.
- Have clients back up data to disk storage. Then let ADSM migrate the data to tape when the amount of disk storage used reaches the migration threshold.

Clients Back Up Directly to Tape: You can choose to have clients back up directly to the new tape storage pool that you defined.

Key choice: If you back up to tape directly, the number of clients that can back up data at the same time is equal to the number of drives available to the storage pool (through the device class). If you have only one drive, only one client at a time can back up data.

- 1 Update the default copy group so that the destination for backups is the new tape storage pool. For example:

```
update copygroup standard standard standard standard -  
type=backup destination=tap3490_pool
```

Note: Instead of updating the default copy group in the STANDARD policy domain, you could define a new management class and a new copy group.

See “Defining and Updating a Backup Copy Group” on page 175.

- 2 Activate this modified policy:

```
activate policysset standard
```

See “Activating Policy Sets” on page 182.

Clients Back Up to Disk Then Data Migrates: Have clients back up data to disk storage. Then let ADSM migrate the data to the new tape storage pool when the amount of disk storage used reaches the migration threshold. For example, you can have data migrate from the default disk storage pool, BACKUPPOOL, by using the following command:

```
update stgpool backuppool nextstgpool=tap3490_pool
```

See “Defining or Updating Storage Pools” on page 110.

Register Clients to the Policy Domain

If you updated the default STANDARD policy to use the new storage pool as a destination for backups from clients, the clients must be registered to that policy domain. To register a client to the STANDARD policy domain, enter this command:

```
register node astro cadet
```

For information on options when registering clients, see “Administrator Registration of Client Nodes” on page 265.

Notes on Operations

The following sections summarize choices and procedures you need to be aware of when operating tape devices for ADSM. The sections give pointers to additional information.

Mount Operations

Volumes are mounted as a result of mount requests from ADSM. You can monitor the mount requests in the following ways:

- Set the MOUNTOP or REPLYOP server options to specify one or more user IDs to receive and respond to mount messages
- Use an administrative client in mount mode or console mode

For more details, see “Understanding the Server Tape Processing” on page 36.

Using the Administrative Client for Mount Messages

The server sends mount request status messages to all administrative clients that have been started with either the special *mount mode* or *console mode* parameter. For example, to start the OS/2 administrative client in mount mode, enter this command:

```
dsmadm -mountmode
```

Collocation

Collocation is a process by which the server attempts to keep all files belonging to a client file space on a minimal number of sequential access storage volumes. You set collocation on or off for each sequential access storage pool, which includes tapes. By using collocation, you can reduce the number of volume mounts required when users restore, retrieve, or recall many files. However, when collocation is on, more volume mounts are required when clients store files.

To understand the advantages and disadvantages of collocation, see “Collocation on Sequential Access Storage Pools” on page 95 and “How Collocation Affects Reclamation” on page 104.

Maintaining the Volume Inventory

You can maintain your tape volume inventory by performing the following tasks:

- Using scratch volumes or private volumes, or both
- Reusing tapes

Sending Volumes Offsite: ADSM expects to be able to access all volumes it knows about. You should not remove volumes from the site (preventing ADSM access) unless the volumes are in a copy storage pool and you inform ADSM that the volumes are offsite. For example, ADSM tries to fill up tape volumes. If a volume containing client backups is only partially full, ADSM later requests that volume be mounted to store additional data. If the volume cannot be mounted, an error occurs. To send data on volumes offsite for safekeeping, use a copy storage pool to make copies that can then be sent offsite and tracked by ADSM. For more information, see “Backing Up Storage Pools” on page 114.

Reusing Tapes in Storage Pools

To reuse tapes in ADSM storage pools, you must do two things:

- Run expiration processing regularly so that client files that have *expired* (are no longer valid) are deleted. See “Expiration Processing of Client Files.”
- Move data to consolidate valid, unexpired files onto fewer tapes.

ADSM offers an automated process called *reclamation* that can be used if your system has more than one drive. See “Reclamation with Multiple Drives.” If you have only one drive, you must use a more manual process. See “Reclamation with One Drive.”

Expiration Processing of Client Files: Expiration processing deletes from the ADSM database any client files that are no longer valid according to the policies you have set. For example, a file is deleted by expiration processing if four backup versions exist, and only three versions are allowed in the backup policy for the file. Expiration processing frees space in your storage pools.

You can run expiration processing by using one or both of the following methods:

- Use the ADSM command EXPIRE INVENTORY. See “Running Expiration Processing to Delete Expired Files” on page 183.
- Set the expiration interval with the server option EXPINTERVAL so that expiration processing runs periodically. For information on server options, see *ADSM Administrator's Reference*.

Reclamation with Multiple Drives: If you are using multiple drives, you can have ADSM reclaim volumes that pass a *reclamation threshold*, a percentage of unused space on the volume. The reclamation threshold is set for each storage pool. See “Space Reclamation for Sequential Access Storage Pools” on page 100.

Reclamation with One Drive: To reclaim tapes with only one drive, you must use the ADSM command MOVE DATA. See “Reclamation in a Device Class with Only One Mount Point” on page 105.

Reusing Volumes Used for Database Backups and Export Operations

When you back up the database or export server information, ADSM records information about the volumes used for these operations in the *volume history* file. ADSM will not allow you to reuse these volumes until you delete the volume information from the volume history file. To reuse volumes that have previously been used for database backup or export, use the DELETE VOLHISTORY command. For information about the volume history file, see “Saving the Volume History File” on page 311.

Understanding the Server Tape Processing

In order to integrate ADSM tapes into your tape library, you need to understand how the server uses tapes. You can either predefine tape volumes to a storage pool or specify that ADSM dynamically acquire scratch tape volumes, as needed.

ADSM automatically reuses predefined tape volumes when all space on a volume becomes available, such as when reclamation occurs. When scratch tapes become empty, ADSM dynamically deletes the volumes from the storage pool and returns the tapes to a scratch pool.

Using the Internal Mounting Facility

You can allow the server to mount tapes directly using the internal mounting facility. To use the internal mounting facility, do not include the EXITVM option in the server options file.

When using the internal mounting facility, the server requests a tape mount by sending the mount operator (defined by the MOUNTOP option) a mount message. The message is repeated (at intervals defined by the MSGINTERVAL option) until the tape is mounted, or until the mount wait time, specified for the specific device class, is exceeded.

A mount request is satisfied after a tape drive has been attached to the ADSM server using the CP ATTACH command. Because this command requires special privileges, it must be issued by a user ID (virtual machine) that has the special privilege or by the ADSM server virtual machine which has been given the special privilege. An ADSM server with the special privilege issues the ATTACH command only after receiving a REPLY command as a response to the mount request. The REPLY command must be submitted by either a user ID (virtual machine) defined with the REPLYOP option or by an administrator with operator privileges. Additional information on CP Command privileges can be found in “Assigning CP Command Privilege Classes for Server and Exit Machines” on page 38.

The reply operator or administrator with operator privilege can cancel mount requests with the CANCEL REQUEST command. The server automatically cancels requests that are not satisfied within the period set by the MOUNTWAIT parameter in the definition of the device class to which the tape belongs.

When a tape volume is deleted from the ADSM server database and the DELETIONEXIT option is specified, the internal mounting facility sends a message to the mount operators indicating that the volume has been deleted. Because the server sends messages directly to the operator, any tape management system your installation is using is bypassed.

Using Exit Machines

Product-sensitive programming interface

An exit machine is a virtual machine that is autologged by the ADSM server in order to satisfy tape mount requests and handle tape deletions. One or more exit machines can be defined with the EXITVM option. As needed, ADSM autologs an exit machine, submitting to it either a tape mount request or a tape deletion notification. The PROFILE EXEC of the exit machine must accept and handle mount request or deletion notification. You should review the two sample EXECs (DSMMOUNT and DSMDELET)

distributed with the ADSM server. You can use these EXECs as is or modify them to meet your installation's needs.

To indicate to ADSM that an exit machine will handle tape deletions, specify at least one exit machine with the EXITVM option and include one DELETIONEXIT option (no parameter). When a tape is deleted from the ADSM database, an exit machine is autologged with tape deletion information passed to it.

When a tape management system is installed and it resolves tape mount requests, one or more exit machines should be defined to ADSM. These machines are then autologged as needed to satisfy mount requests. The exit machine must then communicate with the tape management system as needed. In the meantime, the ADSM process requesting the tape mount is suspended until the mount request is satisfied. However, other ADSM processes can take place. The only time the entire server virtual machine is suspended is when I/O is attempted on the mounted tape and the tape device is not ready.

Exit machines must log off as soon as the mount request is satisfied, or the deletion notification is processed. Otherwise, the ADSM server may not locate an available exit machine the next time it needs one and could suspend the process needing a tape to be mounted.

When the server needs to process a tape, the server autologs an exit machine. If all exit machines are in use, mount and delete requests are added to a first-in-first-out (FIFO) queue until a machine is available. There is no simple way to determine how many exit machines you need. Strike a balance between the following factors:

- The amount of tape activity you expect
- The number of tapes you want the server to be able to mount concurrently, which depends on the number of tape operators you have available
- The mount limits you set when defining device classes

_____ End of Product-sensitive programming interface _____

Assigning CP Command Privilege Classes for Server and Exit Machines

The ADSM server virtual machine can operate effectively with CP command privilege class G (general user). However, the server and the exit machines should be assigned additional privilege classes to make tape processing more flexible.

The following is a discussion of the additional privilege classes that can be assigned to the server and the exit machines. The discussion assumes the standard CP privilege class definitions are being used and any deviation from the standard definition should be taken into consideration. For additional information on the standard privilege class definitions refer to *VM/ESA: CP Command and Utility Reference* (SC24-5773).

Privilege Class Requirements for the Server

Besides privilege class G, the following privilege classes (or their equivalent) may be necessary:

- Class B CP commands:

ATTACH Used whenever no exit machines are specified and the REPLYOP option is specified. The server dedicates tape drives to itself with this command.

AUTOLOG Used to autolog an exit machine as necessary when the server is running under VM/ESA 1.1.5 (370 Feature); the exit machine's password must be specified with the EXITVM option.

MSGNOH Used when specified as the command to use with the MSGCMD option; the server will use the command to send messages to other virtual machines.

XAUTOLOG Used to autolog an exit machine as necessary when the server is running under VM/ESA 2.1 and later.

Note: Privilege class B is not necessary to issue this command when the exit machines are defined with an XAUTOLOG statement in its directory definition. If this approach is implemented then no password is necessary with the EXITVM option statement.

- Class A CP commands:

FORCE Used by the server to log off an exit machine when a CANCEL REQUEST is received indicating that the mount request is no longer needed.

Privilege Class Requirements for the Exit Machines

Besides privilege class G, an exit machine may need additional privileges. The privileges needed is dependent on the processing that will take place in the exit machine. If the DSM MOUNT EXEC is used as distributed, the following privilege class is needed:

- Class B CP commands issued by DSM MOUNT EXEC:

ATTACH Used whenever an exit machine needs to dedicate a tape device to itself.

GIVE Used to transfer a tape device to the ADSM server.

Understanding How the Server Selects and Handles Tapes

In order to effectively manage tape operations, you need to understand how the server selects tapes, requests tape mounts, and maintains information on the condition of tapes. ADSM allows you some control over how it requests tape mounts. See "How ADSM Stores Files in a Storage Pool Hierarchy" on page 86 for information on how the server selects tapes based on your storage pool definitions.

Controlling Tape Mount Request Messages

When ADSM requires a tape, the server sends a message requesting a tape mount. You can control mount messages with server options and a device class parameter.

Server Options:

MOUNTOP	Specifies the user IDs of up to 16 mount operators who will receive all mount-related messages.
MSGCMD	Specifies the VM CP command to be used to send messages.
MSGINTERVAL	Specifies how often the server repeats a mount request before the tape is mounted.
NOTIFY	Specifies up to 16 user IDs that should be notified by message of server errors and abnormal conditions.
REPLYOP	Specifies the user IDs of up to 16 reply operators who can reply to tape mount requests. Normally, these user IDs are the same as those of the mount operators.

Device Class Attribute:

MOUNTWAIT	Specifies how long the ADSM server waits for a mount request to be satisfied.
MOUNTRETENTION	Specifies how long the server allows a mounted tape to sit idle on the tape drive.

Both the MOUNTWAIT and MOUNTRETENTION parameters may be changed by updating the device class. You can change the other options related to tape handling by updating the server options file.

Requesting Tapes

The server sends mount messages to the user ID specified on the MOUNTOP option in the server options file.

The mount operator is also notified of any problems, for example, if the tape is mounted on a drive that cannot correctly read from or write to the tape.

Mount messages are slightly different depending on whether the tape requested belongs to a device class that has a specific format or density for tapes and whether the tape is empty.

If a tape is empty and the device class format or density is DRIVE, the message contains the following information:

- Request number
- Device type (cartridge or reel)
- Volume serial number, either a specific number or one of the following:
 - SCRATCH** Scratch volume
 - EXPORT.n** Nonspecific export volumes (*n* is the sequence number)
 - DBBKUP.n** Nonspecific database backup volumes (*n* is the sequence number)
 - DUMPDB.n** Nonspecific database dump volumes (*n* is the sequence number)
 - IMPORT.n** Nonspecific import volumes (*n* is the sequence number)
- Whether the request is for read-write or read-only

- How long the operator has before the server cancels the request

For example, the following message requests that the VOL001 cartridge be mounted at address 400, read-write, within 60 minutes, and that it is mount request number 1:

```
ANR5210I 001: Mount CARTRIDGE VOL001 at 0400 R/W within 60 minutes.
```

If a tape contains data or the device class format or density is not DRIVE, the message includes the format or density. If the length specified for the device class is not ANY, the message includes the tape length. See “Recording Format and Length (CARTRIDGE)” on page 72 and “Density (REEL)” on page 73 for explanations of the possible values.

For example, if VOL001 has been used on a 3490 tape drive using the improved data recording capability (IDRC), subsequent requests for VOL001 specify the density as 3490C:

```
ANR5210I 001: Mount CARTRIDGE VOL001 at 0400 R/W (3490C) within 60 minutes.
```

If the tape length is specified on the device class as ECCST and the tape format of VOL001 is 3490C, the mount request would specify the tape length with the format:

```
ANR5210I 001: Mount CARTRIDGE VOL001 at 0400 R/W (3490C-ECCST) within 60 minutes.
```

Once the tape is mounted, the server verifies that:

- The device belongs to the requested device type (cartridge or reel)
- The tape drive can read or write at the required density or format
- The length of the cartridge tape is correct (3490B/3490C only)
- The volume is read-only or read-write as requested
- The VOL1 label matches the requested volume

Maintaining Information on Tape Condition

If the server cannot process a tape correctly, it records an error state for the tape so that it knows the tape cannot be processed correctly. General errors are recorded in the activity log; severe errors are recorded in the error log.

There are two error states: *I/O error* and *Unavailable*.

A volume is placed in *I/O error* state whenever the server receives a permanent *I/O error* while processing the tape. A tape in *I/O error* is no longer written to. However, the tape can be mounted when a file must be retrieved.

A volume is placed in *unavailable* state under any of the following conditions:

- The server detects that the volume has been corrupted.
- The CANCEL REQUEST PERMANENT command is issued to cancel a mount request for the volume.
- The volume status is changed to unavailable with the UPDATE VOLUME command.

A tape in unavailable state is no longer requested by the server, either for writing or reading.

You can use the QUERY VOLUME command to show the state of volumes. To try to recover files on unavailable volumes, use the following procedure:

1. Issue the QUERY CONTENT command to determine what files should be on the tape. If the files are out-of-date or otherwise not needed, proceed to step 6.
2. Use the UPDATE VOLUME command to make the tape available for mounting by setting ACCESS to read-only.
3. Try to read the tape by issuing an AUDIT VOLUME command with FIX=NO or by doing a restore or retrieve of one of the files on the tape. If the tape can be read without error, it might have been inadvertently marked as unavailable, as a result of a CANCEL REQUEST PERMANENT command. Ensure the volume status is changed to read-only or read-write, and do not proceed with the following steps.
4. Use the MOVE DATA command to try to recover files you still need.
5. If MOVE DATA does not work, use the AUDIT VOLUME command to synchronize the database with the readable contents of the tape. Unreadable files are deleted from the database, and you cannot recover them from the tape.
6. Use the DELETE VOLUME command to delete the volume from the server's database. If important files are lost, inform the affected users that their files are no longer available.

Handling Tape Mount Requests and Exit Machines

As an administrator with system or operator privilege, you can submit ADSM commands to manage tape mount requests and exit machines. You can:

- Request information on outstanding mount requests
- Request information on mounted tapes
- Request status on one or more exit machines
- Reply to outstanding mount requests
- Cancel an outstanding mount request
- Dismount a mounted tape
- Ready an exit machine to handle mount requests

You can use the DSMOP EXEC (on the program product disk) or the CP SMSG command to submit ADSM commands.

To use the DSMOP EXEC, do the following:

1. Modify the EXEC to specify the user ID of the ADSM Server
2. Put the EXEC in a minidisk or SFS filespace that can be accessed by any VM user IDs that will issue this EXEC
3. Specify the VM user ID in a REPLYOP option statement in the DSMSERV OPT file
4. Enter:


```
dsmop command
```

where:

command Specifies the ADSM command

To use the CP SMSG command, do the following:

1. Specify the VM user ID in a REPLYOP option statement in the DSMSEV OPT file
2. Enter:

```
cp msg serverid command
```

where:

serverid Specifies the server user ID

command Specifies the ADSM command

Querying Mount Requests

You can request information about the status of outstanding tape mount requests with the QUERY REQUEST command. For example, if you enter the following command, information on all outstanding requests is returned to you, including information on how soon the request must be satisfied before the server automatically cancels it, which exit machine is processing the request, and which requests are waiting for an exit machine to become available:

```
query request
```

If you want information about an outstanding request and you know the request number, you can include the request number on the command. For example, to get information on request number 12, enter:

```
query request 12
```

Querying Mounted Tapes

You can request information about the status of tapes that are mounted with the QUERY MOUNT command. For example, if you enter the following command, the volume name and device address of all mounted tapes is returned to you:

```
query mount
```

This command also returns information on whether the tape is in use or is idle.

If you want information about a mounted tape and you know the volume name of the tape, you can include the name on the command. For example, to get information on DSM988, enter:

```
query mount dsm988
```

Querying the Status of Exit Machines

You can request information about the status of exit machines with the QUERY EXIT command. For example, if you enter the following command, the status of each exit machine is returned to you:

```
query exit
```

If you only want information on the status of one exit machine, you can specify the user ID of the machine on the command. For example, to query the status of the DSMOUNT1 exit machine, enter:

```
query exit dsmount1
```

You can also use wild card characters to query more than one exit machine. For example, you can use DSM* to get information on all exit machines that begin with the letters DSM.

Exit machines can have one of the following:

- Ready** The exit machine is waiting for work (not logged on).
- Busy** The exit machine is currently processing a request (logged on)
- Offline** The server marked the exit machine as unusable because it was unable to log on the exit machine. There may be a problem with the machine.

Replying to Mount Requests When Using the Internal Mounting Facility

If you are using the internal mounting facility, you can reply to mount requests either by using the REPLY command or by directly attaching the tape drive to the server.

If you use the REPLY command, the server attaches the drive to itself once you reply to the mount message. For example, the server might issue the following mount request:

```
ANR5210I 001: Mount CARTRIDGE VOL001 at 0400 R/W within 60 minutes.
```

To reply to this message, first mount the volume on an available tape drive (for example, at address FE8), then use the request number provided in the mount request to tell the server which tape drive to attach to itself:

```
reply 1 fe8
```

If you use the ATTACH command, attach the drive directly to the server at the address requested. For example, to attach the drive at FE8 to the DSMSERV server machine at virtual address 400, use the following CP command:

```
attach fe8 dsmserv 400
```

Replying to Mount Requests When Using Exit Machines

If you are using exit machines, all mount requests are satisfied by the exit machines. Reply to mount requests according to your installation procedures.

Readying Exit Machines

When a server cannot automatically log on an exit machine despite repeated attempts, it marks the exit machine as offline. Once you have corrected the problem that prevented the server from logging on the exit machine, you can make the machine available to handle tape mount requests with the READY EXIT command. For example, to reset the status of the DSMOUNT1 exit machine, enter:

```
ready exit dsmount1
```

You can use wild card characters to ready more than one exit machine at a time. The server only readies exit machines that are offline, even if an online exit machine matches the pattern-matching expression you use. For example, the following command readies all offline machines without affecting those that are already available:

```
ready exit *
```

Canceling Mount Requests When Using the Internal Mounting Facility

You can cancel a tape mount request with the CANCEL REQUEST command. In order to cancel the request, you need to know the request number assigned to the request. This number is included on the mount request message, and can also be shown using the QUERY REQUEST command.

If the server requests a tape that is not available (perhaps because it is stored offsite), you can cancel the mount request (request number 1) using the following command:

```
cancel request 1
```

If there is a permanent problem with the tape, and you do not want the server to try to use the tape again, you can issue the following command to force the server to mark the tape volume as unavailable:

```
cancel request 1 permanent
```

You must use the parameter ALL to cancel all requests at one time. However, use this parameter carefully to avoid accidentally canceling requests.

Canceling Mount Requests When Using Exit Machines

When you are using exit machines, use your installation procedures for canceling tape mounts. This ensures that any tape management system you are using is properly notified of the cancellation.

If for some reason these procedures do not work, use the CANCEL REQUEST command to cancel the request. You can also use the CP FORCE command to force off the exit machine that is processing the request. Be aware that this command can create problems with tape management systems.

Dismounting Tapes

You can dismount idle tapes using the DISMOUNT VOLUME or DISMOUNT DEVICE command. For example, to dismount the tape volume named VOL001, enter:

```
dismount volume vol001
```

You can use the QUERY MOUNT command to determine the volume names and status of mounted volumes.

If you know the real address of the tape device on which the volume is mounted (for example, FE8), you can dismount the tape by dismounting the device:

```
dismount device fe8
```

You cannot use wild card characters with these commands.

Chapter 5. Using Exit Machines

This chapter contains Product-sensitive Programming Interface and Associated Guidance Information.

An exit machine provides ADSM an interface to an installation's tape procedures for the purpose of requesting tape devices and tapes. When ADSM requires a tape for a started process, the ADSM server will autolog an exit machine (if available) and pass to it information about the tape device needed, the virtual address that must be used, the volume name of the tape that must be mounted, and other values. The server then waits for the tape device to be dedicated (attached) to it. Once the tape device is attached, ADSM allows the waiting process to continue.

If a tape mount request must be canceled (a CANCEL REQUEST command was submitted to the ADSM server), the exit machine will be logged off by the ADSM server by issuing the CP command FORCE. The ADSM process waiting for the tape mount is then cancelled.

An exit machine will also be autologged whenever ADSM deletes a tape volume from its inventory of volumes. The exit machine must then handle the tape deletion according to the installation's tape procedures.

Sample EXECs are included in the ADSM for VM program product to assist you in setting up the exit machine. These should be reviewed to determine how they can be implemented as is or with changes. The sample EXECs are:

DSMEXIT PROFILE	An exit machine PROFILE EXEC
DSMMOUNT EXEC	Handles tape mount requests. This EXEC must be modified before being used.
DSMDELET EXEC	Handles tape deletion requests. This EXEC must be modified before being used.

The sections listed in the following table begin at the indicated pages.

Section	Page
Tasks:	
Defining Exit Machines	48
Setting up Exit Machines	48
Providing Input to Exit Machines	49
Satisfying Tape Mount Requests	50
Processing DELETE Requests	65

Most tasks presented in this chapter can be performed by using either the graphical user interface (GUI) or the command line interface. Table 11 on page 329 shows whether a task can be performed on the GUI, the command line interface, or both.

For information about issuing ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client. For help performing a task on the graphical user interface, refer to the online help.

Defining the Exit Machines

An exit machine is a virtual machine that will be autologged on the same system as the ADSM server. Up to 32 exit machines can be defined with each machine able to handle only one mount or delete request at a time. The number of exit machines needed by an installation can be determined after considering the following:

- The amount of tape activity expected
- The number of tape processes the ADSM server will handle concurrently
- If the exit machine will issue commands to an automated tape library, the number of requests the library supports
- The mount limits set in the device classes
- Server performance when tape processes are started

An exit machine is defined to your system in your CP directory with the following information:

User ID	A unique name that follows CP and your installation's naming requirements. This name is specified in an EXITVM option statement.
Privilege Class	B and G are the recommended privilege classes in addition to any other required privilege classes.
Virtual storage size	Dependent on the requirements of the installation's procedure that handles mount or delete requests.
Option	Any options required by your installation.
IPL	Do not specify AUTOOCR. Otherwise, the parameter data passed by the ADSM server to the exit machine at the time it is autologged will be lost.
Minidisk	The amount of DASD space and the number of minidisks needed by an exit machine is determined by the procedure used once the machine is autologged. The sample EXECs (DSMMOUNT and DSMDELET) require no DASD space as distributed.

Setting up an Exit Machine

A file named DSMEXIT PROFILE is distributed with the ADSM for VM program product and should be reviewed. This is an example of a PROFILE EXEC that can be implemented by an exit machine. If you intend to use this sample EXEC as is, then copy it to a minidisk or SFS directory where an exit machine can access it. Be sure to rename it to PROFILE EXEC.

Note that the sample DSMEEXIT PROFILE reads the passed parameters from the CMS program stack and passes control to either DSMMOUNT or DSMDELETE. Samples of these two EXECs are included in the ADSM for VM program product. They should be reviewed to make sure they meet your tape procedure's needs. Make changes as appropriate.

Also note that the sample DSMEEXIT PROFILE ends by issuing CP LOGOFF. This must be the last action taken by the PROFILE EXEC of an exit machine. If the exit machine does not log off, the ADSM server will not be able to utilize the machine again. For ADSM to utilize the machine again, you will have to log off the exit machine and then submit a READY EXIT command to the ADSM server.

Providing Input to an Exit Machine

The exit machine will be autologged with one of two CP commands: AUTOLOG when the VM/ESA system is running the 370 feature; otherwise, XAUTOLOG is used. Part of the command will be a string of data that will be placed in the CMS program stack of the exit machine and available to the PROFILE EXEC. The contents of this parameter string will depend on the type of request being submitted. The first word of the string will be MOUNT or DELETE. The rest of the parameters will be separated by blanks.

MOUNT parameters:

servername	The user ID of the ADSM server.
mountwait	The value of the MOUNTWAIT parameter for the device class (in minutes).
request#	The number assigned by the ADSM server to this mount request.
devtype	The type of device being requested (CARTRIDGE or REEL).
volname	The name of the volume to be mounted in the following formats: SCRATCH Scratch volume EXPORT.n Nonspecific export volumes (<i>n</i> is the sequence number) DBBKUP.n Nonspecific database backup volumes (<i>n</i> is the sequence number) DUMPDB.n Nonspecific database dump volumes (<i>n</i> is the sequence number) IMPORT.n Nonspecific import volumes (<i>n</i> is the sequence number)
vaddr	The virtual address that is to be associated with the tape device when attached to the ADSM server.
mode	This will be either R/W (read/write) or R/O (read-only).

density	This is the tape density expected by the ADSM server and will be one of the following:
3480	18-track format: 3480 or 3490
3480XF	18-track extended format: 3480 or 3490
3490B	36-track uncompact (basic) format
3490C	36-track compacted format
3490B-CST	media length specified as CST
3490B-ECCST	media length specified as ECCST
3490C-CST	media length specified as CST
3490C-ECCST	media length specified as ECCST
6250	6250 bits per inch tape reel
1600	1600 bits per inch tape reel
DRIVE	Empty tape requested at the highest format or density of the drive
stgpoolname	The name of the ADSM storage pool name to which the tape is associated; or EXPORT for a tape that is being used in an export process and does not belong to an ADSM storage pool.

DELETE parameters:

servername	The user ID of the ADSM server.
request#	The number assigned by the ADSM server to this delete request.
devtype	The type of device associated with this delete request (CARTRIDGE or REEL).
volname	The name of the volume being deleted by the ADSM server from its inventory.
stgpoolname	The name of the ADSM storage pool name to which the tape is associated.

Satisfying a Tape Mount Request

A tape mount request is satisfied once the requested tape device has been dedicated (attached) to the ADSM server using the virtual address passed to the exit machine. The ADSM server also expects a tape to be mounted and the device be ready for reading and/or writing. If the device is not ready when the ADSM server reads or writes from the device, the ADSM server virtual machine will be suspended by the VM/ESA system until the tape device is readied.

There are a number of methods available for dedicating a tape device to the ADSM server after it has been readied by the exit machine or the tape procedure in use by your installation. One of the following can be used:

- The CP commands DETACH LEAVE followed by ATTACH
- The CP command GIVE

Refer to the manual "VM/ESA: CP Command and Utility Reference" for more information on the CP commands.

After the ADSM server detects that a tape device has been dedicated at the virtual address requested, it verifies the following:

- The device belongs to the requested device type (cartridge or reel)
- The tape device has the required density (if a specific density was specified with the mount request)
- The length of the cartridge tape is correct (3490B/3490C only)
- The volume is either read/write or read-only (as indicated in the mount request)
- The VOL1 label matches the requested volume name.

DSMMOUNT EXEC Examples

This section presents three sample DSMMOUNT EXECs:

Example 1 handles a mount returned to the DSMMOUNT EXEC by a tape library machine.

Example 2 sends a mount request to a tape library machine that attaches the tape drive directly to the server.

Example 3 sends a mount request to a mount operator and attaches the mounted tape to the server.

Example 1: DSMMOUNT Attaches Tape Drive to Server

When the tape management system satisfies a mount request, this example EXEC attaches the tape drive to the server. This example uses the IBM Attachable Media Manager/VM product.

Here is the sequence of events:

1. The server autologs the exit machine, passing the mount request parameter to the exit machine as console data (Figure 9).




Figure 9. The Server Logs on to the Exit Machine

2. The PROFILE EXEC on the exit machine starts the DSMMOUNT EXEC.

3. The exit machine requests a tape mount of the tape management system tape library machine, and the tape library machine sends a mount message to the operator (Figure 10).




Figure 10. The Exit Machine Requests a Mount of the Tape Library Machine

4. The operator replies to the tape library machine mount request, and the tape library machine attaches the tape drive to itself and verifies the VOL1 label. (Figure 11).




Figure 11. The Operator Replies to the Mount Request

5. The tape library machine gives the tape drive to the exit machine because the exit machine made the mount request (Figure 12). In this example, the tape library machine uses the DETACH LEAVE command to detach the tape drive from itself without unloading the tape volume, then the ATTACH command attaches the drive to the exit machine.




Figure 12. The Tape Library Machine Gives the Tape to the Exit Machine

- The DSMMOUNT EXEC gives the tape drive to the server (Figure 13). In this example, the DSMMOUNT EXEC uses the DETACH LEAVE and ATTACH commands to transfer the tape drive and mounted tape to the server.




Figure 13. The Exit Machine Gives the Tape to the Server

7. The tape drive is now attached to the server, and the exit machine logs off (Figure 14).




Figure 14. The Exit Machine Logs Off

Figure 15 shows an example of the DSMMOUNT EXEC that performs this procedure.

```

/*****
* ADSTAR Distributed Storage Manager
*
* Licensed Materials - Property of IBM
*
* 5654-A02 (C) Copyright IBM Corporation 1990, 1996.
* All rights reserved.
*
* Refer to Copyright Instructions.
*****/

Trace Off
Address Command

/* ----- */
/* Get parameter list.
/* ----- */

Arg serverName mountWait requestNum devType volName ,
    serverVaddr mountMode format stgPoolName .

/*****
/**
/**      Customer's mount procedures go here.
/**
/** Note: A volName of DBBKUP.nn, EXPORT.nn or DUMPDB.nn
/**       where nn is numeric, is actually a mount request
/**       for a scratch tape for a database backup, export
/**       or database dump. A volName of SCRTCH is for a
/**       storage pool scratch volume. The mount command
/**       actually issued should be for a scratch volume
/**
/**
/**
myVaddr = 181
rc = 0
ring   = 'RING'
If mountMode = 'R/O' then
ring = 'NORING'

If ((left(volName,7) = 'DUMPDB.') | (left(volName,7) = 'EXPORT.')
 | (left(volName,7) = 'DBBKUP.')) then volName = 'SCRTCH'

'MOUNT' volName 'ON' myVaddr 'WAIT SL' ring 'FOR' serverName

```

Figure 15 (Part 1 of 2). Example 1: Exit Machine Attaches Tape Drive to Server

```

/**                                                    **/
/*****/

/* ----- */
/* Cancel mount if return code not zero.          */
/* (Logging off will cancel the mount.)           */
/* ----- */

If rc ^= 0 Then
  'CP LOGOFF'
/* ----- */
/* Find the real address of the tape drive.        */
/* ----- */

'EXECIO 1 CP ( LIFO STRING QUERY VIRTUAL' myVaddr
If rc ^= 0 Then
  'CP LOGOFF'
Pull . . . . raddr .

/* ----- */
/* Issue command to give the server the           */
/* drive at the correct address.                  */
/* ----- */

'CP DETACH' raddr '* LEAVE'
'CP ATTACH' raddr serverName serverVaddr

/* ----- */
/* Stack a Logoff command and exit.              */
/* ----- */

Push 'CP LOGOFF'
Exit 0

```

Figure 15 (Part 2 of 2). Example 1: Exit Machine Attaches Tape Drive to Server

Example 2: Tape Library Machine Attaches Tape Drive to Server

With this sample DSMMOUNT EXEC, the tape management system satisfies the mount request by attaching the tape drive directly to the server. This example uses the IBM Attachable Media Manager/VM product to perform the tape mounts.

The processing for this example is the same as that for Example 1, except that the DSMMOUNT EXEC does not receive control from the tape library machine after the tape is mounted.

After verifying the VOL1 label, the tape library machine gives the tape drive to the server, as shown in Figure 16.




Figure 16. The Tape Library Machine Gives the Tape to the Server

In this example, the tape library machine uses the GIVE command to detach the tape drive from itself and to give the drive to the server without unloading the tape volume.

Figure 17 shows an example of the DSMMOUNT EXEC that performs this procedure.

```

/*****
* ADSTAR Distributed Storage Manager *
* * *
* Licensed Materials - Property of IBM *
* * *
* 5654-A02 (C) Copyright IBM Corporation 1990, 1996. *
* All rights reserved. *
* * *
* Refer to Copyright Instructions Form Number G120-2083 *
*****/

Trace Off
Address Command

/* ----- */
/* Get parameter list. */
/* ----- */

Arg serverName mountWait requestNum devType volName ,
  serverVaddr mountMode format stgPoolName .
/*****/
/** Customer's mount procedures go here. **/
/** **/
/** Note: A volName of DBBKUP.nn, EXPORT.nn or DUMPDB.nn **/
/** where nn is numeric, is actually a mount request **/
/** for a scratch tape for a database backup, export **/
/** or database dump. A volName of SCRATCH is for a **/
/** storage pool scratch volume. The mount command **/
/** actually issued should be for a scratch volume **/
/** **/
rc = 0
ring = 'RING'
If mountMode = 'R/O' Then
ring = 'NORING'
If ((left(volName,7) = 'DUMPDB.') | (left(volName,7) = 'EXPORT.'))
| (left(volName,7) = 'DBBKUP.') then
volName = 'SCRATCH'

'MOUNT' volName 'ON' serverVaddr 'WAIT SL' ring 'FOR' serverName ,
'GIVETO' serverName
/*****/

/* ----- */
/* Stack a Logoff command and exit. */
/* ----- */

Push 'CP LOGOFF'
Exit 0

```

Figure 17. Example 2: DSMMOUNT EXEC Has the Tape Library Machine Attach Drive to Server

Example 3: DSMMOUNT Requests Tape of Mount Operator

With this sample DSMMOUNT EXEC, mount requests are sent to the operator rather than a tape management system. The operator replies to mount requests using the SMSG command, and the message is in the same format as the REPLY command. The DSMMOUNT EXEC uses the REPLY command to inform the server that the tape is mounted and ready for use. The DSMMOUNT EXEC does not do any authentication or error checking.

Here is the sequence of events:

1. The server autologs the exit machine, and the mount request is passed to the exit machine as console data (Figure 18).




Figure 18. The Server Autologs the Exit Machine

2. The PROFILE EXEC on the exit machine starts the DSMMOUNT EXEC.
3. The exit machine sends a mount request to the operator. (Figure 19).




Figure 19. The Exit Machine Requests a Mount from the Tape Operator

- The operator replies to the mount request with the CP SMSG command. The exit machine uses the REPLY command to tell the server the tape is mounted. The server then attaches the tape drive to itself (Figure 20).




Figure 20. The Operator Replies to the Mount Request

5. The tape drive is attached to the server, and the exit machine logs off (Figure 21).




Figure 21. The Exit Machine Logs Off

Figure 22 shows an example of the DSMMOUNT EXEC that performs this procedure.

```

/*****
* ADSTAR Distributed Storage Manager
*
* Licensed Materials - Property of IBM
*
* 5654-A02 (C) Copyright IBM Corporation 1990, 1996.
* All rights reserved.
*
* Refer to Copyright Instructions Form Number G120-2083
*****/

Trace Off
Address Command

/* ----- */
/* Get parameter list.
/* ----- */

Arg serverName mountWait requestNum devType volName ,
    serverVaddr mountMode format stgPoolName .

/*****
/**
/**      Customer's mount procedures go here.
/**
/** Note: A volName of DBBKUP.nn, EXPORT.nn or DUMPDB.nn
/**      where nn is numeric, is actually a mount request
/**      for a scratch tape for a database backup, export
/**      or database dump. A volName of SCRTCH is for a
/**      storage pool scratch volume. The mount command
/**      actually issued should be for a scratch volume
/**
/**
/**
rc = 0
myVaddr = 181

If ((left(volName,7) = 'DUMPDB.') | (left(volName,7) = 'EXPORT.')
    | (left(volName,7) = 'DBBKUP.')) then
    volName = 'SCRTCH'

mountMsg = requestNum': Mount' devClass volName 'for' serverName ,
           mountMode
If format ^= '' Then
    mountMsg = mountMsg||' ('format')'

'WAKEUP +00 ( NOEXT'

```

Figure 22 (Part 1 of 2). Example 3: DSMMOUNT EXEC Requests Mount through Operator

```

Do while mountWait > 0

  'CP MSG OP' mountMsg 'within' mountWait 'minutes.'
  'WAKEUP +00:01:00 ( SMSG'

  Select
    When rc = 1 Then Do                                /*      SMSG      */
      Parse Upper Pull cmdIssuer . 'REPLY' whichReq whichRaddr .
      'EXEC DSMOP REPLY' whichReq whichRaddr
      Leave
    End

    When rc = 2 Then                                  /*      Timer expired      */
      mountWait = mountWait - 1

    Otherwise Do
      'CP MSG OP Unknown return code from WAKEUP -- canceling mount.'
      Leave
    End
  End /* Select */

End /* Do */

'WAKEUP +00 ( RESEXT'

If mountWait = 0 Then
  'CP MSG OP Mount request timed out -- canceling mount.'

  /*****

  /* ----- */
  /* Stack a Logoff command and exit.          */
  /* ----- */

  Push 'CP LOGOFF'
  Exit 0

```

Figure 22 (Part 2 of 2). Example 3: DSMMOUNT EXEC Requests Mount through Operator

Processing a DELETE Request

Deletion of tape volumes from the ADSM database is conveyed to either an exit machine or to the mount operator (defined with the MOUNTOP option). An exit machine is notified of the tape deletion when both an EXITVM option statement and a DELETIONEXIT statement are specified; or a message is sent to the mount operator when no EXITVM option statement is specified and a DELETIONEXIT and MOUNTOP statement are specified. When a tape library management system must be notified of tapes no longer utilized by the ADSM server, it is recommended that an exit machine be defined, its name specified in an EXITVM option statement and the DELETIONEXIT option statement be specified. Or, if no tape management system exists but another virtual machine must be notified of tape deletions, an exit machine should be used. When a tape is deleted from the ADSM database and an exit machine is defined, the ADSM server will autolog the exit machine passing to it a parameter string. For the

contents of this string, see “Providing Input to an Exit Machine” on page 49. The process in the exit machine must check the first word for the request type, which could be MOUNT or DELETE. When the first word is DELETE, then the appropriate process for handling tape deletions must be invoked. An example of how this is done can be seen in DSMEXIT PROFILE, a sample PROFILE EXEC for the exit machine.

The process that handles the tape deletion request must perform the necessary actions (e.g. notify the tape management system) associated with a tape deletion. This process should not attempt to communicate with the ADSM server concerning the tape being deleted.

When a CANCEL REQUEST is received by the ADSM server to cancel a deletion request, the exit machine that is handling the deletion request will be logged off. Since this may have an adverse effect on a tape management system, canceling of tape deletion requests should be done with care. Canceling of a tape deletion request will not create problems for ADSM since the database will have been updated prior to autologging the exit machine.

When no exit machines are defined and DELETIONEXIT was specified, the ADSM server will send a message to the mount operator (defined by the MOUNTOP option) indicating that the tape has been deleted from the ADSM database.

Example of the DSMDELETE EXEC

Figure 23 shows an example of the DSMDELETE EXEC. In this example, the deletion exit notifies the operator when the server deletes a tape from its database.

```
/******  
* ADSTAR Distributed Storage Manager *  
* * * * *  
* Licensed Materials - Property of IBM *  
* * * * *  
* 5654-A02 (C) Copyright IBM Corporation 1990, 1996. *  
* All rights reserved. *  
* * * * *  
* Refer to Copyright Instructions. *  
*****/  
  
Trace Off  
Address Command  
  
/* ----- */  
/* Get parameter list. */  
/* ----- */  
  
Arg serverName requestNum devType volName stgPoolName .  
  
/******  
/** **/  
/** Customer's delete procedures go here. **/  
'CP MSG OP' serverName 'has deleted' volName 'from' stgPoolName  
/** **/  
/******  
  
/* ----- */  
/* Stack a Logoff command and exit. */  
/* ----- */  
  
Push 'CP LOGOFF'  
Exit 0
```

Figure 23. Example of the DSMDELETE EXEC

Chapter 6. Defining Device Classes

A device class represents a device type that can be used by ADSM. ADSM uses the device class to determine which device and storage volume type to use to:

- Store backup, archive, or space-managed data (primary storage pools)
- Store copies of primary storage pool data (copy storage pools)
- Store database backups
- Export or import ADSM data

One device class can be associated with multiple storage pools. Each storage pool is associated with just one device class.

Each device class is characterized by its *device type*, which indicates the type of storage volumes that are used to store data.

For random access storage, ADSM supports only the DISK device class. The DISK device class is predefined by ADSM. However, you can define many storage pools that are categorized by the DISK device class.

For sequential access storage, ADSM supports the following device types:

CARTRIDGE	Cartridge tape drives, such as IBM 3480, 3490, and 3490E drives
REEL	Half-inch reels, such as IBM 3420, 3422, and 3430
FILE	Storage volumes that are files in the file system of the server machine

The sections listed in the following table begin at the indicated pages.

Section	Page
Tasks:	
Defining and Updating Tape Device Classes	70
Defining and Updating FILE Device Classes	75
Filling Volumes to Capacity	78
Requesting Information about a Device Class	77
Deleting a Device Class	78

Most tasks presented in this chapter can be performed by using either the graphical user interface (GUI) or the command line interface. Table 11 on page 329 shows whether a task can be performed on the GUI, the command line interface, or both.

For information about issuing ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client. For help performing a task on the graphical user interface, refer to the online help.

Defining and Updating Device Classes for Sequential Media

Task	Required Privilege Class
Defining and updating device classes	System or unrestricted storage

You can define and update multiple device classes for each device type. The following sections show how to define the device classes for each supported device type.

Defining and Updating Device Classes for Tape

To use IBM 34xx tape drives and media or reel tape drives and media, you must define a device class whose device type is CARTRIDGE or REEL respectively. Do this by issuing a DEFINE DEVCLASS command with the DEVTYPE parameter. Other parameters specify how to manage data storage operations involving the new device class:

- MOUNTLIMIT
- MOUNTWAIT
- MOUNTRETENTION
- PREFIX
- FORMAT (CARTRIDGE only)
- LENGTH (CARTRIDGE only)
- DENSITY (REEL only)
- ESTCAPACITY
- MAXCAPACITY (CARTRIDGE only)
- EXPIRATION

Mount Limit

When defining a device class, you can limit the number of concurrent volume mounts so that your storage device resources are properly managed. The *MOUNTLIMIT* parameter specifies the maximum number of volumes that can be simultaneously mounted for a given device class.

The default mount limit value is 2; the maximum value for this parameter is 256.

When selecting a mount limit for a device class, be sure to consider the following questions:

- How many storage devices are connected to your system?
Do not specify a mount limit value that is greater than the number of associated available drives in your installation. If the server tries to mount as many volumes as specified by the mount limit and no drives are available for the required volume, an error occurs and client sessions may be terminated.

Note: ADSM cannot share drives between multiple device classes.

- Do you want reclamation of volumes to occur automatically?
If the mount limit is set to one, then ADSM cannot automatically reclaim available space on storage volumes. During the automatic reclamation process, ADSM requires two drives to move data from one volume to another.

If you set the mount limit to one and want to reclaim volumes, you must use a more manual process. See “Reclamation in a Device Class with Only One Mount Point” on page 105.

- How many ADSM processes do you want to run at the same time, using devices in this device class?

ADSM automatically cancels some processes to run other, higher priority processes. If the server is using all available drives in a device class to complete higher priority processes, lower priority processes must wait until a drive becomes available. For example, ADSM cancels the process for a client backing up directly to tape if the drive being used is needed for a server migration or tape reclamation process. ADSM cancels a tape reclamation process if the drive being used is needed for a client restore operation.

If processes are often cancelled by other processes, consider whether you can make more drives available for ADSM use. Otherwise, review your scheduling of operations to reduce the contention for drives.

Mount Wait Period

You can use the *MOUNTWAIT* parameter to specify the maximum amount of time, in minutes, that the server waits for a volume mount request to be satisfied before canceling the request. The default mount wait period is 60 minutes; the maximum value for this parameter is 9999 minutes.

Mount Retention Period

You can use the *MOUNTRETENTION* parameter to specify the amount of time that a mounted volume should remain mounted after its last I/O activity. If this idle time limit is reached, the server dismounts the volume.

For example, if the mount retention value is 60, and a mounted volume remains idle for 60 minutes, then the server dismounts the volume.

If a volume is used frequently, you can improve performance by setting a longer mount retention period to avoid unnecessary mount and dismount operations.

If mount operations are being handled via manual, operator-assisted activities, you may want to use a large mount retention period. For example, if only one operator supports your entire operation on a weekend, then define a long mount retention period so that the operator is not being asked to mount volumes every few minutes.

The default mount retention period is 60 minutes; the maximum value for this parameter is 9999 minutes.

Tape Label Prefix

The *PREFIX* parameter, specifies a value that is used to construct the *file name* string in the standard tape label. The default value for the tape label prefix string is *ADSM*. If the file name already exists in the header label, the file name is preserved.

The ADSM server does not use this file name field. The tape label prefix may be used by tape management systems that use the file name field. This process may be valuable when ADSM tapes are used to export data from one system to another.

Recording Format and Length (CARTRIDGE)

You can use the *FORMAT* parameter to specify the recording format used by ADSM when writing data to a tape and the *LENGTH* parameter to show the tape length. The following table shows the values supported for the CARTRIDGE device classes.

Use the *FORMAT=DRIVE* parameter only if all drives that can be accessed by the device class are identical. If some drives associated with a device class support a higher density format than others, mount errors can occur when you specify *FORMAT=DRIVE*.

For example, suppose a device class uses two incompatible devices such as an IBM 3480 with IDRC capability and an IBM 3480 without IDRC capability. The server might select the high-density recording format of 8500 for each of two new volumes. Later, if the two volumes are to be mounted concurrently, one fails because only one of the drives is capable of the high-density recording format.

The recording format that ADSM uses for a given tape volume is selected when the first piece of data is written to the volume. Note that updating the *FORMAT* parameter of a device class does not affect tapes that already contain data until those tapes are rewritten from the beginning. This process may happen after a volume is reclaimed or deleted, or after all of the data on the volume expires. Table 3 shows the read/write access of supported tape formats.

Table 3. Read/Write Compatibility Tape Devices and Tape Formats

Tape Device	Tape Format Keyword	Read/Write Access
3480	3480	Read/Write
3480	3480XF	Read/Write
3490	3480	Read/Write
3490	3480XF	Read/Write
3490E	3480	Read
3490E	3480XF	Read
3490E	3490B	Read/Write
3490E	3490C	Read/Write

Table 4. Tape Format, Media Type, and Default Estimated Capacity for CARTRIDGE Tape Volumes. * indicates tape formats that support compression. ADSM cannot determine how much compression increases capacity and therefore does not increase the estimated capacity for these tape formats.

Tape Format (FORMAT)	Media Type (LENGTH)	Estimated Capacity (ESTCAPACITY)	Description
3480	(Not applicable)	180MB	18-track basic recording format
3480XF *	(Not applicable)	180MB	18-track compacted recording format
3490B	CST	360MB	36-track basic recording format
3490C *	CST	360MB	36-track compacted recording format
3490B	ECCST	720MB	36-track basic recording format
3490C ¹	ECCST	720MB	36-track compacted recording format

For device classes that support the 3490 basic recording format (3490B) or the 3490 compacted recording format (3490C), you can specify the type of the storage media used with this device class.

Specify one of the following media types:

- CST**—Cartridge System Tape (standard length tape)
- ECCST**—Enhanced Capacity Cartridge System Tape (double length tape)
- ANY**—Specifies that the server accepts either CST or ECCST

For CARTRIDGE device classes specify the recording format parameter (FORMAT=).

When an empty tape cartridge is mounted for the first time, ADSM stores the format in its database. After a format is associated with a tape cartridge, ADSM can only read or write to the volume using the specified format.

Use DRIVE only when the device class has compatible tape devices. If you specify DRIVE for a device class that has non-compatible tape devices, then you must mount volumes on devices that are capable of reading or writing at the format established when the volume was first mounted. This can cause delays if the only tape device which can access the volume is already in use.

Density (REEL)

You can use the *DENSITY* parameter to specify the density used by ADSM when writing data to a reel. The following table shows the values supported for the REEL device classes.

Use the DENSITY=DRIVE parameter only if all drives that can be accessed by the device class are identical. If some drives associated with a device class support a higher density format than others, and you specify DENSITY=DRIVE, mount errors can occur.

The density that ADSM uses for a given tape volume is selected when the first piece of data is written to the volume. Note that updating the DENSITY parameter of a device class does not affect tapes that already contain data until those tapes are rewritten from the beginning. This process may happen after a volume is reclaimed or deleted, or after all of the data on the volume expires.

Table 5 displays the estimated capacity of tape reels used by ADSM.

Table 5. Density and Default Estimated Capacity for REEL Tape Volumes

Density	Estimated Capacity	Description
1600	44MB	Specifies that the reel tape device can read and write 1600 bits per inch
6250	156MB	Specifies that the reel tape device can read and write 6250 bits per inch
DRIVE	—	Lets the server select the recording format to use based on the drive on which the volume is mounted.

Maximum Capacity

You can specify the maximum amount of data that ADSM stores in the device class. This value determines the maximum capacity of the volume. If you do not specify a value, ADSM uses a default method based on IBM 3480 and 3490E device characteristics by using IBM tapes. If the default method does not meet your needs, set the value to less than the maximum capacity of the tape to avoid an end-of-tape situation. If ADSM detects an end-of-tape situation for the specified volume, a warning message is issued and the tape is treated as full.

Estimated Capacity Value

ADSM estimates the capacity of the volumes in a storage pool based on the parameters assigned to the device class that is associated with the storage pool. The estimated capacity value is used by ADSM when making decisions about when to initiate a reclamation process for volumes in the storage pool. It is also used to generate storage pool and volume reports.

You can either accept the default estimated capacity value for a given device class or explicitly specify an estimated capacity that you want the server to use instead of the default.

The default values selected by the server depend on the tape format (CARTRIDGE) or density (REEL) used to write data to the volume (see Table 4 on page 73 for details).

For more information on how ADSM uses the estimated capacity value, see “Filling Volumes to Capacity” on page 78.

Expiration Date for Files Stored on Tape

For each tape device class, you can specify an *expiration date*, which is placed in the tape label. Use the Julian date format of *yyddd* or *yyyyddd*.

ADSM does not use the expiration date. However, if your installation uses other tape management systems, consider setting an expiration date. When a tape management system attempts to mount this tape, it reads the label for the expiration date. If the expiration date has not been reached, then the tape management system will not use this tape volume.

If an expiration date already exists in the tape volume header, ADSM overwrites the expiration date when the tape is empty. The default expiration date is 99365, which means that files are never expired from tape.

Device Class Definition Examples

Here are examples of defining device classes for CARTRIDGE and REEL device types.

3490 Device: In this example, define a device class named 36TRACK to represent 3490E Tape Subsystem devices to be used by ADSM. Set the format to 3490C to specify compacted recording technology and ECCST to specify double length tape. Because of software compaction used at your installation, you know that you can store up to 900MB on double-sided tapes. Therefore, increase the estimated capacity to 900MB.

To optimize the use of available tape mounts, set the tape mount limit to 4, the mount retention period to 30 minutes, and the mount wait time to 30 minutes.

Finally, use the system defaults of ADSM for the tape prefix and 99365 for the expiration date.

To define the device class named 36TRACK tape enter:

```
define devclass 36track devtype=cartridge
format=3490C length=eccst estcapacity=900m
mountlimit=4 mountretention=30 mountwait=30
```

Defining and Updating FILE Device Classes

The FILE device type is used for special device classes whose storage volumes are not physical units, such as tape cartridges, but *simulated* storage volumes. Data is written sequentially into standard files in the file system of the server machine. You can define this device class by issuing a DEFINE DEVCLASS command with the DEVTYPE=FILE parameter.

You can define a device class with a device type of FILE for CMS files on a minidisk or in a Shared File System (SFS) directory. Device classes containing CMS files should not be used for primary storage pools. See Chapter 7, “Managing Storage Pools” on page 81 for details about primary and copy storage pools and “Using Disk for FILE Logical Devices” on page 28 for considerations when using minidisks and SFS file pools.

Because each volume in a FILE device class is actually a file, a volume name is a file name and file type separated by a period.

When you define the FILE device class, you supply additional parameters. The following parameters are used to instruct ADSM how to manage data storage operations for the new device class:

- MOUNTLIMIT
- MAXCAPACITY
- FILEMODE or DIRECTORY (must specify one)

Mount Limit

The mount limit value for FILE device classes is used to restrict the number of volumes (that is, files) that can be concurrently opened for access by data storage and retrieval operations. Any attempts to access more volumes than indicated by the mount limit causes the requester to wait.

For how to determine an appropriate mount limit value for the new device class, see “Mount Limit” on page 70.

Maximum Capacity Value

You can specify a maximum capacity value that restricts the size of volumes (that is, files) associated with a FILE device class. Use the MAXCAPACITY parameter of the DEFINE DEVCLASS command. When the server detects that a volume has reached a size equal to the maximum capacity, it treats the volume as full and stores any new data on a different volume.

The default MAXCAPACITY value for a FILE device class is 1MB.

File Mode or Directory

In the device class definition, for a file on a minidisk, specify the file mode letter of the read/write minidisk. For a file in SFS, specify the name of the SFS directory where the CMS file will exist.

FILE Device Class Examples

Here are two examples of FILE device class definitions, one for backups and one for exports:

```
define devclass backup devtype=file filemode=c
```

```
define devclass export devtype=file directory=vmsysu:mantia.doc
```

Requesting Information about a Device Class

Task	Required Privilege Class
Request information about device classes	Any administrator

You can choose to view a standard or detailed report. The default is a standard report.

To query the server to view a standard report on device classes, enter:

```
query devclass
```

Figure 24 is an example of a standard report for device classes.

Device Class	Device Access Strategy	Storage Pool Count	Device Type	Est. Cap. (MB)	Mount Limit	Mount Ret'n (min)	Mount Wait (min)	Format/Density
CARTRIDGE	Sequential	1	Cart.	180.0	2	60	60	Drive
DISK	Random	4						
REEL	Sequential	0	Reel	140.0	2	60	60	Drive

Figure 24. Example of a Standard Device Class Report

To query a server to view a detailed report for the 3480xf device class, enter:

```
query devclass 3480xf format=detailed
```

Figure 25 on page 78 shows an example of a detailed report for a device class.

```

Device Class: 3480XF
Device Access Strategy: Sequential
Storage Pool Count: 0
Last Update by (administrator): REES
Last Update Date/Time: 03/11/1993 18:13:56
Device Type: Cartridge
Maximum Capacity (MB):
Estimated Capacity (MB): 200.0
Dataset Name Prefix: ADSM
Mount Limit: 2
Mount Retention (min): 60
Label Type: IBMSL
Expiration Date: 99365
Unit Name: 3480
Compression: Yes
Protection: Yes
Retention:

more...

```

Figure 25. Example of a Detailed Device Class Report

Deleting a Device Class

Task	Required Privilege Class
Delete a device classes	System or unrestricted storage

You can delete a device class when:

- No storage pools are assigned to the device class. For information on deleting storage pools, see “Deleting a Storage Pool” on page 126.
- The device class is not being used by an export or import process.

Note: You cannot delete the DISK device class from the server.

Filling Volumes to Capacity

The MAXCAPACITY parameter in a device class indicates the capacity for sequential volumes associated with the device class through the storage pool. If MAXCAPACITY is not specified, a default value is set based on the device type.

When a volume is mounted, ADSM checks the associated device class for the maximum capacity for the volume. The server attempts to write to the volume until it has reaches this capacity.

Note: MAXCAPACITY is ignored for tape volumes used in export and database backup operations. These tapes are written to the physical end of the volume.

You can either accept the default capacity for a given device class, or specify a maximum capacity. You may want to specify the maximum capacity if:

- Data compression is being performed by the drives
- You have volumes of nonstandard size
- You want to restrict the amount of data on each volume

You can initially use the default capacity for a device class, then begin checking volumes when ADSM has filled them. If ADSM is not filling volumes to their actual capacity, you may want to specify the capacity by updating the device class.

If the MAXCAPACITY is greater than the actual capacity of the volumes in the device class and the server writes to the physical end of the volume, the following occur:

Tape cartridge	ADSM issues an end of volume message.
File	An error occurs, and the server stops writing to the volume and marks the volume read-only.

Tape Volume Capacity and Data Compression

Client files can be compressed to decrease the amount of data sent over networks and the space occupied by the data in ADSM storage. With ADSM, files can be compressed by the ADSM client before the data is sent to the ADSM server, and by the device where the file is finally stored. Where the compression is done affects how ADSM views the capacity of the volume where the data is stored.

It may wrongly appear that you are not getting the full use of the capacity of your tapes, for the following reasons:

- A tape device manufacturer often reports the capacity of a tape based on an assumption of compression by the device. If a client compresses a file before it is sent, however, the device may not be able to compress it any further before storing it.
- ADSM records the size of a file as it goes to a storage pool. If the client compresses the file, ADSM records this smaller size in the database. If the drive compresses the file, ADSM is not aware of this compression.

Figure 26 on page 80 compares what ADSM sees as the amount of data stored on tape when compression is done by the device and by the client. For this example, the tape has a physical capacity of 360MB; however, the manufacturer reports the capacity of the tape as 720MB by assuming the device compresses the data by a factor of two.

Suppose a client backs up a 720MB file:

- When the client does *not* compress the file, the server records the file size as 720MB, the file is compressed by the drive to 360MB, and the file fills up one tape.
- When the client compresses the file, the server records the file size as 360MB, the file cannot be compressed any further by the drive, and the file still fills one tape.

In both cases, ADSM considers the volume to be full. However, ADSM considers the capacity of the volume in the two cases to be different: 720MB when the drive

compresses the file, and 360MB when the client compresses the file. Use the QUERY VOLUME command to see the capacity of volumes from ADSM's viewpoint. See "Monitoring the Use of Storage Pool Volumes" on page 135.




Figure 26. Comparing Compression at the Client and Compression at the Device

For how to set up compression on the client, see "User Registration of Client Nodes" on page 265 and "Administrator Registration of Client Nodes" on page 265.

Chapter 7. Managing Storage Pools

A storage pool is a collection of storage volumes belonging to the same device class. The storage volumes contain backed up, archived, or space-managed files. The group of storage pools you set up for ADSM to use is called ADSM's *server storage*.

The sections listed in the following table begin at the indicated pages.

Section	Page
Concepts:	
Storage pools	81
Assigning volumes in storage pools	85
Storage pool hierarchy	85
Server migration of files	89
Cache on disk storage pools	94
Collocation on sequential access storage pools	95
Space reclamation on sequential access storage pools	100
Expiration processing	105
How restore processing works	106
Tasks:	
Estimating space needs for storage pools	110
Defining or updating storage pools	110
Backing up storage pools	114
Using copy storage pools to improve data availability	116
Monitoring the use of storage pools	117
Deleting storage pools	126
Restoring storage pools	127

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Storage Pools

ADSM has two types of storage pools:

Primary storage pool

When a client node backs up, archives, or migrates data, the data is stored in a primary storage pool.

When a user tries to restore, retrieve, recall, or export file data, the requested file is obtained from a primary storage pool if possible. Primary storage pool volumes are always located onsite.

A primary storage pool can use random access storage (DISK device class) or sequential access storage (for example, tape device classes; however, FILE device class is **not** recommended).

ADSM has three default, random access, primary storage pools:

ARCHIVEPOOL	Contains files archived from client nodes
BACKUPPOOL	Contains files backed up from client nodes
SPACEMGPOOL	Contains files migrated from client nodes via the space management function (space-managed files)

ADSM does not require a separate storage pool for space-managed files, but a separate storage pool is recommended. Clients are likely to require fast access to their space-managed files, and therefore you may want to have those files stored in a separate storage pool that uses your fastest disk storage.

Copy storage pool

When an administrator backs up a primary storage pool, the data is stored in a copy storage pool. See “Backing Up Storage Pools” on page 114 for details.

The copy storage pool provides a means of recovering from disasters or media failures. For example, when a client attempts to retrieve a file and the server detects a data-integrity error in the file copy in the primary storage pool, the server marks the file as damaged. At the next attempt to access the file, the server obtains the file from a copy storage pool.

ADSM attempts to access the file from a copy storage pool if the primary copy of the file cannot be obtained for one of the following reasons:

- The primary file copy has been previously marked damaged (for information about damaged files, see “Correcting Damaged Files” on page 319)
- The primary file is stored on a volume that is UNAVAILABLE or DESTROYED
- The primary file is stored on an offline volume
- The primary file is located in a storage pool that is UNAVAILABLE, and the operation is for restore, retrieve, or recall of files to a user, or export of file data

For details, see “Restoring Storage Pools” on page 127, “Using Copy Storage Pools to Improve Data Availability” on page 116, “Recovering a

Lost or Damaged Storage Pool Volume” on page 325, and “Maintaining the Integrity of Files” on page 320.

A copy storage pool can use only sequential access storage (for example, a tape or FILE device class).

Copy storage pool volumes can be moved offsite and still be tracked by ADSM. Moving copy storage pool volumes offsite provides a means of recovering from an onsite disaster.

An Example of Server Storage

Figure 27 shows one way to set up ADSM server storage. In this example, the storage defined for the server includes:

- The three default disk storage pools, all primary storage pools
- One primary storage pool consisting of tape cartridges
- One copy storage pool consisting of tape cartridges

For each of the three disk storage pools, the tape primary storage pool is next in the hierarchy. For more information about setting up a storage hierarchy, see “Storage Pool Hierarchy” on page 85.

All four of the primary storage pools can be backed up to the one copy storage pool. For more information on backing up primary storage pools, see “Backing Up Storage Pools” on page 114.




Figure 27. Example of Server Storage

Comparing Primary and Copy Storage Pools

Table 6 compares the characteristics of primary and copy storage pools.

Table 6. Comparing Primary and Copy Storage Pools

Characteristic	Primary storage pool	Copy storage pool
Destination for backed up or archived files (specified in backup or archive copy groups)	Yes	No
Destination for space-managed files (specified in the management class)	Yes	No
Offsite access mode for volumes	No	Yes
Destroyed access mode for volumes	Yes	No
Random access storage volumes	Yes	No
Sequential access storage volumes	Yes FILE device class is not recommended.	Yes
Contents	Client files (backup versions, archived files, space-managed files)	Copies of files that are stored in primary storage pools
Moving data allowed	Within the same primary storage pool, or to any primary storage pool	Within the same pool only. If volumes are offsite, data is copied from the original files in primary storage pools.
Collocation	Yes (sequential access storage pools only)	Yes
Reclamation	Yes (sequential access storage pools only)	Yes Offsite volumes are handled differently. For details, see "Reclamation of Offsite Volumes" on page 102.
File deletion	Files are deleted: <ul style="list-style-type: none"> • During inventory expiration processing, if the files have expired • When a file space is deleted • When a volume is deleted with the option to discard the data • When a primary storage pool volume is audited with the FIX=YES option, if the files on the volume are damaged and no other copies of the file exist 	Files are deleted: <ul style="list-style-type: none"> • Whenever the primary copy of the file is deleted from the primary storage pool (because of expiration, file space deletion, or volume deletion) • When a volume is deleted with the option to discard the data • When a copy storage pool volume is audited with the FIX=YES option, if the files on the volume are damaged

Assigning Volumes to Storage Pools

Before a storage pool can be used to store data, volumes must be assigned to the pool. Volumes are assigned differently depending on whether the pool is a random access storage pool or a sequential access storage pool.

Assigning Random Access Storage Pool Volumes

Volumes in random access storage pools must be prepared for use (formatted) and then defined. See Chapter 8, “Managing Storage Pool Volumes” on page 131 for information about formatting and defining volumes.

Assigning Sequential Access Storage Pool Volumes

You can define volumes in a sequential access storage pool or you can specify that ADSM dynamically acquire scratch volumes. You can also use a combination of defined and scratch volumes.

Use defined volumes when you want to control precisely which volumes are used in the storage pool. Using defined volumes may be useful when you want to establish a volume naming scheme for ADSM volumes. See Chapter 8, “Managing Storage Pool Volumes” on page 131 for information about defining volumes.

Use scratch volumes when you want to allow ADSM to dynamically acquire a volume when needed and dynamically delete the volume when it becomes empty. For example, you might want to use scratch volumes to avoid the burden of explicitly defining all of the volumes in a given storage pool.

Scratch volumes that ADSM acquired for a primary storage pool are deleted from the ADSM database when they become empty. The volumes are then available for reuse by ADSM or other applications. For scratch volumes that were acquired in a FILE device class, the space that the volumes occupied is freed by ADSM and returned to the file system.

Scratch volumes in a copy storage pool are handled in the same way as scratch volumes in a primary storage pool, except for volumes with the access value of offsite. If an offsite volume becomes empty, it is not immediately returned to the scratch pool. The delay prevents the empty volumes from being deleted from the database and makes it easier to determine which volumes should be returned to the onsite location. The administrator can query ADSM for empty offsite copy storage pool volumes and return them to the onsite location. The volume is returned to the scratch pool only when the access value is changed to READWRITE, READONLY, or UNAVAILABLE.

Storage Pool Hierarchy

Consider using multiple levels of primary storage pools to form a storage hierarchy. For example, assume that your fastest devices are disks, but space on these devices is scarce. You also have tape drives, which are slower to access, but have much greater capacity. You can define a hierarchy so that files are initially stored on the fast disk volumes in one storage pool, to provide clients with quick response to backup and

recall requests. Then, as the disk storage pool becomes full, ADSM migrates, or moves, data to tape volumes in a different storage pool. Migrating files to sequential storage pool volumes is particularly useful because all the files for a node are migrated together and organized in a more orderly way. This is especially helpful if collocation is not enabled.

When defining or updating a storage pool, you establish a hierarchy by identifying the storage pool to which data will be migrated, or moved, if the original storage pool is full or otherwise unavailable.

Restrictions:

1. You cannot establish a chain of storage pools that leads to an endless loop. For example, you cannot define StorageB as the *next* storage pool for StorageA, and then define StorageA as the *next* storage pool for StorageB.
2. The storage pool hierarchy includes only primary storage pools, not copy storage pools.

How ADSM Stores Files in a Storage Pool Hierarchy

Understanding how the server selects and accesses a primary storage pool can help you estimate the amount of space required for each storage pool in the hierarchy.

When a user backs up, archives, or migrates a file from a client node to the server, the server looks at the management class that is bound to the file to determine in which storage pool to store the file. The server then checks the storage pool to determine the following:

- If it is possible to write file data to the storage pool (access mode)
- What maximum file size is allowed in the storage pool
- Whether sufficient space is available on the available volumes in the storage pool
- What the next storage pool used is, if any of the previous conditions prevent the file from being stored in the storage pool being checked

Based on these factors, the server determines if the file can be written to that storage pool or the next storage pool in the hierarchy. As an example of how this might work, assume a company has a storage pool hierarchy as shown in Figure 28 on page 87.




Figure 28. Storage Hierarchy, Read/Write Access, and Maximum File Size

The storage pool hierarchy consists of two storage pools:

DISKPOOL	The top of the storage hierarchy. It contains fast disk volumes for storing data.
TAPEPOOL	The next storage pool in the hierarchy. It contains tape volumes accessed by high-performance tape drives.

Assume a user wants to archive a 5MB file named *FileX*. *FileX* is bound to a management class that contains an archive copy group whose storage destination is DISKPOOL, see Figure 28.

When the user archives the file, the server determines where to store the file based on the following process:

1. The server selects DISKPOOL because it is the specified archive storage destination.
2. Because the access mode for DISKPOOL is read/write, the server checks the maximum file size allowed in the storage pool.
3. The maximum file size allowed in DISKPOOL is 3MB. *FileX* is a 5MB file and therefore cannot be stored in DISKPOOL. The server searches for the next storage pool in the storage hierarchy.
4. The server checks the access mode of TAPEPOOL, which is the next storage pool in the storage hierarchy.
5. The access mode for TAPEPOOL is read/write. The server then checks the maximum file size allowed in the storage pool.
6. Because TAPEPOOL is the last storage pool in the storage hierarchy, no maximum file size is specified. Therefore, if there is available space in TAPEPOOL, *FileX* can be stored in it.

How the Storage Hierarchy Affects Planning for Copy Storage Pools

It is strongly recommended that all primary storage pools that are linked to form a storage hierarchy use the same copy pool for backup. If this is done, then a file that is copied does not need to be recopied when it migrates to another primary storage pool.

For most cases, a single copy storage pool can be used for backup of all primary storage pools. The number of copy storage pools you need depends on the hierarchies you have set up with your primary storage pools and what type of disaster recovery protection you wish to implement.

Multiple copy storage pools may be needed to handle particular situations, including:

- Special processing of certain primary storage hierarchies (for example, archive storage pools or storage pools dedicated to priority clients)
- Creation of multiple copies for multiple locations (for example, to keep one copy onsite and one copy offsite)
- Rotation of full storage pool backups (See “Backing Up Storage Pools” on page 302 for more information.)

Using the Hierarchy to Stage Client Data from Disk to Tape

A common way to use the storage hierarchy is for initially storing client data on disk, then letting ADSM migrate the data to tape. A guideline for how much primary disk storage should be dedicated for this staging of client data is enough storage to handle one night’s worth of the clients’ incremental backups. While not always feasible, this guideline has even more value when considering storage pool backups.

For example, if you have enough disk space for nightly incremental backups for clients and have tape devices, you can set up the following pools:

- A primary storage pool on disk, with enough volumes assigned to contain the nightly incremental backups for clients
- A primary storage pool on tape, which is identified as the next storage pool in the hierarchy for the disk storage pool
- A copy storage pool on tape

Then you can schedule these steps every night:

- 1** Perform an incremental backup of the clients to the disk storage pool.
- 2** After clients complete their backups, back up the disk primary storage pool (now containing the incremental backups) to the copy storage pool.

Backing up disk storage pools before migration processing allows you to copy as many files as possible while they are still on disk. This saves mount requests while performing your storage pool backups.

- 3 Start the migration of the files in the disk primary storage pool to the tape primary storage pool (the next pool in the hierarchy) by lowering the high migration threshold. For example, lower the threshold to 40%.

When this migration completes, raise the high migration threshold back to 100%.

- 4 Back up the tape primary storage pool to the copy storage pool to ensure that all files have been backed up.

The primary sequential storage pools must still be backed up to catch any files that might have been missed in the backup of the disk storage pools (for example, large files that went directly to sequential media).

See “Estimating Space Needs for Storage Pools” on page 107 for more information about storage pool space.

Server Migration of Files

ADSM provides automatic migration to maintain free space in a primary storage pool. For example, ADSM can migrate data stored on a random access disk storage pool to a less expensive sequential access storage pool when the migration threshold parameter you set is exceeded.

Migration Thresholds for Disk Storage Pools

When you define or update a storage pool, set migration thresholds to specify when the server should begin migrating, or moving, data to the next storage pool in the storage hierarchy. This process helps to ensure that there is sufficient free space in the storage pools at the top of the hierarchy, where faster devices can provide the most benefit to clients.

You can use the defaults for the migration thresholds, or you can change the threshold values to identify the maximum and minimum amount of space for a storage pool. See “Defining a Primary Storage Pool” on page 110 for more information about migration thresholds.

Before you define migration thresholds, you should understand how the server determines when to migrate files, and how it chooses which files to migrate. Then you can determine migration thresholds for both disk and sequential access storage pools.

For disk storage pools, migration thresholds can be set lower when cache is enabled. See “The Use of Cache on Disk Storage Pools” on page 94 for information about setting the CACHE parameter.

When Files Are Migrated

When the high migration threshold is reached in a storage pool, ADSM migrates files from the pool to the next storage pool. ADSM first identifies which client node has backed up or migrated the largest single file space or has archived files that occupy the most space. When the server identifies the client node based on these criteria, the server migrates *all* files from *every* file space belonging to that client.

After the files for the first client node are migrated to the next storage pool, the server checks the low migration threshold for the storage pool to determine if the migration process should be stopped. If the amount of space used in the storage pool is now below the low migration threshold, migration ends. If not, another client node is chosen by using the same criteria as described above, and the migration process continues.

For example, Table 7 displays information contained in the database that is used by the server to determine which files to migrate. This example assumes no space-managed files are stored in the storage pool.

Table 7. Database Information on Files Stored in DISKPOOL

Client Node	Backed-Up File Spaces	Archived Files (All Client File Spaces)
TOMC	TOMC/C = 200MB TOMC/D = 100MB	55MB
HTANG	HTANG = 50MB	5MB
PEASE	PEASE/home = 150MB PEASE/temp = 175MB	40MB




Figure 29. The Migration Process and Migration Thresholds

Figure 29 shows what happens when the high migration threshold defined for the disk storage pool *DISKPOOL* is exceeded. When the amount of migratable data in *DISKPOOL* reaches 80%, the server performs the following tasks:

1. Determines that the TOMC/C file space is taking up the most space in the *DISKPOOL* storage pool, more than any other single backed-up or space-managed file space and more than any client node's archived files.

2. Locates all data belonging to node TOMC stored in DISKPOOL. In this example, node TOMC has backed up or archived files from file spaces TOMC/C and TOMC/D stored in the DISKPOOL storage pool.
3. Migrates all data from TOMC/C and TOMC/D to the next available storage pool. In this example, the data is migrated to the tape storage pool, TAPEPOOL.

The server migrates all of the data from both file spaces belonging to node TOMC, even if the occupancy of the storage pool drops below the low migration threshold before the second file space has been migrated.

If the cache option is enabled, files that are migrated remain on disk storage (that is, the files are *cached*) until space is needed for new files. For more information about using cache, see “The Use of Cache on Disk Storage Pools” on page 94.

4. After all files that belong to TOMC are migrated to the next storage pool, the server checks the low migration threshold. If the low migration threshold has not been reached, then the server again determines which client node has backed up or migrated the largest single file space or has archived files that occupy the most space. The server begins migrating files belonging to that node.

In this example, the server migrates *all* files that belong to the client node named PEASE to the TAPEPOOL storage pool.

5. After all the files that belong to PEASE are migrated to the next storage pool, the server checks the low migration threshold again. If the low migration threshold has been reached or passed, then migration ends.

Appropriate Migration Threshold Values

Setting migration thresholds for disk storage pools ensures sufficient free space on faster speed devices, which can lead to better ADSM performance. Choosing thresholds appropriate for your situation takes some experimenting, and you can start by using the default values. You need to ensure that migration occurs frequently enough to maintain some free space but not so frequently that the device is unavailable for other use.

To choose the high-migration threshold, consider:

- The amount of storage capacity provided for each storage pool
- The amount of free storage needed for users to store additional files, without having migration occur

If you set the high-migration threshold too high, the pool may be just under the high threshold, but not have enough space to store an additional, typical client file. Or, with a high threshold of 100%, the pool may become full and a migration process must start before clients can back up any additional data to the disk storage pool. In either case, client files must be stored directly to tape until migration completes, resulting in slower performance.

If you set the high-migration threshold too low, migration runs more frequently and can interfere with other operations.

Keeping the high-migration threshold at a single value means that migration processing could start at any time of day, whenever that threshold is exceeded. You can control when migration occurs by using administrative command schedules to change the threshold. For example, set the high-migration threshold to 95% during the night when clients run their backup operations, then lower the high-migration threshold to 50% during the time of day when you want migration to occur. By scheduling when migration occurs, you can choose a time when your tape drives and mount operators are available for the operation.

To choose the low-migration threshold, consider:

- The amount of free disk storage space needed for normal daily processing. If you have disk space to spare, you can keep more data on the disk (a larger low threshold). If clients' daily backups are enough to fill the disk space every day, you may need to empty the disk (a smaller low threshold).

If your disk space is limited, try setting the threshold so that migration frees enough space for the pool to handle the amount of client data that is typically stored every day. Migration then runs about every day, or you can force it to run every day by lowering the high-migration threshold at a time you choose.

- Whether you use cache on disk storage pools to improve the retrievability of data. If you use cache, you can set the low threshold lower, yet still maintain faster retrieval for some data. Migrated data remains cached on the disk until new client data pushes the data off the disk. Using cache requires more disk space for the database, however.

If you do not use cache, you may want to keep the low threshold at a higher number so that more data stays on the disk.

- How frequently you want migration to occur, based on the availability of sequential access storage devices and mount operators. The larger the low threshold, the shorter time that a migration process runs (because there is less data to migrate). But if the pool refills quickly, then migration occurs more frequently. The smaller the low threshold, the longer time that a migration process runs, but the process runs less frequently.

You may need to balance the costs of larger disk storage pools with the costs of running migration (drives, tapes, and either operators or automated libraries).

- Whether you are using collocation on the next storage pool. When you use collocation, ADSM attempts to store data for different clients on separate tapes, even for clients with small amounts of data. You may want to set the low threshold to keep more data on disk, to avoid having lots of tapes used by clients with only small amounts of data.

Immediate User Access to Files on Disk Storage

Caching is a good method of providing immediate access to files on disk storage, even if the files have been migrated to a tape storage pool. However, cached files are removed from disk when the space they occupy is required. The file then must be obtained from the storage pool to which it was migrated.

To ensure that files remain on disk storage and do not migrate to other storage pools, use one of the following methods:

- Do not define the *next* storage pool.

A disadvantage of using this method is that if the file exceeds the space available in the storage pool, the operation to store the file fails.

- Set the high-migration threshold to 100%.

When you set the high migration threshold to 100%, files will not migrate at all. You can still define the *next* storage pool in the storage hierarchy, and set the maximum file size so that large files are stored in the next storage pool in the hierarchy.

A disadvantage of setting the high threshold to 100% is that once the pool becomes full, client files are stored directly to tape instead of to disk. Performance may be affected as a result.

Migration Thresholds for Sequential Access Storage Pools

Migration from sequential storage pools is performed by volume, to minimize the number of mounts for source volumes. Sequential volumes selected for migration are those that were least recently referenced.

While you can define or update migration thresholds for sequential access storage pools, you probably will not perform this type of migration on a regular basis. This type of operation, such as tape-to-tape migration, has limited benefits compared to disk-to-tape migration and requires at least two tape drives.

However, you may find it necessary to migrate data from one sequential access storage pool to another. For example, if you install a different tape drive or you want to move tape volumes from an automatic tape library to shelf volumes, then migration from a sequential access storage pool may be appropriate.

When defining migration criteria for sequential access storage pools, consider:

- The capacity of the volumes in the storage pool
- The time required to migrate data to the next storage pool
- The speed of the devices that the storage pool uses
- The time required to mount media, such as tape volumes, into drives
- Whether operator presence is required

If you decide to migrate data from one sequential access storage pool to another, ensure that:

- Two drives (mount points) are available, one in each storage pool
- The next storage pool in the storage hierarchy has read/write access.

For information about setting an access mode for sequential access storage pools, see “Defining a Primary Storage Pool” on page 110.

- Collocation is set the same in both storage pools. For example, if collocation is set to *yes* in the first storage pool, then collocation should be set to *yes* in the subordinate storage pool.

When you enable collocation for a storage pool, ADSM attempts to keep all files belonging to a client node on a minimal number of volumes. For information about collocation for sequential access storage pools, see “Collocation on Sequential Access Storage Pools” on page 95.

- You have sufficient staff available to handle any necessary media mount and dismount operations, because the server attempts to reclaim space from sequential access storage pool volumes before it migrates files to the next storage pool.

If you want to limit migration from a sequential access storage pool to another storage pool, set the high-migration threshold to a high percentage, such as 95%.

For information about setting a reclamation threshold for tape storage pools, see “Space Reclamation for Sequential Access Storage Pools” on page 100.

There is no straightforward way to selectively migrate data for a specific node from one sequential storage pool to another. If you know the volumes on which a particular node’s data is stored, you can use the MOVE DATA command to move all files from selected volumes to the new storage pool.

Migration and Copy Storage Pools

Copy storage pools are not part of the storage migration hierarchy. Files are not migrated to or from copy storage pools. The only way to store files in copy storage pools is by using the BACKUP STGPOOL command.

Migration of files between primary storage pools does not affect copy storage pool files. Copy storage pool files do not move when primary storage pool files move.

For example, suppose a copy of a file is made while it is in a disk storage pool. The file then migrates to a primary tape storage pool. If you then back up the primary tape storage pool to the same copy storage pool, a new copy of the file is not needed. ADSM knows it already has a valid copy of the file.

The Use of Cache on Disk Storage Pools

When defining or updating disk storage pools, you can enable or disable cache. When cache is enabled, the migration process leaves behind duplicate copies of files on disk after the server migrates these files to subordinate storage pools in the storage hierarchy. The copies remain in the disk storage pool, but in a *cached* state, so that subsequent retrieval requests can be satisfied quickly. However, if space is needed to store new data in the disk storage pool, the space occupied by cached files can be immediately reused for the new data.

When cache is not used and migration occurs, the server migrates the files to the next storage pool and erases the files from the disk storage pool.

By default, the system enables caching for each disk storage pool. You can change this option by specifying `CACHE=NO` when you define or update a storage pool.

Why Use Cache?

Using cache improves the retrievability of files, because a copy of the file remains on fast disk storage after the primary file is migrated.

When cache is used and migration occurs for the disk storage pool, the server migrates files to the next storage pool, but leaves cached copies of the migrated files in the disk storage pool. The cached copies remain in the disk storage pool until space is needed for new files.

When space is needed, the server reclaims space by writing over the cached files. Files that have the oldest retrieval date and occupy the largest amount of disk space are overwritten first. For example, if File A was last retrieved on 04/16/95 and File B was last retrieved on 06/19/95, then File A is deleted to reclaim space before File B.

Effect of Caching on Storage Pool Statistics: The space utilization statistic for the pool (%Util) includes the space used by any cached copies of files in the storage pool. The migratable data statistic (%Migr) does *not* include space occupied by cached copies of files. ADSM uses the migratable data statistic (%Migr) to compare with migration threshold parameters to determine when migration should begin or end. For more information on storage pool statistics, see “Monitoring the Use of Storage Pools” on page 117.

When Not to Use Cache

Do not use cache if you have limited space for the ADSM database. When you use cache, more database space is needed because the server has to keep track of both the cached copy of the file and the new copy in the subordinate storage pool.

If you disable cache, you may want to set higher migration thresholds for the disk storage pool. A higher migration threshold keeps files on disk longer because migration occurs less frequently.

Collocation on Sequential Access Storage Pools

Collocation is a process in which the server attempts to keep all files belonging to a client node on a minimal number of sequential access storage volumes. You can set collocation on or off for each sequential access storage pool when you define or update the pool.

To have ADSM collocate data when files from different client nodes are mixed in the same storage pool, set collocation to *yes* when you define or update a sequential storage pool. By using collocation, you reduce the number of volume mount operations required when users restore, retrieve, or recall many files from the storage pool. Collocation thus improves access time for these operations. Figure 30 on page 96 shows an example of collocation enabled, with three clients having separate volumes assigned for each client.




Figure 30. Example of Collocation Enabled

When collocation is disabled, the server attempts to use all available space on each volume before selecting a new volume. While this process provides better utilization of individual volumes, user files can become scattered across many volumes. Figure 31 shows an example of collocation disabled, with three clients sharing space on a volume.




Figure 31. Example of Collocation Disabled

When users want to restore, retrieve, or recall a large number of files, media mount operators may be required to mount more volumes to recover user data. The system default is to not use collocation.

To determine whether to use collocation, consider:

- The amount of time available for backup processing
 - If you have limited time for backup, disable collocation because with collocation you have more media mounts.

- The amount of time required to access a particular sequential access storage volume

The access time depends mostly on the type of media involved in the operation. For example, if the storage pool is associated with a tape device class, the access time is relatively long, because tape volumes must be mounted into the appropriate type of drive by either an operator or robotics. However, if the device type of the device class associated with the storage pool is FILE, then the storage volumes can typically be accessed very quickly, and without manual intervention.

- Whether users need to be able to restore or retrieve a large number of files within a short period of time

When users need to restore or retrieve a large number of files, enable collocation. Without collocation, your ability to recover files for users might be delayed because:

- More than one user's files can be stored on the same sequential access storage volume.

For example, if two users attempt to recover a file that resides on the same volume, the second user will be forced to wait until the first user's files are recovered.

- A user's files can be spread across multiple volumes, requiring additional media mounts and dismounts by operators.

- How you want the server to utilize storage space

When collocation is enabled, the server attempts to use all available tape volumes to separate user files before it uses all available space on every tape volume.

When collocation is disabled, the server attempts to use all available space on each tape volume before it selects the next tape volume.

- Whether you have sufficient personnel to manage media mounts during backup, archive, or client migration operations

While collocation helps to reduce the number of mount operations during recovery, operators may experience:

- More mounts when user files are backed up, archived, or migrated from client nodes directly to sequential access volumes
- More mounts during reclamation or migration
- Additional handling of sequential access volumes because the volumes might not be fully used

To reduce the number of media mounts and to use space on sequential volumes more efficiently, you can:

- Define a storage pool hierarchy that requires backed up, archived, or space-managed files to be stored initially in disk storage pools.

When files are migrated from a disk storage pool, the server attempts to migrate all files belonging to the client node which is using the most disk space in the storage pool. This process works well with the collocation option

because the server tries to place all of the files from a given client on the same sequential access storage volume.

- Use scratch volumes for sequential access storage pools to allow the server to select new volumes for collocation.

How the Server Selects Volumes with Collocation Enabled

When collocation is enabled and users back up, archive, or migrate files to sequential access storage, the server attempts to select a volume that already contains files from file spaces belonging to the client node. If no such volume exists, the server selects a volume using the following selection order:

1. An empty predefined volume
2. An empty scratch volume
3. A volume with the most available free space among volumes that already contain data

When the server needs to continue to store data on a second volume, it uses the following selection order to acquire additional space:

1. An empty predefined volume
2. An empty scratch volume
3. A volume on which other user files are already stored
4. A volume that has the most available free space
5. Any available volume in the storage pool

Through this selection process, the server attempts to provide the best use of individual volumes without mixing user files on multiple volumes. For example, Figure 32 shows that volume selection is *horizontal*, where all available volumes are used before all available space on each volume is used. A, B, C, and D represent files from four different client nodes.




Figure 32. Using All Available Sequential Access Storage Volumes with Collocation Enabled

How the Server Selects Volumes with Collocation Disabled

When collocation is disabled, the server attempts to use all available space in a storage volume before it accesses another volume. When storing client files in a sequential

access storage pool where collocation has been disabled, the server first attempts to select a previously used sequential volume with available space.

If none exists, the server selects the volume that contains the most data so that each volume is fully utilized. If no partially full volume exists, the server selects an empty volume.

When the server needs to continue to store data on a second volume, it attempts to select an empty volume. If none exists, the server attempts to select any remaining available volume in the storage pool.

Figure 33 shows that volume utilization is *vertical* when collocation is disabled. In this example, fewer volumes are used because the server attempts to use all available space by mixing user files on individual volumes.




Figure 33. Using All Available Space on Sequential Volumes with Collocation Disabled

Turning Collocation On or Off

After you define a storage pool, you can turn collocation on or off by updating the storage pool. The change in collocation for the pool does not affect files that are already stored in the pool.

For example, if collocation had been off for a storage pool and you turn it on, *from then on* client files stored in the pool are collocated. Files that had previously been stored in the pool are *not* moved to collocate them. As volumes are reclaimed, however, the data in the pool tends to become more collocated. You can also use the MOVE DATA command to move data to new volumes to increase collocation, if you are able to afford the processing time and volume mount activity this would cause.

Collocation on Copy Storage Pools

There are special considerations when using collocation on copy storage pools. Primary and copy storage pools perform different recovery roles. Direct client recovery is typically done from the primary pools while copy storage pools are usually used to

recover the primary pool data. In a disaster where both clients and the server are lost, the copy storage pool volumes will probably be used directly to recover clients. The types of recovery scenarios that are of most concern to you will help to determine whether to use collocation on your copy storage pools.

Another consideration is that collocation on copy storage pools will result in more partially filled volumes and potentially unnecessary offsite reclamation activity.

Collocation typically results in a partially filled sequential volume for each client. This may be acceptable for primary storage pools because these partially filled volumes remain available and can be filled during the next migration process. However, for copy storage pools this may be unacceptable because the storage pool backups are usually made to be taken offsite immediately. If you use collocation for copy storage pools, you will have to decide between:

- Taking more partially filled volumes offsite thereby increasing the reclamation activity when the reclamation threshold is lowered or reached.

or

- Leaving these partially filled volumes onsite until they fill and risk not having an offsite copy of the data on these volumes.

With collocation disabled for a copy storage pool, typically there will be only a single partially filled volume after storage pool backups to this copy storage pool are complete.

Careful consideration should be given before using collocation for copy storage pools. Even customers using collocation for their primary storage pools may wish to disable collocation for copy storage pools. One example of when collocation on copy storage pools may be desirable is when you have few clients, but each of them has large amounts of incremental backup data each day.

See “Collocation on Sequential Access Storage Pools” on page 95 for more information about collocation.

Space Reclamation for Sequential Access Storage Pools

Space on a sequential volume becomes reclaimable as files expire or are deleted from the volume. For example, files become obsolete because of aging or version limits. When the percentage of reclaimable space exceeds a specified level, the *reclamation threshold*, the server begins space reclamation for the volume. You can set a reclamation threshold for each sequential access storage pool when you define or update the pool.

During space reclamation, the server copies active files from the candidate volume to other volumes in the storage pool. For example, Figure 34 on page 101 shows the active files from tapes 1, 2, and 3, being consolidated on tape 4.




Figure 34. Tape Reclamation

After all readable files have been moved to other volumes, one of the following actions is taken for the candidate volume:

- If the volume has been defined to the storage pool, it becomes available for reuse by ADSM
- If the volume has been acquired as a scratch volume, it is deleted from the ADSM database

Volumes in a copy storage pool are reclaimed in the same manner as a primary storage pool with the exception of *offsite* volumes.

Choosing a Reclamation Threshold

The reclamation threshold indicates how much reclaimable space a volume must have before ADSM reclaims the volume. Space is reclaimable because it is occupied by files that have been expired or deleted from the ADSM database, or because it has not been used.

The lower the reclamation threshold, the more frequently the server tries to reclaim space. Frequent reclamation optimizes the use of a sequential access storage pool's space, but can interfere with other processes, such as backups from clients.

Each reclamation process requires *at least* two simultaneous volume mounts, that is, at least two mount points (drives) in the same device class. There must be a sufficient number of volumes, drives (if appropriate), and mount operators (if appropriate) to handle frequent reclamation requests. For more information about mount limit, see "Mount Limit" on page 70.

If you set the reclamation threshold to 50% or greater, ADSM can combine the usable files from two or more volumes onto a single new volume.

If the reclamation threshold is high, reclamation occurs less frequently. A high reclamation threshold is useful if mounting a volume is a manual operation and the operations staff is at a minimum.

Setting the reclamation threshold to 100% prevents reclamation from occurring at all. You might want to do this to control when reclamation occurs, to prevent interfering with other server processes. When convenient for you and your users, you can lower the reclamation threshold to cause reclamation to begin.

Reclamation for Copy Storage Pools

Reclamation of primary storage pool volumes does not affect copy storage pool files.

Reclamation of volumes in copy storage pools is similar to that of primary storage pools. One difference, however, is that most volumes in copy storage pools may be set to an access mode of offsite, making them ineligible to be mounted. During reclamation, valid files on offsite volumes are copied from the original files in the primary storage pools. In this way, valid files on offsite volumes are copied without having to mount these volumes. For more information, see "Reclamation of Offsite Volumes."

Reclamation of copy storage pool volumes should be done periodically to allow reuse of partially filled volumes that are offsite. Reclamation can be done automatically by setting the reclamation threshold for the copy storage pool to less than 100%. However, you need to consider controlling when reclamation occurs because of how offsite volumes are treated. For more information, see "Controlling When Reclamation Occurs for Offsite Volumes" on page 103.

Reclamation of Offsite Volumes

As for other volumes, volumes with the access value of offsite are eligible for reclamation if the amount of empty space on a volume exceeds the reclamation threshold for the copy storage pool. The default reclamation threshold for copy storage pools is 100%, which means that reclamation is not performed.

When an offsite volume is reclaimed, the files on the volume are rewritten to a *read/write* volume. Effectively these files are moved back to the onsite location, but

may be obtained from the offsite volume after a disaster if a database backup is used that references the files on the offsite volume.

The ADSM server reclaims offsite volumes as follows:

1. The server determines which files are still active on the volume to be reclaimed.
2. These active files are obtained from a primary storage pool (or from an onsite volume of a copy storage pool, if necessary).
3. The active files are written to one or more new volumes in the copy storage pool and the database is updated.
4. A message is issued indicating that the offsite volume was reclaimed.

Controlling When Reclamation Occurs for Offsite Volumes

Suppose you plan to make daily storage pool backups to a copy storage pool, then mark all new volumes in the copy storage pool as *offsite* and send them to the offsite storage location. This strategy works well with one consideration if you are using automatic reclamation (reclamation threshold less than 100%).

Each day's storage pool backups will create some number of new copy storage pool volumes, the last one being only partially filled. If this partially filled volume is emptier than the reclaim percentage, this volume becomes eligible for reclamation as soon as you mark it offsite. The reclamation process would cause a new volume to be created with the same files on it. The volume you take offsite would then be empty according to the ADSM database. If you do not recognize what is happening, you could perpetuate this process by marking the new partially filled volume offsite.

One way to resolve this situation is to keep partially filled volumes onsite until they fill up. However, this would mean a small amount of your data would be without an offsite copy for another day.

For this reason, it is recommended you control copy storage pool reclamation by using the default value of 100. This turns reclamation off for the copy storage pool. You can start reclamation processing at desired times by changing the reclamation threshold for the storage pool. To monitor offsite volume utilization and help you decide what reclamation threshold to use, enter the following:

```
query volume * access=offsite format=detailed
```

Depending on your data expiration patterns, you may not need to do reclamation of offsite volumes each day. You may choose to perform offsite reclamation on a less frequent basis. For example, suppose you ship copy storage pool volumes to and from your offsite storage location once a week. You can run reclamation for the copy storage pool weekly, so that as offsite volumes become empty they are sent back for reuse.

When you do perform reclamation for offsite volumes, the following sequence is recommended:

- 1** Back up your primary storage pools to copy storage pools
- 2** Turn on reclamation for copy storage pools by lowering the reclamation threshold
- 3** When reclamation processing completes, turn off reclamation for copy storage pools by raising the reclamation threshold to 100%
- 4** Mark any newly created, copy storage pool volumes as offsite and then move them to the offsite location

This sequence ensures that the files on the new copy storage pool volumes are sent offsite, and are not inadvertently kept onsite because of reclamation.

Delaying Reuse of Reclaimed Volumes

You should delay the reuse of any reclaimed volumes in copy storage pools for as long as you keep your oldest database backup. Delaying reuse may help you to recover data under certain conditions during recovery from a disaster. For more information on delaying volume reuse, see “Delaying Reuse of Sequential Access Volumes” on page 105.

How Collocation Affects Reclamation

If collocation is enabled and reclamation occurs, the server tries to reclaim each user’s files onto a minimal number of volumes. Therefore, if the volumes are manually mounted, the mount operators must:

- Be aware that a tape volume may be rewound more than once if the server completes a separate pass to move each client’s data.
- Mount and dismount multiple volumes to allow the server to select the most appropriate volume on which to move each client data. The server tries to select a volume in the following order:
 1. A volume that already contains files belonging to the client node
 2. An empty volume
 3. The volume with the most available space
 4. Any available volume

If collocation is disabled and reclamation occurs, the server tries to move usable data to new volumes by using the following volume selection criteria:

1. The volume that contains the most data
2. Any partially full volume
3. An empty predefined volume
4. An empty scratch volume

Reclamation in a Device Class with Only One Mount Point

If a device class defined to ADSM has only one mount point, ADSM cannot perform automatic reclamation for volumes in that device class. To reclaim those volumes, use the MOVE DATA command. If the target storage pool is higher in the storage pool hierarchy than the original storage pool, the moved data migrates back to the original storage pool and be written to a new volume. The original storage pool volume is then reclaimed.

Here is an example of how you can do this:

- 1** Define a device class with device type FILE.
- 2** Define a storage pool using the file device class. As the next storage pool, specify the tape storage pool associated with the single mount point device class.
- 3** Move data from tape volumes that need to be reclaimed to the file storage pool.
- 4** Lower the high migration threshold for the file storage pool so that data migrates back to the tape storage pool. When the data migrates, it will be written to new volumes there.

Expiration Processing

When file spaces are deleted, backup files are versioned off, or archive files pass their archive retention period, these files are expired from the ADSM database. Later, when expiration processing runs, information about these files and also any copies of these files made in copy storage pools is removed from the database.

If backup policies are set up appropriately, the need to recover an expired file should be a rare occurrence. If this need occurs, expired files can be recovered by:

1. Restoring the database to a point in time prior to file expiration.
2. Using a primary or copy storage pool volume that has not been rewritten and contains the expired file data at the time of database backup.

You should delay the reuse of copy storage pool volumes that have no active files for as long as you keep your oldest database backup. Delaying reuse may help you to recover data under certain conditions during recovery from a disaster. For more information on delaying volume reuse, see “Delaying Reuse of Sequential Access Volumes.”

Delaying Reuse of Sequential Access Volumes

When you define or update a sequential access storage pool, you can use a parameter called REUSEDELAY. This parameter specifies the number of days that must elapse before a volume can be reused or returned to scratch status, after all files have been expired, deleted, or moved from the volume. When you delay reuse of such volumes, volumes enter the *pending* state once they no longer contain any files. Volumes

remain in the pending state for as long as specified with the REUSEDELAY parameter for the storage pool to which the volume belongs.

Delaying reuse of volumes can be helpful under certain conditions for disaster recovery. When ADSM expires, deletes, or moves files from a volume, the files are not actually erased from the volumes: the database references to these files are removed. Thus the file data may still exist on sequential volumes if the volumes are not immediately reused.

If a disaster forces you to restore the ADSM database using a database backup that is old or is not the most recent backup, some files may not be recoverable because ADSM cannot find them on current volumes. Some of this data may exist on volumes that are in pending state, and you may be able to use them to recover data.

If you back up your primary storage pools, the REUSEDELAY parameter for the primary storage pools should be set to 0, to efficiently reuse primary scratch volumes. For your copy storage pools, you should delay reuse of volumes for as long as you keep your oldest database backup.

For an example of using database backup and delaying volume reuse, see "Protecting Your Database and Storage Pool" on page 322. For more information about expiration, see "Expiration Processing" on page 105.

How Restore Processing Works

ADSM provides two commands that allow an administrator to recreate files in a primary storage pool using copies in a copy storage pool:

RESTORE STGPOOL

Restores all files in a storage pool that have been previously identified as having data-integrity errors. These files are also known as *damaged* files. This command also restores all files on any volumes that have been designated as *destroyed* using the UPDATE VOLUME command. See "Restoring Storage Pools" on page 127 for more detailed information.

RESTORE VOLUME

Recreates files that reside on a volume or volumes in the same primary storage pool. This command can be used to recreate files for one or more volumes that have been lost or damaged. See "Restoring Storage Pool Volumes" on page 149 for more detailed information.

ADSM uses database information to determine which files should be restored for a volume or storage pool, so restore processing does not require that the original volumes be accessed. For example, if a primary storage pool volume becomes damaged, the RESTORE VOLUME command could be used to recreate files that were stored on that volume, even though the volume itself is not readable. However, if the administrator were to delete the damaged files with DISCARDDATA=YES, the database reference to the files on the primary storage pool volume and all references to copies of the files on copy storage pool volumes, would be removed from the database. It would not be possible to restore those files.

Restore processing obtains files from a copy storage pool and stores these files on new primary storage pool volumes. Database references to files on the original primary storage pool volumes are then deleted. If a primary storage pool volume becomes empty because all files that were stored on that volume have been restored to other volumes, the empty volume is automatically deleted from the database.

To facilitate restore processing of entire volumes, ADSM has a *destroyed* volume access mode. This mode is used to designate primary volumes for which files are to be restored. If a volume has an access mode of destroyed, ADSM does not mount that volume for either read or write access. You can change the access mode of a volume to destroyed in one of two ways:

- By using the RESTORE VOLUME command. The RESTORE VOLUME command automatically changes the access mode of specified volumes to destroyed using a volume list provided as part of the command.
- By using the UPDATE VOLUME command. Before using the RESTORE STGPOOL command to restore volumes in a storage pool, the administrator must update the access mode of the volumes to destroyed.

The destroyed designation for volumes is important during restore processing, particularly when the RESTORE STGPOOL command is used to restore a large number of primary storage pool volumes after a major disaster:

- You can designate as destroyed only those volumes that need to be restored. If some volumes are known to be usable after a disaster, the access state of the usable volumes should not be set to destroyed, so they will not be restored.
- Once the administrator has identified the primary volumes to be restored, and has changed the access mode of these volumes to destroyed, new volumes can be added to the storage pool. The new volumes are used to contain the files as they are restored from the copy storage pool volumes, and can also be used for storage of new files that may be backed up, archived, or migrated by the end users.
- The designation of destroyed volumes allows ADSM to keep track of the files that still need to be restored from copy storage pools. If restore processing is ended before completion for any reason, you can start the restore again. Processing would be resumed and only the files that still reside on destroyed volumes would need to be restored.

Estimating Space Needs for Storage Pools

This section provides guidelines for estimating the initial storage space required for your installation. It assumes the use of the following default random access (disk) storage pools provided by ADSM:

- BACKUPPOOL for backed up files
- ARCHIVEPOOL for archived files
- SPACEMGPOOL for files migrated from client nodes (space-managed files)

As your storage environment grows, you may want to consider how policy and storage pool definitions affect where workstation files are stored. Then you can define and

maintain multiple storage pools in a hierarchy that allows you to contain storage costs by using sequential access storage pools in addition to disk storage pools, and still provide appropriate levels of service to users.

To help you determine how to adjust your policies and storage pools, get information about how much storage is being used (by client node) and for what purposes in your existing storage pools. For more information on how to do this, see “Requesting Information on Storage Occupancy” on page 123.

Estimating Space Needs in Random Access Storage Pools

To estimate the amount of storage space required for each random access (disk) storage pool:

- Determine the amount of disk space needed for different purposes:
 - For backup storage pools, provide enough disk space to support efficient daily incremental backups.
 - For archive storage pools, provide sufficient space for a user to archive a moderate size file system without causing migration from the disk pool to occur.
 - For storage pools for space-managed files, provide enough disk space to support the daily space-management load from HSM clients, without causing migration from the disk pool to occur.
- Decide what percentage of this data you want to keep on disk storage space and establish migration thresholds to have the server migrate the remainder of the data to less expensive storage media in sequential access storage pools.

See “Appropriate Migration Threshold Values” on page 91 for recommendations on setting migration thresholds.

Estimating Space for Backed Up Files in a Random Access Storage Pool

To compute the total amount of space needed for all backed up files stored in a single random access (disk) storage pool, such as BACKUPPOOL, use the following formula:

$$\text{Backup space} = \text{AvgWkstSize} * \text{Utilization} * \text{VersionExpansion} * \text{NumWkst}$$

Backup Space	The total amount of storage pool disk space needed.
AvgWkstSize	The average data storage capacity of a workstation, in MB. For example, if the typical workstation at your installation has two 70MB hard drives, then the average workstation storage capacity is 140MB.
Utilization	An estimate of the fraction of each workstation disk space used, in the range 0 to 1. For example, if you expect that workstations are 75% full, then use 0.75.

VersionExpansion An expansion factor (greater than 1) that takes into account the additional backup versions, as defined in the copy group. A rough estimate allows 5% additional files for each backup copy. For example, for a version limit of 2, use 1.05, and for a version limit of 3, use 1.10.

NumWkst The estimated total number of workstations ADSM supports.

If compression is used, the amount of space required may be less than the amount calculated, depending on whether the data is compressible.

Estimating Space for Archived Files in a Random Access Storage Pool

Computing the amount of storage space for archived files is more difficult, because the number of archived files generated by users is not necessarily proportional to the amount of data stored on their workstations.

To estimate the total amount of space needed for all archived files in a single random access (disk) storage pool, such as ARCHIVEPOOL, determine what percentage of user files are typically archived.

Work with policy administrators to calculate this percentage based on the number and type of archive copy groups defined. For example, if policy administrators have defined archive copy groups for only half of the policy domains in your enterprise, then you can estimate that you will need less than 50% of the amount of space you have defined for backed up files.

Because additional storage space can be added at any time, you can start with a modest amount of storage space and increase the space by adding storage volumes to the archive storage pool, as required.

Estimating Space Needs in Sequential Access Storage Pools

To estimate the amount of space required for sequential access storage pools, consider:

- The amount of data being migrated from disk storage pools
- The length of time backed up files are retained, as defined in backup copy groups
- The length of time archived files are retained, as defined in archive copy groups
- How frequently you reclaim unused space on sequential volumes

See “Space Reclamation for Sequential Access Storage Pools” on page 100 for information about setting a reclamation threshold.

- Whether or not you use collocation to reduce the number of volume mounts required when restoring or retrieving large numbers of files from sequential volumes

If you use collocation, you may need additional tape drives and volumes.

See “Collocation on Sequential Access Storage Pools” on page 95 for information about using collocation for your storage pools.

- The type of storage devices and sequential volumes supported at your installation

Defining or Updating Storage Pools

This section provides examples of how you can set up a storage pool hierarchy for an organization in your installation.

Task	Required Privilege Class
Define storage pools	System
Update storage pool information	System or unrestricted storage

Defining a Primary Storage Pool

When you define a primary storage pool, be prepared to provide some or all of the information shown in Table 8. Some information applies only to random access storage pools or only to sequential access storage pools.

Table 8 (Page 1 of 2). Information for Defining a Storage Pool

Information	Explanation	Applies to Random Access	Applies to Sequential Access
Device class	Specifies the name of the device class assigned for the storage pool. This is a required parameter.	Yes	Yes
Pool type	Specifies that you want to define a primary storage pool (this is the default). Updating a storage pool cannot change whether it is a primary or a copy storage pool.	Yes	Yes
Access mode	<p>Defines access to volumes in the storage pool for user operations (such as back up and restore) and system operations (such as reclamation and server migration). Possible values are:</p> <p>Read/Write User and system operations can read from or write to the volumes.</p> <p>Read-Only User operations can read from the volumes, but not write. However, system processes can move files within the volumes in the storage pool.</p> <p>Unavailable No new writes are permitted to volumes in the storage pool from other volumes outside the storage pool. However, system processes (like reclamation) are permitted to move files within the volumes in the storage pool.</p>	Yes	Yes

Table 8 (Page 2 of 2). Information for Defining a Storage Pool

Information	Explanation	Applies to Random Access	Applies to Sequential Access
Maximum file size	To exclude large files from a storage pool, set a maximum file size. Do not set a maximum file size for the last storage pool in the hierarchy unless you want to exclude very large files from being stored in server storage.	Yes	Yes
Name of the next storage pool	Specifies the name of the next storage pool where files can be migrated or stored.	Yes	Yes
Migration thresholds	Specifies a percentage of storage pool occupancy at which ADSM begins migrating files to the next storage pool (high threshold) and the percentage when migration stops (low threshold).	Yes	Yes
Migration process	Specifies the number of processes that are used for migrating files from this storage pool.	Yes	—
Cache	Enables or disables cache. When cache is enabled, copies of files migrated by the server to the next storage pool are left on disk after the migration. In this way, a retrieval request can be satisfied quickly.	Yes	—
Maximum number of scratch volumes	By providing a nonzero value, you specify that ADSM dynamically acquires scratch volumes.	—	Yes
Collocation	<i>Collocation</i> is a process in which the server attempts to keep all files belonging to a client file space on a minimal number of sequential access storage volumes.	—	Yes
Reclamation threshold	Specifies what percentage of reclaimable space can accumulate on a volume before the server initiates a space reclamation process for the volume.	—	Yes
Reuse delay period	Specifies an integer that defines the number of days that must elapse after all of the files have been deleted from a volume, before the volume can be rewritten or returned to the scratch pool.	—	Yes

Example: Defining a Storage Pool Hierarchy

For this example, suppose you have determined that an engineering department requires a separate storage hierarchy. You want the department's backed up files to go to a disk storage pool. When that pool fills, you want the files to migrate to a tape storage pool. You want the pools to have the following characteristics:

- Disk primary storage pool
 - The pool named ENGBACK1 is the storage pool for the engineering department.

- The size of the largest file that can be stored is 5MB. Files larger than 5MB are stored in the tape storage pool.
- Files migrate from the disk storage pool to the tape storage pool when the disk pool is 85% full. File migration to the tape storage pool stops when the disk pool is down to 40% full.
- The access mode is the default, read/write.
- Cache is used.
- Tape primary storage pool
 - The name of the pool is BACKTAPE.
 - The pool uses the device class TAPE, which has already been defined.
 - No limit is set for the maximum file size, because this is the last storage pool in the hierarchy.
 - To group files from the same client on a small number of volumes, use collocation.
 - Use scratch volumes for this pool, with a maximum number of 100 volumes.
 - The access mode is the default, read/write.
 - Use the default for reclamation: Reclaim a partially full volume (to allow reuse) when 60% of the volume's space can be reclaimed.

There are two ways to define the storage pools in a storage pool hierarchy: from the top down or from the bottom up. Defining the hierarchy from the bottom up requires fewer steps. To define the hierarchy from the bottom up, perform the following steps:

- 1** Define the storage pool named BACKTAPE with the following command:

```
define stgpool backtape tape
description='tape storage pool for engineering backups'
maxsize=nolimit collocate=yes maxscratch=100
```

- 2** Define the storage pool named ENGBACK1 with the following command:

```
define stgpool engback1 disk
description='disk storage pool for engineering backups'
maxsize=5M nextstgpool=backtape highmig=85 lowmig=40
```

Example: Updating a Storage Pool Hierarchy

If you have already defined the storage pool at the top of the hierarchy, you can update the storage hierarchy to include a new storage pool.

For example, suppose you had already defined the ENGBACK1 disk storage pool. Now you have decided to set up a tape storage pool to which files from ENGBACK1 can migrate. Perform the following steps to define the new tape storage pool and update the hierarchy:

- 1 Define the storage pool named BACKTAPE with the following command:

```
define stgpool backtape tape
description='tape storage pool for engineering backups'
maxsize=nolimit collocate=yes maxscratch=100
```

- 2 Specify that BACKTAPE is the next storage pool defined in the storage hierarchy for ENGBACK1. To update ENGBACK1, enter:

```
update stgpool engback1 nextstgpool=backtape
```

Defining a Copy Storage Pool

When you define a copy storage pool, be prepared to provide some or all of the following information:

Device class

Specifies the name of the device class assigned for the storage pool. This is a required parameter.

Pool type

Specifies that you want to define a copy storage pool. This is a required parameter. Updating a storage pool cannot change whether the pool is a primary or copy storage pool.

Access mode

Defines access to volumes in the storage pool for user operations (such as backup and restore) and system operations (such as reclamation).

Possible values are:

Read/Write User and system operations can read from or write to the volumes.

Read-Only User operations can read from the volumes, but not write. However, system processes can move files within the volumes in the storage pool.

Unavailable Specifies that users cannot access files stored on volumes in the copy storage pool. Files can be moved within the volumes of the copy storage pool, but no new writes are permitted to the volumes in the storage pool from volumes outside the storage pool.

Maximum number of scratch volumes

By providing a nonzero value, you specify that ADSM dynamically acquires scratch volumes.

Collocation

Collocation is a process in which the server attempts to keep all files belonging to a client node on a minimal number of sequential access storage volumes.

Reclamation threshold

Specifies when to initiate reclamation of volumes in the copy storage pool. Reclamation is a process that moves any remaining active, fragmented files from one volume to another volume, thus making the original volume available for reuse. A volume is eligible for reclamation when the percentage of unused space on the volume is greater than the reclaim parameter value.

Reclamation processing works differently for offsite storage pool volumes compared to other volumes. When a copy storage pool volume that is offsite becomes eligible for reclamation, the reclamation process attempts to retrieve the active files on the reclaimable volume from a primary or copy storage pool volume that is onsite, and then write these files to an available volume in the original copy storage pool.

Reuse delay period

Specifies an integer that defines the number of days that must elapse after all of the files have been deleted from a volume before the volume can be rewritten or returned to the scratch pool.

Example: Defining a Copy Storage Pool

Assume you need to have copies of the files stored in BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL (default disk storage pools) for disaster recovery purposes. An ADSM administrator uses the DEFINE STGPOOL command to create a copy storage pool named DISASTER-RECOVERY. It was decided to use only scratch tapes so the maximum number of scratch volumes is set to an appropriate value.

```
define stgpool disaster-recovery cartridge pooltype=copy  
maxscratch=100
```

To store data in the new storage pool, you must back up the primary storage pools (BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL) to the DISASTER-RECOVERY pool. See “Backing Up Storage Pools.”

Backing Up Storage Pools

Administrators can back up primary storage pools into copy storage pools.

Multiple primary storage pools can be backed up to one copy storage pool. A primary storage pool can be backed up to multiple copy storage pools if multiple copies are necessary. However, it is recommended that the entire primary storage pool hierarchy be backed up to the same copy storage pool for easier management of storage volumes.

Task	Required Privilege Class
Back up storage pools	System, unrestricted storage, or restricted storage for the copy storage pool

The BACKUP STGPOOL command is used to copy files into a copy storage pool. Because the copies are made incrementally, the backup process may be cancelled if desired. Reissuing the BACKUP STGPOOL command allows the backup to continue from the spot the backup was cancelled. For example, to back up the ARCHIVEPOOL primary pool to the DISASTER-RECOVERY copy pool, enter:

```
backup stgpool archivepool disaster-recovery
```

The BACKUP STGPOOL command can also be scheduled. The administrator can define schedules to initiate incremental backups of files in the primary storage pools. For example, to back up the BACKUPPOOL, ARCHIVEPOOL, and the TAPEPOOL every night, the following commands are scheduled:

```
backup stgpool backuppool disaster-recovery maxprocess=4
backup stgpool archivepool disaster-recovery maxprocess=4
backup stgpool tapepool disaster-recovery maxprocess=4
```

These commands use multiple (4), parallel processes to perform an incremental backup of each primary storage pool to the copy pool. The only files backed up to the DISASTER-RECOVERY pool are files for which a copy does not already exist in the copy storage pool. See Chapter 10, "Automating Operations" on page 193 for information about scheduling commands.

Notes:

1. Backing up storage pools places additional space requirements on the ADSM database.
2. If a copy is to be generated in a specific copy storage pool and a copy already exists with the same insertion date, no action is taken.
3. File copies stored in a copy storage pool do not migrate from that copy storage pool to any other.
4. Copies of files that remain on disk after being migrated to the next storage pool (cached files) are not backed up when the disk storage pool is backed up.

5. Set the MAXPROCESS parameter to the number of mount points or drives that can be dedicated to this operation.

See “Backing Up Storage Pools” on page 302 for more information about using storage pool backup in your disaster recovery strategy.

Using Copy Storage Pools to Improve Data Availability

Copy storage pools enable multiple copies of files to be maintained, thus reducing the potential for data integrity loss due to media failure. If the primary file is not available or becomes corrupted, ADSM accesses and uses the duplicate file from a copy storage pool.

Example: Simple Hierarchy with One Copy Storage Pool

A company has a storage hierarchy consisting of two primary storage pools: one random access storage pool (DISK-POOL) and one tape storage pool (CART-POOL, with device class CARTRIDGE). The files stored in the random access storage pool are migrated to the tape storage pool. Because the files are important to the function of the company, the company wants to back up the files in both primary storage pools to a copy storage pool.

The administrator decides to schedule daily incremental backups of the files in the primary storage pools. The administrator performs the following steps:

- 1 Create a copy storage pool called CART-COPYPOOL, with the same device class as the CART-POOL primary storage pool, by issuing the following command:

```
define stgpool cart-copypool cartridge pooltype=copy
maxscratch=50
```

Notes:

- a. Because scratch volumes are allowed in this copy storage pool, you do not need to define volumes for the pool.
 - b. All of the storage volumes in the copy storage pool CART-COPYPOOL are located onsite.
- 2 Perform the initial backup of the primary storage pools to the new copy storage pool. Copy the files in the primary storage pools to the copy storage pool CART-COPYPOOL by issuing the following commands:

```
backup stgpool disk-pool cart-copypool
backup stgpool cart-pool cart-copypool
```

- 3 Define schedules to automatically run the commands for backing up the primary storage pools to the copy storage pool. The commands to schedule are those that you issued in step 2.

To minimize tape mounts, back up the disk storage pool first, then the tape storage pool.

For more information about scheduling, see Chapter 10, "Automating Operations" on page 193.

Monitoring the Use of Storage Pools

Any administrator can query for information about a storage pool by viewing a standard or a detailed report. Use these reports to monitor storage pool usage, including:

- Whether you need to add space to your disk and sequential access storage pools
- The status of the process of migrating data from one to storage pool to the next storage pool in the storage hierarchy
- The use of disk space by cached copies of files that have been migrated to the next storage pool

Monitoring the Use of Storage Pool Space

To query the server to view a standard report for all storage pools defined to the system, enter:

```
query stgpool
```

Figure 35 shows a standard report with all storage pools defined to the system. To monitor the use of storage pool space, review the *Estimated Capacity* and *%Util* columns.

Storage Pool Name	Device Class Name	Estimated Capacity (MB)	%Util	%Migr	High Mig%	Low Mig%	Next Storage Pool
ARCHIVEPOOL	DISK	0.0	0.0	0.0	90	70	
BACKTAPE	TAPE	180.0	85.0	100.0	90	70	
BACKUPPOOL	DISK	80.0	51.6	51.6	50	30	BACKTAPE
COPYPOOL	TAPE	300.0	42.0				
ENGBACK1	DISK	0.0	0.0	0.0	85	40	BACKTAPE

Figure 35. Information about Storage Pools

Estimated Capacity

Specifies the space available in the storage pool in megabytes.

For disk storage pools, this value reflects the total amount of available space in the storage pool, including any volumes that are varied offline.

For sequential access storage pools, this value is an estimate of the total amount of available space on all volumes in the storage pool, including volumes that have *unavailable*, *read-only*, *offsite*, or *destroyed* access mode, and all scratch volumes that can be acquired in this storage pool. Volumes in a sequential access storage pool, unlike those in a disk storage pool, do not contain preallocated space. Data is written to a volume as necessary until the end of the volume is reached. For this reason, the estimated capacity is truly an *estimate* of the amount of available space in a sequential access storage pool.

%Util

Specifies, as a percentage, the space used in each storage pool.

For disk storage pools, this value reflects the total number of disk blocks currently allocated by ADSM. Space is allocated for backed up, archived, or space-managed files that are eligible for server migration, cached files that are copies of server-migrated files, and files that reside on any volumes that are varied offline.

Note: The value for %Util can be higher than the value for %Migr if you query for storage pool information while a backup or archive transaction is in progress. The value for %Util is determined by the amount of space actually allocated (while the transaction is in progress), while the value for %Migr only represents the space occupied by *committed* files. At the end of the transaction, %Util and %Migr become synchronized.

For sequential access storage pools, this value is the percentage of the total bytes of storage available that are currently being used to store active (non-expired) data. Because the server can only estimate the available capacity of a sequential access storage pool, this percentage also reflects an estimate of the actual utilization of the storage pool.

Example: Monitoring the Capacity of a Backup Storage Pool

Figure 35 on page 117 shows that the estimated capacity for a disk storage pool named BACKUPPOOL is 80MB, which is the amount of available space on disk storage. More than half (51.6%) of the available space is occupied by either backup files or cached copies of backup files.

The estimated capacity for the tape storage pool named BACKTAPE is 180MB, which is the total estimated space available on all tape volumes in the storage pool. This report shows that 85% of the estimated space is currently being used to store workstation files.

Note: This report also shows that volumes have not yet been defined to the ENGBACK1 storage pool, because the storage pool shows an estimated capacity of 0.0MB.

Monitoring Migration Processes

Four fields on the standard storage pool report provide you with information about the migration process. They include:

%Migr

Specifies the percentage of data in each storage pool that can be migrated. This value is used to determine when to start or stop migration.

For disk storage pools, this value represents the amount of disk space occupied by backed up, archived, or space-managed files that can be migrated to another storage pool, including files on volumes that are varied offline. Cached data are excluded in the %Migr value.

For sequential access storage pools, this value is the percentage of the total volumes in the storage pool that actually contain data at the moment. For example, assume a storage pool has four explicitly defined volumes, and a maximum scratch value of six volumes. If only two volumes actually contain data at the moment, then %Migr will be 20%.

This field is blank for copy storage pools.

High Mig%

Specifies when ADSM can begin migrating data from this storage pool. Migration can begin when the percentage of data that can be migrated reaches this threshold. (This field is blank for copy storage pools.)

Low Mig%

Specifies when ADSM can stop migrating data from this storage pool. Migration can end when the percentage of data that can be migrated falls below this threshold. (This field is blank for copy storage pools.)

Next Storage Pool

Specifies the primary storage pool destination to which data is migrated. (This field is blank for copy storage pools.)

Example: Monitoring the Migration of Data Between Storage Pools

ADSM sets a default of 90% for the high migration threshold and 70% for the low migration threshold for each primary storage pool.

Figure 35 on page 117 shows that the predefined migration thresholds for BACKUPPOOL storage pool have been updated to 50% for the *high migration threshold* and 30% for the *low migration threshold*.

When the amount of migratable data stored in the storage pool reaches 50%, the server can begin to migrate files to BACKTAPE.

To monitor the migration of files from BACKUPPOOL to BACKTAPE, enter:

```
query stgpool back*
```

See Figure 36 on page 120 for an example of the results of this command.

If caching is on for a disk storage pool and files are migrated, the %Util value does not change because the cached files still occupy space in the disk pool. However, the

%Migr value decreases because the space occupied by cached files is no longer migratable.

Storage Pool Name	Device Class Name	Estimated Capacity (MB)	%Util	%Migr	High Mig%	Low Mig%	Next Storage Pool
BACKTAPE	TAPE	180.0	95.2	100.0	90	70	
BACKUPPOOL	DISK	80.0	51.6	28.8	50	30	BACKTAPE

Figure 36. Information on Backup Storage Pools

You can query the server to monitor the migration process by entering:

```
query process
```

A message similar to Figure 37 is displayed:

Process Number	Process Description	Status
2	Migration	Disk Storage Pool BACKUPPOOL, Moved Files: 1086, Moved Bytes: 2555579, Unreadable Files: 0, Unreadable Bytes: 0

Figure 37. Information on the Migration Process

When migration is finished, the server displays the following message:

```
ANR1101I Migration ended for storage pool BACKUPPOOL.
```

Handling Problems during the Migration Process

A problem can occur during the migration process that causes the migration process to be suspended. For example, there may not be sufficient space in the storage pool to which data is being migrated. When migration is suspended, the process might be retried.

At this point, a system administrator can:

- Cancel the migration process. See “Canceling the Migration Process” on page 121 for additional information.

- End the migration process by changing the attributes of the storage pool from which data is being migrated. See “Ending the Migration Process by Changing Storage Pool Characteristics” on page 121 for additional information.
- Provide additional space. See “Providing Additional Space for the Migration Process” on page 122 for additional information.

The server attempts to restart the migration process every 60 seconds for several minutes and then will terminate the migration process.

Canceling the Migration Process

To stop server migration when a problem occurs or when you need the resources the process is using, you can cancel the migration.

First determine the identification number of the migration process by entering:

```
query process
```

A message similar to Figure 38 is displayed:

Process Number	Process Description	Status
1	Migration	ANR1113W Migration suspended for storage pool BACKUPPOOL - insufficient space in subordinate storage pool.

Figure 38. Getting the Identification Number of the Migration Process

Then you can cancel the migration process by entering:

```
cancel process 1
```

Ending the Migration Process by Changing Storage Pool Characteristics

Some errors cause the server to continue attempting to restart the migration process after 60 seconds. (If the problem still exists after several minutes, the migration process will end.) To stop the repeated attempts at restart, you can change some characteristics of the storage pool from which data is being migrated. Depending on your environment, you can:

- Set higher migration thresholds for the storage pool from which data is being migrated. The higher threshold means the storage pool must have more migratable data before migration starts. This change delays migration.

In the example in “Example: Monitoring the Migration of Data Between Storage Pools” on page 119, you could update the disk storage pool BACKUPPOOL.

- Add volumes to the pool from which data is being migrated. Adding volumes decreases the percentage of data that is migratable (%Migr).

In the example in “Example: Monitoring the Migration of Data Between Storage Pools” on page 119, you could add volumes to the disk storage pool BACKUPPOOL to increase its storage capacity.

Note: Do this only if you received an out-of-space message for the storage pool to which data is being migrated.

Providing Additional Space for the Migration Process

A migration process can be suspended because of insufficient space in the storage pool to which data is being migrated. To allow the migration process to complete, you can provide additional storage volumes for that storage pool.

In the example in “Example: Monitoring the Migration of Data Between Storage Pools” on page 119, you could add volumes to the BACKTAPE storage pool or increase the maximum number of scratch tapes allowed for it. Either way, you increase the storage capacity of BACKTAPE.

Monitoring the Use of Cache Space on Disk Storage

The %Util value includes cached data on a volume (when cache is enabled) and the %Migr value excludes cached data. Therefore, when cache is enabled and migration occurs, the %Migr value decreases while the %Util value remains the same. The %Util value remains the same because the migrated data remains on the volume as cached data. In this case, the %Util value only decreases when the cached data expires.

If you update a storage pool from CACHE=YES to CACHE=NO, the cached files will not disappear immediately. The %Util value will be unchanged. The cache space will be reclaimed over time as the server needs the space, and no additional cached files will be created.

To determine whether cache is being used on disk storage and to monitor how much space is being used by cached copies, query the server for a detailed storage pool report. For example, to request a detailed report for BACKUPPOOL, enter:

```
query stgpool backuppool format=detailed
```

Figure 39 on page 123 displays a detailed report for the storage pool.


```

Storage Pool Name: BACKUPPOOL
Storage Pool Type: PRIMARY
Device Class Name: DISK
Estimated Capacity (MB): 80.0
    %Util: 42.0
    %Migr: 29.6
    High Mig%: 50
    Low Mig%: 30
Migration Processes:
    Next Storage Pool: BACKTAPE
Maximum Size Threshold: No Limit
    Access: Read/Write
Description:
    Cache Migrated Files?: Yes
    Collocate?:
Reclamation Threshold:
Maximum Scratch Volumes Allowed:
    Delay Period for Volume Reuse: 0 Day(s)
    Migration in Progress?: Yes
    Amount Migrated (MB): 0.10
Elapsed Migration Time (seconds): 5
    Reclamation in Progress?:
Volume Being Migrated/Reclaimed:
    Last Update by (administrator): SERVER_CONSOLE
    Last Update Date/Time: 04/07/1995 16:47:49

```

Figure 39. Detailed Storage Pool Report

When *Cache Migrated Files?* is set to *yes*, the value for %Util should not change because of migration, because cached copies of files migrated to the next storage pool remain in disk storage.

This example shows that utilization remains at 42%, even after files have been migrated to the BACKTAPE storage pool, and the current amount of data eligible for migration is 29.6%.

When *Cache Migrated Files?* is set to *no*, the value for %Util more closely matches the value for %Migr because cached copies are not retained in disk storage.

Requesting Information on Storage Occupancy

Task	Required Privilege Class
Query the server for information about server storage	Any administrator

Any administrator can request information about server storage occupancy. Use the QUERY OCCUPANCY command for reports with information broken out by node or file space. Use this report to determine the amount of space used by:

- Client node and file space
- Storage pool or device class
- Type of data (backup, archive, or space-managed)

You can also use this report to evaluate the average size of workstation files stored in server storage.

Amount of Space Used by Client Node

Any administrator can request information about the space used by each client node and file space:

- How much data has been backed up, archived, or migrated to server storage
- How many of the files that are in server storage have been backed up to a copy storage pool
- The amount of storage space being used

To determine the amount of server storage space used by the /home file space belonging to the client node SSTEINER, for example, enter:

```
query occupancy ssteiner /home
```

Remember that file space names are case-sensitive and must be entered exactly as they are known to the server. Use the QUERY FILESPACE command to determine the correct capitalization. For more information, see “Requesting Information about File Spaces” on page 269.

Figure 40 shows the results of the query. The report shows the number of files backed up, archived, or migrated from the /home file space belonging to SSTEINER. The report also shows how much space is occupied in each storage pool.

If you back up the ENGBACK1 storage pool to a copy storage pool, the copy storage pool would also be listed in the report. To determine how many of the client node’s files in the primary storage pool have been backed up to a copy storage pool, compare the number of files in each pool type for the client node.

Node Name	Filespace Name	Storage Pool Name	Number of Files	Space Occupied (MB)
SSTEINER	/home	ENGBACK1	513	3.52

Figure 40. A Report of the Occupancy of Storage Pools by Client Node

Amount of Space Used by Storage Pool or Device Class

You can monitor the amount of space being used by an individual storage pool, a group of storage pools, or storage pools categorized by a particular device class. Creating occupancy reports on a regular basis can help you with capacity planning.

To query the server for the amount of data stored in backup tape storage pools belonging to the CARTRIDGE device class, for example, enter:

```
query occupancy devclass=cartridge
```

Figure 41 displays a report on the occupancy of tape storage pools assigned to the CARTRIDGE device class.

Node Name	Filespace Name	Storage Pool Name	Number of Files	Space Occupied (MB)
HTANG	OS2C	ARCTAPE	5	.92
HTANG	OS2C	BACKTAPE	21	1.02
PEASE	/home/peas-	ARCTAPE	492	18.40
	e/dir			
PEASE	/home/peas-	BACKTAPE	33	7.60
	e/dir			
PEASE	/home/peas-	BACKTAPE	2	.80
	e/dir1			
TOMC	/home/tomc	ARCTAPE	573	20.85
	/driver5			
TOMC	/home	BACKTAPE	13	2.02

Figure 41. A Report on the Occupancy of Storage Pools by Device Class

Amount of Space Used by Backed Up, Archived, or Space-Managed Files

You can query the server for the amount of space used by backed up, archived, and space-managed files. By determining the average size of workstation files stored in server storage, you can estimate how much storage capacity you might need when registering new client nodes to the server. See “Estimating Space Needs for Storage Pools” on page 107 and “Estimating Space for Archived Files in a Random Access Storage Pool” on page 109 for information about planning storage space.

To request a report about backup versions stored in the disk storage pool named BACKUPPOOL, for example, enter:

```
query occupancy stgpool=backuppool type=backup
```

Figure 42 on page 126 displays a report on the amount of server storage used for backed up files.

Node Name	Filespace Name	Storage Pool Name	Number of Files	Space Occupied (MB)
HTANG	OS2C	BACKUPPOOL	513	23.52
HTANG	OS2D	BACKUPPOOL	573	20.85
PEASE	/marketing	BACKUPPOOL	132	12.90
PEASE	/business	BACKUPPOOL	365	13.68
TOMC	/	BACKUPPOOL	177	21.27

Figure 42. A Report of the Occupancy of Backed Up Files in Storage Pools

To determine the average size of backup versions stored in BACKUPPOOL, complete the following steps using the data provided in Figure 42:

- 1** Add the number of megabytes of space occupied by backup versions.
In this example, backup versions occupy 92.22MB of space in BACKUPPOOL.
- 2** Add the number of files stored in the storage pool.
In this example, 1760 backup versions reside in BACKUPPOOL.
- 3** Divide the space occupied by the number of files to determine the average size of each file backed up to the BACKUPPOOL.
In this example, the average size of each workstation file backed up to BACKUPPOOL is about 0.05MB, or approximately 50KB.

You can use this average to estimate the capacity required for additional storage pools that are defined to ADSM.

Deleting a Storage Pool

Task	Required Privilege Class
Delete storage pools	System

Before a storage pool can be deleted, ensure that:

- All volumes within the storage pool have been deleted

Ensure that you have saved any readable data that you want to preserve by issuing the MOVE DATA command. Moving all of the data that you want to preserve may require you to issue the MOVE DATA command several times.

Before you begin deleting all volumes that belong to the storage pool, change the access mode of the storage pool to unavailable so that no files can be written to or read from volumes in the storage pool.

See “Deleting a Storage Pool Volume with Data” on page 148 for information about deleting storage volumes.

- The storage pool is not identified as the next storage pool within the storage hierarchy

To determine whether this storage pool is referenced as the next storage pool within the storage hierarchy, query for storage pool information as described in “Monitoring the Use of Storage Pool Space” on page 117.

Update any storage pool definitions to remove this storage pool as a subordinate storage pool in the storage hierarchy by performing one of the following:

- Naming another storage pool as the next storage pool in the storage hierarchy
- Entering double quotes (“”) on the *next* parameter to remove this storage pool from the storage hierarchy definition.

See “Defining or Updating Storage Pools” on page 110 for information about updating storage pool definitions.

- The storage pool to be deleted is not specified as the destination for any copy group in any management class within the active policy set of any domain. Also, a storage pool to be deleted cannot be the destination for space-managed files (specified in any management class within the active policy set of any domain). If this pool is a destination and the pool is deleted, operations fail because there is no storage space to store the data.

Restoring Storage Pools

An administrator can recreate files in a primary storage pool using duplicate copies in copy storage pools by issuing the RESTORE STGPOOL command. The files must have been copied to the copy storage pools by using the BACKUP STGPOOL command.

Task	Required Privilege Class
Restoring storage pools	System, unrestricted storage, or restricted storage

The RESTORE STGPOOL command restores specified primary storage pools that have files with the following problems:

- The primary copy of the file has been identified as having data-integrity errors during a previous operation. Files with data-integrity errors are marked as damaged.
- The primary copy of the file resides on a volume that has an access mode of DESTROYED. For how the access mode of a volume changes to the DESTROYED access mode, see “How Restore Processing Works” on page 106.

When you restore a storage pool, be prepared to provide the following information:

Primary storage pool

Specifies the name of the primary storage pool that is being restored.

Copy storage pool

Specifies the name of the copy storage pool from which the files are to be restored. This information is optional. If you do not specify a particular copy storage pool, ADSM restores the files from any copy storage pool where it can find them.

New storage pool

Specifies the name of the new primary storage pool to which to restore the files. This information is optional. If you do not specify a new storage pool, ADSM restores the files to the original primary storage pool.

Maximum number of processes

Specifies the number of parallel processes that are used for restoring files.

Preview

Specifies whether you want to preview the restore operation before it is actually performed.

See “Correcting Damaged Files” on page 319 and “Backup and Recovery Scenarios” on page 322 for examples of using the RESTORE STGPOOL command.

What Happens When a Storage Pool Is Restored

When you restore a storage pool, ADSM determines which files are in the storage pool being restored, according to the ADSM database. Using file copies from a copy storage pool, ADSM restores the files that were in the storage pool to the same or a different storage pool.

Note: Cached copies of files are never restored. Any cached files that have been identified as having data-integrity errors or that reside on a *destroyed* volume will be removed from the database during restore processing.

The RESTORE STGPOOL command with the PREVIEW=YES parameter can be used to identify volumes that contain damaged primary files. During restore processing, a message is issued for every volume in the restored storage pool that contains damaged, non-cached files. To identify the specific files that are damaged on these volumes, use the QUERY CONTENT command.

After the files are restored, the old references to these files in the primary storage pool are deleted from the database. This means that ADSM now locates these files on the volumes to which they were restored, rather than on the volumes on which they were previously stored. If a destroyed volume becomes empty because all files have been restored to other locations, the destroyed volume is automatically deleted from the database.

The RESTORE STGPOOL command generates a background process that can be canceled with the CANCEL PROCESS command. If a RESTORE STGPOOL background process is canceled, some files may have already been restored prior to the cancellation. To display information about background processes, use the QUERY PROCESS command.

When a Storage Pool Restoration is Incomplete

The restoration of a storage pool volume may be incomplete. Use the `QUERY CONTENT` command to get more information on the remaining files on volumes for which restoration was incomplete. The restoration may be incomplete for one or more of the following reasons:

- Files were either never backed up or the backup copies are marked as damaged.
- A copy storage pool was specified on the `RESTORE` command, but files were backed up to a different copy storage pool. If you suspect this is a problem, use the `RESTORE` command again without specifying a copy storage pool from which to restore files. The `PREVIEW` option can be used on the second `RESTORE` command, if you do not actually want to restore files.
- Volumes in the copy storage pool needed to perform the restore operation are offsite or unavailable. Check the activity log for messages that occurred during restore processing.
- Backup file copies in copy storage pools were moved or deleted by other AD SM processes during restore processing. To prevent this problem, do not issue the following commands for copy storage pool volumes while restore processing is in progress:
 - `MOVE DATA`
 - `DELETE VOLUME (DISCARDATA=YES)`
 - `AUDIT VOLUME (FIX=YES)`

Also, you can prevent reclamation processing for your copy storage pools by setting the `RECLAIM` parameter to 100 with the `UPDATE STGPOOL` command.

Chapter 8. Managing Storage Pool Volumes

The sections listed in the following table begin at the indicated pages.

Section	Page
Concepts:	
Storage pool volumes	131
Access modes for storage pool volumes	132
Tasks:	
Adding random access storage pool volumes	133
Defining storage pool volumes	133
Updating storage pool volumes	133
Monitoring the use of storage pool volumes	135
Auditing a storage pool volume	139
Moving files from one volume to another volume	143
Deleting storage pool volumes	147
Restoring storage pool volumes	149

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Storage Pool Volumes

Volumes in storage pools contain backed up, archived, or space-managed data from clients. Storage pools are either random access or sequential access, depending on the device type of the device class to which the pool is assigned.

Random access storage pools are always associated with the DISK device class and all volumes in this type of storage pool have the same form.

Each volume defined in a sequential access storage pool must be the same type as the device type of the associated device class. The device types are:

- CARTRIDGE** A volume is a 3480 or 3490 cartridge system tape.
- REEL** A volume is a half-inch tape reel.
- FILE** A volume is a file in the file system of the server machine

Access Modes for Storage Pool Volumes

Access to any volume in a storage pool is determined by the access mode assigned to that volume. You can change the access mode of a volume. The ADSM server can also change the access mode based on what happens when it tries to access a volume. For example, if the server cannot write to a read/write access volume, the server automatically changes the access mode to read-only.

The access modes are:

Read/write	<p>Allows files to be read from or written to a volume in the storage pool.</p> <p>If the server cannot write to a read/write access volume, the server automatically changes the access mode to read-only.</p>
Read-only	<p>Allows files to be read from but not written to a disk or tape volume.</p>
Unavailable	<p>Specifies that the volume is not available for any type of access by the ADSM server.</p>
Destroyed	<p>Specifies that a primary storage pool volume has been permanently damaged. Neither users nor system processes (like migration) can access files stored on the volume.</p> <p>This access mode is used to indicate an entire volume that should be restored using the <code>RESTORE STGPOOL</code> or <code>RESTORE VOLUME</code> command. After all files on a destroyed volume are restored to other volumes, the destroyed volume is automatically deleted from the database.</p> <p>Only volumes in primary storage pools can be updated to destroyed.</p> <p>If you update a random access storage pool volume to destroyed, you cannot vary the volume online. If you update a sequential access storage pool volume to destroyed, ADSM does not attempt to mount the volume.</p> <p>If a volume contains no files and the <code>UPDATE VOLUME</code> command is used to change the access mode to destroyed, the volume is deleted from the database.</p>
Offsite	<p>Specifies that a copy storage pool volume is at an offsite location and therefore cannot be mounted. Use this mode to help you track volumes that are offsite. ADSM treats offsite volumes differently, as follows:</p> <ul style="list-style-type: none">• Mount requests are not generated for offsite volumes• Data can be reclaimed or moved from offsite volumes by retrieving files from other storage pools• Empty, offsite scratch volumes are not deleted from the copy storage pool <p>Only volumes in a copy storage pool can be updated to offsite.</p>

Adding Random Access Storage Pool Volumes

To prepare minidisks to be used as ADSM storage pool volumes, use the DSMMDISK EXEC, which is provided with ADSM for VM:

```
dsmmdisk
```

You will be prompted for:

- Minidisk virtual address for each storage pool
- Whether to format the minidisk using CMS FORMAT

Defining Storage Pool Volumes

Task	Required Privilege Class
Define volumes in any storage pool	System or unrestricted storage
Define volumes in specific storage pools	System, unrestricted storage, or restricted storage for those pools

When you define a storage pool volume, you inform the server that the volume is available for storing backup, archive, or space-managed data.

For a random access storage pool, volumes must be predefined. For a sequential access storage pool, the ADSM server can use dynamically acquired scratch volumes, predefined volumes, or a combination.

To define a volume named VOL1 in the ENGBACK3 storage pool, enter:

```
define volume engback3 vol1
```

Using Scratch Volumes: You do not have to define volumes in sequential storage pools if you use the MAXSCRATCH parameter when you define or update the storage pool. Setting MAXSCRATCH to a nonzero value lets the storage pool dynamically acquire volumes as needed. The volumes are automatically defined as they are acquired. The volumes are also automatically deleted from the storage pool when the server no longer needs them.

Before a sequential access scratch volume can be used, it must have a standard label.

Updating Storage Pool Volumes

Task	Required Privilege Class
Update volumes	System or operator

You can update the attributes of a storage pool volume assigned to a primary or copy storage pool. Update a volume to:

- Reset any error state for a volume, by updating the volume to an access mode of read/write.
- Change the access mode of a volume, for example if a tape cartridge is moved offsite (offsite access mode) or damaged (destroyed access mode).
- Change the location for a volume in a sequential access storage pool.

When using the UPDATE VOLUME command, be prepared to supply some or all of the following information:

Volume name

Specifies the name of the storage pool volume to be updated. You can specify a group of volumes to update by using wildcard characters in the volume name, or by specifying the storage pool, device class, current access mode, or status of the volumes you want to update. See the parameters that follow.

New access mode

Specifies the new access mode for the volume (how users and system processes (like migration) can access files in the storage pool volume).

A random access volume must be varied offline before you can change its access mode to *unavailable* or *destroyed*. To vary a volume offline, use the VARY command.

If a scratch volume that is empty and has an access mode of offsite is updated so that the access mode is read/write, read-only, or unavailable, the volume will be deleted from the database.

Location

Specifies the location of the volume. This parameter can be specified only for volumes in sequential-access storage pools.

Storage pool

Restricts the update to volumes in the specified storage pool.

Device class

Restricts the update to volumes in the specified device class.

Current access mode

Restricts the update to volumes that currently have the specified access mode.

Status

Restricts the update to volumes with the specified status (online, offline, empty, pending, filling, or full).

Preview

Specifies whether you want to preview the update operation without actually performing the update.

An example of when to use the UPDATE VOLUME command might be if you accidentally damage VOL1, you can change the access mode to unavailable so that no data can be written to or read from the volume. Enter the following command:

```
update volume vol1 access=unavailable
```

Monitoring the Use of Storage Pool Volumes

Task	Required Privilege Class
Display information about volumes	Any administrator

You can query the server for general information about storage pool volumes, or you can view a detailed report to evaluate:

- Current access mode and status of the volume
- Amount of available space on the volume
- Amount of reclaimable space on a sequential access volume
- Location
- Contents of a storage pool volume (user files on the volume)

Requesting General Information about Storage Pool Volumes

To query the server for general information about all volumes defined to the server, enter:

```
query volume
```

Volume Name	Storage Pool Name	Device Class	Estimated Capacity (MB)	%Util	Volume Status
201	BACKUPPOOL	DISK	400.1	18.3	On-Line
DA0001	ARCTAPE	CARTRIDGE	0.0	0.0	Empty
DA0002	ARCTAPE	CARTRIDGE	0.0	0.0	Empty
DB0001	BACKTAPE	CARTRIDGE	0.0	0.0	Empty
DB0001	BACKTAPE	CARTRIDGE	180.0	11.7	Filling
DB0002	BACKTAPE	CARTRIDGE	0.0	0.0	Empty

Figure 43. Standard Information about Storage Pool Volumes

Requesting Detailed Information about Storage Pool Volumes

To query the server for a detailed report on the volume named DB0001 in the storage pool named BACKTAPE, enter:

```
query volume db0001 stgpool=backtape format=detailed
```

Figure 44 on page 136 shows the output of this detailed query.

```
Volume Name: DB0001
Storage Pool Name: BACKTAPE
Device Class: CARTRIDGE
Estimated Capacity (MB): 180.0
    %Util: 11.7
Volume Status: Filling
Access: Read/Write
Pct. Reclaimable Space: 1
Scratch Volume?: No
In Error State?: No
Number of Writable Sides: 1
Number of Times Mounted: 5
Write Pass Number: 2
Approx. Date Last Written: 03/29/1993 12:04:30
Approx. Date Last Read: 03/30/1993 09:30:02
Number of Write Errors: 0
Number of Read Errors: 0
Last Update by (administrator): PENNER
Last Update Date/Time: 03/23/1993 13:16:04
```

Figure 44. Detailed Information about a Storage Volume

Use this report to:

- Ensure that the volume is available for use.

Check the *volume status* to see if a disk volume has been varied offline, or if a sequential access volume is currently being filled with data.

Check the *access mode* to determine whether files can be read from or written to this volume.

- Monitor the use of storage space.

The *estimated capacity* is determined by the device class associated with the storage pool to which this volume belongs. Based on the estimated capacity, the system tracks the percentage of space occupied by client files. In this example, 11.7% of the estimated capacity is currently in use.

- Monitor the life of a sequential access volume.

In this example, DB0001 is not a scratch volume, which means that it will be reused by the BACKTAPE storage pool after space has been reclaimed or deleted from the volume.

The *write pass number* indicates the number of times the volume has been written to, starting from the beginning of the volume. A value of one indicates that a volume is being used for the first time. In this example, DB0001 has a write pass number of two, which indicates space on this volume may have been reclaimed or deleted once before. Be sure to compare this value to the specifications provided with the media that you are using. In particular, the manufacturer recommendations for the maximum number of write passes for some types of tape media may require that you retire your tape volumes after reaching the limit in order to ensure the integrity of your data. To retire volumes, move the data off the

volume by using the MOVE DATA command. See “Moving Files from One Volume to Another Volume” on page 143.

Use the *number of times mounted* and the *approximate date last written to or read from* to help you estimate the life of the volume. For example, if more than six months have passed since the last time this volume has been written to or read from, you should audit the volume to ensure that files can still be accessed. See “Auditing a Storage Pool Volume” on page 139 for information about auditing a volume.

- Monitor the error status of the volume.
The server reports when the volume is in an error state and automatically updates the access mode of the volume to read-only. The *number of write errors* and *number of read errors* indicate the type and severity of the problem. Audit a volume when it is placed in error state. See “Auditing a Storage Pool Volume” on page 139 for information about auditing a volume.
- Determine the location of a volume in a sequential access storage pool.
When you define or update a sequential access volume, you can give location information for the volume. The detailed query displays this location name. The location information can be useful to help you track volumes, for example, offsite volumes in copy storage pools.
- Determine when the state of a volume in a sequential access storage pool became *pending*
A sequential access volume is placed in the pending state after the last file is deleted or moved from the volume. All the files that pending volumes had contained were expired or deleted, or were moved from the volume. Volumes remain in the pending state for as long as specified with the REUSEDelay parameter for the storage pool to which the volume belongs.

Requesting Information about Storage Pool Volume Contents

Any administrator can request information about the contents of a storage pool volume. Viewing the contents of a storage volume is useful when a volume is damaged or before you:

- Request the server to correct any inconsistencies
- Move files from one volume to other volumes
- Delete a volume from a storage pool

Because ADSM tracks the contents of a storage volume through its database, the requested volume need not be accessed in order to determine its contents.

The report generated by a QUERY CONTENT command shows the contents of a volume. This report can be extremely large and may take a long time to produce. To reduce the size of this report, narrow your search by selecting one or all of the following search criteria:

Node name

Name of the node

File space name

Remember that file space names are case-sensitive and must be entered exactly as they are known to the server. Use the QUERY FILESPACE command to find out the correct capitalization.

Number of files to be displayed

Enter a positive integer, such as 10, to list the first ten files stored on the volume. Enter a negative integer, such as -15, to list the last fifteen files stored on the volume.

Filetype

Specifies which types of files, that is, backup versions, archive copies, or space-managed files, or a combination of these.

Format of how the information is displayed

Standard or detailed information for the specified volume.

Damaged

Specifies whether to restrict the query output either to files that are known to be damaged, or to files that are not known to be damaged.

Copied

Specifies whether to restrict the query output to either files that are backed up to a copy storage pool, or to files that are not backed up to a copy storage pool.

Viewing a Standard Report on the Contents of a Volume

To view the first seven backup files on volume DB0001 from file space /usr on client node TOMC, for example, enter:

```
query content db0001 node=tomc filespace=/usr count=7 type=backup
```

Figure 45 displays a standard report that shows the first seven files from file space /usr on TOMC stored in DB0001.

Node Name	Type	Filespace Name	Client's Name for File
TOMC	Bkup	/usr	/bin/ acctcom
TOMC	Bkup	/usr	/bin/ acledit
TOMC	Bkup	/usr	/bin/ ac1put
TOMC	Bkup	/usr	/bin/ admin
TOMC	Bkup	/usr	/bin/ ar
TOMC	Bkup	/usr	/bin/ arcv
TOMC	Bkup	/usr	/bin/ banner

Figure 45. A Standard Report on the Contents of a Volume

Viewing a Detailed Report on the Contents of a Volume

To query the server to display detailed information about the last three files stored on volume VOL1, enter:

```
query content vol1 count=-3 format=detailed
```

Figure 46 displays a detailed report that shows the last three files, in reverse order, stored on VOL1. For example, the *test.scr* file is the last file stored on the volume. The segment number, 1/2, identifies that this is the first volume on which *test.scr* resides. The file spans to a second tape volume.

For disk volumes, the *Cached copy?* field identifies whether the file is a cached copy of a file that has been migrated to the next storage pool in the hierarchy.

```
Node Name: PEASE
Type: Bkup
Filespace Name: /home
Client's Name for File: /pease/dir1/code/ut1/ test.scr
Stored Size: 435
Segment Number: 1/2
Cached Copy?: No

Node Name: PEASE
Type: Bkup
Filespace Name: /home
Client's Name for File: /pease/dir1/code/ut1/ header.scr
Stored Size: 514
Segment Number: 1/1
Cached Copy?: No

Node Name: PEASE
Type: Bkup
Filespace Name: /home
Client's Name for File: /pease/dir1/code/ut1/ appl.scr
Stored Size: 1,013
Segment Number: 1/1
Cached Copy?: No
```

Figure 46. Viewing a Detailed Report of the Contents of a Volume

Auditing a Storage Pool Volume

Use this section to help you audit storage pool volumes for data integrity.

Task	Required Privilege Class
Audit volumes in storage pools over which they have authority	Restricted storage privilege
Audit a volume in any storage pool	System privilege, unrestricted storage privilege

The server database contains information about files on storage pool volumes. If there are inconsistencies between the information in the database and the files actually stored in a storage pool volume, users cannot access their files.

To ensure that all files are accessible on volumes in a storage pool, audit any volumes you suspect may have problems by using the `AUDIT VOLUME` command. You should audit a volume when:

- The volume is damaged
- The volume has not been accessed for a long period of time, for example, after six months
- A read or write error occurs while accessing the volume
- The database has been restored to an earlier point in time, and the volume is either a disk volume or a volume that was identified as being reused or deleted since the database backup took place

What Happens When You Audit Storage Pool Volumes

When you audit a volume, a background process is started. During the auditing process, the server:

- Records results of the audit in the activity log
- Sends informational messages about processing to the server console
- Prevents new files from being written to the volume

You can specify whether you want the server to correct the database if inconsistencies are detected. The system default is to report inconsistencies that are found, but to not correct the errors.

If files with integrity errors are detected, the handling of these files depends on the following:

- The type of storage pool to which the volume is assigned
- The `FIX` option of the `AUDIT VOLUME` command
- The location of file copies

To display the results of a volume audit after it has completed, use the `QUERY ACTLOG` command. See “Requesting Information from the Activity Log” on page 227.

Volumes in a Primary Storage Pool

For a volume in a primary storage pool, the values for the `FIX` parameter on an `AUDIT VOLUME` command have the following effects:

FIX=NO

ADSM reports, but does not delete, any database records that refer to files found with logical inconsistencies.

If the `AUDIT VOLUME` command detects a data-integrity error in a file:

- ADSM marks the file as *damaged* in the database. If a backup copy is stored in a copy storage pool, the file can be restored using the RESTORE VOLUME or RESTORE STGPOOL command.
- If the file is a cached copy, references to the file on this volume can be deleted by issuing the AUDIT VOLUME command and specifying FIX=YES.

If the AUDIT VOLUME command does not detect a data-integrity error in a file that had previously been marked as damaged, the state of the file is reset so that the file can be used. For example, if a dirty tape head caused some files to be marked damaged, you can clean the head and then audit the volume to make the files accessible again.

FIX=YES

ADSM fixes any inconsistencies as they are detected.

If the AUDIT VOLUME command detects a data-integrity error in a file:

- If a backup copy is not stored in a copy storage pool, ADSM deletes all database records that refer to the file.
- If a backup copy is stored in a copy storage pool, ADSM marks the file as damaged in the database. The file can then be restored using the RESTORE VOLUME or RESTORE STGPOOL command.
- If the file is a cached copy, ADSM deletes the database records that refer to the cached file. The primary file is stored on another volume.

If the AUDIT VOLUME command does not detect a data-integrity error in a file that had previously been marked as damaged, ADSM resets the state of the file so that it can be used. For example, if a dirty tape head caused some files to be marked damaged, you can clean the head and then audit the volume to make the files accessible again.

Volumes in a Copy Storage Pool

For volumes in a copy storage pool, the values for the FIX parameter on an AUDIT VOLUME command have the following effects:

FIX=NO

The error is reported and the file copy marked as *damaged* in the database.

FIX=YES

References to the file on the audited volume are deleted.

Auditing a Volume in a Disk Storage Pool

To audit a disk volume named 501, for example, and have only summary messages sent to the activity log and server console, enter:

```
audit volume 501 quiet=yes
```

The audit volume process is run in the background, and the server returns an informational message as follows:

```
ANR2323I Audit Volume NOFIX process started for volume
501 (process id 4).
```

To view the status of the audit volume process, enter:

```
query process
```

The following figure displays an example of the report you receive about the audit volume process.

```
Process Number  Process Description  Status
-----
4 Audit Volume (Inspect Only)  Storage Pool BACKUPPOOL, Volume 501
Files Processed: 680, Irretrievable
Files Found: 0, Partial Files Skipped:
0
```

To display the results of a volume audit after it has completed, you can issue the QUERY ACTLOG command.

Auditing Multiple Volumes in a Sequential Access Storage Pool

When you audit a sequential storage volume containing files that span multiple volumes, the server selects all associated volumes and begins the audit process with the first volume on which the first file resides. For example, Figure 47 shows five volumes defined to ENGBACK2. In this example, File A spans VOL1 and VOL2, and File D spans VOL2, VOL3, VOL4, and VOL5.




Figure 47. Tape Volumes with Files A, B, C, D, and E

If you request that the server audit volume VOL3, the server first accesses volume VOL2, because File D begins at VOL2. When volume VOL2 is accessed, the server *only* audits File D. It does not audit the other files on this volume.

Because File D spans multiple volumes, the server accesses volumes VOL2, VOL3, VOL4, and VOL5 to ensure that there are no inconsistencies between the database and the storage pool volumes.

For volumes that require manual mount and dismount operations, the audit process can require significant manual intervention.

Auditing a Single Volume in a Sequential Access Storage Pool

To audit a single volume in a sequential storage pool, you can request that the server skip any files that span from the single volume to other volumes in the storage pool. This option is useful when the volume you want to audit contains part of a file, the rest of which resides on a different, damaged volume.

For example, to audit only volume VOL5 in the example in Figure 47 on page 142 and have the server fix any inconsistencies found between the database and the storage volume, enter:

```
audit volume vol5 fix=yes skippartial=yes
```

Moving Files from One Volume to Another Volume

You can move files from one volume to another volume in the same or a different storage pool. The volumes can be onsite volumes or offsite volumes. During normal operations, you do not need to move data. You might need to move data in some situations, for example, when you need to salvage any readable data from a damaged ADSM volume.

During the data movement process, the server:

- Moves any readable files to available volumes in the specified destination storage pool
- Deletes any cached copies from a disk volume
- Attempts to bypass any files that previously have been marked as damaged

During the data movement process, users cannot access the volume to restore or retrieve files, and no new files can be written to the volume.

Note: Files in a copy storage pool do not move when primary files are moved.

Task	Required Privilege Class
Move files from a volume in any storage pool to an available volume in any storage pool	System or unrestricted storage
Move files from one volume to an available volume in any storage pool to which you are authorized	Restricted storage

Moving Data to Other Volumes in the Same Storage Pool

Moving files from one volume to other volumes in the same storage pool is useful:

- When you want to free up all space on a volume so that it can be deleted from the ADSM server

See “Deleting Storage Pool Volumes” on page 147 for information about deleting backed up, archived, or space-managed data before you delete a volume from a storage pool.

- To salvage readable files from a volume that has been damaged
- When you want to delete cached files from disk volumes

If you want to force the removal of cached files, you can delete them by moving data from one volume to another volume. During the move process, ADSM deletes cached files remaining on disk volumes.

If you move data between volumes within the same storage pool and you run out of space in the storage pool before all data is moved from the target volume, then you cannot move all the data from the target volume. In this case, consider moving data to available space in another storage pool as described in “Moving Data to Another Storage Pool.”

Moving Data to Another Storage Pool

You can move all data from a volume in one storage pool to volumes in another storage pool. You might do this, for example, when you have only one tape drive in a library and you want to manually reclaim tape volumes. When you specify a target storage pool that is different than the source storage pool, ADSM uses the storage hierarchy to move data if more space is required.

Note: Data cannot be moved from a primary storage pool to a copy storage pool. Data in a copy storage pool cannot be moved to any other storage pool.

You can move data from random access storage pools to sequential access storage pools. For example, if you have a damaged disk volume and you have a limited amount of disk storage space, you could move all files from the disk volume to a tape storage pool. Moving files from a disk volume to a sequential storage pool may require many volume mount operations if the target storage pool is collocated. Ensure that you have sufficient personnel and media to move files from disk to sequential storage.

Moving Data from an Offsite Volume in a Copy Storage Pool

You can move data from offsite volumes without bringing the volume onsite.

Processing of the MOVE DATA command for primary storage pool volumes does not affect copy storage pool files.

Processing of the MOVE DATA command for volumes in copy storage pools is similar to that of primary storage pools, with the following exceptions:

- Most volumes in copy storage pools may be set to an access mode of *offsite*, making them ineligible to be mounted. During processing of the MOVE DATA command, valid files on offsite volumes are copied from the original files in the primary storage pools. In this way, valid files on offsite volumes are copied without having to mount these volumes. These new copies of the files are written to another volume in the copy storage pool.
- With the MOVE DATA command, you can move data from any primary storage pool volume to any primary storage pool. However, you can move data from a copy storage pool volume *only* to another volume within the same copy storage pool.

When you move files from a volume marked as offsite, ADSM:

1. Determines which files are still active on the volume from which you are moving data
2. Obtains these files from a primary storage pool or from another copy storage pool
3. Copies the files to one or more volumes in the destination copy storage pool

Procedure for Moving Data

1 Before you move files from a volume, complete the following steps:

- a. If you want to ensure that no new files are written to a volume after you move data from it, change the volume's access mode to read-only. This prevents the server from filling the volume with data again as soon as data is moved. You might want to do this if you want to delete the volume.

See "Updating Storage Pool Volumes" on page 133 for information about updating the access mode of a storage pool volume.

- b. Ensure sufficient space is available on volumes within the specified destination storage pool by:
 - 1) Querying the source storage volume to determine how much space is required on other volumes. See "Monitoring the Use of Storage Pool Volumes" on page 135 for information about requesting information about a storage volume.
 - 2) Querying the specified destination storage pool to ensure there is sufficient capacity to store the files being moved. See "Monitoring the Use of Storage Pool Space" on page 117 for information about querying a storage pool.

- c. If you need more storage space, define volumes or increase the maximum number of scratch volumes in the specified destination storage pool.
See “Defining Storage Pool Volumes” on page 133 for preparing volumes to be used for server storage.
- d. If you are moving files from a volume in a sequential storage pool to another volume in the same storage pool, ensure that the mount limit of the device class associated with the storage pool is greater than one.
See “Requesting Information about a Device Class” on page 77 for requesting information about the mount limit value for the device class.
- e. If you are moving files from a tape volume to a tape storage pool, ensure that the two tape drives required are available.

2 Move the data using the MOVE DATA command.

For example, to move the files stored in volume 501 to any available volume in the BACKTAPE storage pool, enter:

```
move data 501 stgpool=backtape
```

When you move data from a volume, the server starts a background process and sends informational messages, such as:

```
ANR1140I Move Data process started for volume 501 (process ID 5).
```

Requesting Information about the Data Movement Process

To request information on the data movement process, enter:

```
query process
```

Figure 48 shows an example of the report that you receive about the data movement process.

Process Number	Process Description	Status
5	Move Data	Storage Pool BACKUPPOOL, Volume ADSM.STORAGE.POOL001, Target Pool BACKTAPE Moved Files: 0, Moved Bytes: 0, Unreadable Files: 0, Unreadable Bytes: 0

Figure 48. Information on the Data Movement Process

Monitoring the Movement of Data between Volumes

You can query the server for volume information to monitor the movement of data between volumes. For example, to see how much data has moved from the source volume in a move operation (501) to available volumes in the BACKTAPE storage pool, enter:

```
query volume * stgpool=back*
```

Figure 49 shows all defined volumes in storage pools beginning with the name BACK. This example shows that the BACKTAPE storage pool is filling as files are moved from 501 to available volumes in the backup tape storage pool.

Volume Name	Storage Pool Name	Device Class	Estimated Capacity (MB)	%Util	Volume Status
501	BACKUPPOOL	DISK	40.0	36.2	On-Line
DB0001	BACKTAPE	CARTRIDGE	180.0	14.3	Filling
DB0002	BACKTAPE	CARTRIDGE	0.0	0.0	Empty

Figure 49. Volume Information Showing Data Movement

Deleting Storage Pool Volumes

You can delete volumes, and optionally the client files they contain, from either primary or copy storage pools.

If files that are not cached are deleted from a primary storage pool volume, any copies of these files in copy storage pools will also be deleted.

Files in a copy storage pool are never deleted unless:

- The volume that contains the copy file is deleted by using the DISCARDDATA=YES option.
- A data-integrity error is detected by using AUDIT VOLUME with the FIX=YES option for a copy storage pool volume.
- The primary file is deleted because:
 - Policy-based file expiration
 - File space deletion
 - Deletion of the primary storage pool volume

Note: If you are deleting many volumes, it is recommended that you delete the volumes one at a time. Concurrently deleting many volumes can adversely affect server performance.

Task	Required Privilege Class
Delete volumes from any storage pool	System or unrestricted storage
Delete volumes from storage pools over which they have authority	Restricted storage

Deleting an Empty Storage Pool Volume

You can delete empty storage pool volumes. For example, to delete an empty volume named ADSTM03, enter:

```
delete volume adsm03
```

On an administrative client, you will receive the following confirmation messages, unless the client is running with the NOCONFIRM option:

```
ANR2200W This command will delete volume ADSTM03
from its storage pool after verifying that the volume
contains no data.
Do you wish to proceed? (Y/N)
```

After you respond yes, the server generates a background process to delete the volume.

Deleting a Storage Pool Volume with Data

To prevent you from accidentally deleting backed up, archived, or space-managed files from server storage, the server does not allow you to delete a volume that contains user data unless you specify DISCARDATA=YES on the DELETE VOLUME command.

For example, to discard all data from volume ADSTM03 and delete the volume from its storage pool, enter:

```
delete volume adsm03 discarddata=yes
```

The server generates a background process and deletes data in a series of batch database transactions. After all files have been deleted from the volume, the server deletes the volume from the storage pool. If the volume deletion process is cancelled or if a system failure occurs, the volume might still contain data. Reissue the DELETE VOLUME command and explicitly request the server to discard the remaining files on the volume.

To delete a volume but not the files it contains, move the files to another volume. See "Moving Files from One Volume to Another Volume" on page 143 for information about moving data from one volume to another volume.

Residual data: Even after you move data, residual data may remain on the volume because of I/O errors or because of files that were previously marked as damaged. (ADSM does not move files that are marked as damaged.) To delete any volume that contains residual data that cannot be moved, you must explicitly specify that files should be discarded from the volume.

Restoring Storage Pool Volumes

An administrator can recreate files in primary storage pool volumes using copies in a copy storage pool by issuing the RESTORE VOLUME command.

Task	Required Privilege Class
Restore volumes in any storage pool for which they have authority	System, unrestricted storage, or restricted storage

Use the RESTORE VOLUME command to restore all files that are currently stored on one or more volumes in the same primary storage pool, and that were previously backed up to copy storage pools by using the BACKUP STGPOOL command.

When using the RESTORE VOLUME command, be prepared to supply some or all of the following information:

Volume name

Specifies the name of the volume in the primary storage pool for which to restore files.

Usage tip: To restore more than one volume in the same primary storage pool, issue this command once and specify a list of volumes to be restored. When you specify more than one volume, ADSM attempts to minimize volume mounts for the copy storage pool.

Copy storage pool name

Specifies the name of the copy pool from which the files are to be restored. This information is optional. If you do not specify a particular copy storage pool, ADSM restores the files from any copy storage pool where it can find them.

New storage pool

Specifies the name of the new primary storage pool to which to restore the files. This information is optional. If you do not specify a new storage pool, ADSM restores the files to the original primary storage pool.

Maximum number of processes

Specifies the maximum number of parallel processes that are used for restoring files.

Preview

Specifies whether you want to preview the restore operation without actually restoring data.

See “Recovering a Lost or Damaged Storage Pool Volume” on page 325 for an example of using the RESTORE VOLUME command.

What Happens When a Volume Is Restored

When you restore a volume, ADSM obtains a copy of each file that was on the volume from a copy storage pool, and then stores the files on a different volume.

Cached files: Cached copies of files are never restored. Any cached files that reside on a volume that is being restored are removed from the database during restore processing.

After files are restored, the old references to these files in the primary storage pool are deleted from the database. ADSM will now locate these files on the volumes to which they were restored, rather than on the volume on which they were previously stored.

This command changes the access mode of the volumes being restored to *destroyed*. When the restoration is complete (when all files on the volume are restored to other locations), the destroyed volume is empty and is then automatically deleted from the database.

The RESTORE VOLUME command generates a background process that can be canceled with the CANCEL PROCESS command. If a RESTORE VOLUME background process is canceled, some files may have already been restored prior to the cancellation. To display information on background processes, use the QUERY PROCESS command.

When a Volume Restoration is Incomplete

The restoration of a volume may be incomplete. Use the QUERY CONTENT command to get more information on the remaining files on volumes for which restoration was incomplete. The restoration may be incomplete for one or more of the following reasons:

- Files were either never backed up or the backup copies are marked as damaged.
- A copy storage pool was specified on the RESTORE command, but files were backed up to a different copy storage pool. If you suspect this is a problem, use the RESTORE command again without specifying a copy storage pool from which to restore files. The PREVIEW option can be used on the second RESTORE command, if you do not actually want to restore files.
- Volumes in the copy storage pool needed to perform the restore operation are offsite or unavailable. Check the activity log for messages that occurred during restore processing.

- Backup file copies in copy storage pools were moved or deleted by other ADSM processes during restore processing. To prevent this problem, do not issue the following commands for copy storage pool volumes while restore processing is in progress:
 - MOVE DATA
 - DELETE VOLUME (DISCARDATA=YES)
 - AUDIT VOLUME (FIX=YES)

Also, you can prevent reclamation processing for your copy storage pools by setting the RECLAIM parameter to 100 with the UPDATE STGPOOL command.

Part 3. Policies

Chapter 9. Managing Policies

ADSM policies control how and when user files are backed up and archived to server storage and how user files are migrated to server storage.

The sections listed in the following table begin at the indicated pages.

Section	Page
Concepts:	
Policy operations	156
Policy objects	157
Management classes	159
Expiration processing	163
File eligibility for policy operations	164
How client migration works with backup and archive	167
Tasks:	
Using the standard storage management policies	168
Creating your own storage management policies	169
Defining a policy domain	172
Defining a policy set	173
Defining a management class	174
Defining a backup copy group	175
Defining an archive copy group	179
Assigning a default management class	181
Validating and activating policy sets	181
Starting expiration processing	183
Querying policy objects	184
Deleting policy objects	187

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Operations Controlled by Policy

ADSM policies govern the following operations, which are discussed in this section:

- Backup and restore
- Archive and retrieve
- Client migration and recall

Backup and Restore

To guard against the loss of information, ADSM can copy files, subdirectories, and directories to media controlled by ADSM. Backups can be controlled by administrator-defined policies and schedules, or users can request backups of their own data. ADSM provides two types of backup:

Incremental backup

The backup of files according to policy defined in the backup copy group of the management class for the files. An incremental backup typically backs up all files that are new or that have changed since the last incremental backup.

Selective backup

Backs up only files that the user specifies. The files must also meet some of the policy requirements defined in the backup copy group.

When a user restores a backup version of a file, ADSM sends a copy of the file to the client node. The backup version remains in ADSM storage.

If more than one backup version exists, a user can restore the active backup version of the file or any inactive backup versions.

Archive and Retrieve

To preserve files for later use or for records, a user can request ADSM to copy files, subdirectories, and directories for long-term storage on media controlled by ADSM. When users archive files, they can choose to have ADSM erase the original files from their workstation after the files are archived.

When a user retrieves a file, ADSM sends a copy of the file to the client node. The archived file remains in ADSM storage.

Migration and Recall

If the Hierarchical Storage Management (HSM) feature of ADSM is activated on a client node, users can migrate files from client node storage to server storage and recall files to the client node as needed. HSM frees space on client nodes for new data and makes more efficient use of your storage.

Files that are migrated and recalled with the HSM client are also called *space-managed* files.

For details about using HSM on clients, see *ADSM Using the UNIX HSM Clients*.

Migration

When a file is migrated to the server, it is replaced on the client node with a small stub file of the same name as the original file. The stub file contains data needed to locate the migrated file on server storage.

ADSM provides selective and automatic migration. Selective migration lets users migrate files by name. The two types of automatic migration are:

Threshold If space usage exceeds a high threshold set at the client node, migration begins and continues until usage drops to the low threshold also set at the client node.

Demand If an out-of-space condition occurs for a client node, migration begins and continues until usage drops to the low threshold.

To prepare for efficient automatic migration, ADSM copies a percentage of user files from the client node to the server. The *premigration* process occurs whenever ADSM completes an automatic migration. The next time free space is needed at the client node, the files that have been premigrated to the server can quickly be changed to stub files on the client. The default premigration percentage is the difference between the high and low thresholds.

Files are selected for automatic migration and premigration based on the number of days since the file was last accessed and also on other factors set at the client node.

Recall

ADSM provides selective and transparent recall. Selective recall lets users recall files by name. Transparent recall occurs automatically when a user accesses a migrated file.

Reconciliation

Migration and premigration can create inconsistencies between client node and server storage. For example, if a user deletes a migrated file from the client node, the copy remains at the server. At regular intervals set at the client node, ADSM compares client node and server storage and reconciles the two by deleting from the server any outdated files or files that do not exist at the client node.

Policy Objects

Policy administrators specify how files are backed up, archived, migrated from client node storage, and managed in ADSM storage through ADSM policy objects. These objects implement ADSM policies. Figure 50 on page 158 shows the objects and their relationships.




Figure 50. ADSM Policy Objects

Backup copy group

Controls how ADSM performs backup processing of files associated with the management class. A backup copy group determines the following:

- If a file is backed up (even if it has not changed since the last backup)
- How many days must elapse before a file can be backed up again
- How to handle files that are in use during backup
- Where the server stores backup versions of files and directories
- How many backup versions the server keeps of files and directories
- How long the server keeps backup versions of files and directories

Archive copy group

Controls how ADSM performs archive processing of files associated with the management class. An archive copy group determines the following:

- How to handle files that are in use during archive
- Where the server stores archived copies of files
- How long the server keeps archived copies of files

Management class

Associates backup and archive groups with files and specifies if and how client node files are migrated to storage pools. A management class can contain one backup copy group, one archive copy group, both a backup and archive copy group, or no copy groups. Users can *bind* (that is, associate) their files to a management class through the include-exclude list.

Policy set

Specifies the management classes that are available to groups of users. Policy sets contain one or more management classes: a *default management class* and any number of additional management classes.

Policy domain

Lets an administrator group client nodes by the policies that govern their files and by the administrators who manage their policies. A policy domain contains one or more policy sets, but only one policy set (named ACTIVE) can be active at a time. ADSM uses the active policy set to manage files for client nodes assigned to a policy domain.

You can use policy domains to:

- Provide default storage management policies
- Group client nodes with similar storage management requirements
- Direct files from different groups of clients to different storage hierarchies based on need (different file destinations with different storage characteristics)
- Restrict the number of management classes to which clients have access

Management Classes

Each client node is assigned to a single policy domain, and the client node has access only to the management classes contained in the domain. The management classes specify whether client files are migrated to storage pools (hierarchical storage management). The copy groups in these management classes specify the number of backup versions retained in ADSM storage and the length of time to retain backup versions and archive copies.

For example, if a group of users needs only one backup version of their files, you can create a policy domain that contains only one management class whose backup copy group allows only one backup version. Then you can assign the client nodes for these users to the policy domain. See “Administrator Registration of Client Nodes” on page 265 for information on registering client nodes and assigning policy domains to them.

Management Class Configuration

Before defining a management class, consider whether the management class should contain:

A backup copy group and an archive copy group

For example, most users need to back up and archive documents, spread sheets, and graphics.

A backup copy group only

For example, some users only want to back up application files (such as database, log, or history files that change daily).

An archive copy group only

A management class that contains only an archive copy group is useful for users who create:

- Point-in-time files. For example, an engineer can archive the design of an electronic component and the software that created the design. Later, the engineer can use the design as a base for a new electronic component.
- Files that are rarely used but need to be retained for a long time. A client can erase the original file without affecting how long the archive copy is retained in ADSM storage. Examples include legal records, patient records, and tax forms.

Attention: A management class that contains neither a backup nor an archive copy group prevents a file from ever being backed up or archived. This type of management class is not recommended for most users. Use such a management class carefully to prevent users from mistakenly selecting it. If users bind their files to a management class without copy groups, ADSM issues warning messages.

Default Management Classes

Each policy set must include a default management class, which is used:

- To manage files that are not bound to a specific management class, as defined by the INCLUDE option in the include-exclude list.
- To manage existing backup versions when a management class name is deleted from the server as described in “How Files Are Associated with a Management Class” on page 161.
- To manage existing archive copies when a management class is deleted from the server. ADSM does not rebind archive copies but does use the archive copy group (if one exists) in the default management class.

A typical default management class should do the following:

- Meet the storage management needs for most of your users
- Contain both a backup copy group and an archive copy group
- Set serialization static or shared static to ensure the integrity of backed up and archived files
- Retain backup versions and archive copies for a sufficient amount of time
- Retain directories for at least as long as any files are associated with the directory

Other management classes can contain copy groups tailored either for the needs of special sets of users or for the needs of most users under special circumstances.

The Include-Exclude List

A user can define an include-exclude list to specify which files are eligible for backup services, which files can be migrated from the client (space-managed), and how ADSM manages backed up, archived, and space-managed files.

If a user does not create an include-exclude list:

- All files belonging to the user are eligible for backup services.
- The default management class governs backup, archive, and space-management policies.

With an include-exclude list, users can:

- Exclude files or directories from backup and client migration operations
For example, Figure 51 shows that the SSTEINER node ID excludes all core files from being eligible for backup and client migration.
- Include any previously excluded files
For example, Figure 51 shows that the files in the /home/ssteiner directory are excluded. The include statement that follows, however, means that the /home/ssteiner/options.scr file is eligible for backup and client migration.
- Bind a file to a specific management class
For example, Figure 51 shows that all files and subdirectories belonging to the /home/ssteiner/driver5 directory are managed by the criteria defined in the MCENGBK2 management class.

```
exclude /.../core
exclude /home/ssteiner/*
include /home/ssteiner/options.scr
include /home/ssteiner/driver5/.../* mcengbk2
```

Figure 51. Example of an Include-Exclude List

ADSM processes the include-exclude list from the bottom up, and stops when it finds an include or exclude statement that matches the file it is processing. The order in which the include and exclude options are listed therefore affect which files are included and excluded. For example, suppose you switch the order of two lines in the example, as follows:

```
include /home/ssteiner/options.scr
exclude /home/ssteiner/*
```

The exclude statement comes last, and excludes all files in the /home/steiner directory. When ADSM is processing the include-exclude list for the options.scr file, it finds the exclude statement first. This time, the options.scr file is *excluded*.

For information on how to create an include-exclude list, see the user's publication for the appropriate client.

How Files Are Associated with a Management Class

Binding is the process of associating a file with a management class. The policies defined in the management class then apply to the bound files. Binding occurs when a file is backed up, archived, or migrated by the client.

- For backing up a file, a client can specify a management class in the client's include-exclude list (include-exclude options file for UNIX clients), or can accept the default management class.

For directories, the client can specify a management class by using the DIRMC option in the client options file. If no management class is specified for a directory, ADSM chooses the management class with the longest retention period in the backup copy group (retention period for the only backup version).

- For archiving a file, the client can specify a management class in the client's include-exclude list, can specify a management class with the ARCHMC option on the archive command, or can accept the default management class.
- For migrating a file, a client can specify a management class in the client's include-exclude options file, or can accept the default management class.

The default management class is the management class identified as the default in the active policy set. If a client backs up, archives, and migrates a file to the same server, the management class specified for a file using an include-exclude option applies no matter what the operation (backup, archive, or migrate). If a client backs up and archives a file to one server, and migrates the file to a different server, the client can specify one management class for the file for backup and archive, and a different one for migrating. See the user's publication for the appropriate client for details.

A file remains bound to a management class name even if the attributes of the management class change. The following scenario illustrates this process:

1. A file named REPORT.TXT is bound to the default management class that contains a backup copy group specifying that up to three backup versions can be retained in server storage.
2. During the next week, three backup versions of REPORT.TXT are stored in ADSM storage. The active and two inactive backup versions are bound to the default management class.
3. The administrator assigns a new default management class that contains a backup copy group specifying only up to two backup versions.
4. The administrator then activates the policy set, and the new default management class takes effect.
5. Expiration processing occurs (see "Expiration Processing" on page 163 for details). REPORT.TXT is still bound to the default management class, which now includes new retention criteria. Therefore, the oldest inactive version is expired, and one active and one inactive backup version remain in storage.

Rebinding Files to Management Classes

Rebinding is the process of associating a file with a new management class. Backup versions of files are rebound in the following cases:

- The user changes the management class specified in the include-exclude list and does a backup.
- An administrator activates a policy set in the same policy domain as the client node, and the policy set does not contain a management class with the same name as the management class to which a file is currently bound.
- An administrator assigns a client node to a different policy domain, and the active policy set in that policy domain does not have a management class with the same name.

Backup versions of a directory can be rebound when the user specifies a different management class using the DIRMC option in the client option file, and when the directory gets backed up.

If a file is bound to a management class that no longer exists, ADSM uses the default management class to manage the backup versions. When the user does another backup, ADSM rebinds the file and any backup versions to the default management class. If the default management class does not have a backup copy group, ADSM uses the backup retention grace period specified for the policy domain.

Note: Archive copies are never rebound because each archive operation creates a different archive copy. Archive copies remain bound to the management class name specified when the user archived them. If the management class no longer exists or no longer contains an archive copy group, ADSM uses the default management class. If the default management class does not contain an archive copy group, ADSM uses the archive retention grace period specified for the policy domain.

Expiration Processing

Backup and archive copy groups can specify the criteria that make copies of files eligible for deletion from server storage. However, even when a file becomes eligible for deletion, the file is not deleted until expiration processing occurs. If expiration processing does not occur periodically, storage pool space occupied by expired client files is not reused, and the ADSM server requires increased storage space.

See “Running Expiration Processing to Delete Expired Files” on page 183 for details about how to invoke expiration processing.

File Eligibility for Policy Operations

This section describes how ADSM selects files for the following operations:

- Full and partial incremental backups
- Selective backup
- Archive
- Migration from a client node (hierarchical storage management)

Incremental Backup

Clients can choose to back up their files using full or partial incremental backup. A full incremental backup ensures that clients' backed-up files are always managed according to policies. Clients should use full incremental backup whenever possible.

When a client uses partial incremental backup, only files that have changed since the last incremental backup are backed up. Attributes in the management class that would cause the file to be backed up when doing a full incremental backup are ignored. For example, unchanged files are not backed up even when they are assigned to a management class that specifies absolute mode and the frequency (minimum days between backups) specified has passed. The server also does less processing; for example, the server does not expire files or rebind management classes to files during a partial incremental backup. Because a partial incremental backup should complete more quickly and require less memory, however, clients may need to use it if the backup window is limited.

If clients must use partial incremental backups, they should periodically perform full incremental backups to ensure that complete backups are done and backup files are stored according to policies. For example, clients can do partial incremental backups every night during the week, and a full incremental backup on the weekend.

Full Incremental Backup

When a user requests a full incremental backup, ADSM performs the following steps to determine eligibility:

1. Checks each file against the user's include-exclude list:
 - Files that are excluded are not eligible for backup.
 - If files are not excluded and a management class is specified with the INCLUDE option, ADSM uses that management class.
 - If files are not excluded but a management class is not specified with the INCLUDE option, ADSM uses the default management class.
 - If no include-exclude list exists, all files in the client domain are eligible for backup, and ADSM uses the default management class.
2. Checks the management class of each included file:
 - If there is a backup copy group, ADSM goes to step 3.
 - If there is no backup copy group, the file is not eligible for backup.
3. Checks the *mode*, *frequency*, and *serialization* defined in the backup copy group.

- | | |
|----------------------|---|
| Mode | Specifies whether the file is backed up only if it has changed since the last backup (<i>modified</i>) or whenever a backup is requested (<i>absolute</i>). |
| Frequency | Specifies the minimum number of days that must elapse between backups. |
| Serialization | Specifies how files are handled if they are modified while being backed up and what ADSM does if modification occurs. |
- If the mode is *modified* and the minimum number of days have elapsed since the file was last backed up, ADSM determines if the file has been changed since it was last backed up:
 - If the file has been changed and the serialization requirement is met, the file is backed up.
 - If the file has not been changed, it is not backed up.
 - If the mode is *modified* and the minimum number of days have not elapsed since the file was last backed up, the file is not eligible for backup.
 - If the mode is *absolute*, the minimum number of days have elapsed since the file was last backed up, and the serialization requirement is met, the file is backed up.
 - If the mode is *absolute* and the minimum number of days have not elapsed since the file was last backed up, the file is not eligible for backup.

Partial Incremental Backup

When a user requests a partial incremental backup, ADSM performs the following steps to determine eligibility:

1. Checks each file against the user's include-exclude list:
 - Files that are excluded are not eligible for backup.
 - If files are not excluded and a management class is specified with the INCLUDE option, ADSM uses that management class.
 - If files are not excluded but a management class is not specified with the INCLUDE option, ADSM uses the default management class.
 - If no include-exclude list exists, all files in the client domain are eligible for backup, and ADSM uses the default management class.
2. Checks the management class of each included file:
 - If there is a backup copy group, ADSM goes to step 3.
 - If there is no backup copy group, the file is not eligible for backup.
3. Checks the date and time of the last incremental backup by the client, and the *serialization* requirement defined in the backup copy group. (Serialization specifies how files are handled if they are modified while being backed up and what ADSM does if modification occurs.)

- If the file has not changed since the last incremental backup, the file is not backed up.
- If the file has changed since the last incremental backup and the serialization requirement is met, the file is backed up.

Selective Backup

When a user requests a selective backup, ADSM performs the following steps to determine eligibility:

1. Checks the file against any include or exclude statements contained in the user include-exclude list:
 - Files that are not excluded are eligible for backup. If a management class is specified with the INCLUDE option, ADSM uses that management class.
 - If no include-exclude list exists, the files selected are eligible for backup, and ADSM uses the default management class.
2. Checks the management class of each included file:
 - If the management class contains a backup copy group and the serialization requirement is met, the file is backed up. Serialization specifies how files are handled if they are modified while being backed up and what ADSM does if modification occurs.
 - If the management class does not contain a backup copy group, the file is not eligible for backup.

An important difference between selective backup and full incremental backup is that a file is backed up, without regard for whether the file has changed. This result may not always be what you want. For example, suppose a management class specifies to keep three backup versions of a file. If the client uses incremental backup, the file is backed up only when it changes, and the three versions in storage will be at different levels. If the client uses selective backup, the file is backed up regardless of whether it has changed. If the client uses selective backup on the file three times without changing the file, the three versions of the file in server storage are identical. Earlier, different versions are lost.

Archive

When a user requests the archiving of a file or a group of files, ADSM performs the following steps to determine eligibility:

1. Checks the files against the user's include-exclude list to see if any management classes are specified:
 - ADSM uses the default management class for files that are not bound to a management class.
 - If no include-exclude list exists, ADSM uses the default management class unless the user specifies another management class. See the user's publication for the appropriate client for details.
2. Checks the management class for each file to be archived.

- If the management class contains an archive copy group and the serialization requirement is met, the file is archived. Serialization specifies how files are handled if they are modified while being archived and what ADSM does if modification occurs.
- If the management class does not contain an archive copy group, the file is not archived.

Automatic Migration from a Client Node

A file is eligible for automatic migration from a client node if it meets all of the following criteria:

- It resides on a node on which the root user has added and activated hierarchical storage management. It must also reside in a local file system to which the root user has added space management, and not in the root (/) or /tmp file system.
- It is not excluded from migration in the include-exclude list.
- It meets management class requirements for migration:
 - The file is not a character special file, a block special file, a FIFO special file (that is, a named pipe file) or a directory.
 - The file is assigned to a management class that calls for space management.
 - The management class calls for automatic migration after a specified number of days, and that time has elapsed.
 - A backup version of the file exists if the management class requires it.
 - The file is larger than the stub file that would replace it (plus one byte) or the file system block size, whichever is larger.

How Client Migration Works with Backup and Archive

As an administrator, you can define a management class that specifies automatic migration under certain conditions. For example, if the file has not been accessed for at least 30 days and a backup version exists, the file is migrated. You can also define a management class that allows users to selectively migrate whether or not a backup version exists. Users can also choose to archive files that have been migrated:

- If the file is backed up or archived to the server to which it was migrated, ADSM copies the file from the migration storage pool to the backup or archive storage pool. For a tape-to-tape operation, each storage pool must have a tape drive.
- If the file is backed up or archived to a different server, ADSM accesses the file by using the migrate-on-close recall mode. The file resides on the client node only until ADSM stores the backup version or the archived copy in the backup or archive storage pool.

When a client restores a backup version of a migrated file, ADSM deletes the migrated copy of the file from server storage the next time reconciliation is run.

When a client archives a file that is migrated and does not specify that the file is to be erased after it is archived, the migrated copy of the file remains in server storage. When a client archives a file that is migrated and specifies that the file is to be erased, ADSM deletes the migrated file from server storage the next time reconciliation is run.

The default management class delivered with ADSM specifies that a backup version of a file must exist before the file is eligible for migration.

Using the Standard Storage Management Policies

ADSM provides a set of policy objects, named STANDARD. If you use these standard objects, you can begin using ADSM immediately.

When you register a client node, the default is to assign the node to the STANDARD policy domain. If users register their own workstations during open registration, they are also assigned to the STANDARD policy domain.

ADSM provides a standard policy domain, policy set, management class, backup copy group, and archive copy group. Each policy object is named STANDARD. The attributes of the ADSM-supplied objects are as follows:

Standard Policy Domain

When a backed up file is no longer associated with a backup copy group, it remains in server storage for 30 days (backup retention grace period).

When an archived file is no longer associated with an archive copy group, it remains in server storage for 365 days (archive retention grace period).

Standard Policy Set (ACTIVE)

The default management class is STANDARD.

Standard Management Class

Client files are not space-managed (no client HSM).

Standard Backup Copy Group

Files are backed up to the default disk storage pool, BACKUPPOOL.

An incremental backup is performed only if the file has changed since the last backup.

Files cannot be backed up while they are being modified.

Up to two backup versions of a file on the client's system are retained in server storage. The most recent backup version is retained for as long as the original file is on the client file system. All other versions are retained for up to 30 days.

One backup version of a file that has been deleted from the client's system is retained in server storage for 60 days.

Standard Archive Copy Group

Files are backed up to the default disk storage pool, ARCHIVEPOOL.

Files cannot be archived while they are being modified.

An archive copy is kept for up to 365 days.

Creating Your Own Storage Management Policies

Task	Required Privilege Class
Define or copy a policy domain	System
Update a policy domain over which you have authority	Restricted policy
Define, update, or copy policy sets and management classes in any policy domain	System or unrestricted policy
Define, update, or copy policy sets and management classes in policy domains over which you have authority	Restricted policy
Define or update copy groups in any policy domain	System or unrestricted policy
Define or update copy groups that belong to policy domains over which you have authority	Restricted policy
Assign a default management class to a nonactive policy set in any policy domain	System or unrestricted policy
Assign a default management class to a nonactive policy set in policy domains over which you have authority	Restricted policy
Validate and activate policy sets in any policy domain	System or unrestricted policy
Validate and activate policy sets in policy domains over which you have authority	Restricted policy
Start inventory expiration processing	System

You may need more flexibility in your storage management policies than the standard ADSM policy objects provide. If so, you can create your own policies in either of two ways: you can define the objects by specifying each attribute, or you can copy existing objects and update only those attributes that you want to change. The following table shows another advantage of copying objects: some associated objects are copied in a single operation.

If you copy:	You create:
Policy Domain	A new policy domain with: <ul style="list-style-type: none"> • A copy of each policy set from the original domain • A copy of each management class in each original policy set • A copy of each copy group in each original management class
Policy Set	A new policy set in the same policy domain with: <ul style="list-style-type: none"> • A copy of each management class in the original policy set • A copy of each copy group in the original management class
Management Class	A new management class in the same policy set and a copy of each copy group in the management class

The rest of this chapter describes the tasks involved in creating new storage management policies for your installation:

- 1 Define policy domains to manage groups of client nodes. See page 172.

- 2** Define policy sets for different storage management policies. See page 173.
- 3** Define management classes to match users' storage management requirements. See page 174.
- 4** Define backup copy groups to specify which files can be backed up and how to manage backup versions. See page 175.
- 5** Define archive copy groups to specify whether a file can be archived if it is in use and to manage archive copies. See page 179.
- 6** Assign a default management class to each policy set to match the most common storage management requirements of client nodes in the policy domain. See page 181.
- 7** Validate all policy sets, and activate one policy set for each policy domain. See page 182.
- 8** Start expiration processing. See page 183.

To help users take advantage of ADSM, you can set up the policy environment by doing the following:

- Create include-exclude lists for inexperienced users or for users who have simple storage management needs
- Provide a sample include-exclude list to users who want to specify how ADSM manages their files. You can show users who prefer to manage their own files how to:
 - Request information about management classes.
 - Select a management class that meets backup and archive requirements.
 - Use include-exclude lists to bind management classes to their files.

For information on how to create an include-exclude list, see the user's publication for the appropriate client.

- Automate incremental back up procedures by defining schedules for each policy domain. Then associate schedules with client nodes in each policy domain. For information on schedules, see Chapter 10, "Automating Operations" on page 193.

Example: Sample Policy Objects

Figure 52 on page 171 shows the policies for an engineering department. This example is used throughout the rest of this chapter.

The domain contains two policy sets, STANDARD and SUMMER. The policy set named STANDARD is active. Only one policy set can be active at a time. When a policy set is activated, the server makes a copy of the policy set and names it ACTIVE.

The ACTIVE policy set contains four management classes: ENGINEERING, MCENG, MCENGBK3, and MCENGAR2. The default management class is MCENG.




Figure 52. An Example of Policy Objects Defined for an Engineering Department

Defining and Updating a Policy Domain

When you update or define a policy domain, you specify:

Backup Retention Grace Period

Specifies the number of days to retain an inactive backup version when the server cannot rebind the file to an appropriate management class. The backup retention grace period protects backup versions from being immediately expired when the management class to which a file is bound no longer exists or no longer contains a backup copy group, and the default management class does not contain a backup copy group.

Backup versions of the file managed by the grace period are retained in server storage only for the backup retention grace period. This period starts from the day of the backup. For example, if the backup retention grace period for the STANDARD policy domain is used and set to 30 days, backup versions using the grace period expire in 30 days from the day of the backup.

Backup versions of the file continue to be managed by the grace period unless one of the following occurs:

- The client binds the file to a management class containing a backup copy group and then backs up the file
- A backup copy group is added to the file's management class
- A backup copy group is added to the default management class

Archive Retention Grace Period

Specifies the number of days to retain an archive copy when the management class for the file no longer contains an archive copy group and the default management class does not contain an archive copy group. The retention grace period protects archive copies from being immediately expired.

The archive copy of the file managed by the grace period is retained in ADSM storage for the number of days specified by the archive retention grace period. This period starts from the day on which the file is first archived. For example, if the archive retention grace period for the policy domain STANDARD is used, an archive copy expires 365 days from the day the file is first archived.

The archive copy of the file continues to be managed by the grace period unless an archive copy group is added to the file's management class or to the default management class.

Example: Defining a Policy Domain

To create a new policy domain you can do one of the following:

- Copy an existing policy domain and update the new domain
- Define a new policy domain from the beginning

Note: When you copy an existing domain, you also copy any associated policy sets, management classes, and copy groups.

For example, to copy and update, follow this procedure:

- 1 Copy the STANDARD policy domain to the ENGPOLDOM policy domain by entering:

```
copy domain standard engpoldom
```

ENGPOLDOM now contains the standard policy set, management class, backup copy group, and archive copy group.

- 2 Update the policy domain ENGPOLDOM so that the backup retention grace period is extended to 90 days and the archive retention grace period is extended to 2 years by entering:

```
update domain engpoldom description='Engineering Policy Domain'  
backretention=90 archretention=730
```

Defining and Updating a Policy Set

When you define or update a policy set, specify:

Policy domain name

Names the policy domain to which the policy set belongs

Example: Defining a Policy Set

A business with seasonal employees needs two policy sets. During most of the year, most users would use the STANDARD policy set. During the summer, it would activate the SUMMER policy set to provide new management classes for users who are seasonal employees. To create the SUMMER policy set in the STANDARD policy domain, the business would perform the following steps:

- 1 Copy the STANDARD policy set and name the new policy set SUMMER:

```
copy policyset standard standard summer
```

Note: When you copy an existing policy set, you also copy any associated management classes and copy groups.

- 2 Update the description of the policy set named SUMMER:

```
update policyset standard summer  
description='Policy set activated during summer for STANDARD domain'
```

Defining and Updating a Management Class

When you define or update a management class, specify:

Policy domain name

Names the policy domain to which the management class belongs.

Policy set name

Names the policy set to which the management class is assigned.

Whether hierarchical storage management (HSM) is to be done

Specifies that the files are eligible for both automatic and selective migration, only selective migration, or no migration.

How frequently files can be migrated

Specifies the minimum number of days that must elapse since a file was last accessed before it is eligible for automatic migration.

Whether backup is required

Specifies whether a backup version of a file must exist before the file can be migrated.

Where migrated files are to be stored

Specifies the name of the storage pool in which migrated files are stored. Your choice could depend on factors such as:

- The number of client nodes migrating to the storage pool. When many user files are stored in the same storage pool, volume contention can occur as users try to migrate files to or recall files from the storage pool.
- How quickly the files must be recalled. If users need immediate access to migrated versions, you can specify a disk storage pool as the destination.

Note: You cannot specify a copy storage pool as a destination.

Example: Define a New Management Class

Create a new management class containing a backup copy group and an archive copy group:

- 1 Copy the STANDARD management class from the STANDARD policy set to the new management class (named MCENG) by entering:

```
copy mgmtclass engpoldom standard standard mceng
```

The server copies the management class description, standard backup copy group, and standard archive copy group to MCENG.

- 2 Update the description of the MCENG management class by entering:

```
update mgmtclass engpoldom standard mceng  
description='Engineering Mgmt Class - Backup & Archive Copy Groups'
```

Defining and Updating a Backup Copy Group

To define or update a backup copy group on the graphical user interface or command line, specify:

Where backed up files are to be stored

Specifies a defined storage pool. Your choice can depend on factors such as:

- The number of client nodes backing up to the storage pool. When many user files are stored in the same storage pool, volume contention can occur as users try to back up to or restore files from the storage pool.
- How quickly the files must be restored. If users need immediate access to backup versions, you could specify a disk storage pool as the destination.

Note: You cannot specify a copy storage pool.

If files can be modified during backup

Specifies how files are handled if they are modified while being backed up and what ADSM does if modification occurs. This attribute, called serialization, can be one of four values:

Static

Specifies that if the file or directory is modified during a backup, ADSM does not back it up. ADSM does not retry the backup.

Shared Static

Specifies that if the file or directory is modified during a backup, ADSM does not back it up. However, ADSM retries the backup as many times as specified by the CHANGINGRETRIES option in the client options file.

Dynamic

Specifies that a file or directory is backed up on the first attempt, even if the file or directory is being modified during the backup.

Shared Dynamic

Specifies that if a file or directory is modified during a backup attempt, ADSM backs it up on its last try even if the file or directory is being modified. ADSM retries the backup as many times as specified by the CHANGINGRETRIES option in the client options file.

For most files, set serialization to either static or shared static to prevent the server from backing up a file while it is being modified.

Attention: If a file is backed up while it is in use (shared dynamic or dynamic serialization), the copy may not contain all the changes and may not be usable.

However, you may want to define a copy group with a serialization of shared dynamic or dynamic for files where log records are continuously added, such as an error log. If you only have copy groups that use static or shared static, these files may never be backed up because they are constantly in use. With shared dynamic or dynamic, the log files are backed up. However, the backup version may contain a truncated message.

Note: When certain users or processes open files, they deny read access to the files for any other user or process. When this happens, even with serialization set to dynamic or shared dynamic, ADSM does not back up the file.

How frequently files can be backed up

Specifies the minimum number of days that must elapse between full incremental backups. Frequency works with the mode parameter, which specifies whether a file or directory is considered for full incremental backup only if it has changed since the last backup or regardless of whether it has been changed. ADSM does not check this attribute when a user requests a partial incremental backup or a selective backup for a file. You can select from two modes:

Modified

A file is considered for full incremental backup only if it has changed since the last backup. A file is considered changed if any of the following items is different:

- Date on which the file was last modified
- File size
- File owner
- File permissions

Absolute

A file is considered for full incremental backup regardless of whether it has changed since the last backup.

For example, if frequency is 3 and mode is modified, a file or directory is backed up only if it has been changed and if three days have passed. If frequency is 3 and mode is absolute, a file or directory is backed up after three days have passed whether or not the file has changed.

Use the modified mode when users want to retain multiple backup versions. If the mode is set to absolute, users may have three *identical* backup versions, rather than three different backup versions.

Absolute mode can be useful for forcing a full backup. It can also be useful for ensuring that OS/2 files with extended attributes are backed up, because ADSM does not detect changes to the extended attributes.

When you set the mode to absolute, set frequency to 0 if you want to ensure that a file is backed up each time full incremental backups are scheduled for or initiated by a client.

How many backup versions to retain

Specifies the number of backup versions. Multiple versions of files are useful when users continually update files and sometimes need to restore the original file from which they started. Two parameters determine how many active and inactive backup copies to retain:

Versions Data Exists

The maximum number of different backup versions that the server retains for files and directories currently on the workstation.

If users select a management class that allows more than one backup version, the most current version is called the *active* version. All other versions are called *inactive* versions.

For example, in Figure 53 on page 178, the most current version of REPORT.TXT was created on Friday at 3 p.m. There are two inactive versions of REPORT.TXT.

When the maximum number of backup versions is exceeded, the oldest version expires and the server deletes it the next time expiration processing runs.

For example, if the maximum number of versions allowed for MEMO.DAT is three, and a user runs a backup process that creates a fourth version, the oldest version expires. In this example, the backup version created on Thursday at 8:05 a.m. expires.

How many inactive versions ADSM keeps is also related to the parameter for how long inactive versions are kept (Retain Extra Versions). Inactive versions can expire when their age exceeds the value specified for retaining extra versions, even when the number of versions is not exceeded.




Figure 53. Example of Active and Inactive Versions of Backed Up Files

Versions Data Deleted

The maximum number of different backup versions that the server retains for files and directories that have been erased from a workstation. The server ignores this parameter while the file or directory remains on the workstation.

If users erase a file or directory from their client nodes, then the next time a full incremental backup is run, the server changes the active backup version to inactive. The oldest versions that are more than the number specified by this parameter then expire, and the server deletes them the next time expiration processing runs.

The expiration date for the remaining versions is based on the Retain Extra Versions and Retain Only Version parameters.

How long to retain files in storage

Specifies how long to retain backup versions:

Retain Extra Versions

Specifies the retention time, in days, for all but the most recent backup version. The value of this parameter determines which versions are deleted during inventory expiration processing.

If NOLIMIT is specified, inactive backup versions are deleted based on the Versions Data Exists or Versions Data Deleted parameters.

Retain Only Version

Specifies how many days ADSM retains the only backup version it has of a file when the original file has been deleted from the workstation.

If NOLIMIT is specified, the last version is retained forever unless a user or administrator deletes the file from server storage.

Example: Define a Backup Copy Group

Define a backup copy group belonging to the MCENG management class in the STANDARD policy set belonging to the ENGPOLDOM policy domain. This new copy group must do the following:

- Let users back up changed files, regardless of how much time has elapsed since the last backup
- Retain up to 4 inactive backup versions when the original file resides on the user workstation
- Retain up to four inactive backup versions when the original file is deleted from the user workstation
- Retain extra inactive backup versions for 90 days
- If there is only one backup version, retain it for 600 days after the original is deleted from the workstation
- Prevent files from being backed up if they are in use
- Store files in the ENGBACK1 storage pool

To define the backup copy group, enter:

```
define copygroup engpoldom standard mceng standard
destination=engback1 serialization=static
verexists=5 verdeleted=4 retextra=90 retonly=600
```

Defining and Updating an Archive Copy Group

To define or update an archive copy group on the graphical user interface or command line, specify:

Where archived files are to be stored

Specifies a defined storage pool. Your choice can depend on factors such as:

- The number of client nodes archiving files to the storage pool. When many

user files are stored in the same storage pool, volume contention can occur as users archive files to and retrieve files from the storage pool.

- How quickly the files must be restored. If users need immediate access to archive copies, you could specify a disk storage pool as the destination.

Note: You cannot specify a copy storage pool as a destination.

If files can be modified during archive

Specifies how files are handled if they are modified while being archived and what ADSM does if modification occurs. This attribute, called serialization, can be one of four values:

Static

Specifies that if the file is modified during an archiving process, ADSM does not archive it. ADSM does not retry the archive.

Shared Static

Specifies that if the file is modified during an archive process, ADSM does not archive it. However, ADSM retries the archive process as many times as specified by the CHANGINGRETRIES option in the client options file.

Dynamic

Specifies that a file is archived on the first attempt, even if the file is being modified during the archive process.

Shared Dynamic

Specifies that if the file is modified during the archive attempt, ADSM archives it on its last try even if the file is being modified. ADSM retries the archive process as many times as specified by the CHANGINGRETRIES option in the client options file.

For most files, set serialization to either static or shared static to prevent the server from archiving a file while it is being modified.

Attention: If a file is archived while it is in use (shared dynamic or dynamic serialization), the copy may not contain all the changes and may not be usable.

However, you may want to define a copy group with a serialization of shared dynamic or dynamic for files where log records are continuously added, such as an error log. If you only have copy groups that use static or shared static, these files may never be archived because they are constantly in use. With shared dynamic or dynamic, the log files are archived. However, the archive copy may contain a truncated message.

Note: When certain users or processes open files, they deny read access to the files for any other user or process. When this happens, even with serialization set to dynamic or shared dynamic, ADSM does not back up the file.

How long to retain an archived copy

Specifies the number of days to retain an archived copy in storage. When the time elapses, the archived copy expires and ADSM deletes the file the next time expiration processing runs.

Example: Define an Archive Copy Group

Define an archive copy group belonging to the MCENG class that:

- Allows users to archive a file if it is not in use
- Retains the archive copy for 730 days
- Stores files in the ENGARCH1 storage pool

To define a STANDARD archive copy group to the MCENG management class in the STANDARD policy set belonging to the ENGPOLDOM policy domain, enter:

```
define copygroup engpoldom standard mceng standard
type=archive destination=engarch1 serialization=static
retver=730
```

Assigning a Default Management Class

After you have defined your policy sets and the management classes that they contain, you must assign a default management class for each policy set. See “Default Management Classes” on page 160 for suggestions about the content of default management classes.

Example: Assign a Default Management Class

To assign the STANDARD management class as the default management class for the SUMMER policy set in the STANDARD policy domain, enter:

```
assign defmgmtclass standard summer standard
```

The STANDARD management class was copied from the STANDARD policy set to the SUMMER policy set (see “Example: Defining a Policy Set” on page 173). Before the new default management class takes effect, you must activate the policy set.

Validating and Activating Policy Sets

After you have defined your policy sets and assigned management classes to them, you can validate those policy sets and activate one policy set for the policy domain.

Validating Policy Sets

When you validate a policy set, the server examines the management class and copy group definitions in the specified policy set and reports on conditions that need to be considered if the policy set is activated.

Validation fails if the policy set does not contain a default management class. The following conditions result in warning messages during validation:

- The storage destinations specified for backup, archive, or migration do not refer to defined storage pools.

A backup, archive, or migration operation will fail when the operation involves storing a file in a storage pool that does not exist.

- A storage destination specified for backup, archive, or migration is a copy storage pool.
- The default management class does not contain a backup or archive copy group.

When the default management class does not contain a backup or archive copy group, any user files bound to the default management class *are not* backed up or archived.

- The current ACTIVE policy set names a management class that is not defined in the policy set being validated.

When users back up files that were bound to a management class that no longer exists in the active policy set, backup versions are rebound to the default management class. See “How Files Are Associated with a Management Class” on page 161 for details.

When the management class to which an archive copy is bound no longer exists and the default management class does not contain an archive copy group, the archive retention grace period is used to retain the archive copy. See “Defining and Updating a Policy Domain” on page 172 for details.

- The current ACTIVE policy set contains copy groups that are not defined in the named policy set.

When users perform a backup and the backup copy group no longer exists in the management class to which a file is bound, backup versions are managed by the default management class if it contains a backup copy group. If the default management class does not contain a backup copy group, backup versions are managed by the backup retention grace period, and the workstation file is not backed up. See “Defining and Updating a Policy Domain” on page 172.

- A management class specifies that a backup version must exist before a file can be migrated from a client node, but the management class does not contain a backup copy group.

Activating Policy Sets

To activate a policy set, specify a policy domain and policy set name. When you activate a policy set, the server:

- Performs a final validation of the contents of the policy set
- Copies the original policy set to the active policy set

After a policy set has been activated, the original and the ACTIVE policy sets are two separate objects. For example, updating the original policy set has no effect on the ACTIVE policy set. You cannot update the ACTIVE policy set. To change its contents, you must do the following:

1. Copy the ACTIVE policy set to a policy set with another name.
2. Update the new policy set.
3. Validate the new policy set.
4. Activate the new policy set to have the server use the changes.

Example: Validating and Activating a Policy Set

Validating and activating the SUMMER policy set in the STANDARD policy domain is a two-step process:

- 1 To validate the SUMMER policy set, enter:

```
validate policyset standard summer
```

- 2 To activate the SUMMER policy set, enter:

```
activate policyset standard summer
```

Running Expiration Processing to Delete Expired Files

Copies of files that have expired are not deleted from server storage until expiration processing occurs. You can run expiration processing either automatically or by command. You control automatic expiration processing by using the expiration interval option (EXPINTERVAL) in the ADSM options file (DSMSERV OPT). For details, see *ADSM Administrator's Reference*. You can manually start expiration processing by issuing the following command:

```
expire inventory
```

Expiration processing then deletes eligible backup versions and archive file copies. Backup versions are eligible based on policy in the backup copy group (how long and how many inactive versions are kept). Archive file copies are eligible based on policy in the archive copy group (how long archived copies are kept).

When expiration processing runs, normally ADSM sends detailed messages about policy changes made since the last time expiration processing ran. The messages are about changes made that affect client files, such as deleting a management class or a copy group. You can reduce the number of messages about policy changes that are generated during expiration processing by using a *quiet* option in the server options, or a QUIET=YES parameter with the EXPIRE INVENTORY command. When you use the quiet option or parameter, ADSM issues messages about policy changes during expiration processing only when files are deleted, and either the default management class or retention grace period for the domain has been used to expire the files.

Querying Policy Objects

Task	Required Privilege Class
Query any policy domain, policy set, management class, or copy group	Any administrator

You can request information about the contents of ADSM policy objects. For example, you might want to do this before creating new objects or helping users to choose policies that fit their needs.

You can specify the output of a query in either standard or detailed format. The examples in this book are in standard format. Refer to *ADSM Administrator's Reference* for examples of detailed format output.

Querying Copy Groups

To request information about backup copy groups (the default) in the ENGPOLDOM engineering policy domain, enter:

```
query copygroup engpoldom * *
```

The following shows the output from the query. It shows that the ACTIVE policy set contains two backup copy groups that belong to the MCENG and STANDARD management classes.

Policy Domain Name	Policy Set Name	Mgmt Class Name	Copy Group Name	Versions Data Exists	Versions Data Deleted	Retain Extra Versions	Retain Only Version
ENGPOLDOM	ACTIVE	MCENG	STANDARD	5	4	90	600
ENGPOLDOM	ACTIVE	STANDARD	STANDARD	2	1	30	60
ENGPOLDOM	STANDARD	MCENG	STANDARD	5	4	90	600
ENGPOLDOM	STANDARD	STANDARD	STANDARD	2	1	30	60
ENGPOLDOM	SUMMER	MCENG	STANDARD	2	1	30	60
ENGPOLDOM	SUMMER	STANDARD	STANDARD	2	1	30	60

To request information about archive copy groups in the ENGPOLDOM engineering policy domain, enter:

```
query copygroup engpoldom * type=archive
```

The following shows the output from the query.

Policy Domain Name	Policy Set Name	Mgmt Class Name	Copy Group Name	Retain Version
ENGPOLDOM	ACTIVE	MCENG	STANDARD	730
ENGPOLDOM	ACTIVE	STANDARD	STANDARD	365
ENGPOLDOM	STANDARD	MCENG	STANDARD	730
ENGPOLDOM	STANDARD	STANDARD	STANDARD	365
ENGPOLDOM	SUMMER	MCENG	STANDARD	730
ENGPOLDOM	SUMMER	STANDARD	STANDARD	365

Querying Management Classes

To request information about management classes in the ENGPOLDOM engineering policy domain, enter:

```
query mgmtclass engpoldom * *
```

The following figure is the output from the query. It shows that the ACTIVE policy set contains the MCENG and STANDARD management classes.

Policy Domain Name	Policy Set Name	Mgmt Class Name	Default Mgmt Class ?	Description
ENGPOLDOM	ACTIVE	MCENG	Yes	Engineering Management Class with Backup and Archive Copy Groups
ENGPOLDOM	ACTIVE	STANDARD	No	
ENGPOLDOM	STANDARD	MCENG	Yes	Engineering Management Class with Backup and Archive Copy Groups versions
ENGPOLDOM	STANDARD	STANDARD	No	
ENGPOLDOM	SUMMER	MCENG	Yes	Engineering Management Class with Backup and Archive Copy Groups versions
ENGPOLDOM	SUMMER	STANDARD	No	

Querying Policy Sets

To query the system for information about policy sets in the ENGPOLDOM engineering policy domain, enter:

```
query policyset engpoldom *
```

The following figure is the output from the query. It shows an ACTIVE policy set and two inactive policy sets, STANDARD and SUMMER.

Policy Domain Name	Policy Set Name	Default Mgmt Class Name	Description
ENGPOLDOM	ACTIVE	MCENG	Policy Set Activated During Summer
ENGPOLDOM	STANDARD		
ENGPOLDOM	SUMMER	MCENG	Policy Set Activated During Summer

Querying Policy Domains

To request information about a policy domain (for example, to determine if any client nodes are registered to that policy domain), enter:

```
query domain *
```

The following figure is the output from the query. It shows that both the ENGPOLDOM and STANDARD policy domains have client nodes assigned to them.

Policy Domain Name	Activated Policy Set	Activated Default Mgmt Class	Number of Registered Nodes	Description
ENGPOLDOM	SUMMER	ENGMC	3	Engineering Policy Domain
STANDARD	STANDARD	STANDARD	3	Installed default policy domain.

Deleting Policy Objects

You cannot delete the ACTIVE policy set or objects in that policy set. When you delete a policy object, you also delete any objects belonging to it.

Task	Required Privilege Class
Delete policy domains	System
Delete any policy sets, management classes, or copy groups	System or unrestricted policy
Delete policy sets, management classes, or copy groups that belong to policy domains over which you have authority	Restricted policy

You can delete the policy objects named STANDARD that ADSM provides. However, all STANDARD policy objects are restored whenever you reinstall the ADSM server. If you reinstall the server after the STANDARD policy objects have been deleted, messages are issued during processing of a subsequent DSMSEV AUDIT DB command. The messages indicate that an instance count does not agree with actual data. DSMSEV AUDIT DB does not delete the STANDARD policy objects, but corrects the instance count to include the restored STANDARD policy objects.

Deleting Copy Groups

You can delete a backup or archive copy group that does not belong to a management class in the ACTIVE policy set.

For example, to delete the backup and archive copy groups belonging to the MCENG and STANDARD management classes in the SUMMER policy set, enter:

```
delete copygroup engpoldom summer mceng type=backup
delete copygroup engpoldom summer standard type=backup
delete copygroup engpoldom summer mceng type=archive
delete copygroup engpoldom summer standard type=archive
```

Deleting Management Classes

You can delete a management class that does not belong to the ACTIVE policy set.

For example, to delete the MCENG and STANDARD management classes from the SUMMER policy set, enter:

```
delete mgmtclass engpoldom summer mceng
delete mgmtclass engpoldom summer standard
```

When you delete a management class from a policy set, the server deletes the management class and all copy groups that belong to the management class in the specified policy domain.

Deleting Policy Sets

Authorized administrators can delete any policy set other than the ACTIVE policy set. For example, to delete the SUMMER policy set from the ENGPOLDOM engineering policy domain, enter:

```
delete policyset engpoldom summer
```

When you delete a policy set, the server deletes all management classes and copy groups that belong to the policy set within the specified policy domain.

Deleting Policy Domains

You can delete a policy domain that has no client nodes registered to it. To determine if any client nodes are registered to a policy domain, issue the QUERY DOMAIN or the QUERY NODE command.

For example, to delete the STANDARD policy domain, perform the following steps:

- 1** Request a list of all client nodes assigned to the STANDARD policy domain by entering:

```
query node * domain=standard
```

- 2** If client nodes are assigned to the policy domain, remove them in either of the following ways:
 - Assign each client to a new policy domain. For example, enter the following commands:

```
update node htang domain=engpoldom  
update node tomc domain=engpoldom  
update node pease domain=engpoldom
```

If the active policy set in ENGPOLDOM does not have the same management class names as in the active policy set of the STANDARD policy domain, then backup versions of files may be bound to a different management class name, as described in “How Files Are Associated with a Management Class” on page 161.

- Delete each node from the STANDARD policy domain.

3 Delete the policy domain by entering:

```
delete domain standard
```

When you delete a policy domain, the server deletes the policy domain and all policy sets (including the ACTIVE policy set), management classes, and copy groups that belong to the policy domain.

Part 4. Automating Operations

Chapter 10. Automating Operations

ADSM includes a central scheduling component that allows the automatic processing of administrative commands and client operations during a specific time period when the schedule is activated.

Administrative commands can be scheduled for use in tuning server operations and to start functions that require significant server or system resources. Automating these operations allows the administrator to ensure that server resources are available when needed by clients.

Administrators can use central scheduling to automate client operations so that clients do not have to perform the operations manually. You can schedule the following client operations:

- Backups (incremental and selective)
- Archives
- Restores
- Retrieves
- Client operating system commands
- Executable scripts on the client (containing operating system commands, ADSM commands, or both)

Each administrative command and each scheduled client operation is called an *event*. Each scheduled event is tracked by the server and recorded in the database. Event records can be deleted from the database as needed to recover database space.

The sections listed in the following table begin at the indicated pages.

Section	Page
Tasks:	
Automating server operations	194
Automating client operations	195
Coordinating client schedules	198
Tailoring schedules	204
Copying schedules	208
Deleting schedules	209
Managing client node associations	212
Managing scheduled events	209

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, refer to *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Automating Server Operations

You can define a schedule to automate administrative commands. Functions that require significant server or system resources can be automatically scheduled to execute at a time when server resources are available and client node processing is at a minimum.

Notes:

1. Scheduled administrative command output is directed to the activity log. This output cannot be redirected. For information about the length of time activity log information is retained in the database, see "Managing the Activity Log" on page 226.
2. You cannot schedule MACRO or QUERY ACTLOG commands.

This section describes how to set up a basic administrative command schedule using ADSM defaults. To later update or tailor your schedules, see "Tailoring Schedules" on page 204.

Task	Required Privilege Class
Define, update, copy, or delete administrative schedules	System
Display information about scheduled operations	Any administrator

Defining the Schedule

Use the DEFINE SCHEDULE command to create a new schedule to process an administrative command. Include the following parameters:

- Specify the administrative command to be issued (CMD=).
- Specify whether the schedule is to be activated (ACTIVE=).

For example:

```
define schedule backup_archivepool type=administrative  
cmd='backup stgpool archivepool recoverypool' active=yes
```

This command results in the following:

- The schedule created is *BACKUP_ARCHIVEPOOL*.
- The schedule is to process the administrative command:
backup stgpool archivepool recoverypool

This command specifies that primary storage pool ARCHIVEPOOL is backed up to the copy storage pool RECOVERYPOOL.

- The schedule is currently active.
- Administrative command output is redirected to the activity log.
- The following defaults are in effect:
 - The start date and time defaults to the current date and time.
 - The length of the startup window is 1 hour.
 - The priority for the schedule is 5. If schedules conflict, the schedule with the highest priority (lowest number) is run first.
 - The schedule never expires.

To change the defaults, see “Tailoring Schedules” on page 204.

Verifying the Schedule

You can verify the details of what you have scheduled by using the QUERY SCHEDULE command. When you use the QUERY SCHEDULE command, you must specify the TYPE=ADMINISTRATIVE parameter to view an administrative command schedule. The following figure shows an example of a report that is displayed after you enter:

```
query schedule backup_archivepool type=administrative
```

*	Schedule Name	Start Date/Time	Duration	Period	Day
-	BACKUP_ARCHIVEPOOL	11/15/1995 14:08:11	1 H	1 D	Any

Note: The asterisk (*) in the first column specifies whether the corresponding schedule has expired. If there is an asterisk in this column, the schedule has expired.

You can check when the schedule is projected to run and whether it ran successfully by using the QUERY EVENT command. For information about querying events, see “Querying Event Records” on page 209.

Automating Client Operations

To automate client operations, you can define a new schedule or update an existing schedule. When you define a schedule, you assign it to a specific policy domain. You can define more than one schedule for each policy domain.

This section describes how to automate a basic client operation, incremental backup. The example uses ADSM defaults. To later update or tailor your schedules, see “Tailoring Schedules” on page 204.

To set up a client schedule on the server:

1. Define a schedule (DEFINE SCHEDULE command).
2. Associate client nodes with the schedule (DEFINE ASSOCIATION command).
3. After client nodes have been associated with a schedule, the client must start the client scheduler to use the server's schedule.
4. Verify the schedule (QUERY SCHEDULE and QUERY EVENT commands).

Task	Required Privilege Class
Define, update, copy, or delete any client schedules	System or unrestricted policy
Define, update, copy, or delete client schedules for specific policy domains	System, unrestricted policy, or restricted policy for those domains
Display information about scheduled operations	Any administrator

Defining the Client Schedule

To define a schedule for incremental backups, use the DEFINE SCHEDULE command. You must specify the policy domain to which the schedule belongs and the name of the schedule (the policy domain must already be defined). For example:

```
define schedule engpoldom weekly_backup
```

This command results in the following:

- Schedule *WEEKLY_BACKUP* is defined for policy domain *ENGPOLDOM*.
- The following defaults are in effect:
 - The scheduled action is an incremental backup (the default action).
 - The priority for the operation is 5. If schedules conflict, the schedule with the highest priority (lowest number) is run first.
 - The schedule window begins now and the schedule itself has 1 hour to start.
 - The start window is scheduled every day.
 - The schedule never expires.

To change the defaults, see “Tailoring Schedules” on page 204.

Associating Client Nodes with Schedules

Client nodes process operations according to the schedules associated with the nodes. To associate client nodes with a schedule, use the DEFINE ASSOCIATION command. A client node can be associated with more than one schedule. However, a node must be assigned to the policy domain to which a schedule belongs.

After a client schedule is defined, you can associate client nodes with it by identifying the following information:

- Policy domain to which the schedule belongs
- List of client nodes to be associated with the schedule

To associate the ENGNODE client node with the WEEKLY_BACKUP schedule, both of which belong to the ENGPOLDOM policy domain, enter:

```
define association engpoldom weekly_backup engnode
```

Starting the Scheduler on the Clients

The client scheduler must be started before work scheduled by the ADSM administrator can be initiated.

To start the client scheduler, the client must issue the SCHEDULE command provided with the ADSM backup-archive client. For example, on an OS/2 client, issue the following command:

```
> dsmc schedule
```

The client can choose to start the client scheduler when the operating system is started, or can start it at any appropriate time. For example, an OS/2 client can include the SCHEDULE command in the startup.cmd file to start the client scheduler when the operating system is started.

For more information, refer to the appropriate *ADSM Using the Backup-Archive Client*.

After the client node starts the client scheduler, it continues to run and initiates scheduled events until it is stopped.

Verifying the Schedule

You can verify what you have scheduled by using the QUERY SCHEDULE command. You can check whether the schedule ran successfully by using the QUERY EVENT command.

Verifying the Schedule

When you request information about schedules, the server displays the following information:

- Schedule name
- Policy domain name
- Type of operation to be performed
- Start date and time for the initial startup window
- Duration of the startup window
- Time period between startup windows
- Day of the week on which scheduled operations can begin

The following figure shows an example of a report that is displayed after you enter:

```
query schedule engpoldom
```

Domain	* Schedule Name	Action	Start Date/Time	Duration	Period	Day
ENGPOLDOM	MONTHLY_BACKUP	Inc Bk	09/21/1995 12:45:14	2 H	2 Mo	Sat
ENGPOLDOM	WEEKLY_BACKUP	Inc Bk	09/21/1995 12:46:21	4 H	1 W	Sat

Checking whether the Schedule Completed Successfully

A scheduled client operation, called an *event*, is tracked by the server. You can get information about projected and actual scheduled processes by using a general query. You can get information about scheduled processes that did not complete successfully by using exception reporting.

For example, you can issue the following command to find out which events were missed in the ENGPOLDOM policy domain for the WEEKLY_BACKUP schedule in the previous week:

```
query event engpoldom weekly_backup begindate=-7 begintime=now  
enddate=today endtime=now exceptionsonly=yes
```

For more information about managing event records, see “Managing Scheduled Event Records” on page 209.

Coordinating Client Schedules

By coordinating client schedules, you can control the workload that scheduled operations place on the server and clients.

The following sections describe:

- Setting the scheduling mode
- Specifying the schedule period for incremental backup operations
- Controlling the server’s scheduled workload
- Controlling client contact with the server

Task	Required Privilege Class
<ul style="list-style-type: none"> • Set the scheduling mode • Set the maximum percentage of sessions for scheduled operations • Randomize schedule start times • Set how often clients query the server • Set the maximum number of times the client node scheduler can retry a command that failed • Set the time between retry attempts 	System

Setting the Scheduling Mode

The central scheduler on the server uses the default of both *client-polling* and *server-prompted* scheduling modes to process scheduled client operations. This default mode is specified as *any*. When the scheduling mode is *any*, the client can choose either scheduling mode. If you specify only one mode for the server, the clients must specify the same mode in their options file. Otherwise, scheduled client work is not processed. The default mode for the clients is *polling*.

Setting Client-Polling Scheduling Mode on the Server

You can use the client-polling scheduling mode with all communication methods.

With this mode, the following occurs:

1. A client node queries the server at prescribed time intervals to obtain a schedule. This interval is set with a client node option. For information about client options, refer to the appropriate *ADSM Using the Backup-Archive Client*.
2. When the scheduled start time begins, the client node performs the scheduled operation and sends the results to the server.
3. The client node then queries the server for its next scheduled operation.

To have clients poll the server for scheduled operations, enter:

```
set schedmodes polling
```

Note: When the scheduling mode on the server is set to *polling*, the mode on the client node also must be set to *polling* for scheduled work to be processed.

Setting the Server-Prompted Scheduling Mode on the Server

You can use the server-prompted scheduling mode only with client nodes that communicate with the server by using the TCP/IP communication method.

With this mode, the following occurs:

1. Client nodes register their addresses with the server.
2. The server contacts the client when scheduled operations need to be performed and a session is available.

3. When contacted, the client node queries the server for the operation, performs the operation, and sends the results to the server.

To have the server prompt client nodes when operations need to be performed, enter:

```
set schedmodes prompted
```

Note: When the scheduling mode on the server is set to prompted, the scheduling mode on the client node also must be set to prompted for scheduled work to be processed.

Setting the Any Scheduling Mode on the Server

To let the server support both client-polling and server-prompted scheduling modes, enter:

```
set schedmodes any
```

In this case, the client node may choose the scheduling mode and scheduled work will begin as specified.

Setting the Scheduling Mode on Client Nodes

Users (root users on UNIX systems) set the scheduling mode on client nodes. They specify either the client-polling or the server-prompted scheduling mode on the command line or in the client user options file (client system options file on UNIX systems).

For more information, refer to the appropriate *ADSM Using the Backup-Archive Client*.

Specifying the Schedule Period for Incremental Backup Operations

When you define a backup copy group, you specify the copy frequency, which is the minimum interval between successive backups. See “Defining and Updating a Backup Copy Group” on page 175. When you define a schedule, you specify the length of time between processing of the schedule. Consider the backup copy group frequencies you have defined in each management class in a policy domain when you specify the schedule period for incremental backups. Schedules for incremental backups do not need to be processed more often than the backup copy group frequency.

Controlling the Server’s Scheduled Workload

To enable the server to complete all schedules for clients, you may need to use trial and error to control the workload. To estimate how long client operations take, test schedules on several representative client nodes. Keep in mind, for example, that the first incremental backup for a client node takes longer than subsequent incremental backups.

Increasing the size of the startup window (by increasing the schedule's duration) can also affect whether a schedule completes successfully. A larger startup window gives the client node more time to attempt initiation of a session with the server.

The settings for randomization and the maximum percentage of scheduled sessions can affect whether schedules are successfully completed for client nodes. Users receive a message if all sessions are in use when they attempt to process a schedule. If this happens, you can increase randomization and the percentage of scheduled sessions allowed to make sure the server can handle the workload.

An administrator can:

- Set the maximum percentage of concurrent client/server sessions for scheduled operations
- Randomize schedule start times for client operations

Setting the Maximum Percentage of Sessions for Scheduled Operations

The number of concurrent client/server sessions is defined by the server option for the maximum client sessions, but you can set a maximum percentage of concurrent client/server sessions allowed for processing scheduled operations. Limiting the number of sessions available for scheduled operations ensures that sessions are available when users initiate any unscheduled operations, such as restoring or retrieving files, or backing up or archiving files.

If the number of sessions for scheduled operations is insufficient, you can increase either the total number of sessions or the maximum percentage of scheduled sessions. However, increasing the total number of sessions can adversely affect server performance, and increasing the maximum percentage of scheduled sessions can reduce the server opportunity to process unscheduled operations.

For example, assume that the maximum number of sessions between client nodes and the server is 80. If you want 25 percent of these sessions to be used by central scheduling, enter:

```
set maxschedsessions 25
```

The server allows 20 sessions to be used for scheduled operations.

For information about the MAXSESSIONS option, refer to *ADSM Administrator's Reference*.

Randomizing Schedule Start Times

To randomize start times for schedules means to scatter each schedule's start time across its startup window. A startup window is the start time and duration during which a schedule must be initiated.

For the client-polling scheduling mode, you can specify the percentage of the startup window that the server can use to randomize start times for different client nodes associated with a schedule.

If you set randomization to 0, no randomization occurs. This process can result in communication errors if many client nodes try to contact the server at the same instant.

The maximum percentage of randomization allowed is 50 percent. This limit ensures that half of the startup window is available for retrying scheduled commands that have failed.

It is possible, especially after a client node or the server has been restarted, that a client node may not poll the server until *after* the beginning of the startup window in which the next scheduled event is to start. In this case, the starting time is randomized over the specified percentage of the *remaining* duration of the startup window.

Consider the following situation:

- The startup window for a particular event is from 8:00 to 9:00
- Ten client nodes are associated with the schedule
- Nine client nodes poll the server before 8:00
- One client node does not poll the server until 8:30

To set randomization to 50 percent enter:

```
set randomize 50
```

The result is that the nine client nodes that polled the server *before* the beginning of the startup window are assigned randomly selected starting times between 8:00 and 8:30. The client node that polled at 8:30 receives a randomly selected starting time that is between 8:30 and 8:45.

Controlling Contact with the Server

To control how often client nodes contact the server to perform a scheduled operation, an administrator can set:

- How often clients query the server
- The number of command retry attempts
- The amount of time between retry attempts

Users (root users on UNIX systems) can also set these values in their client user options files (client system options files for UNIX systems). However, user values are overridden by the values that the administrator specifies.

The client node communication paths to the server can vary widely with regard to response time or the number of gateways. In such cases, you can choose *not* to set these values so that users can tailor them for their own needs.

Setting How Often Clients Query the Server

For the client-polling scheduling mode, you can specify the maximum number of hours the scheduler on a client node waits between attempts to contact the server to obtain a schedule.

You can set this period to correspond to the frequency with which the schedule changes are being made. If client nodes poll more frequently for schedules, changes to scheduling information (through administrator commands) are propagated more quickly to client nodes. However, increased polling by client nodes also increases network traffic.

If you want to have all clients using polling mode contact the server every 24 hours, enter:

```
set querieschedperiod 24
```

Setting the Number of Command Retry Attempts

You can specify the maximum number of times the scheduler on a client node can retry a scheduled command that fails.

The maximum number of command retry attempts does not limit the number of times that the client node can contact the server to obtain a schedule. The client node never gives up when trying to query the server for the next schedule.

Be sure not to specify so many retry attempts that the total retry time is longer than the average startup window.

If you want to have all client schedulers retry a failed attempt to process a scheduled command only twice, enter:

```
set maxcmdretries 2
```

Setting the Amount of Time between Retry Attempts

You can specify the number of minutes the scheduler on a client node waits between retry attempts after a failed attempt to contact the server or after a scheduled command fails to process. You can use this number in conjunction with the number of command retry attempts to control when a client node contacts the server to process a failed command.

Try setting this period to half of the estimated time it takes to process an average schedule.

If you want to have the client scheduler retry failed attempts to contact the server or to process scheduled commands every 15 minutes, enter:

```
set retryperiod 15
```

Tailoring Schedules

To control more precisely when and how your schedules run, you can specify values for schedule parameters instead of accepting the defaults when you define or update schedules.

You can define or update schedules for both administrative commands and client operations. Some parameters for the DEFINE and UPDATE commands apply to both administrative command and client schedules, while others only apply to one type of schedule. This section describes the following:

- Common schedule parameters
- Parameters for administrative command schedules
- Parameters for client schedules

Common Schedule Parameters

The following parameters on the DEFINE and UPDATE commands apply both to administrative command and client schedules:

Schedule name

All schedules must have a unique name, which can be up to 30 characters.

Initial start date, time, and day

You can specify a past date, the current date, or a future date for the initial start date for a schedule with the STARTDATE parameter.

You can specify a start time, such as 6 p.m. with the STARTTIME parameter.

You can also specify the day of the week on which the startup window begins with the DAYOFWEEK parameter. If the start date and start time fall on a day that does not correspond to your value for the day of the week, the start date and time are shifted forward in 24-hour increments until the day of the week is satisfied.

If you select a value for the day of the week other than ANY, then depending on the values for PERIOD and PERUNITS, schedules may not be processed when you expect. Use the QUERY EVENT command to project when schedules will be processed to ensure that you achieve the desired result.

Duration of a startup window

You can specify the duration of a startup window, such as 12 hours, with the DURATION and DURUNITS parameters. The server must start the scheduled service within the specified duration but does not necessarily complete it within

that period of time. If the schedule needs to be retried for any reason, the retry attempt must begin before the startup window elapses or the operation does not restart.

Make the window duration long enough so that all client nodes scheduled for that window have a chance to start the operation. You may have to set the window to a longer period if the number of client nodes processing the schedule is greater than the number of available scheduled sessions.

If the schedule does not start during the startup window, the server records this as a *missed event* in the database. To identify any schedules that may have been missed, you can get an exception report from the server for events. For more information, see “Querying Event Records” on page 209.

How often to run the scheduled service

You can set the schedule frequency based on a period of hours, days, weeks, months, or years with the PERIOD and PERUNITS parameters. To have weekly backups, for example, set the period to one week with PERIOD=1 and PERUNITS=WEEKS.

Expiration date

You can specify an expiration date for a schedule with the EXPIRATION parameter if the services it initiates are required for only a specific period of time. If you set an expiration date, the schedule is not used after that date, but it still exists. You must delete the schedule to remove it from the database.

Priority

You can assign a priority to schedules with the PRIORITY parameter. For example, if you define two schedules for one client node, and they have the same startup window, the server runs the schedule with the highest priority first. A schedule with a priority of 1 is started before a schedule with a priority of 3.

Specifying Administrative Command Schedule Parameters

The following parameters on the DEFINE and UPDATE commands apply only to administrative command schedules:

Administrative schedule name

If you are defining or updating an administrative command schedule, you **must** specify the schedule name.

Type of schedule

If you are updating an administrative command schedule, you **must** specify TYPE=ADMINISTRATIVE on the UPDATE command. If you are defining a new administrative command schedule, this parameter is assumed if the CMD parameter is specified.

Command

When you define an administrative command schedule, you **must** specify the complete command that is processed with the schedule with the CMD parameter. These commands are used to tune server operations or to start functions that require significant server or system resources. The functions include:

- Migration
- Reclamation
- Export and import
- Database backup

Whether or not the schedule is active

Administrative command schedules can be active or inactive when they are defined or updated. Active schedules are processed when the specified command window occurs. Inactive schedules are not processed until they are made active by an UPDATE SCHEDULE command with the ACTIVE parameter set to YES.

Example: Defining and Updating an Administrative Command Schedule

To schedule the backup of the ARCHIVEPOOL primary storage pool, enter:

```
define schedule backup_archivepool type=administrative
cmd='backup stgpool archivepool recoverypool'
active=yes starttime=20:00 period=2
```

This command specifies that, starting today, the ARCHIVEPOOL primary storage pool is to be backed up to the RECOVERYPOOL copy storage pool every two days at 8 p.m.

To update the BACKUP_ARCHIVEPOOL schedule, enter:

```
update schedule backup_archivepool type=administrative
starttime=22:00 period=3
```

Starting with today, the BACKUP_ARCHIVEPOOL schedule begins the backup every three days at 10 p.m.

Specifying Client Schedule Parameters

The following parameters on the DEFINE and UPDATE commands apply only to client schedules:

Domain name

A client schedule belongs to a policy domain.

Type of action

The following actions are possible:

- Perform an incremental backup
- Perform a selective backup
- Archive selected files
- Restore selected files
- Retrieve selected files
- Issue a client command
- Run an executable script (called a macro by ADSM; also known as a command file, a batch file, or a script on different client operating systems)

Restrictions: Not all clients can run all scheduled operations, even though ADSM allows you to define the schedule on the server and associate it with the client. For example, a Windows 3.1 client cannot run a schedule when the action is to restore or retrieve files, issue a command, or run an executable script. A Macintosh client cannot run a schedule when the action is to restore or retrieve files, or run an executable script.

Which files or commands to process

For incremental backup operations, you can specify which file spaces to process with the OBJECTS parameter, or allow the server to perform the backup based on the default client domain specified in the client user options file. Users can specify a default client domain by using the DOMAIN option in the client user options file. For information about specifying the DOMAIN option, refer to *ADSM Using the Backup-Archive Client* for the appropriate client.

For selective backup, archive, restore, and retrieve operations, you must specify the files to process. You can use wildcard characters to select multiple files. The file spaces and file names must follow the naming conventions of the client node. Therefore, you may need to define different schedules for different platforms.

If you are scheduling a command, you must specify the entire command.

If you are scheduling the running of an executable script, you must specify the executable script file name.

Client options

You can specify options that are supplied to the DSMC command when the schedule is processed. You can specify most options from the client's option file. For more information, refer to the appropriate client manual.

When applicable, these options override the options specified by a client node after it has successfully contacted the server.

Do not include the following options because they have no effect on the execution of the scheduled command:

- MAXCMDRETRIES
- QUERYSCHEDPERIOD
- RETRYPERIOD
- SCHEDLOGNAME
- SCHEDMODE

- TCPCLIENTADDRESS
- TCPCLIENTPORT

To help you decide which client options and which file names or file spaces to specify when defining or updating a schedule, you can try them out during an unscheduled operation from the client node. For information about client options, refer to *ADSM Using the Backup-Archive Client* for the appropriate client.

Example: Defining a New Client Schedule

You can define a new schedule for backing up or archiving client nodes in a specified policy domain. When you define a schedule, you assign it to a specific policy domain. You can define more than one schedule for each policy domain.

To define a schedule of incremental backups for the ENGPOLDOM policy domain, enter:

```
define schedule engpoldom engweekly action=incremental
period=1 perunits=weeks
```

This command sets the incremental backup period for schedule ENGWEEKLY to one week to match the backup copy group frequency of the management class in the STANDARD policy set of the ENGPOLDOM policy domain.

Example: Updating an Existing Client Schedule

You can update an existing client schedule for backing up or archiving client nodes in a specified policy domain.

To update the ENGWEEKLY client schedule, enter:

```
update schedule engpoldom engweekly period=5 perunits=days
```

The ENGWEEKLY schedule is updated so that the incremental backup period is now every five days.

Copying Schedules

You can create a new schedule by copying an existing client or administrative schedule. When you copy a schedule, ADSM copies the following information:

- A description of the schedule
- All parameter values from the original schedule

You can then update the new schedule to meet your needs. You can copy a client schedule to another policy domain or to a newly named schedule in the same policy domain.

When you copy a client schedule, none of the client node associations are copied to the new schedule. You must associate the new schedule with client nodes before it can be used. The associations for the old schedule are not changed. See “Associating Client Nodes with Schedules” on page 196 for more information.

To copy the WINTER client schedule that belongs to policy domain DOMAIN1 to DOMAIN2 and name the new schedule WINTERCOPY, enter:

```
copy schedule domain1 winter domain2 wintercopy
```

To copy the BACKUP_ARCHIVEPOOL administrative schedule and name the new schedule BCKSCHED, enter:

```
copy schedule backup_archivepool bcksched type=administrative
```

Deleting Schedules

When you delete a schedule, all associations with client nodes are also deleted. See “Associating Client Nodes with Schedules” on page 196.

To delete all schedules in the ENGPOLDOM policy domain, enter:

```
delete schedule engpoldom *
```

Managing Scheduled Event Records

Task	Required Privilege Class
Display information about events	Any administrator
Set the retention period for event records	System
Delete event records	System or unrestricted policy

Each scheduled administrative command and each scheduled client operation is called an *event*. All scheduled events, including their status, are tracked by the server.

Querying Event Records

To help manage schedules for client operations and administrative commands, you can request information about scheduled and completed events. You can request general or exception reporting queries.

- To get information about past and projected scheduled processes, use a general query. If the time range you specify includes the future, the query output shows which events should occur in the future based on current schedules.
- To get information about scheduled processes that did not complete successfully, use exception reporting.

To minimize the processing time when querying events:

- Minimize the time range
- For client schedules, restrict the query to those policy domains, schedules, and client node names for which information is required

Query events regularly to see which events did not run successfully. For example, you can issue the following command to find out which events were missed in the previous 24 hours, for the DAILY_BACKUP schedule in the STANDARD policy domain:

```
query event standard daily_backup begindate=-1 begintime=now
enddate=today endtime=now exceptiononly=yes
```

Figure 54 shows an example of the results of this query. To find out why a schedule was missed or failed, you may need to check the schedule log on the client node itself. For example, a schedule can be missed because the scheduler was not started on the client node.

Scheduled Start	Actual Start	Schedule Name	Node Name	Status
03/06/1996 20:30:00		DAILY_BACKUP	ANDREA	Missed
03/06/1996 20:30:00		DAILY_BACKUP	EMILY	Missed

Figure 54. Exception Report of Events

Figure 55 on page 211 shows an example of a general report for client node GOODELL that is displayed after you enter:

```
query event standard weekly_backup node=goode11
enddate=today+7
```


Scheduled Start	Actual Start	Schedule Name	Node Name	Status
03/09/1996 06:40:00	03/09/1996 07:38:09	WEEKLY_BACKUP	GOODELL	Started
03/16/1996 06:40:00		WEEKLY_BACKUP	GOODELL	Future

Figure 55. General Report of Events

To query an event for an administrative command schedule, you must specify the `TYPE=ADMINISTRATIVE` parameter. Figure 56 shows an example of the results of the following command:

```
query event * type=administrative
```

Scheduled Start	Actual Start	Schedule Name	Status
03/17/1996 14:08:11	03/17/1996 14:08:14	BACKUP_ARCHI- VEPOOL	Completed

Figure 56. Query Results for an Administrative Schedule

Removing Event Records from the Database

You can specify how long event records stay in the database before the server deletes them. You can also manually remove event records from the database.

If you issue a query for event records that have been removed, the status of those events may appear as *Uncertain*. To ensure that you find out about any missed events before the event records are deleted from the database, you should query events at least as often as you delete records from the database.

Setting the Event Record Retention Period

You can specify the retention period for event records in the database. After the retention period passes, the server automatically removes the event records from the database. At installation, the retention period is set to 10 days.

To set the retention period to 15 days, enter:

```
set eventretention 15
```

Event records are automatically removed from the database after both of the following conditions are met:

- The specified retention period has passed
- The startup window for the event has elapsed

Deleting Event Records

Because event records are deleted automatically, you do not have to manually delete them from the database. However, you may want to manually delete event records to increase available database space.

To delete all event records written prior to 11:59 p.m. on June 30, 1995, enter:

```
delete event 06/30/1995 23:59
```

Managing Client Associations with Schedules

Task	Required Privilege Class
Associate client nodes with any client schedules	System, unrestricted policy, or restricted policy

Querying Associations

You can display information about which client nodes are associated with a specific schedule. For example, you should query an association before deleting a client schedule.

When you query the system for information about node associations, the server returns the following information:

- Name of the schedule
- Name of the policy domain to which the schedule belongs
- Names of the clients that are currently associated with the schedule

The following figure shows the report that is displayed after you enter:

```
query association engpoldom
```

```
Policy Domain Name: ENGPOLDOM
  Schedule Name: MONTHLY_BACKUP
  Associated Nodes: MAB SSTEINER

Policy Domain Name: ENGPOLDOM
  Schedule Name: WEEKLY_BACKUP
  Associated Nodes: MAB SSTEINER
```

Deleting Associations

When you delete the association of a client node to a client schedule, the client data is no longer managed according to the schedule. However, the remaining client nodes still use the schedule.

To delete the association of the ENGNOD client from the ENGWEEKLY schedule, enter:

```
delete association engpoldom engweekly engnod
```

Rather than delete a schedule, you may want to delete all associations to it and save the schedule for possible use in the future.

Part 5. Maintaining the Server

Chapter 11. Managing Server Operations

Administrators can manage server operations. These operations include such tasks as starting and halting the server, managing client sessions, and monitoring server information. The sections listed in the following table begin at the indicated pages.

Section	Page
Tasks:	
Starting, halting, or restarting the server	217
Managing client sessions	219
Disabling or enabling server access	221
Managing server processes	222
Varying disk volumes online or offline	224
Requesting information about server status	224
Setting the server name	225
Querying server options	225
Managing the activity log	226
Monitoring accounting records	228
Getting help on commands and error messages	230

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Starting, Halting, and Restarting the Server

Task	Required Privilege Class
Start, halt, and restart the server	System or operator

Starting the Server

To start the server, from the Ready prompt enter:

```
dsmserv
```

ADSM displays the following information when the server is started:

- Product licensing and copyright information

- Processing information about the server options file
- Communication protocol information
- Database and recovery log information
- Storage pool volume information
- Server generation date
- Progress messages and any errors encountered during server initialization

After the server has started, you can enter administrative commands from the server console command line.

Entering Administrative Commands

Enter administrative commands from the `adsm>` prompt, which is automatically displayed when the server is started.

To limit access to the server without halting ADSM, you can disconnect from the server console by entering:

```
adsm>
#cp disc
```

The `#` character is the default symbol defined as `LINEEND` on your virtual machine.

To reconnect with the server, enter the ADSM server user ID and password. After you have logged on to the server, the virtual machine is in one of two states: `CP READ` or `RUNNING`. The state is displayed at the lower right corner of the screen. If the state is `CP READ`, enter the `CP` command `BEGIN` to continue processing:

```
b
```

Halting the Server

You can halt the server without warning if an unplanned operating system problem requires you to return control to the operating system.

When you halt the server, all processes are abruptly stopped and client sessions are canceled, even if they are not completed. Any in-progress transactions are rolled back when the server is restarted. When the server is halted, administrator activity is not possible.

If possible, halt the server only after current administrative and client node sessions have completed or canceled. To shut down the server without severely impacting administrative and client node activity with the server, you must:

1. Disable the server to prevent new client node sessions from starting, as described in “Disabling or Enabling Server Access” on page 221.

2. Query for session information to identify any existing administrative and client node sessions, as described in “Requesting Information about Client Sessions” on page 219.
3. Notify any existing administrative and client node sessions that you plan to shut down the server. ADSM does not provide a network notification facility; you must use external means to notify users.
4. Cancel any existing administrative or client node sessions, as described in “Canceling a Client Session” on page 221.
5. Find out if any other processes are running, such as server migration or inventory expiration, by using the QUERY PROCESS command. If a database backup process is running, allow it to complete before halting the server. If other types of processes are running, cancel them by using the CANCEL PROCESS command.
6. Halt the server to shut down all server operations by using the HALT command.

Restarting the Server

To start the server after it has been halted, follow the instructions in “Starting the Server” on page 217.

When you restart the server after it has been halted, ADSM rolls back any operations that had been in process to ensure that the database remains in a consistent state.

Managing Client Sessions

Task	Required Privilege Class
Display information about client sessions	Any administrator
Cancel a client session	System or operator

A *client session* can be either an administrative or a client node session.

If you want to prevent clients from accessing the server for an extended period of time, use the LOCK and UNLOCK commands for client node and administrator sessions, or disable the server.

For information on locking or unlocking administrators from the server, see “Locking and Unlocking Administrators from the Server” on page 263. For information on locking or unlocking client nodes from the server, see “Locking and Unlocking Client Nodes” on page 267.

Requesting Information about Client Sessions

When administrators or users log on to the server, an administrative or client node session is established with the server. Each client session is assigned a unique session number.

To request information about client sessions, enter:

```
query session
```

Figure 57 shows a sample client session report.

Sess Number	Comm. Method	Sess State	Wait Time	Bytes Sent	Bytes Recvd	Sess Type	Platform	Client Name
3	Tcp/Ip	IdleW	9 S	7.8 K	706	Admin	OS/2	TOMC
5	Tcp/Ip	IdleW	0 S	1.2 K	222	Admin	OS/2	GUEST
6	Tcp/Ip	Run	0 S	117	130	Admin	OS/2	MARIE

Figure 57. Information about Client Sessions

Check the *session state* and *wait time* to determine the session state of the server and how long (in seconds, minutes, or hours) the session has been in the current state. The server session state can be one of the following:

- Start** Connecting with a client session.
- Run** Executing a client request.
- End** Ending a client session.
- RecvW** Waiting to receive an expected message from the client while a database transaction is in progress. A session in this state is subject to the COMMTIMEOUT limit.
- SendW** Waiting for acknowledgement that the client has received a message sent by the server.
- MediaW** Waiting for removable media to become available.
- IdleW** Waiting for communication from the client, and a database transaction is NOT in progress. A session in this state is subject to the IDLETIMEOUT limit.

If a client does not initiate communication within the specified time limit set by the IDLETIMEOUT option in the server options file, then ADSM cancels the client session.

For example, if the IDLETIMEOUT option is set to 30 minutes, and a user does not initiate any operations within those 30 minutes, then ADSM cancels the client session. The client session is automatically reconnected to the server when it starts to send data again.

Canceling a Client Session

You may cancel a client session when:

- A user is unable to continue with work because the system is not responding
- You want all sessions cancelled before halting the server

To cancel a client session, you must identify it by session number. You can display a session number by issuing a query for session information. For example, if the session number is 6, you cancel that session by entering:

```
cancel session 6
```

If you want to cancel all backup and archive sessions, enter:

```
cancel session all
```

If an operation, such as a backup or an archive process, is interrupted when you cancel the session, ADSM rolls back the results of the current transaction. That is, any changes made by the operation that are not yet committed to the database are undone. If necessary, the cancellation process may be delayed.

When user and administrator sessions are cancelled, those persons must log on to the server again. If they were in the process of performing a function when the session was cancelled, they must reissue their last command.

If the session you cancel is currently waiting for a media mount, the mount request is automatically cancelled.

If the session is in the Run state when it is canceled, the cancellation process does not take place until the session enters the SendW, RecvW, or IdleW state.

Disabling or Enabling Server Access

Task	Required Privilege Class
Disable and enable client node access to the server	System or operator
Display server status	Any administrator

Disabling the server prevents users from establishing client node sessions with the server. This command does not affect system processes like migration and reclamation. To disable the server, enter:

```
disable
```

When you disable the server, administrators can still access it, and current client node activity completes unless the user logs off or you cancel the client node session.

After the server has been disabled, you can enable the server to resume normal operations and allow users to access it by entering:

```
enable
```

You can issue the QUERY STATUS command to determine if the server is enabled or disabled.

Managing Server Processes

Task	Required Privilege Class
Display information about a server background process	Any administrator
Cancel a server process	System

When a user or administrator issues an ADSM command or uses a graphical user interface to perform an operation, the server initiates a process, such as registering a client node, deleting a management class, or canceling a client session.

Many processes occur quickly and are run in the foreground, while others take longer to complete. To allow you to perform other tasks during long-running operations, ADSM runs the following operations as background processes:

- Auditing licenses
- Auditing a volume
- Backing up the database
- Backing up a storage pool
- Defining a database copy
- Defining a recovery log copy
- Deleting a database volume
- Deleting a file space
- Deleting a recovery log volume
- Deleting a storage volume
- Expiring the inventory
- Exporting or importing data
- Extending the database or recovery log
- Migrating files from one storage pool to the next storage pool
- Moving data from a storage volume
- Reclaiming space from tape storage volumes
- Reducing the database or recovery log
- Restoring a storage pool
- Restoring a volume
- Varying a database or recovery log volume online

The server assigns each background process an ID number and displays the process ID when the operation starts. For example, if you issue an EXPORT NODE command, ADSM displays a message similar to the following:

```
EXPORT NODE started as Process 10
```

Requesting Information about Server Processes

You can request information about server background processes. If you know the process ID number, you can use the number to limit the search. However, if you do not know the process ID, you can display information about all background processes by entering:

```
query process
```

Figure 58 shows a server background process report after a DELETE FILESPACE command was issued. The report displays a process ID number, a description and a completion status for each background process.

Process Number	Process Description	Status
2	DELETE FILESPACE	Deleting filespace DRIVE_D for node CLIENT1: 172 files deleted.

Figure 58. Information about Background Processes

Canceling Server Processes

You can cancel a server background process by specifying its ID number in the following command:

```
cancel process 2
```

You can issue the QUERY PROCESS command to find the process number. See “Requesting Information about Server Processes” for details.

If the process you want to cancel is currently waiting for a tape volume to be mounted (for example, a process initiated by EXPORT, IMPORT, or MOVE DATA commands), the mount request is automatically cancelled.

Varying Disk Volumes Online or Offline

Task	Required Privilege Class
Vary a disk volume online or offline	System or operator

To perform maintenance on a disk volume or to upgrade disk hardware, you can vary a disk volume offline. For example, to vary the disk volume named 301 offline, enter:

```
vary offline 301
```

If ADSM encounters a problem with a disk volume, the server automatically varies the volume offline.

After you have replaced the disk volume, you can make it available to the server by varying the volume online. For example, to make the disk volume named 301 available to the server, enter:

```
vary online 301
```

Requesting Information about Server Status

Any administrator can request information about the general server parameters defined by SET commands. To query the status of the server, enter:

```
query status
```

ADSM displays information about the server, such as:

- When the server was installed
- Whether the server is enabled or disabled
- Whether client registration is open or closed
- Whether passwords are required for client/server authentication
- How long passwords are valid
- Whether accounting records are being generated
- How long messages remain in the activity log before being deleted
- How many client sessions can concurrently communicate with the server
- How many client node sessions are available for scheduled work
- What percentage of the scheduling startup window is randomized
- What scheduling mode is being used

- How frequently client nodes can poll for scheduled work
- How many times and how frequently a client node can retry a failed attempt to perform a scheduled operation
- How long event records are retained in the database

Setting the Server Name

Task	Required Privilege Class
Specify the server name	System

At installation, the server name is set to ADSM. After installation, you can use the SET SERVERNAME command to change the server name. You can use the QUERY STATUS command to see the name of the server.

To specify the server name as WELLS_DESIGN_DEPT., for example, enter the following:

```
set servername wells_design_dept.
```

Querying Server Options

Task	Required Privilege Class
Query server options	Any administrator

Use the QUERY OPTION command to display information about one or more server options.

You can issue the QUERY OPTION command with no operands to display general information about all defined server options. You also can issue the QUERY OPTION command with a specific option name or pattern-matching expression to display information on one or more server options.

To display general information about all defined server options, enter:

```
query option
```

Managing the Activity Log

Task	Required Privilege Class
Change the size of the activity log	System or unrestricted storage
Set the activity log retention period	System
Monitor the activity log	Any administrator

The activity log contains all messages normally sent to the server console during server operation. The only exceptions are responses to commands entered at the console, such as responses to QUERY commands. Examples of messages sent to the activity log include:

- When client sessions start or end
- When migration starts and ends
- When backup versions are expired
- What data is exported to tape
- When expiration processing is performed
- What export or import processing is performed

Any error messages sent to the server console are also stored in the activity log.

Use the following sections to adjust the size of the activity log, set an activity log retention period, and request information about the activity log.

Changing the Size of the Activity Log

Because the activity log is stored in the database, the size of the activity log should be factored into the amount of space allocated for the database, allowing at least 1MB of additional space for the activity log.

The size of your activity log depends on how many messages are generated by daily processing operations and how long you want to retain those messages in the activity log. When retention time is increased, the amount of accumulated data also increases requiring additional database storage.

When there is not enough space in the database or recovery log for activity log records, ADSM stops recording and sends messages to the server console. If you increase the size of the database or recovery log, ADSM starts activity log recording again. For information about increasing the size of the database or recovery log, see "Adding Space to the Database or Recovery Log" on page 238.

If you do not have enough space in the database for the activity log, you can do one of the following:

- Allocate more space to the database
- Reduce the length of time that messages are retained in the activity log

Setting the Activity Log Retention Period

You can specify how long activity log information is retained in the database by using the SET ACTLOGRETENTION command.

The server automatically deletes messages from the activity log after they have passed the specified age. At installation, the activity log retention period is set to one day. To change the retention period to 30 days, for example, enter:

```
set actlogretention 30
```

You can display the current retention period for the activity log by querying the server status.

Requesting Information from the Activity Log

You can request information stored in the activity log. To minimize processing time when querying the activity log, you can:

- Specify a time period in which messages have been generated. The default for the QUERY ACTLOG command shows all activities that have occurred in the previous hour.
- Specify the message number of a specific message or set of messages.
- Specify a string expression to search for specific text in messages.
- Specify the QUERY ACTLOG command from the command line for large queries instead of using the graphical user interface.

For example, to review messages generated on May 30 between 8 a.m. and 5 p.m., enter:

```
query actlog begindate=05/30/1996 enddate=05/30/1996  
begintime=08:00 endtime=17:00
```

To request information about messages related to the expiration of files from the server storage inventory, enter:

```
query actlog msgno=0813
```

See the *ADSM Messages* for message numbers.

To request information about messages generated from the IMPORT NODE command, enter:

```
query actlog search='import node'
```

Monitoring ADSM Accounting Records

General-use programming interface

Task	Required Privilege Class
Set accounting records on or off	System

ADSM accounting records show the server resources used during a session. This information lets you track resources used by a client node session. At installation, accounting is set off. You can set accounting on by entering:

```
set accounting on
```

When accounting is set on, the server creates a session resource usage accounting record whenever a client node session ends. CPU usage information is not recommended for use in billing because it does not account for all CPU time used for the client. In addition to time not recorded for database activity during the session, CPU usage for migration, expiration, reclamation, and administrator activities on behalf of a client are not recorded.

ADSM creates three accounting records whenever a session ends. The records are submitted to CP through Diagnose X'4C' for placement in an accounting file. Each record has an 80-character card image format.

VM Accounting Record Type '01'

Column	Field Type	Contents
0-7	EBCDIC	User ID of the ADSM server.
8-37	EBCDIC	Client registered node name. If the node name is greater than 30 characters, the node name is listed as: first...last where <i>first</i> is the first 17 characters of the node name and <i>last</i> is the last 10 characters of the node name.
38-51	EBCDIC	Date and time of accounting (yyyymmddhhmmss).
52-55	Binary	Duration of session, in seconds.
56-59	Binary	Number of archive database objects inserted during the session.
60-63	Binary	Number of backup database objects inserted during the session.
64-67	Binary	Amount of archived data, in kilobytes, sent by the client to the server.
68-71	Binary	Amount of backed up data, in kilobytes, sent by the client to the server.

Column	Field Type	Contents
72–75	Binary	A four-byte integer field that contains the same number in each triplet of accounting records and a different number between accounting records. For instance, the first triplet of accounting records contains a correlation field of X'00000001', the second triplet contains a correlation field of X'00000002', and so on.
76	N/A	Reserved for IBM use.
77	Binary	ADSM accounting record identification code (X'01').
78–79	EBCDIC	VM accounting record identification code ("C0").

VM Accounting Record Type '02'

Column	Field Type	Contents
0–7	EBCDIC	User ID of the ADSM server.
8–15	EBCDIC	Client owner name (UNIX).
16–23	EBCDIC	Node type.
24–31	EBCDIC	Communication method used for session.
32–35	Binary	Number of archive database objects retrieved during the session.
36–39	Binary	Number of backup database objects retrieved during the session.
40–43	Binary	Amount of space, in kilobytes, retrieved by archived objects.
44–47	Binary	Amount of space, in kilobytes, retrieved by backed up objects.
48–51	Binary	Amount of Idle Wait time during the session, in seconds.
52–55	Binary	Amount of Communications Wait time during the session, in seconds.
56–59	Binary	Amount of Media Wait time during the session, in seconds.
60–63	Binary	Amount of CPU time used by the server for basic client activity, in seconds. This includes CPU time to send or receive data from the client, but does not include CPU time to place data on, or retrieve it from database storage.
64	Binary	Authentication method used.
65	Binary	Normal termination indicator (Normal=X'01').
66	Binary	Client session type. A value of 5 indicates a scheduling session. A value of 5 indicates a client session that is running a schedule.
67	N/A	Reserved for ADSM use.
68–71	Binary	Total amount of data communicated between client-server, in Kilobytes.

Column	Field Type	Contents
72–75	Binary	A four-byte integer field that contains the same number in each triplet of accounting records and a different number between accounting records. For instance, the first triplet of accounting records contains a correlation field of X'00000001', the second triplet contains a correlation field of X'00000002', and so on.
76	N/A	Reserved for IBM use.
77	Binary	ADSM accounting record identification code (X'02').
78–79	EBCDIC	VM accounting record identification code ("C0").

VM Accounting Record Type '03'

Column	Field Type	Contents
0–7	EBCDIC	User ID of the ADSM server.
8–15	EBCDIC	Client owner name (UNIX).
16–23	EBCDIC	Node type.
24–31	EBCDIC	Communication used for session.
32–35	Binary	Number of space-managed database objects inserted during the session.
36–39	Binary	Amount of space-managed data, in kilobytes, sent by the client to the server.
40–43	Binary	Number of space-managed database objects retrieved during the session.
44–47	Binary	Amount of space, in kilobytes, retrieved by space-managed objects.
48–71	N/A	Reserved for ADSM use.
72–75	Binary	A four-byte integer field that contains the same number in each triplet of accounting records and a different number between accounting records. For instance, the first triplet of accounting records contains a correlation field of X'00000001', the second triplet contains a correlation field of X'00000002', the third triplet contains a correlation field of X'00000003', and so on.
76	N/A	Reserved for IBM use.
77	Binary	ADSM accounting record identification code (X'03').
78–79	Binary	VM accounting record identification code ("C0").

End of General-use programming interface

Getting Help on Commands and Error Messages

Any administrator can issue the HELP command to display information about administrative commands and messages from the server and the administrative command line client.

You can issue the HELP command with no operands to display a menu of help selections. You also can issue the HELP command with operands that specify help menu numbers, commands and subcommands, or message numbers.

To display the help menu, enter:

```
help
```

To display help information on the REMOVE commands, enter:

```
help remove
```

To display help information on a specific message, such as ANR0992I for example, enter:

```
help 0992
```

Additional information is also available in the online documentation.

Chapter 12. Managing the Database and Recovery Log

Task	Required Privilege Class
Manage disk volumes used by the database and recovery log	System or unrestricted storage
Display information about the database and recovery log	Any administrator

The sections listed in the following table begin at the indicated pages.

Section	Page
Concepts:	
Database and recovery log	233
Tasks:	
Estimating database or recovery log space requirements	236
Adding space to the database or recovery log	238
Deleting space from the database or recovery log	242
Optimizing the performance of the database or recovery log	246

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Database and Recovery Log

The database, recovery log, and storage pool volumes are closely related. The ADSM database contains information needed for server operations and information about client data that has been backed up, archived, and space-managed.

Note: The client data itself is stored in storage pools, not in the database.

The database contains pointers to the locations of all client files in the ADSM storage pools.

Changes to the database are recorded in the recovery log in order to maintain a consistent database image. These changes are the result of transactions between clients and the server. Examples of activities that can occur in a transaction are: defining a management class or copy group, archiving or backing up a client file, and registering an administrator or a client node.

The database contains:

- Information about client nodes and administrators
- Policies and schedules
- Server settings
- Locations of client files on server storage
- Information about server operations (for example, activity logs and event records)

The recovery log contains information about updates that have not yet been committed to the database.

Note: If the database is unusable, the entire ADSM server is unavailable. If a database is lost and cannot be recovered, the backup, archive, and space-managed data for that server is lost. See Chapter 15, “Protecting and Recovering Your Data” on page 297 for steps that you can take to protect your database.

How ADSM Processes Transactions

Both the database and the recovery log have buffer pools. To support multiple transactions from concurrent client sessions, the server holds transaction log records in the recovery log buffer pool until they can be written to the recovery log. These records remain in the buffer until the active buffer becomes full or ADSM forces log records to the recovery log.

Changes resulting from transactions are held in a buffer pool temporarily and not made to the database immediately. Therefore, the database and recovery log are not always consistent.

When all log records for a transaction are written to the recovery log, the server updates the database. The transaction is then committed to the database. At some point after a transaction is committed, the server deletes the transaction record from the recovery log.

How Space is Managed by the Server

ADSM tracks all volumes defined to the database as one logical volume and all volumes defined to the recovery log as another logical volume. For example, in Figure 59, the database consists of four volumes: 301 through 304. ADSM tracks the database as a single logical volume.




Figure 59. A Server Database

To manage the database and recovery log effectively, you must understand the following concepts:

- Available space, page 235
- Assigned capacity, page 235
- Utilization, page 235

Available Space

Not all of the space that is allocated for the database or recovery log volumes is available to be used for database and recovery log information. To calculate the available space, ADSM:

- Subtracts 1MB from each physical volume for overhead.
- Divides the remaining space into 4MB partitions. Any remaining space on a volume is unusable.

See “Step 1: Allocating Space for the Database and Recovery Log” on page 238 for an example of how this calculation is used.

Assigned Capacity

Assigned capacity is the portion of available space that can be used for database or recovery log information. During installation, the server automatically extends the database and recovery log so that assigned capacity matches the available space.

If you add volumes after installation, you increase your available space. However, to increase the assigned capacity, you must also extend the database or recovery log. See “Step 3: Extending the Capacity of the Database or Recovery Log” on page 241 for details.

Utilization

Utilization is the percent of the database or recovery log assigned capacity used at a specific time. *Maximum percent utilized* is the highest utilization since the utilization statistics were last reset.

For example, an installation performs most backups after midnight. Figure 60 on page 236 shows that utilization statistics for the recovery log were reset at 9 p.m. the previous evening and that the maximum utilization occurred at 12 a.m.




Figure 60. An Example of Recovery Log Utilization

Unless an unusually large number of objects are deleted, the database maximum percent utilized is usually close to the utilization percentage.

Estimating and Monitoring Database and Recovery Log Space Requirements

As a general guideline, you should allocate to the database from 5% to 10% of the space required for server storage. For example, if you need 10GB of server storage, your database should be between 500MB and 1GB. See “Estimating Space Needs for Storage Pools” on page 107 for details.

If you back up primary storage pools to copy storage pools, the database also requires about 200 bytes of overhead space for each file in a copy storage pool.

The size of the recovery log depends on the number of concurrent client sessions and the number of background processes executing on the server.

Note: The maximum number of concurrent client sessions is set in the server options.

Begin with at least 12MB for the recovery log. If you will be using the database backup and recovery functions in roll-forward mode, you should begin with at least 25MB. See “Database Backup” on page 299 and “Estimating the Size of the Recovery Log” on page 308 for more information.

Monitoring the Database and Recovery Log

After your ADSM system is operational, you should monitor the database and recovery log to see if you should add or delete space.

You can reset the maximum utilization counters for the database and recovery log to monitor daily utilization. To set the maximum utilization percentage equal to the current utilization, you might want to reset the utilization statistics each day.

Utilization statistics are reset in two ways:

- Automatically when the server is restarted
- By issuing the RESET DBMAXUTILIZATION or RESET LOGMAXUTILIZATION commands

For example, to reset the maximum utilization statistic for the database, enter:

```
reset dbmaxutilization
```

To display information about the database, enter:

```
query db
```

The server displays a report, like this:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
96	96	0	92	4,096	24,576	86	0.3	0.3

To display information about the recovery log, enter:

```
query log
```

The server displays a report, like this:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
12	12	0	8	4,096	3,072	68	2.2	2.2

See the indicated pages for details about the following entries:

- Available space, page 235
- Assigned capacity, page 235
- Utilization and maximum utilization, page 235

On the basis of the these queries, you may decide to adjust the size of the database or recovery log. If utilization is high, you may want to add space. If utilization is low, you may want to delete space. See “Adding Space to the Database or Recovery Log” on page 238 or “Deleting Space from the Database or Recovery Log” on page 242.

Adding Space to the Database or Recovery Log

During the ADSM server installation, you allocated space for the database and recovery log and defined the allocated physical volumes to the server.

Attention: You must not change the size of allocated database or recovery log volumes. If you change the size of a volume, ADSM may not initialize correctly, and data may be lost. However, you can define additional volumes and extend the capacity of the database or recovery log.

You can add or delete database or recovery log volumes while the server is running.

To add space to the database or recovery log perform the following steps:

- “Step 1: Allocating Space for the Database and Recovery Log”
- “Step 2: Defining Database or Recovery Log Volumes to ADSM” on page 240
- “Step 3: Extending the Capacity of the Database or Recovery Log” on page 241

Step 1: Allocating Space for the Database and Recovery Log

The size of the database or recovery log volumes affects space utilization, as is shown in the following examples:

Example 1: An Inefficient Allocation of Space

You allocate four 24MB volumes for the database. For each volume, ADSM:

- Subtracts 1MB for overhead, leaving 23MB of available space
- Divides the 23MB into five 4MB partitions and 3MB of unused space

The available space is only 80MB out of the allocated 96MB.

Example 2: A More Efficient Allocation of Space

You allocate four 25MB volumes for the database. For each volume, ADSM:

- Subtracts 1MB of overhead, leaving 24MB of available space
- Divides the 24MB into six 4MB partitions and no unused space

The available space for the database logical volume is 96MB out of the allocated 100MB, as shown in Figure 61 on page 239.




Figure 61. An Example of Available Space

Notes:

1. For performance reasons, define more than one volume for the database and recovery log, and place these volumes on separate disks to allow simultaneous access to different parts of the database or recovery log.
2. When possible, assign each database and recovery log volume to separate DASD strings, preferably on DASD with different control units and channels.
3. To protect database and recovery log volumes from media failure, you can use the mirroring feature. See “Mirroring the Database and Recovery Log” on page 303 for information on the mirroring feature.
4. To use disk space efficiently, allocate a few large disk volumes rather than many small disk volumes. In this way, you avoid losing space to ADSM overhead processing.

If you already have a number of small volumes and want to consolidate the space into one large volume, see “Deleting Space from the Database or Recovery Log” on page 242.

For example, you can allocate an additional 101MB to the database as volume 305. To install the ADSM server and set up the database and recovery log disks, you used the DSMINST EXEC. After installation, however, the DSMINST EXEC would erase any existing database and recovery log volumes. Instead, use the DSMMDISK EXEC to:

- Identify a minidisk virtual address space for each volume
- Format each minidisk by using CMS FORMAT, if requested
- Reserve each minidisk by using CMS RESERVE
- Initialize each minidisk

To invoke the DSMMDISK EXEC, enter:

```
dsmmdisk
```

Step 2: Defining Database or Recovery Log Volumes to ADSM

To define a database volume named 305, enter:

```
define dbvolume 305
```

When 305 is defined, it becomes a part of the logical view of the server database. Thus, the server still sees a single logical database volume, which is now composed of five physical volumes. Because 1MB from 305 is used for overhead process, 100MB is added to the database to increase the available space to 196MB. However, the assigned capacity remains at 96MB, and ADSM cannot use the space until the capacity is extended (see “Step 3: Extending the Capacity of the Database or Recovery Log” on page 241).

After you define your volumes, you can verify the change by querying the database or recovery log. To query the database, enter:

```
query db
```

The server displays a report, like this:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	96	100	92	4,096	24,576	86	0.3	0.3

In the information displayed, the value in the *maximum extension* field should equal the available space of the new volume. In this example, a 101MB volume was allocated. This report shows that the available space has increased by 100MB; the assigned capacity is unchanged at 96MB; and the maximum extension is 100MB. Figure 62 on page 241 illustrates these changes.

Allocated Space on Physical Volumes		Available Space for the Database	Assigned Capacity
101 MB		100 MB	
25 MB		24 MB	24 MB
25 MB		24 MB	24 MB
25 MB		24 MB	24 MB
25 MB		24 MB	24 MB
Totals 201 MB		196 MB	96 MB

Figure 62. Adding Volumes Increases Available Space

You can also use the QUERY DBVOLUME and QUERY LOGVOLUME commands to display information about the physical volumes that make up the database and recovery log.

Step 3: Extending the Capacity of the Database or Recovery Log

You must extend the database or recovery log in 4MB increments. If you do not specify the extension in 4MB increments, ADSM rounds up to the next 4MB partition. Thus, if you specify 1MB, ADSM extends the capacity by 4MB.

For example, to increase the capacity of the database by 100MB, enter:

```
extend db 100
```

When you extend the database or recovery log, ADSM starts a background process to format the new space. You can issue a QUERY PROCESS command to check on the status of the process.

The result of this command is that the assigned capacity of the database is increased by 100MB, and now equals the available space, as shown in Figure 63 on page 242.




Figure 63. Extending the Capacity of the Database

You can query the database or recovery log (QUERY DB and QUERY LOG commands) to verify their assigned capacities. The server would display a report, like this:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	196	0	192	4,096	50,176	111	0.2	0.2

After the database has been extended, the available space and assigned capacity are both equal to 196MB.

Deleting Space from the Database or Recovery Log

You may want to delete database or recovery log volumes for a number of reasons:

- You have a significant amount of space that is unused.
- You want to consolidate a number of small volumes, each of which may have unusable space (see “Step 1: Allocating Space for the Database and Recovery Log” on page 238 for details).

When a database or recovery log volume is deleted, the server tries to move any data on the volume being deleted to the other physical volumes that make up the logical database or recovery log.

To delete space, perform the following steps:

1. Determine if you can delete one or more volumes (page 243).
2. As needed, reduce the capacity of the database to free up existing space in the database or recovery log, as described in “Step 2: Reducing the Capacity of the Database or Recovery Log” on page 244
3. Delete the volume (page 245).

Step 1: Determining If Volumes Can Be Deleted

To determine if volumes can be deleted from the database or recovery log, check the volume sizes and the amount of unused space.

To check the sizes of the volumes in the database, enter:

```
query dbvolume format=detailed
```

The server displays the following type of information:

```
Volume Name (Copy 1): 301
    Copy Status: Sync'd
Volume Name (Copy 2):
    Copy Status: Undefined
Volume Name (Copy 3):
    Copy Status: Undefined
Available Space (MB): 24
Allocated Space (MB): 24
    Free Space (MB): 0
```

In this example, you determine that 301, 302, 303, and 304 each have 24MB of available space, and 305 has 100MB.

To determine if there is enough unused space to delete one or more volumes, enter:

```
query db
```

The server displays the following type of report. Check the *Maximum Reduction* column for the amount of assigned capacity not being used.

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	196	0	176	4,096	50,176	4,755	9.5	9.5

In this example, the database could be reduced by up to 176MB. This is enough space to allow the deletion of 301, 302, 303, and 304.

If there is not enough space on the remaining volumes, allocate more space and define an additional volume, as described in “Step 1: Allocating Space for the Database and Recovery Log” on page 238 and “Step 2: Defining Database or Recovery Log Volumes to ADSM” on page 240 and continue with “Step 2: Reducing the Capacity of the Database or Recovery Log.”

Step 2: Reducing the Capacity of the Database or Recovery Log

The *maximum reduction* identifies the number of megabytes by which you can reduce the database or recovery log. By reducing the database or recovery log, you might be able to free up enough space to delete a volume.

You can reduce the capacity of the database or recovery log in 4MB increments. If you do not reduce in 4MB increments, ADSM rounds up to the next 4MB partition. Thus, if you specify 5MB, ADSM reduces the capacity by 8MB.

For example, assume that based on the utilization of the database, 305 alone could contain all the data. To reduce the database by the amount of available space in 301 through 304, 96MB, enter:

```
reduce db 96
```

Reducing capacity is run as a background process and can take a long time. You can issue a QUERY PROCESS command to check on the status of the process.

You can query the database to verify how much unused space is available after reduction. For example, after reducing the database by 96MB, the assigned capacity is 100MB and the maximum extension is 96MB, as shown in the following example:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	100	96	92	4,096	24,576	86	0.3	0.3

Step 3: Deleting a Volume from the Database or Recovery Log

After you reduce the database or recovery log, use the smaller size for a few days. If the maximum utilization does not go over 70%, you can delete extra volumes.

Notes:

1. You cannot delete volumes if there is not enough free space for the server to move existing data from the volume being deleted to other physical volumes in the database or recovery log.
2. You cannot delete the last volume of the database or recovery log.

In our example, you determined that you can delete the four 24MB volumes from the database. You have reduced the database by 96MB. To delete 301 through 304 from the database, enter:

```
delete dbvolume 301
delete dbvolume 302
delete dbvolume 303
delete dbvolume 304
```

When you request that volumes be deleted from the database or recovery log, the server moves existing data from the volumes being deleted to available space on other volumes. Figure 64 on page 246 shows data moved from 301, 302, 303, and 304 to available space on 305.




Figure 64. Deleting Database Volumes

After the data has been moved, these volumes are deleted from the server.

Optimizing the Performance of the Database or Recovery Log

The size of the database and recovery log buffer pools can affect performance at the cost of greater memory. For example, a large database buffer pool can improve performance, and a large recovery log buffer pool reduces how often the server forces records to the recovery log.

Adjusting the Database Buffer Pool

You can adjust the size of the database buffer pool by updating the server option for it.

Step 1: Resetting Database Buffer Pool Utilization Statistics

To gather statistics on database use, reset the buffer pool statistics on a regular basis and chart the results. Initially, you might want to monitor the database twice a day. Later, when most client nodes have been registered to the server, you can reset statistics each week. To reset the database buffer pool, enter:

```
reset bufpool
```

Step 2: Requesting Information about the Database Buffer Pool

To see if the database buffer pool is adequate for database performance, enter:

```
query db format=detailed
```

The server displays a report, like this:

```
Available Space (MB): 196
Assigned Capacity (MB): 196
Maximum Extension (MB): 0
Maximum Reduction (MB): 176
  Page Size (bytes): 4,096
    Total Pages: 50,176
    Used Pages: 4,755
      %Util: 9.5
      Max. %Util: 9.5
    Physical Volumes: 5
  Buffer Pool Pages: 128
Total Buffer Requests: 1,193,212
  Cache Hit Pct.: 99.73
  Cache Wait Pct.: 0.00
```

Use the following fields to evaluate your current use of the database buffer pool:

Buffer Pool Pages

The number of pages in the database buffer pool. This value is determined by the server option for the size of the database buffer pool. At installation, the database buffer pool is set to 512KB, which equals 128 database pages.

Total Buffer Requests

The number of requests for database pages since the server was last started or since the last reset of the buffer pool. If you regularly reset the buffer pool, you can see trends over time.

Cache Hit Pct

The percentage of requests for cached database pages in the database buffer pool that were not read from disk.

A high *cache hit percentage* indicates that the size of your database buffer pool is adequate. If the cache hit percentage is below 90%, consider increasing the size of the database buffer pool.

Cache Wait Pct

The percentage of requests for database pages that had to wait for a buffer to become available in the database buffer pool.

When the cache wait percentage is greater than 0, increase the size of the database buffer pool.

Step 3: Set the Size of the Database Buffer Pool

You can set the size of the database buffer pool by setting the buffer pool size option (BUFPOOLSIZE). You can set options by editing the server options file (see *ADSM Administrator's Reference*).

Adjusting the Recovery Log Buffer Pool

You can adjust the size of the recovery log buffer pool by updating the server option for it.

Step 1: Requesting Information about the Recovery Log Buffer Pool

To see how the buffer pool size affects recovery log performance, enter:

```
query log format=detailed
```

The server displays a report, like this:

```
Available Space (MB): 12
Assigned Capacity (MB): 12
Maximum Extension (MB): 0
Maximum Reduction (MB): 8
  Page Size (bytes): 4,096
    Total Pages: 3,072
    Used Pages: 227
    %Util: 7.4
    Max. %Util: 69.6
  Physical Volumes: 1
    Log Pool Pages: 32
  Log Pool Pct. Util: 6.25
  Log Pool Pct. Wait: 0.00
```

Use the following fields to optimize the log buffer pool size for your installation:

Log Pool Pages

The number of pages in the recovery log buffer pool. This value is set by the server option for the size of the recovery log buffer pool. At installation, the default setting is 128KB, which equals 32 recovery log pages.

Log Pool Pct. Util

The percentage of pages used to write changes to the recovery log after a transaction is committed.

A low *log pool percent utilization* (under 10%) indicates that the size of your recovery log buffer pool is adequate. As this number increases, consider increasing the size of the recovery log buffer pool.

Log Pool Pct. Wait

The percentage of requests for a page that is not available because all pages are waiting to write to the recovery log.

If the *log pool percentage wait* value is greater than 0, increase the size of the recovery log buffer pool.

Step 2: Setting the Size of the Recovery Log Buffer Pool

You can set the size of the recovery log buffer pool by setting the buffer pool size option (LOGPOOLSIZE). You can set options by editing the server options file (see *ADSM Administrator's Reference*).

Chapter 13. Managing Licensing, Privilege Classes, and Registration

This section provides the information necessary for a system administrator to control authorization and access to the server. The sections listed in the following table begin at the indicated pages.

Section	Page
Tasks:	
Managing ADSM licenses	251
Ensuring client/server authentication	255
Registering administrators or updating information	256
Granting administrative authority	256
Revoking or reducing administrative authority	260
Managing administrator access	262
Managing client node registration	264
Registering an application programming interface to the server	271
Managing client node access	267
Requesting information about client nodes	268
Requesting information about file spaces	269
Deleting file spaces and client nodes from the server	270

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Managing ADSM Licenses

Task	Required Privilege Class
Register licenses Audit licenses Schedule automatic license audits	System
Display license information	Any administrator

If an ADSM system exceeds the terms of its license agreement, one of the following occurs:

- The server issues a warning message indicating that it is not in compliance with the licensing terms.
- Operations fail because the server is not licensed for specific features.

For details, see “License Compliance” on page 254. In either case, you must contact your IBM account representative or authorized reseller to modify your agreement.

Licensed Features

The base ADSM VM server license supports an unlimited number of administrative clients, one OS/2 backup-archive client, and a specified set of removable media devices.

Notes:

1. In this licensing section, the term *client* is used to refer to backup-archive clients, unless otherwise noted.
2. For current information about supported clients and devices, check with your authorized reseller. You can also call the IBM Information Support Center at 1-800-IBM-3333 and ask for STAR 20, or you can send an E-mail note to askibm-rsvp@info.ibm.com with STAR 20 in the body of the note.

You must register a new license if you want to make any of the following changes to your license agreement:

- Add support for additional clients. The base license allows for one OS/2 backup-archive client. If you want to add clients in an environment other than OS/2, you must register a new license for that feature also (see the next item in this list). See “Registering Additional Clients.”
- Add support for clients in environments other than OS/2. The base license allows only for backup-archive clients on OS/2. See “Registering Clients Other Than OS/2” on page 253.
- Add support for storage devices not covered by the existing agreement. See “Registering Device Support Modules” on page 253.
- Add a second server attachment to an already supported library. See “Registering Secondary Server Attachment” on page 254.

Registering Additional Clients

You register the server to support a specified number of clients beyond the one OS/2 backup-archive client supported by the base license. Those additional clients can be in any environment for which your system is licensed (see “Registering Clients Other Than OS/2” on page 253).

For example, to register three additional clients, enter:

```
register license clients 3
```

Note: The options file must be accessible in write mode. If it is not, a new options file containing only the new license information is created on the first read/write disk.

If you register more clients than your server is licensed to support, the server issues a warning message. However, operations continue normally.

Registering Clients Other Than OS/2

You can obtain licenses for environment support features that allow the server to support clients other than OS/2.

Environment support features are:

DESKTOP

OS/2, DOS, Macintosh, Novell NetWare, Windows, or Windows 32-bit

UNIX

Any UNIX clients such as AIX, HP-UX, or SunOS

OPENEDITION

OpenEdition MVS

SPACEMGMT

HSM clients

To register more than one environment support feature, issue a separate REGISTER LICENSE command for each feature. For example, to allow AIX clients and HSM clients, issue:

```
register license unix
register license spacemgmt
```

Registering Device Support Modules

You can obtain licenses for device support modules that allow the server to support a variety of storage devices. Device support modules for storage devices are numbered 1 through 4, and each module includes all devices supported by any lower-numbered module. For example, Device Support Module 4 supports any device supported by Device Support Modules 1, 2, and 3. The VM base license includes Device Support Modules 1 and 2.

To let the server attach storage devices in Device Support Module 3, enter:

```
register license devicemod3
```

Any attempt to define a library or drive that requires a device support module fails if the module is not registered. If you try to mount a volume requiring a library or drive that is not licensed, the operation also fails.

The *ADSM Licensed Program Specifications and License Information* list the devices and libraries supported by each device support module. However, device support is continually expanded. For current information about supported devices, check with IBM or your authorized reseller, or call the IBM Information Support Center at 1-800-IBM-3333 and ask for STAR 20.

Registering Secondary Server Attachment

You can obtain a license for attaching a secondary server to a library. For example, if you have a license for Device Support Module 4, you can get a license that lets you attach a secondary server to a library in that module. Register that license by entering:

```
register license secondaryserverattach
```

License Compliance

If license terms change (for example, a new license is specified for the server), the server conducts an audit to determine if the current server configuration conforms to the license terms.

The server also periodically audits compliance with the license terms. The results of this audit are used to check and enforce license terms. If 30 days have elapsed since the previous license audit, the administrator cannot cancel the audit.

The number of client nodes for which a server is licensed is enforced when the server is in open registration mode. If the terms of the license are violated by the addition of another registered node, the server issues a warning message stating that it is out of compliance.

If the server is not licensed to support a type of client (environment support) or device (device support module), server operations fail when you try to use the client or device. If one or more of the features or device support modules are licensed on the server, you receive error messages if you exceed your license terms.

Monitoring Licenses

An administrator can monitor license compliance by:

Auditing licenses

Use the `AUDIT LICENSES` command or the GUI to compare the current configuration with the current licenses.

Note: During a license audit, the server calculates, by node, the amount of backup, archive, and space management storage in use. This calculation can take a great deal CPU time and can stall other

server activity. Use the NOAUDITSTORAGE option to specify that storage is not to be calculated as part of a license audit.

Displaying license information

Use the QUERY LICENSE command or the GUI to display details of your current licenses and determine licensing compliance.

Scheduling automatic license audits

Use the SET LICENSEAUDITPERIOD command or the GUI to specify the number of days between automatic audits.

Ensuring Client/Server Authentication

Task	Required Privilege Class
Set password authentication Set password expiration	System

To ensure that only authorized administrators and client nodes are communicating with an authorized server, you can require the use of passwords. You can also require that users regularly change their passwords.

Setting Password Authentication

At installation, ADSM automatically sets password authentication on. With password authentication set to on, all users must enter a password when accessing the server. To allow administrators and client nodes to access ADSM without entering a password, issue the following command:

```
set authentication off
```

Attention: Setting password authentication off reduces data security.

Setting User Password Expiration

At installation, ADSM sets a password expiration of 90 days. You can reset the expiration period from 1 to 9999 days. For example, to set the expiration period to 120 days, issue the following command:

```
set passexp 120
```

The expiration period begins when an administrator or client node is first registered to the server. If a user password is not changed within this period, the server prompts the user to change the password the next time the user tries to access the server.

Registering Administrators or Updating Information

Task	Required Privilege Class
Register an administrator or update information about other administrators	System
Update information about yourself	Any administrator

To register an administrator, specify a user ID and password. You also can provide contact information such as the user name and telephone number. Contact information is displayed when you query administrator information (`format=detailed`).

To register the administrator with a user ID of `DAVEHIL` and the password of *birds*, enter the `REGISTER ADMIN` command:

```
register admin davehil birds contact='backup team'
```

Note: At installation, the server console is defined with a special user ID, which is named `SERVER_CONSOLE`. This name is reserved and cannot be used by another administrator. At installation, the `SERVER_CONSOLE` user ID can be used to register other administrators and grant system privilege.

An administrator with system privilege can revoke or grant new privileges to the `SERVER_CONSOLE` user ID. However, you cannot update, lock, rename, or remove the `SERVER_CONSOLE` user ID from `ADSM`. The `SERVER_CONSOLE` user ID does not have a password. Therefore, you cannot use the user ID from an administrative client unless you set authentication off.

If as an administrator you forget your password, you can reset the password by issuing the `UPDATE ADMINISTRATOR` command. For example, to change his password to *ganymede*, `DAVEHIL` enters:

```
update admin davehil ganymede
```

Note: The `SERVER_CONSOLE` administrator's ID and contact information cannot be updated.

Granting Administrative Authority

Task	Required Privilege Class
Grant authority to other administrators	System

After administrators are registered, they can make queries and request command-line help. To perform other ADSM functions, they must be granted authority by being assigned one or more administrative privilege classes.

This section describes the privilege classes, which are illustrated in Figure 65. An administrator with system privilege can perform any ADSM function. Administrators with policy, storage, operator, or analyst privileges can perform subsets of ADSM functions.




Figure 65. Administrative Privilege Classes

System Privilege

An administrator with *system privilege* can perform any ADSM administrative task.

The following tasks can be performed only by administrators with system privilege:

- Register or remove administrators
- Grant or revoke all levels of administrative authority
- Lock or unlock administrators from the server
- Rename administrators or update administrator information
- Define or delete policy domains and storage pools
- Import or export data from the server
- Cancel administrative background processes
- Set operating parameters for the server
- Perform license audits
- Grant privilege classes to other administrators

To grant the system privilege class to administrator KACZ, enter:

```
grant authority kacz classes=system
```

Unrestricted Policy Privilege

An administrator with *unrestricted policy privilege* can manage the backup and archive services for client nodes assigned to any policy domain. When new policy domains are defined to the server, an administrator with unrestricted policy privilege is automatically authorized to manage the new policy domains.

An administrator with unrestricted policy privilege can:

- Register client nodes in any policy domain
- Manage any client node access to the server
- Delete any client node files from storage pools
- Manage policy objects within any policy domain

Note: System privilege is required to copy, define, or delete the policy domains themselves.

- Manage schedules, that automatically back up or archive files
- Associate client nodes to schedules defined in the same policy domain

To grant unrestricted policy privilege to administrator SMITH, enter:

```
grant authority smith classes=policy
```

Restricted Policy Privilege

An administrator with *restricted policy privilege* can perform the same operations as an administrator with unrestricted policy privilege **but only for specified policy domains**.

An administrator with restricted policy privilege can:

- Register a client node to an authorized policy domain
- Manage access for client nodes assigned to an authorized policy domain
- Delete files from storage pools for client nodes in authorized policy domains
- Manage policy objects in authorized policy domains
- Manage backup or archive schedules in authorized policy domains
- Associate schedules to client nodes assigned to an authorized policy domain

To grant restricted policy privilege over the policy domain named ENGPOLDOM, to administrator JONES enter:

```
grant authority jones domains=engpoldom
```

Unrestricted Storage Privilege

An administrator with *unrestricted storage privilege* has the authority to manage the database, recovery log, and all storage pools.

An administrator with unrestricted storage privilege can:

- Define volumes to the database or recovery log
- Extend or reduce the size of the database or recovery log
- Create mirrored copy sets of the database or recovery log
- Delete volumes from the database or recovery log
- Manage disk and tape device classes
- Define volumes to any disk or tape storage pools
- Move data from a storage pool to any other storage pool
- Delete volumes from any storage pool
- Audit volumes belonging to any storage pool

Note: However, an administrator with unrestricted storage privilege cannot define or delete storage pools.

To grant unrestricted storage privilege to administrator COYOTE, enter:

```
grant authority coyote classes=storage
```

Restricted Storage Privilege

Administrators with *restricted storage privilege* can manage only those storage pools to which they are authorized. They cannot manage the database or recovery log.

For those authorized storage pools, administrators with restricted storage privilege can:

- Define volumes to the storage pools
- Move data from one volume to another in a storage pool
- Delete volumes from the storage pools
- Audit volumes belonging to the storage pools

For example, assume that you have these tape storage pools: TAPEPOOL1, TAPEPOOL2, and TAPEPOOL3. To grant restricted storage privilege for these storage pools to administrator HOLLAND, you could enter:

```
grant authority holland stgpools=tape*
```

HOLLAND is restricted to managing storage pools beginning with "TAPE" that existed when the authority was granted. HOLLAND is not authorized to manage any storage pools that are defined after authority has been granted.

To add a new storage pool, TAPEPOOL4, to HOLLAND's authority, enter:

```
grant authority holland stgpools=tapepool4
```

Operator Privilege

Administrators with *operator privilege* control the immediate operation of the ADSM server and the availability of storage media.

An administrator with operator privilege can:

- Disable the server to prevent clients from accessing the server
- Enable the server for access by clients
- Cancel client/server sessions
- Vary disk volumes on or off line to perform maintenance
- Reset the error status for tape volumes
- Manage tape mounts
- Halt the server, when necessary

To grant operator privilege to administrator BILL, enter:

```
grant authority bill classes=operator
```

Analyst Privilege

An administrator with *analyst privilege* can issue commands that reset the counters that track server statistics.

To grant analyst privilege to administrator MARYSMITH, enter:

```
grant authority marysmith classes=analyst
```

Changing Administrative Authority

Task	Required Privilege Class
Extend, revoke, or reduce administrative privilege classes	System

You can extend, revoke or reduce another administrator's authority.

Extending Administrative Privilege

Granting authority to an administrator adds to any existing privilege classes; it does not override those classes.

For example, JONES has restricted policy privilege for policy domain ENGPOLDOM. Enter the following command to extend JONES' authority to policy domain MKTPOLDOM and add operator privilege:

```
grant authority jones domains=mktpoldom classes=operator
```

Revoking One or More Administrative Privilege Classes

You can revoke part of an administrator's authority by specifying the administrator's user ID and one or more privilege classes.

Assume that rather than revoking all of the privilege classes for administrator JONES you wished only to revoke his operator authority and his policy authorization to policy domain MKTPOLDOM. You would enter:

```
revoke authority jones classes=operator domains=mktpoldom
```

JONES still has policy privilege to the ENGPOLDOM policy domain.

Revoking All Administrative Privilege Classes

To revoke all administrative privilege classes, do not specify any privilege classes, policy domains, or storage pools. For example, to revoke both the storage and operator privilege classes from administrator JONES enter:

```
revoke authority jones
```

Reducing Privilege Classes

You can reduce an administrator's authority simply by revoking one or more privilege classes and granting one or more other classes.

For example, administrator HOGAN has system authority. To reduce HOGAN to the operator privilege class do the following:

1. Revoke the system privilege class by entering:

```
revoke authority hogan classes=system
```

2. Grant operator privilege class by entering:

```
grant authority hogan classes=operator
```

Managing Administrator Access

An administrator can control access to the server by renaming or removing an administrator, or by locking and unlocking an administrator from the server.

Task	Required Privilege Class
Rename an administrator user ID Remove other administrators from the server Temporarily prevent other administrators from accessing the system	System privilege
Display administrator information	Any administrator

Renaming an Administrator

You can rename an administrator ID when an employee wants to be identified by a new ID, or you want to assign an existing administrator ID to another person. You cannot rename an administrator ID to one that already exists on the system.

For example, if administrator HOLLAND leaves your organization, you can assign administrative privilege classes to another user by completing the following steps:

1. Assign HOLLAND's user ID to WAYNESMITH by issuing the RENAME ADMIN command:

```
rename admin holland waynesmith
```

By renaming the administrator ID, you remove HOLLAND as a registered administrator from the server. In addition, you register WAYNESMITH as an administrator with the password, contact information, and administrative privilege classes previously assigned to HOLLAND.

2. Change the password to prevent the previous administrator from accessing the server by entering:

```
update admin waynesmith new_password contact="development"
```

Note: The administrator SERVER_CONSOLE cannot be renamed.

Removing Administrators

You can remove administrators from the server so that they no longer have access to administrator functions. For example, to remove registered administrator ID SMITH, enter:

```
remove admin smith
```

Notes:

1. You cannot remove the last system administrator from the system.
2. You cannot remove the administrator SERVER_CONSOLE.

Locking and Unlocking Administrators from the Server

You can lock out administrators to temporarily prevent them from accessing ADSM.

For example, administrator MARYSMITH takes a leave of absence from your business. You can lock her out by entering:

```
lock admin marysmith
```

When she returns, any system administrator can unlock her administrator ID by entering:

```
unlock admin marysmith
```

MARYSMITH can now access ADSM to complete administrative tasks.

Note: You cannot lock or unlock the SERVER_CONSOLE ID from the server.

Requesting Information about Administrators

Any administrator can query the server to view administrator information. You can also query all administrators authorized with a specific privilege class.

For example, to query the system for a detailed report on administrator ID DAVEHIL, issue the QUERY ADMIN command:

```
query admin davehil format=detailed
```

Figure 66 on page 264 displays a detailed report.

```

Administrator Name: DAVEHIL
Last Access Date/Time: 02/09/1996 19:49:46
Days Since Last Access: 1
Password Set Date/Time: 02/08/1996 19:49:31
Days Since Password Set: 1
  Locked?: No
  Contact: backup team
  System Privilege:
  Policy Privilege: ENGPOLDOM
  Storage Privilege:
  Analyst Privilege:
  Operator Privilege:
Registration Date: 02/09/1996 19:00:00
Registering Administrator: REES

```

Figure 66. A Detailed Administrator Report

Managing Client Nodes

Task	Required Privilege Class
Set registration to open or closed	System
Register client nodes to any policy domain	System or unrestricted policy
Register client nodes to specific policy domains	System, unrestricted policy, or restricted policy for those domains
Update, rename, lock, or unlock any client nodes	System, unrestricted policy
Update, rename, lock, or unlock client nodes assigned to specific policy domains	System, unrestricted policy, or restricted policy for those domains
Request information about client nodes or file spaces	Any administrator
Delete any file space from storage pools	System or unrestricted policy
Delete file spaces defined for client nodes assigned to specific policy domains	System, unrestricted policy, or restricted policy for those domains
Remove any client nodes	System or unrestricted policy
Remove client nodes assigned to specific policy domains	System, unrestricted policy, or restricted policy for those domains

Managing client node registration includes:

- Setting client node registration to open or closed
- Registering client nodes
- Updating client node information
- Managing client node access
- Requesting information about client nodes
- Requesting information about file spaces
- Deleting file spaces and client nodes

Setting Client Node Registration

Before a user can request backup or archive services, the workstation, or client node, must be registered with the server.

ADSM provides two methods for registering client nodes with an ADSM server:

Open registration

Users register their own client nodes.

Closed registration

An administrator must register each client node.

At installation, registration is set to closed. To set registration to open, enter:

```
set registration open
```

Note: Existing registered client nodes are not affected by changes to the registration process.

User Registration of Client Nodes

Under open registration, when a user accesses ADSM from an unregistered workstation, the server prompts the user for a password and contact information and registers the workstation as a client node with the server. On UNIX systems, only the root user can register a workstation as a client node with the server.

ADSM sets the following defaults:

- Assigns each client node to the policy domain STANDARD.
- Allows each client user to choose whether or not to compress files. On a UNIX system a root user can define whether compression is used by entering the COMPRESSION option in the **dsm.opt** client options file.
- Allows each client node user to delete archived copies (but not backed up files) from storage pools.

To change the defaults after the client node has been registered, you can update the client node (see “Updating Client Node Information” on page 267).

Administrator Registration of Client Nodes

To register a client node under open or closed registration, an administrator provides some or all of the following information:

- The node name. UNIX users should provide the value returned by the HOSTNAME command to the administrator.
- The node password.
- The policy domain to which the client node is assigned.
- Whether the user can compress files before they are backed up, archived, or space-managed.

Compression saves throughput time and server storage but requires more workstation memory and CPU cycles. Typically, a workstation with a slow processor connected to the server on a high-speed transmission line does not benefit from compression. To optimize performance or to ease memory constraints at the workstation, an ADSM administrator can restrict file compression.

You can select one of three options:

- Compress files
- Do not compress files
- Use the value set in the COMPRESSION option

The COMPRESSION option can be set in the client system options file or in the API configuration file.

- Whether the user is allowed to delete backed up or archived files from storage pools, by using the DSMC DELETE FILESPACE or DSMC DELETE ARCHIVE command.

If users cannot delete archived or backed up files, an administrator must do so (see “Deleting File Spaces and Client Nodes” on page 270).

For example, you want to register three workstations from the engineering department and assign them to the *ENGPOLDOM* policy domain. (Before you can assign client nodes to a policy domain, the policy domain must exist. For how to define a policy domain, see Chapter 9, “Managing Policies” on page 155.)

You want to set file compression on and let the users delete backed up or archived files from storage pools. From an administrative client, you can use the macro facility to register more than one client node at a time.

For this example, you create a macro file named *REGENG.MAC*, that contains the following REGISTER NODE commands:

```
register node ssteiner choir contact='department 21'  
domain=engpoldom compression=yes archdelete=yes backdelete=yes  
register node carolh skiing contact='department 21, second shift'  
domain=engpoldom compression=yes archdelete=yes backdelete=yes  
register node mab guitar contact='department 21, third shift'  
domain=engpoldom compression=yes archdelete=yes backdelete=yes
```

Next, issue the MACRO command:

```
macro regeng.mac
```

For information on the MACRO command, see *ADSM Administrator's Reference*.

Managing Client Node Access

You can control client node access to ADSM by updating or renaming client nodes or by locking and unlocking client nodes from the server.

Updating Client Node Information

You can update the following client node information:

- The user password or contact information
- The policy domain to which the client node is assigned

Note: An administrator with restricted policy privilege must be authorized to the current policy domain and to the new policy domain.

- Whether file compression is required
- Whether users can delete backed up or archived files from storage pools

For example, you can update client node TOMC to prevent him from deleting archived files from storage pools by entering:

```
update node tomc archdelete=no
```

Renaming Client Nodes

You can rename a client node if the workstation network name or host name changes.

For example, with UNIX systems, users define their ADSM node named based on the value returned by the HOSTNAME command. When users access the server, their ADSM user IDs match the host name of their workstations. If the host name changes, you can update a client node user ID to match the new host name.

For example, to rename CAROLH to ENGNODE enter:

```
rename node carolh engnode
```

ENGNODE retains the contact information and access to backup and archive data that belonged to CAROLH. All files backed up or archived by CAROLH now belong to ENGNODE.

Locking and Unlocking Client Nodes

You can prevent a client node from accessing the server and performing functions such as back up and restore or archive and retrieve. You can later let the client node reaccess the server. For example, to prevent client node MAB from accessing the server, enter:

```
lock node mab
```

To let client node MAB reaccess the server, enter:

```
unlock node mab
```

Requesting Information about Client Nodes

You can request information about client nodes. For example, as a policy administrator, you might query the server about all client nodes assigned to the policy domains for which you have authority. Or you might query the server for detailed information about one client node.

Client Nodes Assigned to Specific Policy Domains

You can display information about client nodes assigned to specific policy domains. For example, to view information about client nodes assigned to STANDARD and ENGPOLDOM policy domains, enter:

```
query node * domain=standard,engpoldom
```

The output from that command might look like this:

Node Name	Platform	Policy Domain Name	Days Since Last Access	Days Since Password Set	Locked?
DEBBYG	DOS	STANDARD	2	12	No
ENGNODE	AIX	ENGPOLDOM	<1	1	No
HTANG	OS/2	STANDARD	4	11	No
MAB	AIX	ENGPOLDOM	<1	1	No
PEASE	AIX	STANDARD	3	12	No
SSTEINER	(?)	ENGPOLDOM	<1	1	No

A Specific Client Node

You can view information about specific client nodes. For example, to review the registration parameters defined for client node PEASE, enter:

```
query node pease format=detailed
```

The resulting report would look like this:

```
Node Name: PEASE
Platform: AIX
Policy Domain Name: STANDARD
Last Access Date/Time: 02/21/1996 10:58:36
Days Since Last Access: 3
Password Set Date/Time: 02/09/1996 10:02:00
Days Since Password Set: 12
Locked?: No
Contact:
Compression: Yes
Archive Delete Allowed?: No
Backup Delete Allowed?: No
Registration Date: 02/09/1996 10:02:00
Registering Administrator: REES
Last Communication Method Used: Tcp/Ip
Bytes Received Last Session: 1,719
Bytes Sent Last Session: 602
Duration of Last Session (sec): 184.63
Pct. Idle Wait Last Session: 99.69
Pct. Comm. Wait Last Session: 0.00
Pct. Media Wait Last Session: 0.00
```

Requesting Information about File Spaces

A *file space name* identifies a group of files that are stored as a logical unit in server storage. On registered client nodes, users can define file spaces for their workstation.

On client nodes such as OS/2 or DOS, a file space name identifies a logical partition, such as the volume label of a disk drive. For example, a volume with the label XYZ is a different file space from a volume with the label ABC.

On client nodes such as AIX or SunOS, a file space name identifies a file system or file space defined by a user with the VIRTUALMOUNTPOINT option. With this option, users can define a virtual mount point for a file system to back up or archive files beginning with a specific directory or subdirectory. For information on the VIRTUALMOUNTPOINT option, refer to the appropriate *ADSM Using the Backup-Archive Client*.

You can display file space information in order to:

- Identify file spaces defined to each client node, so that you can delete each file space from the server before removing the client node from the server
- Monitor the space used on workstation's disks
- Monitor whether backups are completing successfully for the file space
- Determine the date and time of the last backup

You display file space information by identifying the client node name and file space name.

Note: File space names are case-sensitive and must be entered exactly as known to the server.

For example, to view information about file spaces defined for client node PEASE, enter:

```
query filesystem pease *
```

The following figure shows the output from this command. The report shows that client node ID PEASE:

- Has three file spaces on an AIX workstation
- Runs the *JFS* file system
- The amount of used and available space in each file space

Node Name	Filespace Name	Platform	Filespace Type	Capacity (MB)	%Util
PEASE	/home/peas-e/dir	AIX	JFS	196.0	91.7
PEASE	/home/peas-e/dir1	AIX	JFS	328.0	81.0
PEASE	/home/peas-e/dir2	AIX	JFS	46.9	96.0

Deleting File Spaces and Client Nodes

You can delete a client node from a server, but first you must delete any that client's data from server storage by deleting any file spaces belonging to the node.

Deleting a File Space

You may want to delete a file space when:

- Users are not authorized to delete backed up or archived files in storage pools

The authority to delete backed up or archived files from server storage is set when a client node is registered. See "Setting Client Node Registration" on page 265 and "Administrator Registration of Client Nodes" on page 265 for information on allowing users to delete files in storage pools.

For example, client node PEASE no longer needs archived files in file space */home/pease/dir2*. However, he does not have the authority to delete those files. You can delete them by entering:

```
delete filesystem pease /home/pease/dir2 type=archive
```

- You want to remove a client node from the server

You must delete a user's files from storage pools before you can remove a client node. For example, to delete all file spaces belonging to client node ID DEBBYG, enter:

```
delete filesystem debbyg * type=any
```

- You want to delete files belonging to a specific owner

For client nodes that support multiple users, such as UNIX, a file owner name is associated with each file on the server. The owner name is the user ID of the operating system, such as the UNIX user ID. When you delete a file space belonging to a specific owner, only files that have the specified owner name in the file space are deleted.

Removing Client Nodes

After all file spaces belonging to a client node have been deleted (see "Deleting a File Space" on page 270), you can delete the client node.

For example, to remove client node DEBBYG, enter:

```
remove node debbyg
```

Registering an Application Programming Interface to the Server

Workstation users can request ADSM services by using an application that uses the ADSM application programming interface (API). An administrator uses the REGISTER NODE command to register the workstation as an ADSM client.

Understanding How the Compression Option is Set

For applications that use the ADSM API, compression can be determined by:

- An administrator during registration who can:
 - Require that files are compressed
 - Restrict files from being compressed by the client
 - Allow the application or client user to determine the compression status

- The client options file. If an administrator does not set compression on or off, ADSM checks the compression status set in the client options file. The client options file is required, but the API user configuration file is optional.
- One of the object attributes. When an application sends an object to the server, some object attributes can be specified. One of the object attributes is a flag that indicates whether or not the data has already been compressed. If the application turns this flag on during either a backup or an archive operation, then ADSM does not compress the data a second time. This process overrides what the administrator sets during registration.

For more information on setting options for the API and on controlling compression, see *ADSM Using the Application Programming Interface*.

Understanding How the File Deletion Option is Set

For applications using the ADSM API, the file deletion option can be set by:

- An administrator during registration

If an administrator does not allow the file deletion, then an ADSM administrator must delete any objects or file spaces associated with the workstation from server storage.

If an administrator allows file deletion, then ADSM checks the client options file.
- An application using the ADSM API deletion program calls

If the application uses the **dsmDeleteObj** or **dsmDeleteFS** program call, then objects or files are marked for deletion when the application is executed.

Chapter 14. Exporting and Importing Data

ADSM provides an export-import facility that allows you to copy all or part of a server to removable media (export) so that data can be transferred to another server (import).

Task	Required Privilege Class
Perform export and import operations	System
Display information about export and import operations	Any administrator

This chapter takes you through the export and import tasks. The sections listed in the following table begin at the indicated pages.

Section	Page
Concepts:	
Data that can be exported and imported	274
Tasks:	
Preparing to export or import data	274
Monitoring export and import processes	276
Exporting data to sequential media volumes	280
Importing data from sequential media volumes	284

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Data That Can Be Exported and Imported

Administrators can export or import the following types of ADSM data:

- Server control information, which includes:
 - Administrator definitions
 - Client node definitions
 - Policy and scheduling definitions
- File data from server storage, which includes file space definitions and authorization rules. You can request that file data be exported in any of the following groupings of files:
 - Active and inactive versions of backed up files, archive copies of files, and space-managed files
 - Active versions of backed up files, archive copies of files, and space-managed files
 - Active and inactive versions of backed up files
 - Active versions of backed up files
 - Archive copies of files
 - Space-managed files

Your decision on what information to export depends on why you are exporting that information:

- To copy information to a second server to balance the workload across servers, use the EXPORT NODE, EXPORT POLICY, and EXPORT ADMIN commands. For example, when many client nodes access the same server, users contend for communication paths, server resources, and tape mounts during a restore or retrieve operation.

To relieve a server of some workload and improve its performance, you may want to take one or all of the following actions:

- Move a group of client nodes to a second server
- Move policy definitions associated with these client nodes
- Move administrator definitions for administrators who manage these client nodes

When you complete the import to the second server, you can delete file spaces, client nodes, policy objects, scheduling objects and administrators from the source server to reduce contention for server resources.

- To copy data for the purpose of installing a new server, use the EXPORT SERVER command to copy all data to sequential media volumes.

Preparing to Export or Import Data

Before you export or import data, complete the following tasks:

- Use the export or import command with the PREVIEW parameter to verify what data will be moved
- Prepare sequential media for exporting and importing data

Using Preview before Exporting or Importing Data

ADSM provides the PREVIEW option on the EXPORT and IMPORT commands. With PREVIEW=YES, the report shows how much data will be transferred without actually moving any data. With PREVIEW=NO, the export or import operation is performed.

Issue each EXPORT or IMPORT command with PREVIEW=YES to determine which objects and how much data will be moved. ADSM sends the following types of messages to the server console and to the activity log for each operation:

Export Reports the types of objects, number of objects, and number of bytes that would be copied to sequential media volumes. Use this information to determine how many sequential media volumes you need to prepare for an export operation.

Import Reports the number and types of objects found on the sequential media volumes that meet your import specifications, and reports information about any problems that it detects, such as corrupted data. Use this information to determine which data to move from sequential media volumes to the server and to determine if you have enough storage pool space allocated on the server for the import operation to succeed.

To determine how much space is required to export server definitions and all backup versions, archive copies, and space-managed files to sequential media volumes, enter:

```
export server filedata=all preview=yes
```

After you issue this command, the server starts a background process and issues a message similar to the following:

```
EXPORT SERVER started as Process 4
```

You can view the preview results on the server console and by querying the activity log.

You can request information about the background process, as described in “Requesting Information about an Export or Import Process” on page 277. If necessary, you can cancel an export or import process, as described in “Canceling Server Processes” on page 223.

Planning for Sequential Media Used to Export Data

To export data, you must specify a device class that supports sequential media and identify the volumes that will be used to store the exported data. Use this section to help you select the device classes and prepare sequential media volumes.

Selecting a Device Class

You can query the source and the target servers about device classes to select a device class on each server that supports the same device type. If you cannot find a

device class on each server that supports a like device type, then define a new device class for a device type that is available to both servers. See Chapter 6, “Defining Device Classes” on page 69.

Note: If the mount limit for the device class selected is reached when you request an export (that is, if all the drives are busy), ADSM automatically cancels lower priority operations, such as reclamation, to make a mount point available for the export.

Estimating the Number of Tapes to Label

To estimate the number of tapes required to store export data, divide the number of bytes to be moved by the estimated capacity of a volume.

For example, cartridge system tape volumes used with 3490 tape devices have an estimated capacity of 360MB. If the preview shows that you need to transfer 720MB of data, then label at least two tape volumes before you export the data.

Using Scratch Media

ADSM allows you to use scratch media to ensure that you have sufficient space on which to store all export data. If you use scratch media, be sure to record their label names and the order in which they were mounted.

Labeling Tapes

During an import process, you must specify the order in which tape volumes will be mounted. This order must match the order in which tapes have been mounted during the export process.

To ensure that tapes are mounted in the correct order, label tapes with information that identifies the order in which they are mounted during the import process. For example, label tapes as DSM001, DSM002, DSM003, and so on to indicate the order in which data is stored on the tape volumes.

When you export data, record the date and time for each labeled volume. Store this information in a safe location, because you will need the information when you import the data to the server.

Monitoring Export and Import Processes

ADSM provides you with a number of methods for monitoring export or import processes.

- You can view information about a process that is running on the server console or from an administrative client running in console mode.
- You can query the activity log for status information when a process has completed, from the server console or from an administrative client running in batch or interactive mode.

Requesting Information about an Export or Import Process

After you issue an EXPORT or IMPORT command, the server starts a background process, assigns a process ID to the operation, and displays the process ID when the operation starts.

You can query an export or import process by specifying the process ID number. For example, to request information about the EXPORT SERVER operation, which started as process 4, enter:

```
query process 4
```

If you issue a preview version of an EXPORT or IMPORT command and then query the process, ADSM reports the types of objects to be copied, the number of objects to be copied, and the number of bytes to be copied.

When you export or import data and then query the process, ADSM displays the number and types of objects copied so far, and the total number of bytes that have been transferred, along with information on any media mount requests that may be outstanding for the process.

For guidance information on querying background processes, see “Requesting Information about Server Processes” on page 223.

Viewing Information from the Server Console

When you issue an IMPORT or EXPORT command, either from the server console or from an administrative client, information is displayed on the server console. Figure 67 on page 278 shows an example of the information that is displayed after issuing an EXPORT SERVER command.

```

ANR0610I EXPORT SERVER started by SERVER_CONSOLE as process 1.
ANR0639I EXPORT SERVER: Processing domain ENGPOLDOM.
ANR0640I EXPORT SERVER: Processing policy set ACTIVE in policy domain
ENGPOLDOM.
ANR0640I EXPORT SERVER: Processing policy set STANDARD in policy domain
ENGPOLDOM.
ANR0641I EXPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set ACTIVE.
ANR0641I EXPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set STANDARD.
ANR0643I EXPORT SERVER: Processing archive copy group in domain
ENGPOLDOM, set STANDARD, management class ACTIVE.
ANR0643I EXPORT SERVER: Processing archive copy group in domain
ENGPOLDOM, set STANDARD, management class STANDARD.
ANR0643I EXPORT SERVER: Processing backup copy group in domain
ENGPOLDOM, set STANDARD, management class ACTIVE.
ANR0643I EXPORT SERVER: Processing backup copy group in domain
ENGPOLDOM, set STANDARD, management class STANDARD.
ANR0604I EXPORT SERVER: No schedules were found in policy domain * for
exporting.
ANR0635I EXPORT SERVER: Processing node TOMC.
ANR0605I EXPORT SERVER: No schedule associations were found in
policy domain * for exporting.
ANR0637I EXPORT SERVER: Processing file space DRIVED for node TOMC.
ANR0637I EXPORT SERVER: Processing file space OS2 for node TOMC.
ANR0637I EXPORT SERVER: Processing file space OS2VDISK for node TOMC.
ANR0617I EXPORT SERVER: Processing completed successfully.
ANR0620I EXPORT SERVER: Copied 1 domain(s).
ANR0621I EXPORT SERVER: Copied 2 policy set(s).
ANR0622I EXPORT SERVER: Copied 2 management class(es).
ANR0623I EXPORT SERVER: Copied 4 copy group(s).
ANR0626I EXPORT SERVER: Copied 1 node definition(s).
ANR0627I EXPORT SERVER: Copied 3 file space(s), 16 archive file(s)
and 0 backup file(s).
ANR0629I EXPORT SERVER: Copied 3045632 bytes of data.
ANR0611I EXPORT SERVER started by SERVER_CONSOLE as process 1 has ended.

```

Figure 67. Sample Export Server Output Sent to the Server Console

Viewing Information from an Administrative Client

Use the console mode from an administrative client to monitor export or import operations or to capture processing messages to an output file. For example, to start an administrative session in console mode on an OS/2 client, enter:

```
> dsmadm -consolemode
```

While the system is running in console mode, you cannot enter any administrative commands from the client session. You can, however, start another administrative client session for entering commands (for example, QUERY PROCESS) if you are using a multitasking workstation, such as OS/2 or AIX.

If you want ADSM to write all terminal output to a file, specify the `OUTFILE` option with a destination. For example, to write output to the `SAVE.OUT` file, enter:

```
> dsmadmc -consolemode -outfile=save.out
```

For information about using the `CONSOLE` mode option and ending an administrative session in console mode, see *ADSM Administrator's Reference*.

Querying the Activity Log for Export or Import Information

After an export or import process has completed, you can query the activity log for status information and possible error messages.

To minimize processing time when querying the activity log for export or import information, restrict the search by specifying *export* or *import* in the `SEARCH` parameter of the `QUERY ACTLOG` command.

For example, to determine how much data will be moved after issuing the preview version of the `EXPORT SERVER` command, query the activity log by entering:

```
query actlog search=export
```

Figure 68 on page 280 displays a sample activity log report.

Date/Time	Message
05/03/1995 10:50:28	ANR0610I EXPORT SERVER started by ADSMADMIN as process 1.
05/03/1995 10:50:28	ANR0639I EXPORT SERVER: Processing domain ENGPOLDOM.
05/03/1995 10:50:28	ANR0640I EXPORT SERVER: Processing policy set ACTIVE in policy domain ENGPOLDOM.
05/03/1995 10:50:28	ANR0640I EXPORT SERVER: Processing policy set STANDARD in policy domain ENGPOLDOM.
05/03/1995 10:50:29	ANR0641I EXPORT SERVER: Processing management class STANDARD in domain ENGPOLDOM, set ACTIVE.
05/03/1995 10:50:29	ANR0641I EXPORT SERVER: Processing management class STANDARD in domain ENGPOLDOM, set STANDARD.
05/03/1995 10:50:29	ANR0643I EXPORT SERVER: Processing archive copy group in domain ENGPOLDOM, set STANDARD, management class ACTIVE.
05/03/1995 10:50:29	ANR0643I EXPORT SERVER: Processing archive copy group in domain ENGPOLDOM, set STANDARD, management class STANDARD.
05/03/1995 10:50:29	ANR0642I EXPORT SERVER: Processing backup copy group in domain ENGPOLDOM, set STANDARD, management class ACTIVE.
05/03/1995 10:50:29	ANR0642I EXPORT SERVER: Processing backup copy group in domain ENGPOLDOM, set STANDARD, management class STANDARD.
05/03/1995 10:50:29	ANR0604I EXPORT SERVER: No schedules were found in policy domain * for exporting.
05/03/1995 10:50:29	ANR0635I EXPORT SERVER: Processing node TOMC.
05/03/1995 10:50:29	ANR0605I EXPORT SERVER: No schedule associations were found in policy domain * for exporting.
05/03/1995 10:50:29	ANR0637I EXPORT SERVER: Processing file space DRIVED for node TOMC.
05/03/1995 10:50:29	ANR0637I EXPORT SERVER: Processing file space OS2 for node TOMC.
05/03/1995 10:50:29	ANR0637I EXPORT SERVER: Processing file space OS2VDISK for node TOMC.
05/03/1995 10:50:32	ANR0617I EXPORT SERVER: Processing completed successfully.
05/03/1995 10:50:32	ANR0620I EXPORT SERVER: Copied 1 domain(s).
05/03/1995 10:50:32	ANR0621I EXPORT SERVER: Copied 2 policy set(s).
05/03/1995 10:50:32	ANR0622I EXPORT SERVER: Copied 2 management class(es).
05/03/1995 10:50:32	ANR0623I EXPORT SERVER: Copied 4 copy group(s).
05/03/1995 10:50:32	ANR0626I EXPORT SERVER: Copied 1 node definition(s).
05/03/1995 10:50:32	ANR0627I EXPORT SERVER: Copied 3 file space(s), 16 export file(s) and 0 backup file(s).
05/03/1995 10:50:32	ANR0629I EXPORT SERVER: Copied 3045632 bytes of data.
05/03/1995 10:50:32	ANR0611I EXPORT SERVER started by ADSMADMIN as process 1 has ended.

Figure 68. Sample Activity Log Report on Exported Data

Exporting Data to Sequential Media Volumes

You can export all server control information or a subset of server control information by specifying one or more of the following export commands:

- EXPORT SERVER
- EXPORT ADMIN
- EXPORT NODE
- EXPORT POLICY

When you export data, you must specify the device class to which export data can be written. You must also list the volumes in the order in which they are mounted when the data is imported. See “Labeling Tapes” on page 276 for information on labelling tape volumes.

Deciding When to Export Data

When you issue an EXPORT command, the operation runs as a background process. This process allows you to continue performing administrative tasks. In addition, users can continue to back up, archive, migrate, restore, retrieve, or recall files from ADSM.

If you choose to perform an export operation during normal working hours, be aware that administrators can change server definitions and users may modify files that are in server storage. If administrators or users modify data shortly after it has been exported, then the information copied to tape may not be consistent with data stored on the source server.

If you want to export an exact point-in-time copy of server control information, you can prevent administrative and other client nodes from accessing the server. See “Preventing Administrative Clients from Accessing the Server” and “Preventing Client Nodes from Accessing the Server.”

Preventing Administrative Clients from Accessing the Server

Administrators can change administrator, policy, or client node definitions during an export process. To prevent administrators from modifying these definitions, you can lock out administrator access to the server and cancel any administrative sessions before issuing an EXPORT command. After the export process is complete, unlock administrator access.

For more information on canceling sessions, see “Canceling a Client Session” on page 221. For more information on locking or unlocking administrators from the server, see “Locking and Unlocking Administrators from the Server” on page 263.

Preventing Client Nodes from Accessing the Server

If client node information is exported while the same client is backing up, archiving, or migrating files, the latest file copies for the client may not be exported to tape. To prevent users from accessing the server during export operations, cancel existing client sessions as described in “Canceling a Client Session” on page 221. Then you can do one of the following:

- Disable server access to prevent client nodes from accessing the server, as described in “Disabling or Enabling Server Access” on page 221.

This option is useful when you export all client node information from the source server and want to prevent all client nodes from accessing the server.

- Lock out particular client nodes from server access, as described in “Locking and Unlocking Client Nodes” on page 267.

This option is useful when you export a subset of client node information from the source server and want to prevent particular client nodes from accessing the server until the export operation is complete.

After the export operation is complete, allow client nodes to access the server again by:

- Enabling the server, as described in “Disabling or Enabling Server Access” on page 221.
- Unlocking client nodes, as described in “Locking and Unlocking Client Nodes” on page 267

Exporting Server Data

When you issue the EXPORT SERVER command, the server exports all server control information. You can also export file data information with the EXPORT SERVER command.

For example, you want to export definitions and all file data to four defined tape cartridges, which are supported by the CARTRIDGE device class. You want ADSM to use scratch volumes if the four volumes are not enough, and so you use the default of SCRATCH=YES. To issue this command, enter:

```
export server devclass=cartridge  
volumenames=dsm001,dsm002,dsm003,dsm004 filedata=all
```

During the export process, ADSM exports definition information before it exports file data information. This ensures that definition information is stored on the first tape volumes. This process allows you to mount a minimum number of tapes during the import process, if your goal is to copy only control information to the target server.

In the example above, the server exports:

- Administrator definitions
- Client node definitions
- Policy domain, policy set, management class, and copy group definitions
- Schedule definitions and client node associations
- File space definitions
- File space authorization rules
- Backed up, archived, and space-managed files

Exporting Administrator Information

When you issue the EXPORT ADMIN command, the server exports administrator definitions. Each administrator definition includes:

- Administrator name, password and contact information
- Any administrative privilege classes the administrator has been granted
- Whether the administrator ID is locked from server access

You can specify a list of administrator names, or you can export all administrator names from the server to tape volumes.

In the following example, definitions for the DAVEHIL and PENNER administrator IDs will be exported to the DSM001 tape volume, which is supported by the CARTRIDGE device class. Do not allow any scratch media to be used during this export process. To issue this command, enter:

```
export admin davehil,penner devclass=cartridge
volumenames=dsm001 scratch=no
```

Exporting Client Node Information

When you issue the EXPORT NODE command, the server exports client node definitions. Each client node definition includes:

- User ID, password, and contact information
- Name of the policy domain to which the client is assigned
- File compression status
- Whether the user has the authority to delete backed up or archived files from server storage
- Whether the client node ID is locked from server access

Optionally, you can specify whether to export file data. File data includes file space definitions and authorization rules. You can request that file data be exported in any of the following groupings of files:

- Active and inactive versions of backed up files, archive copies of files, and space-managed files
- Active versions of backed up files, archive copies of files, and space-managed files
- Active and inactive versions of backed up files
- Active versions of backed up files
- Archive copies of files
- Space-managed files

When client file data is exported, ADSM copies files to export volumes in the order of their physical location in server storage. This process minimizes the number of mounts required during the export process.

If you do not explicitly specify that you want to export file data, then ADSM only exports client node definitions.

For example, suppose you want to do the following:

- Export definitions for client nodes and file spaces in the ENGPOLDOM policy domain
- Export any active backup versions of files belonging to these client nodes
- Export this information to scratch volumes in the CARTRIDGE device class

To issue this command, enter:

```
export node filespace=* domains=engpoldom
filedata=backupactive devclass=cartridge
```

In this example, the server exports:

- Definitions of client nodes assigned to the engineering policy domain
- File space definitions and backup authorizations for each client node in the engineering policy domain
- Active versions of backed up files belonging to the client nodes assigned to the engineering policy domain

Exporting Policy Information

When you issue the EXPORT POLICY command, the server exports the following information belonging to each specified policy domain:

- Policy domain definitions
- Policy set definitions, including the active policy set
- Management class definitions, including the default management class
- Backup copy group and archive copy group definitions
- Schedule definitions
- Associations between client nodes and schedules

For example, suppose you want to export policy and scheduling definitions from the policy domain named ENGPOLDOM. You want to use tape volumes DSM001 and DSM002, which belong to the CARTRIDGE device class, but allow the server to use scratch tape volumes if necessary. To issue this command, enter:

```
export policy engpoldom
devclass=cartridge volumenames=dsm001,dsm002
```

Importing Data from Sequential Media Volumes

Before you import data to a new target server, you must:

1. Install ADSM on the target server. This step includes defining disk space for the database and recovery log.

For information on installing ADSM, see *ADSM Quick Start*.

2. Define server storage for the target server.

Because each server operating system handles devices differently, ADSM does not export server storage definitions. Therefore, you must define initial server storage for the target server. ADSM must at least be able to use a drive that is compatible

with the export media. This task can include defining libraries, drives, device classes, storage pools, and volumes. See the *ADSM Administrator's Guide* that applies to the target server.

After ADSM is installed and set up on the target server, a system administrator can import all server control information or a subset of server control information by specifying one or more of the following import commands:

- IMPORT SERVER
- IMPORT ADMIN
- IMPORT NODE
- IMPORT POLICY

This section guides you through the entire process of importing all server control information and file data from tape volumes to a new target server. This process includes:

- Previewing information before you import data
- Importing definitions
- Tailoring server storage definitions on the target server
- Importing file data

After you understand how to import server control information and file data information, you can import any subset of data to the target server.

Step 1: Previewing Information before You Import Data

Before you import any data to the target server, preview each import command to determine what data you want to import to the target server. You can import all or a subset of export data from tapes.

When you set `PREVIEW=YES`, tape operators must mount export tape volumes so that the target server can calculate the statistics reported by the use of this parameter.

For example, to preview information for the `IMPORT SERVER` command, enter:

```
import server devclass=cartridge preview=yes
volumenames=dsm001,dsm002,dsm003,dsm004
```

Figure 69 on page 286 shows an example of the messages sent to the server console and the activity log.

```

ANR0402I Session 3 started for administrator SERVER_CONSOLE (Server).
ANR1363I Import volume DSM001 opened (sequence number 1).
ANR0610I IMPORT SERVER started by SERVER_CONSOLE as process 2.
ANR0612I IMPORT SERVER: Reading EXPORT SERVER data from server ADSM exported
05/07/1995 12:39:48.
ANR0639I IMPORT SERVER: Processing domain ENGPOLDOM.
ANR0640I IMPORT SERVER: Processing policy set ACTIVE in policy domain
ENGPOLDOM.
ANR0640I IMPORT SERVER: Processing policy set STANDARD in policy domain
ENGPOLDOM.
ANR0641I IMPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set ACTIVE.
ANR0641I IMPORT SERVER: Processing management class MCENG in domain
ENGPOLDOM, set STANDARD.
ANR0641I IMPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set STANDARD.
ANR0643I IMPORT SERVER: Processing archive copy group in domain
ENGPOLDOM, set ACTIVE, management class STANDARD.
ANR0643I IMPORT SERVER: Processing archive copy group in domain ENGPOLDOM,
set STANDARD, management class MCENG.
ANR0643I IMPORT SERVER: Processing archive copy group in domain ENGPOLDOM,
set STANDARD, management class STANDARD.
ANR0642I IMPORT SERVER: Processing backup copy group in domain ENGPOLDOM,
set ACTIVE, management class STANDARD.
ANR0642I IMPORT SERVER: Processing backup copy group in domain ENGPOLDOM,
set STANDARD, management class MCENG.
ANR0642I IMPORT SERVER: Processing backup copy group in domain ENGPOLDOM,
set STANDARD, management class STANDARD.
ANR0638I IMPORT SERVER: Processing administrator DAVEHIL.
ANR0638I IMPORT SERVER: Processing administrator PENNER.
ANR0635I IMPORT SERVER: Processing node TOMC.
ANR0636I IMPORT SERVER: Processing file space OS2 for node TOMC as file
space OS1.
ANR0636I IMPORT SERVER: Processing file space DRIVED for node TOMC as file
space DRIVE1.
ANR0636I IMPORT SERVER: Processing file space OS2VDISK for node TOMC as file
space OS2VDIS1.
ANR1365I Import volume DSM001 closed (end reached).
ANR1363I Import volume DSM002 opened (sequence number 2).
ANR1365I Import volume DSM002 closed (end reached).
ANR1363I Import volume DSM003 opened (sequence number 3).
ANR1365I Import volume DSM003 closed (end reached).
ANR1363I Import volume DSM004 opened (sequence number 4).
ANR1365I Import volume DSM004 closed (end reached).
ANR0617I IMPORT SERVER: Processing completed successfully.
ANR0620I IMPORT SERVER: Copied 1 domain(s).
ANR0621I IMPORT SERVER: Copied 2 policy set(s).
ANR0622I IMPORT SERVER: Copied 2 management class(es).
ANR0623I IMPORT SERVER: Copied 6 copy group(s).
ANR0625I IMPORT SERVER: Copied 2 administrator(s).
ANR0626I IMPORT SERVER: Copied 1 node definition(s).
ANR0627I IMPORT SERVER: Copied 3 file space(s), 0 archive file(s) and 462
backup file(s).
ANR0629I IMPORT SERVER: Copied 8856358 bytes of data.
ANR0611I IMPORT SERVER started by SERVER_CONSOLE as process 2 has ended.

```

Figure 69. Sample Report Created by Issuing Preview for an Import Server Command

Use the value reported for the total number of bytes copied to estimate if you have sufficient storage pool space on the server to store imported file data.

For example, Figure 69 shows that 8 856 358 bytes of data will be imported. Ensure that you have at least 8 856 358 bytes of available space in the backup storage pools defined to the server. You can use the `QUERY STGPOOL` and `QUERY VOLUME` commands to determine how much space is available in the server storage hierarchy.

In addition, the preview report shows that 0 archive files and 462 backup files will be imported. Because backup data is being imported, ensure that you have sufficient space in the backup storage pools used to store this backup data. See “Step 3: Tailoring Server Storage Definitions on the Target Server” on page 289 for information on identifying storage pools on the target server.

For information on specifying the `PREVIEW` parameter, see “Using Preview before Exporting or Importing Data” on page 275. For information on reviewing the results of a preview operation, see “Monitoring Export and Import Processes” on page 276.

Step 2: Importing Definitions

Next, you want to import server control information, which includes:

- Administrator definitions
- Client node definitions
- Policy domain, policy set, management class, and copy group definitions
- Schedule definitions and client node associations

However, do not import file data at this time, because some storage pools named in the copy group definitions may not exist yet on the target server.

Before you import server control information, do the following:

- Read and understand the following information:
 - “Determining Whether to Replace Existing Definitions”
 - “Understanding How ADSM Imports Active Policy Sets” on page 288
- Start an administrative client session in console mode to capture import messages to an output file. See “Directing Import Messages to an Output File” on page 288.

Then import the server control information from specified tape volumes. See “Importing Server Control Information” on page 289.

Determining Whether to Replace Existing Definitions

By using the `REPLACEDFS` option, you can specify whether to replace existing definitions on the target server when ADSM encounters an object with the same name during the import process.

For example, if a definition exists for the `ENGPOLDOM` policy domain on the target server before you import policy definitions, then you must specify `REPLACEDFS=YES` to have ADSM replace the existing definition with the data from the export tape.

Definitions that can be replaced include administrator, client node, policy, or schedule definitions. The default is to not replace existing definitions on the target server.

Understanding How ADSM Imports Active Policy Sets

When ADSM imports policy definitions, the following objects are imported to the target server:

- Policy domain definitions
- Policy set definitions, including the ACTIVE policy set
- Management class definitions
- Backup copy group definitions
- Archive copy group definitions
- Schedule definitions defined for each policy domain
- Client node associations, if the client node definition exists on the target server

If ADSM encounters a policy set named ACTIVE on the tape volume during the import process, it uses a temporary policy set named `$$ACTIVE$$` to import the active policy set.

After `$$ACTIVE$$` is imported to the target server, ADSM activates this policy set. During the activation process, the server validates the policy set by examining the management class and copy group definitions.

ADSM reports on the following conditions, which result in warning messages during validation:

- The storage destinations specified in the backup copy groups and the archive copy groups do not refer to defined storage pools.
- The default management class does not contain a backup or archive copy group.
- The current ACTIVE policy set contains management class names that are not defined in the policy set to be activated.
- The current ACTIVE policy set contains copy group names that are not defined in the policy set to be activated.

After each `$$ACTIVE$$` policy set has been activated, ADSM deletes that `$$ACTIVE$$` policy set from the target server. To view information about active policy on the target server, you can use the following commands:

- `QUERY COPYGROUP`
- `QUERY MGMTCLASS`
- `QUERY POLICYSET`

Results from issuing the `QUERY DOMAIN` command show the activated policy set as `$$ACTIVE$$`. ADSM uses the `$$ACTIVE$$` name to show you that the policy set which is currently activated for this domain is the policy set that was active at the time the export was performed.

Directing Import Messages to an Output File

The information generated by the validation process can help you define a storage hierarchy that supports the storage destinations currently defined in the import data.

You can direct import messages to an output file to capture any error messages that are detected during the import process by starting an administrative client session in console mode before you invoke this import command.

For example, to direct messages to an output file named IMPSERV.OUT, enter:

```
> dsmadm -consolemode -outfile=impserv.out
```

Importing Server Control Information

Now you are ready to import the server control information. Based on the information generated during the preview operation, you know that all definition information has been stored on the first tape volume named DSM001. Specify that this tape volume can be read by a device belonging to the CARTRIDGE device class.

From an administrative client session or from the server console, enter:

```
import server filedata=none devclass=cartridge  
volumenames=dsm001
```

Step 3: Tailoring Server Storage Definitions on the Target Server

After you import definition information, use the reports generated by the import process to help you tailor storage for the target server.

To tailor server storage definitions on the target server, complete the following steps:

1. Identify any storage destinations specified in copy groups and management classes that do not match defined storage pools:
 - If the policy definitions you imported included an ACTIVE policy set, that policy set is validated and activated on the target server. Error messages generated during validation include whether any management classes or copy groups refer to storage pools that do not exist on the target server. You have a copy of these messages in a file if you directed console messages to an output file as described in “Directing Import Messages to an Output File” on page 288.
 - Query management class and copy group definitions to compare the storage destinations specified with the names of existing storage pools on the target server.

To request detailed reports for all management classes, backup copy groups, and archive copy groups in the ACTIVE policy set, enter these commands:

```
query mgmtclass * active * format=detailed
query copygroup * active * standard type=backup format=detailed
query copygroup * active * standard type=archive format=detailed
```

2. If storage destinations for management classes and copy groups in the ACTIVE policy set refer to storage pools that are not defined, do one of the following:
 - Define storage pools that match the storage destination names for the management classes and copy groups, as described in “Defining or Updating Storage Pools” on page 110.
 - Change the storage destinations for the management classes and copy groups. Do the following:
 - a. Copy the ACTIVE policy set to another policy set
 - b. Modify the storage destinations of management classes and copy groups in that policy set, as required
 - c. Activate the new policy set

For information on copying policy sets, see “Defining and Updating a Policy Set” on page 173.

Depending on the amount of client file data that you expect to import, you may want to examine the storage hierarchy to ensure that sufficient storage space is available. Storage pools specified as storage destinations by management classes and copy groups may fill up with data. For example, you may need to define additional storage pools to which data can migrate from the initial storage destinations.

Step 4: Importing File Data Information

After you have defined the appropriate storage hierarchy on the target server, you can import file data from the tape volumes. File data includes file space definitions and authorization rules. You can request that file data be imported in any of the following groupings of files:

- Active and inactive versions of backed up files, archive copies of files, and space-managed files
- Active versions of backed up files, archive copies of files, and space-managed files
- Active and inactive versions of backed up files
- Active versions of backed up files
- Archive copies of files
- Space-managed files

Before you import file data information:

- Understand how ADSM handles duplicate file space names

- Decide whether to keep the original creation date for backup versions and archive copies or to import file data using an adjusted date.

Then you can import file data to the target server.

Understanding How Duplicate File Spaces Are Handled

When ADSM imports file data information, it imports any file spaces belonging to each specified client node. If a file space definition already exists on the target server for the node, ADSM does *not* replace the existing file space name.

If ADSM encounters duplicate file space names when it imports file data information, it creates a new file space name for the imported definition by replacing the final character or characters with a number. A message showing the old and new file space names is written to the server console and to the activity log.

For example, if the C_DRIVE and D_DRIVE file space names reside on the target server for node FRED and on the tape volume for FRED, then the server imports the C_DRIVE file space as C_DRIV1 file space and the D_DRIVE file space as D_DRIV1 file space, both assigned to node FRED.

Deciding Whether to Use a Relative Date When Importing File Data

When you import file data, you can keep the original creation date for backup versions and archive copies, or you can specify that ADSM use an adjusted date.

Because tape volumes containing exported data might not be used for some time after the export operation that created them, the original dates defined for backup versions and archive copies may be old enough that files are expired immediately by policy when the data is imported to the target server.

To prevent backup versions and archive copies from being expired immediately, specify DATES=RELATIVE on the IMPORT NODE or IMPORT SERVER commands to adjust for the elapsed time since the files were exported to tape.

For example, assume that data exported to tape includes an archive copy archived five days prior to the export operation. If the tape volume resides on the shelf for six months before the data is imported to the target server, ADSM resets the archival date to five days prior to the import operation.

If you want to keep the original backup and archive dates set for backup versions and archive copies, then use DATES=ABSOLUTE, which is the default. If you use the absolute value, then any files whose retention period has passed will be expired shortly after they are imported to the target server.

Issuing an Import Server or Import Node Command

You can import file data, either by issuing the IMPORT SERVER or IMPORT NODE command. When you issue either of these commands, you can specify which type of files should be imported for all client nodes specified and found on the export tapes.

You can specify any of the following values to import file data:

All

Specifies that all active and inactive versions of backed up files, archive copies of files, and space-managed files for specified client nodes are imported to the target server

None

Specifies that no files are imported to the target server; only client node definitions are imported

Archive

Specifies that only archive copies of files are imported to the target server

Backup

Specifies that only backup copies of files, whether active or inactive, are imported to the target server

Backupactive

Specifies that only active versions of backed up files are imported to the target server

Allactive

Specifies that only active versions of backed up files, archive copies of files, and space-managed files are imported to the target server

Spacemanaged

Specifies that only files that have been migrated from a user's local file system (space-managed files) are imported

For example, suppose you want to import all backup versions of files, archive copies of files, and space-managed files to the target server. You do not want to replace any existing server control information during this import operation. Specify the four tape volumes that were identified during the preview operation. These tape volumes can be read by any device in the CARTRIDGE device class. To issue this command, enter:

```
import server filedata=all replacedefs=no
devclass=cartridge volumenames=dsm001,dsm002,dsm003,dsm004
```

Considerations When Importing Data

You can use an import command to copy a subset of the information on export tapes to the target server. For example, if a tape was created with EXPORT SERVER, you can import only node information from the tape by using IMPORT NODE.

While ADSM allows you to issue any import command, data cannot be imported to the server if it has not been exported to tape. For example, if a tape is created with the EXPORT POLICY command, an IMPORT NODE command will not find any data on the tape because node information is not a subset of policy information.

Table 9 on page 293 shows the commands you can use to import a subset of exported information to a target server.

Table 9. Importing a Subset of Information from Tapes

If tapes were created with this export command:	You can issue this import command:	You cannot issue this import command:
EXPORT SERVER	IMPORT SERVER IMPORT ADMIN IMPORT NODE IMPORT POLICY	—
EXPORT NODE	IMPORT NODE IMPORT SERVER	IMPORT ADMIN IMPORT POLICY
EXPORT ADMIN	IMPORT ADMIN IMPORT SERVER	IMPORT NODE IMPORT POLICY
EXPORT POLICY	IMPORT POLICY IMPORT SERVER	IMPORT ADMIN IMPORT NODE

Recovering from Errors during the Import Process

During import processing, the server may encounter invalid data due to corruption during storage on tape or in the database prior to the export operation. If invalid data is encountered during an import operation, the server does the following:

- If a new object is being defined, the default value is used
- If the object already exists, the existing parameter is not changed

The server reports on the affected objects to the server console and the activity log during import and export operations. You should query these objects when the import process is complete to see if they reflect information that is acceptable to you.

Each time you run the IMPORT NODE or IMPORT SERVER command with the FILEDATA parameter equal to a value other than NONE, ADSM creates a new file space and imports data to it. This process ensures that the current import does not overwrite data from a previous import. For information on how ADSM handles duplicate file spaces, see “Understanding How Duplicate File Spaces Are Handled” on page 291.

A file space definition may already exist on the target server for the node. If so, an administrator with system privilege can issue the DELETE FILESPACE command to remove file spaces that are corrupted or no longer needed. For more information on the DELETE FILESPACE command, refer to the *ADSM Administrator's Reference*.

Renaming a File Space

An imported file space can have the same name as a file space that already exists on a client node. In this case, the server does not overlay the existing file space, and the imported file space is given a new system generated file space name. This new name may match file space names that have not been backed up and are unknown to the server. In this case, you can use the RENAME FILESPACE command to rename the imported file space to the naming convention used for the client node.

Part 6. Protecting the Server

Chapter 15. Protecting and Recovering Your Data

If your ADSM database or recovery log are unusable, the entire ADSM server is unavailable. Failure, damage, or loss of the database, recovery log, or storage pools can cause the unrecoverable loss of client data. If a storage pool volume is lost and cannot be recovered, any client data on the volume is also lost. This chapter describes how ADSM can guard against these situations and helps you to choose the method that is best for your installation. The term *tape* is used often in the following descriptions. It refers to any kind of sequential access, removable media.

The sections listed in the following table begin on the indicated pages.

Section	Page
Concepts:	
Levels of data protection provided by ADSM	297
Protecting Data:	
How to back up storage pools	302
How to mirror the database and recovery log	302
How to back up the database	306
Recovering Data	
How to recover the database and recovery log from mirrored copies	314
How to recover the database from backups	314
How to recover damaged files	314
Backup and recovery scenarios	322

In this chapter, most examples illustrate how to perform tasks by using the ADSM command line interface. For information about the ADSM commands, see *ADSM Administrator's Reference*, or issue the HELP command from the command line of an ADSM administrative client.

Appendix A, "Interface Cross-Reference" on page 329 lists each command and shows if its function is also available on the administrative client GUI.

Levels of Protection

ADSM provides various methods for protecting ADSM data. For the most comprehensive coverage, they should be used together. They are:

- Storage pool backup
- Database and recovery log mirroring
- Database backup

This section describes each method and presents the benefits and costs of each.

Attention: ADSM Version 1 provided database salvage commands to re-establish the server database if a catastrophic error occurred. Although these commands are still available, the Version 2 database backup and recovery functions replace them and should be used to ensure the best level of protection for your server. Database salvage commands involve a lengthy process. You should not use them without help from your IBM service representative.

Storage Pool Protection

ADSM stores client data on volumes in storage pools. If one or more storage pool volumes is lost or damaged, the client data may be permanently lost. However, you can back up random or sequential access pools to sequential access copy storage pools and move the volumes offsite. Then if data is lost or damaged, you can restore individual volumes or entire storage pools from the data in the copy storage pools.

Database and Recovery Log Protection

In addition to all the information about your ADSM system, the database contains information (including pointers) about all the client data in your storage pools. The recovery log contains records of changes to the database. If you lose the recovery log, you lose the changes that have been made since the last database backup. If you lose the database, you lose all your client data.

You have several ways to protect this information:

- Mirror the database, or the recovery log, or both
- Back up the database to tape
- Back up the database to tape and in the recovery log save all the changes made to the database since that backup (this is called *roll-forward* mode).

Mirroring

You can prevent the loss of the database or recovery log due to a hardware failure, by mirroring them. Mirroring writes the same data to multiple disks simultaneously. However, mirroring does not protect against a disaster or a hardware failure that affects multiple drives or causes the loss of the entire system. While ADSM is running, you can dynamically start or stop mirroring and change the capacity of the database.

ADSM mirroring provides the following benefits:

- Protection against database and recovery log media failures
- Uninterrupted ADSM operations if a database or recovery log volume fails.
- Avoidance of costly database recoveries

However, there are also costs:

- Mirroring doubles the required DASD for the mirrored volumes.
- Mirroring results in decreased performance

Database Backup

ADSM can perform full and incremental backups of the database to tape while the server is running and available to clients. With ADSM in *normal* mode, the backup media can then be stored onsite or offsite and can be used to recover the database up to the point of the backup. You can run full or incremental backups as often as needed to ensure that the database can be restored to an acceptable point in time.

Note: You can run up to 32 incremental backups between full backups.

You can provide even more complete protection if you specify that ADSM run in *roll-forward* mode. With ADSM in *roll-forward* mode and with an intact recovery log, you can recover the database up to its most current state (the point at which the database was lost).

For the fastest recovery time and greatest availability of the database, mirror both the database and recovery log and periodically back up the database. When operating in roll-forward mode, mirroring better ensures that you have an intact recovery log, which is necessary to restore the database to its most current state.

Normal Mode versus Roll-Forward Mode: Roll-forward mode offers the highest level of protection for your data. However, there are costs to roll-forward mode. The following table describes the protection afforded by each mode and the requirements for each mode.

Level of Protection	
Normal Mode	Roll-forward Mode
Recover to a point in time of the latest full or incremental backup only	Recover to a point in time of the latest full or incremental backup or, with an intact recovery log, to the most current state
Recover with loss of client data that has been: <ul style="list-style-type: none">• Backed up since the last database backup.• Moved due to storage pool migration, reclamation, or move data operations since the last database backup and then overwritten.	With an intact recovery log, recover to the most current state with no loss of client data
You must restore the entire database even if only one volume is damaged.	You can restore a single volume
	Preferable if the server supports HSM clients (space-managed files should be protected as fully as possible from hardware failure)

Storage Requirements

Normal Mode	Roll-forward Mode
Does not require a recovery log to restore to a point in time. The recovery log keeps only uncommitted transactions, and its size is not affected by normal mode.	Requires an intact recovery log to restore to the most current state. The recovery log keeps all transactions since the last database backup. In roll-forward mode you should significantly increase the recovery log size. However: <ul style="list-style-type: none"> • Frequent database backups reduce recovery log storage requirements (after a backup is completed, recovery log records preceding the backup are deleted). • Mirroring the recovery log requires much less space than mirroring the database.
For the greatest availability, you should mirror the database and recovery log or place them on devices that guarantee availability.	You should mirror the recovery log to recover to the most current state. <p>Note: Unlike mirroring the database, roll-forward recovery does not provide continuous operations after a media failure. This is because the database must be brought down to perform the recovery.</p>

The following table compares four typical ADSM data recovery configurations, two for roll-forward mode and two for normal mode. In all four cases, the storage pools and the database are backed up. The benefits and costs are:

Mirroring	Whether the database and recovery log are mirrored. Mirroring costs additional disk space.
Coverage	How completely you can recover your data. Roll-forward recovery cannot be done if the recovery log is not intact. However, roll-forward mode does support point-in-time recovery.
Speed to Recover	How quickly data can be recovered

Mode	Mirroring	Coverage	Speed to Recover
Roll-Forward	Log and database	Greatest	Fastest
	Log Only	Medium	Moderate
Normal	Log and database	Medium	Moderate
	None	Least	Slowest

An Overview of the Process

Before you learn the details of protecting and recovering your data, read the following scenarios for protecting and recovering data. These scenarios are presented in detail in “Backup and Recovery Scenarios” on page 322.

Protecting Your Database and Storage Pool

1. Create a copy storage pool
2. Do a full backup of the primary storage pools to the copy storage pool
3. Do the following daily:
 - a. Do incremental backups of the primary storage pools to copy storage pools
 - b. Back up the database
 - c. Save the volume history file (which describes ADSM volumes) the device configuration file (which describes the devices ADSM uses) and your server options
 - d. Move offsite: copy storage pool volumes, database backup volumes, the volume history file, the device configuration file, and your server options

Recovering to a Point in Time

1. Install ADSM on a replacement processor
2. Move the database and storage pool backup volumes onsite
3. Restore the database from the latest backup level
4. Audit storage pool disk volumes and any tape volumes that were reused or added since the last backup.
5. Delete from the database any volumes in the copy storage pool that were onsite at the time of the disaster
6. Define new volumes in the primary storage pool
7. Restore the primary storage pool volumes from those in the copy storage pools

Recover a Lost or Damaged Storage Pool Volume

1. Identify the copy pool volumes containing backup copies of the files in the lost or damaged volume
2. Mark the copy volumes as unavailable
3. Bring the copy volumes onsite and mark them as read/write
4. Restore the destroyed files
5. Mark the copy volumes offsite and move them offsite

Backing Up Storage Pools

Task	Required Privilege Class
Define, back up, or restore storage pools Restore volumes	System, unrestricted storage, or restricted storage (only for those pools to which you authorized)
Update volumes	System or operator
Query volumes or storage pools	Any administrator

You can create backup copies of client files that are stored in your primary storage pools. The backup copies are stored in copy storage pools and can be used to restore the original files if they are damaged, lost, or unusable.

Primary storage pools should be backed up incrementally each day to the same copy storage pool (see Figure 70). Backing up to the same copy storage pool ensures that files do not need to be recopied if they have migrated to the next pool.




Figure 70. Copy Storage Pools

With scheduled storage pool backups and migrations and with sufficient disk storage, most copies can be made from the disk storage pool before the files are migrated to tape, thus avoiding unnecessary mounts. Here is the sequence:

1. Clients back up or archive data to disk
2. Back up the primary storage pools to copy storage pools
3. Data is migrated from disk storage pools to primary tape storage pools

Backing up storage pools requires an additional 200 bytes of space in the database for each file copy. As more files are added to the copy storage pools, reevaluate your database size requirements.

For recovery scenarios that involve backed up copies of storage pools, see “Recovering to a Point in Time from a Disaster” on page 324 and “Recovering a Lost or Damaged Storage Pool Volume” on page 325.

Mirroring the Database and Recovery Log

This section explains how to:

- Allocate disk volumes to mirror the database and recovery log
- Define ADSM mirrored volume copies
- Monitor ADSM mirrored volume copies

Task	Required Privilege Class
Define database and recovery log volumes	System or unrestricted storage
Query mirrored volumes	Any administrator

The following scenario shows the importance of mirroring in the recovery process: As the result of a sudden power outage, a partial page write occurs. The recovery log is now corrupted and not completely readable. Without mirroring, transaction recovery operations cannot complete when the server is restarted. However, if the recovery log is mirrored and a partial write is detected, a mirror volume can be used to construct valid images of the missing pages.

Allocating Volume Copies to Separate Physical Disks

By separating volume copies on different physical devices, you protect the server against media failure and increase the availability of the database and recovery log. It is strongly recommended that ADSM mirrored copies be placed on separate devices, preferably behind separate controllers or head disk assemblies (HDA). If you cannot assign each volume copy to its own physical disk, then allocate them as shown in Table 10.

Table 10. Separating Volume Copies on HDAs

Physical Disk	Volume	Volume
Physical Disk 1	Database volume copy 1	Recovery log volume copy 3
Physical Disk 2	Recovery log volume copy 1	Database volume copy 2
Physical Disk 3	Database volume copy 3	Recovery log volume copy 2

ADSM mirrored volumes should have the same capacity as the original volumes.

Defining Database or Recovery Log Mirrored Volumes

To mirror the database or recovery log, define a volume copy for each volume in the database or recovery log.

For example, the database consists of five volumes named 301, 302, 303, 304, and 305. To mirror the database, you must have five volumes that match the original volumes in size. Figure 71 shows a mirrored database in which 301-305 are mirrored by 401-405.




Figure 71. Mirrored Volumes

To create the mirrored volumes, do the following:

1. For each mirrored volume, include an MDISK statement in the directory definition. For example, to mirror the original volume 301 on the copy volume 401, which is the same size as 301, include the following statements:

```
MDISK 301 3380 0901 120 VOL001 MR
MDISK 401 3380 1105 120 VOL001 MR
```

2. Halt and log off the ADSM server.
3. Log on to but do not restart the ADSM server.
4. Use the DSMMDISK command to prepare the minidisks. You are prompted to enter the new minidisk virtual addresses.
Note: Use DSMMDISK only to prepare minidisks not currently being used by ADSM.
5. Start the ADSM server, and define the mirrored volumes to ADSM.

For example, the mirrored volumes are defined by entering the following commands:

```

define dbcopy 301 401
define dbcopy 302 402
define dbcopy 303 403
define dbcopy 304 404
define dbcopy 305 405

```

After a volume copy is defined, ADSM synchronizes the volume copy with the original volume. This process can range from minutes to hours, depending on the size of the volumes and performance of your system. After synchronization is complete, the volume copies are mirror images of each other.

Note: The mirror read and mirror write server options specify modes for reading and writing database and recovery log pages. See *ADSM Administrator's Reference* for details.

Requesting Information about Mirrored Volumes

You can request information about mirrored database or recovery log volumes by using the QUERY DBVOLUME and QUERY LOGVOLUME commands. For example:

```
query dbvolume
```

This command results in the following display:

Volume Name (Copy 1)	Copy Status	Volume Name (Copy 2)	Copy Status	Volume Name (Copy 3)	Copy Status
301	Sync'd	401	Sync'd		Undef-
302	Sync'd	402	Sync'd		ined
303	Sync'd	403	Sync'd		
304	Sync'd	404	Sync'd		
305	Sync'd	405	Sync'd		

- Each pair of vertical columns displays an image of the database or recovery log. For example, 401, 402, 403, 404, and 405 (Copy 2) represent one image of the database.
- Each horizontal column displays a *group of mirrored volumes*. For example, 301, and 401 represent two volume copies.

Backing Up the Database

Requesting a database backup (“Doing Full and Incremental Backups” on page 314) is a simple operation. However, before you do your first backup, you must take some or all of the following steps:

- Define device classes for backups (optional)
- Set the recovery log mode
- Adjust the recovery log size (optional)
- Set a database backup trigger (roll-forward mode only)

To restore your data, you must also save copies of the following information:

- Volume history file
- Device configuration file
- Server options file
- Database and recovery log set up (the output from detailed queries of your database and recovery log volumes)

Defining Device Classes for Backups

You can use existing device classes for backups or define new ones. For incremental backups you can specify a device class different from the one used for full backups.

For example, you can write full backups to a tape device and incremental backups to a disk device. Specifying a device class with a device type of FILE is useful if an incremental backup is run based on a database backup trigger. You should do this only if you are also backing up the files to tape and taking them off site. Otherwise, in a disaster you can only restore the full backup.

You can also reserve one or more device classes and, therefore, mount points for automatic backups only. In this way, you avoid trying to run a backup based on the database backup trigger with no mount point available. If a database backup, which is a high priority operation, shares a device class with a low priority operation, such as reclamation, and all the mount points are in use, ADSM automatically cancels the lower priority operation. This frees a mount point for the database backup.

Note: Device class definitions are saved in the device configuration files (see “Saving the Device Configuration Backup File” on page 312).

Setting the Recovery Log Mode

You set the recovery log mode to either *normal* or *rollforward*. If you do not set the recovery log mode, ADSM runs in normal mode. See “Database Backup” on page 299 for a description of the two modes and for a comparison their benefits and costs.

To set the log mode to normal, enter:


```
set logmode normal
```

To set the log mode to roll-forward, enter:

```
set logmode rollforward
```

Note: The log mode is not in rollforward mode until you perform the first full database backup after entering this command.

Scheduling Database Backups

Database backups can tie up resources (mount points and tapes) and, depending on the type of backup and the size of your database, can take some time. You will probably want to schedule your backups to occur, when possible, after certain activities and at specific times of the day.

To ensure that you have the most recent database information, you might back up the database after activities such as:

- Significant backup or archive activities
- Migration between storage pools
- Reclamation
- MOVE DATA or DELETE VOLUME commands
- Storage pool backups

You would usually back up your storage pools daily and immediately back up the database. Depending on the amount of client data and frequency of the activities mentioned above, you may back up less often.

Consider the following when you decide what kind of backups to do and when to do them:

Full backups

- Take longer to run than incremental backups
- Have shorter recovery times than incremental backups (you must load only one set of volumes to restore the entire database)

Full backups are required:

- For the first backup
- If there have been 32 incremental backups since the last full backup
- After changing the log mode to roll-forward
- After changing the database size (an extend or reduce operation)

Incremental backups

- Take less time to run than full backups
- Have longer recovery times than full backups because a full backup must be loaded first

Estimating the Size of the Recovery Log

In both normal mode and roll-forward mode, the volume of ADSM transactions affects how large you should make your recovery log. As more clients are added and the volume of concurrent transactions increases, you can extend the size of the log. In roll-forward mode you must also consider how often you perform database backups. In this mode, the recovery log keeps all transactions since the last database backup and typically requires significantly more space than is required in normal mode.

How, then, do you determine how large your recovery log should be in roll-forward mode? You need to determine how much recovery log space is used between database backups. For example, if you plan daily incremental backups, you should check your daily usage over a period of time. You can use the following procedure to make your estimate:

1. Start by setting your log mode to normal. In this way you are less likely to exceed your log space if your initial setting is too low for roll-forward mode.
2. After a scheduled database backup, issue the following command to reset the statistic on the amount of recovery log space used since the last reset:

```
reset logconsumption
```

3. Just before the next scheduled database backup, issue the following command to display the current recovery log statistics:

```
query log format=detailed
```

The **Cumulative Consumption** field contains the log space in megabytes used by the server since the statistic was last reset. Record the value.

4. Reiterate steps 2 and 3 over at least one week.
5. Increase the highest cumulative consumption value by 30 to 40 percent. Set your recovery log size to this increased value to account for periods of unusually high activity.

For example, over a period of a week the highest cumulative consumption value was 500MB. If you set your recovery log to 650MB you should have sufficient space between daily backups.

For information on how to adjust the recovery log size, see “Adding Space to the Database or Recovery Log” on page 238 or “Deleting Space from the Database or Recovery Log” on page 242.

Note: If the recovery log runs out of space, you may not be able to start the server for normal operation. You can create an additional recovery log volume if needed to start the server and perform the needed database backup. For example, to create a 5MB volume A00, issue the following command:

```
dsmserv extend log a00 5mb
```

Volume sizes are specified in multiples of 4MB plus 1 MB for overhead.

Setting a Database Backup Trigger

In roll-forward mode, a database backup trigger can cause ADSM to back up the database automatically. When the space occupied in the recovery log reaches a specified percentage, ADSM automatically runs a full or incremental backup of the database and deletes any unnecessary recovery log records.

Attention: The database backup trigger is intended to initiate a backup when you have scheduled a database backup but the recovery log utilization has grown faster than planned. It should not be used in place of coordinating your recovery log size and your scheduled backups. A database backup has a greater priority than many other operations. A backup based on a trigger could occur at a time of high activity and affect your other operations. To control the timing of scheduled database backups, adjust the recovery log size so that the trigger does not cause the database to be backed up at non-scheduled times.

Setting a database backup trigger is optional, but it is recommended to ensure that the recovery log does not run out of space before the next backup.

If the log mode is changed from normal to roll-forward, the next database backup must be a full backup. If a database backup trigger is defined when you set the log mode to roll-forward, the full backup is done automatically. The server does not start saving log records for roll-forward recovery until this full backup completes successfully.

In “Estimating the Size of the Recovery Log” on page 308 you determined the size of your recovery log. Your database backup trigger should be based on that procedure. For example, your recovery log typically consumes less than 500MB between backups, and your log size is 650MB. You do not want the trigger to initiate a backup except in unusual circumstances. Therefore you should set the trigger no lower than 75 percent (approximately 500MB).

To set the database backup trigger at 75 percent and run 20 incremental backups to every full backup, enter:

```
define dbbackuptrigger logfullpct=75 devclass=cartridge  
numincremental=20
```

If you do not specify the LOGFULLPCT and NUMINCREMENTAL parameters, the trigger defaults to 50 percent and ADSM runs 6 incremental backups to every full backup. Each incremental backup, whether automatic or by command, is added to the count of incremental backups run. Each full backup, whether automatic or by command, resets the count for incremental backups to zero. When you specify 0 for the NUMINCREMENTAL parameter, ADSM automatically runs only full backups.

Note: If you issue a BACKUP DB command with the TYPE=INCREMENTAL parameter, ADSM performs an incremental backup of the database regardless of the NUMINCREMENTAL setting. For example, you set NUMINCREMENTAL to 5, and there have been five incremental backups since the last full backup. If you then issue BACKUP DB TYPE=INCREMENTAL, an incremental backup is still taken, and the counter for the number of incremental backups since the last full backup is set to 6. This occurs if the BACKUP DB command is issued either by an administrator or through an administrative schedule.

After you set the database backup trigger, you might find that automatic backups occur too often. Check the backup trigger percentage by entering:

```
query dbbackuptrigger
```

ADSM displays the following information:

```
Full Device Class: CARTRIDGE
Incremental Device Class: CARTRIDGE
Log Full Percentage: 75
Incrementals Between Fulls: 6
Last Update by (administrator): SERVER_CONSOLE
Last Update Date/Time: 03/06/1996 10:49:23
```

This information shows that the trigger is set to 75 percent. If automatic backups are occurring too often, you could increase the value to 80 percent by entering:

```
update dbbackuptrigger logfullpct=80
```

If the database backup trigger automatically runs backups more often than you want and the setting is high (for example, 90 percent or higher), you should probably increase the recovery log size. If you no longer want to use the database backup trigger, enter:

```
delete dbbackuptrigger
```

After you delete the database backup trigger, ADSM no longer runs automatic database backups.

Note: If you delete the trigger and stay in roll-forward mode, transactions fail when the log fills. Therefore, you should change the log mode to normal. Remember, however, that normal mode does not let you perform roll-forward recovery.

Saving the Volume History File

The volume history file contains information about the following:

- Sequential access storage pool volumes that have been added, reused (through reclamation or MOVE DATA operations), or deleted (during DELETE VOLUME operations or reclamation)
- Database backup volumes
- Export volumes for administrator, node, policy, and server data

ADSM updates the volume history file as volumes are added. However, you must periodically run a delete operation to discard outdated information about volumes (see “Deleting Volume History Information” on page 312 for details).

This information is stored in the database, but during a database restore, it is not available from there. To perform a restore, therefore, ADSM must get the information from the volume history file.

To ensure the availability of the information, you can do any of the following:

- Store at least one copy of the volume history information on a disk separate from the database, or offsite
- Store a copy of the volume history file offsite with your database backups
- Store a remote copy, for example, on an SFS file pool
- Store a printout of the information stored offsite

Note: You can recover the database without a volume history file. However, because you must examine every volume that may contain database backup information, this is a time consuming and error-prone task.

The VOLUMEHISTORY server option lets you specify backup volume history files (for details, see the *ADSM Administrator's Reference*). After the server is restarted, whenever ADSM updates volume information in the database, it also updates the same information in the backup files specified by the VOLUMEHISTORY option.

You can also back up the volume history information at any time, by entering:

```
backup volhistory
```

If you do not specify file names, ADSM backs up the volume history information to *all* files specified with the VOLUMEHISTORY server option.

Deleting Volume History Information

You should periodically delete outdated information from the volume history file. For example, if you keep your backups for seven days, any information older than that is not needed (see the example below). When information about database backup volumes or export volumes is deleted, the volumes return to scratch status in the libraries attached to the server and may be reused. For scratch volumes with device type FILE, the files are deleted. When information about volumes in storage pools is deleted, the volumes themselves are not affected.

To display volume history information up to yesterday, enter:

```
query volhistory enddate=today-1
```

For example, to delete information that is seven days old or older, enter:

```
delete volhistory todate=today-7
```

Saving the Device Configuration Backup File

The device configuration file contains information about the device classes needed to read backup data. Whenever ADSM updates device configuration information in the database, it updates the device configuration file.

This information is stored in the database, but during a database restore, it is not available from there. To perform a restore, therefore, ADSM must get the information from the device configuration file.

To ensure the availability of the information, you can do any of the following:

- Store at least one backup copy of the device configuration file on a disk separate from the database
- Store your device configuration stored offsite with your volume history file and database backups
- Store a remote copy, for example, on an SFS file pool
- Store a printout of the information stored offsite

The DEVCONFIG server option lets you specify backup device configuration files (for details, see the *ADSM Administrator's Reference*). After the server is restarted, whenever ADSM updates device configuration information in the database, it also updates the same information in the backup files.

During a database restore operation, ADSM tries to open the first device configuration file. If it cannot open or read that file, ADSM tries to use any remaining device configuration files (in the order in which they occur in the server options) until it finds

one that is usable. If none can be found, you must recreate the file. See “Recreating a Device Configuration File” on page 313 for details.

You can also back up the device configuration information at any time, by entering:

```
backup devconfig
```

If you do not specify file names, ADSM backs up the device configuration file to *all* files specified with the DEVCONFIG server option.

If you lose your device configuration file and need it to restore the database, you must recreate it manually. See “Recreating a Device Configuration File” for details.

Recreating a Device Configuration File

The following commands read and execute the device configuration file:

- DSMSERV RESTORE DB
- DSMSERV LOADDB
- DSMSERV DISPLAY DBBACKUPVOLUME

If no device configuration file is found, you must recreate it before you can start the restore operation. The device configuration file must follow these conventions:

- You must provide the DEFINE DEVCLASS commands that apply to the devices needed to mount the volumes read by the ADSM command that you issued.
- You can use command defaults.
- The file can include blank lines.
- A single line can be up to 1550 characters.
- The file can include continuation characters and comments as described in the *ADSM Administrator's Reference*.

The following figure shows an example of a device configuration file:

```
/* IBM AdStar Distributed Storage Manager Device Configuration */  
define devclass cartridge devtype=cartridge
```

Doing Full and Incremental Backups

The first back up of your database must be a full backup. You can run up to 32 incremental backups between full backups.

To perform a full backup of your database to the CARTRIDGE device class, for example, enter:

```
backup db type=full devclass=cartridge
```

In this example, ADSM writes the backup data to scratch volumes. You can also specify volumes by name. After a full backup, you can perform incremental backups, which copy only the changes to the database since the previous backup.

To do an incremental backup of the database to the CARTRIDGE device class, enter:

```
backup db type=incremental devclass=cartridge
```

Recovering by Using Mirrored Volumes

If a mirrored volume fails due to media failure, you can recover the volume by taking the following steps:

1. View the status of the database and recovery log volumes (QUERY DBVOLUME or QUERY LOGVOLUME).
2. If necessary, place the failing volume offline from ADSM (DELETE DBVOLUME or DELETE LOGVOLUME). The server usually does this automatically.
3. Fix the failing physical device.
4. Allocate space to be used for a new volume (DSMMDISK EXEC). The server should be halted first.
5. Bring the volume online (DEFINE DBCOPY or DEFINE LOGCOPY).

After a database or recovery log volume copy is defined, the server synchronizes the volume copy with its associated database or recovery log volume.

Recovering by Using Database and Storage Pool Backups

This section explains how to recover by using backups of the database and storage pools. The following topics are included:

- Restoring to a point in time
- Restoring to the most current state

To perform a restore, you should have the following information, preferably stored offsite:

- A full database backup
- Any incremental database backups between the last full backup and the point in time to which you are recovering
- Copy storage pool volumes
- On tape or diskette, or as printouts:
 - Server options file
 - Volume history file
 - Device configuration file
 - Database and recovery log setup (the output from detailed queries of your database and recovery log volumes)




Figure 72. Recovery from a Disaster

Restoring a Database to a Point in Time

Point-in-time recovery is normally used for situations such as disaster recovery or to remove the effects of errors that can cause inconsistencies in the database.

Here is the procedure for restoring the database:

1. Rename and save a copy of the volume history file if it exists. After the database is restored, any volume history information pointed to by the server options is lost. You will need this information to identify the volumes to be audited.
2. If the device configuration file is unavailable, recreate it manually (see "Recreating a Device Configuration File" on page 313). Put the recreated file in the server work library. You can do the same with the server options file.
3. Issue the DSMSEV RESTORE DB command. For example, to restore the database to a backup series that was created on April 19, 1996, enter:

```
dsmserv restore db todate=04/19/1996
```

ADSM does the following:

- a. Reads the volume history file to locate the last full backup that occurred on or before the specified date and time.
Note: If the volume history file is not available, you must mount tape volumes in the correct order or specify their order on the DSMSEV RESTORE DB command.
- b. Using the device configuration file, requests a mount of the first volume, which should contain the beginning of the full backup.
- c. Restores the backup data from the first volume.
- d. Continues to request mounts and to restore data from the backup volumes that contain the full backup and any incremental backups that occurred on or before the date specified.

From the old volume history information (generated by the QUERY VOLHISTORY command) you need a list of all the volumes that were reused (STGREUSE), added (STGNEW), and deleted (STGDELETE) since the original backup. Use this list to perform the following steps.

4. Audit all disk volumes, all reused volumes, and any deleted volumes located by the AUDIT VOLUME command with the FIX=YES parameter.

This process identifies files recorded in the database that can no longer be found on the volume. If a copy of the file is in a copy storage pool, the file on the audited volume is marked as damaged. Otherwise, the file is deleted from the database and is lost.

5. If the audit detects any damaged files, issue the RESTORE STGPOOL command to restore those files after you have audited the volumes in the storage pool.

Include the `FIX=YES` parameter on the `AUDIT VOLUME` command to delete database entries for files not found in the copy storage pool.

6. Mark as destroyed any volumes that cannot be located, and recover those volumes from copy storage pool backups. If no backups are available, delete the volumes from the database by using the `DELETE VOLUME` command with the `DISCARDDATA=YES` parameter.
7. Redefine any storage pool volumes that were added since the database backup.

Some files may be lost if they were moved since the backup (due to migration, reclamation, or move data requests) and the space occupied by those files has been reused. You can minimize this loss by using the `REUSEDELAY` parameter when defining or updating sequential access storage pools. This parameter delays volumes from being returned to scratch or being reused.

By backing up your storage pool and your database, you reduce the risk of losing data. To further minimize loss of data, you can:

- Mark the backup volumes in the copy storage pool as `OFFSITE` and move them to an offsite location.

In this way the backup volumes are preserved and are not reused or mounted until they are brought onsite. Ensure that you mark the volumes as `OFFSITE` before you back up the database.

- Back up the database immediately after you back up the storage pools.
- Turn off migration and reclamation while you back up the database.
- Do not perform any `MOVE DATA` operations while you back up the database.
- Use the `REUSEDELAY` interval to prevent your copy storage pool volumes from being reused or deleted before they might be needed.

If your old volume history file shows that any of the copy storage pool volumes needed to restore your storage pools have been reused (`STGREUSE`) or deleted (`STGDELETE`), you may not be able to restore all your files. You can avoid this problem by including the `REUSEDELAY` parameter when you define your copy storage pools.

After a restore, the volume inventories for ADSM and for your tape management system may be inconsistent. For example, after a database backup, a new volume is added to ADSM. The tape management system inventory records the volume as belonging to ADSM. If the database is restored from the backup, ADSM has no record of the added volume, but the tape management system does. You must synchronize these inventories.

Point-in-Time Restore without a Volume History File

If you are doing a point-in-time restore and a volume history file is not available, you must enter the volume names in the DSMSERV RESTORE DB command in the sequence in which they were written to. First, however, issue the DSMSERV DISPLAY DBBACKUPVOLUME command to read your backup volumes and display the information needed to arrange them in order (backup series, backup operation, and volume sequence):

```
dsmserv display dbbackupvolume devclass=cartridge
volumenames=dsm012,dsm023,dsm037,dsm038,dsm058,dsm087
```

For example, the most recent backup series consists of three operations:

- 0** A full backup on three volumes in the sequence dsm023, dsm037, and dsm087
- 1** An incremental backup on one volume, dsm012
- 2** An incremental backup on two volumes in the sequence dsm038 and dsm058

You would issue three commands in the following order:

```
dsmserv restore db volumenames=dsm023,dsm037,dsm087
devclass=cartridge commit=no

dsmserv restore db volumenames=dsm012
devclass=cartridge commit=no

dsmserv restore db volumenames=dsm038,dsm058
devclass=cartridge commit=no
```

Storage Pool Backups in Point-of-Time Restore

The following example shows the importance of storage pool backups with a point-in-time restore. In this example, the storage pool was not backed up with the BACKUP STGPOOL command.

- 9:30 a.m.* Client A backs up its data to Volume 1.
- Noon* The system administrator backs up the database.
- 1:30 p.m.* Client A's files on Volume 1 (disk), is migrated to tape (Volume 2).
- 3:00 p.m.* Client B backs up its data to Volume 1.
The server places Client B's files in the location that contained Client A's files prior to the migration.
- 3:30 p.m.* The server goes down.
- 3:40 p.m.* The system administrator reloads the noon version of the database by using the DSMSERV RESTORE DB command.

4:40 p.m. Volume 1 is audited. The following then occurs:

1. The server compares the information on Volume 1 and with the restored database (which matches the database at noon).
2. The audit does not find Client A's files on Volume 1 where the reloaded database indicates they should be. Therefore, the server deletes these Client A file references.
3. The database has no record that Client A's files are on Volume 2, and the files are, in effect, lost.
4. The database has no record that Client B's files are on Volume 1, and the files are, in effect, lost.

If roll-forward recovery had been used, the database would have been rolled forward to 3:30 p.m. when the server went down, and neither Client A's files nor Client B's files would have been lost. If a point-in-time restore of the database had been performed and the storage pool had been backed up, Client A's files would not have been deleted by the volume audit and could have been restored with a RESTORE VOLUME or RESTORE STGPOOL command. Client B's files would still have been lost, however.

Restoring a Database to its Most Current State

You can use roll-forward recovery to restore a database to its most current state if:

- ADSM has been in roll-forward mode continuously from the time of the last full backup to the time the database was damaged or lost.
- The last backup series created for the database is available. A backup series consists of a full backup, all applicable incremental backups, and all recovery log records for database changes since the last backup in the series was run.

To restore the database to its most current state, enter:

```
dsmserv restore db
```

Note: Roll-forward recovery does not apply if all recovery log volumes are lost. However, with the server running in roll-forward mode, you can still perform point-in-time recovery in such a case.

Correcting Damaged Files

A data-integrity error can be caused by such things as a tape deteriorating or being overwritten or by a drive needing cleaning. If a data-integrity error is detected when a client tries to restore, retrieve, or recall a file or during a volume audit, ADSM marks the file as damaged. If the same file is stored in other copy storage pools, the status of those file copies is not changed.

If a client tries to access a file that is marked as damaged and an undamaged copy is available on an onsite copy storage pool volume, ADSM sends the user the undamaged copy.

Files that are marked as damaged cannot be:

- Restored, retrieved, or recalled
- Moved by migration, reclamation, or the MOVE DATA command
- Backed up during a BACKUP STGPOOL operation if the primary file is damaged
- Restored during a RESTORE STGPOOL or RESTORE VOLUME operation if the backup copy in a copy storage pool is damaged

Maintaining the Integrity of Files

To maintain the data integrity of user files, you can:

1. Detect damaged files before the users do.

The AUDIT VOLUME command marks a file as damaged if a data-integrity error is detected for the file. If an undamaged copy is in an onsite copy storage pool, it is used to provide client access to the file.

2. Reset the damaged status of files if the error that caused the change to damaged status was temporary.

You can use the AUDIT VOLUME command to correct situations when files are marked damaged due to a temporary hardware problem, such as a dirty tape head. ADSM resets the damaged status of files if the volume in which the files are stored is audited and no data-integrity errors are detected.

3. Correct files that are marked as damaged.

If a primary file copy is marked as damaged and a usable copy exists in a copy storage pool, the primary file can be corrected using the RESTORE VOLUME or RESTORE STGPOOL command. For an example, see “Restore Damaged Files.”

4. Regularly run commands to identify files that are marked as damaged:

- The RESTORE STGPOOL command displays the name of each volume in the restored storage pool that contains one or more damaged primary files. Use this command with the preview option to identify primary volumes with damaged files without actually performing the restore operation.
- The QUERY CONTENT command with the DAMAGED option lets you display damaged files on a specific volume.

For an example of how to use these commands, see “Restore Damaged Files.”

Restore Damaged Files

If you use copy storage pools, you can restore damaged client files. You can also check storage pools for damaged files and restore the files. This section explains how to restore damaged files based on the scenario in “Example: Simple Hierarchy with One Copy Storage Pool” on page 116.

If a client tries to access a file stored in CART-POOL and a data integrity error occurs, the file in CART-POOL is automatically marked as damaged. Future accesses to the

file automatically use the copy in CART-COPYPOOL as long as the copy in CART-POOL is marked as damaged.

To restore any *damaged* files in CART-POOL, you can define a schedule that issues the following command periodically:

```
restore stgpool cart-pool
```

You can check for and replace any files that develop data-integrity problems in CART-POOL or in CART-COPYPOOL. For example, every three months, query the volumes in CART-POOL and CART-COPYPOOL by entering the following commands:

```
query volume stgpool=cart-pool  
query volume stgpool=cart-copypool
```

Then issue the following command for each volume in CART-POOL and CART-COPYPOOL:

```
audit volume <volname> fix=yes
```

If a data integrity error occurs on a file in CART-POOL, that file is marked *damaged* and an error message is produced. If a data integrity error occurs on file in CART-COPYPOOL, that file is deleted and a message is produced.

Restore *damaged* primary files by entering:

```
restore stgpool cart-pool
```

Finally, create new copies in CART-COPYPOOL by entering:

```
backup stgpool cart-pool cart-copypool
```

Backup and Recovery Scenarios

This section presents scenarios for protecting and recovering an ADSM server. You can modify the procedures to meet your needs.

These scenarios assume a storage hierarchy consisting of:

- The default random access storage pools (BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL)
- TAPEPOOL, a tape storage pool

Protecting Your Database and Storage Pool

A company's standard procedures include the following:

- Perform reclamation of its copy storage pool, once a week. Reclamation for the copy storage pools is turned off at other times.

Note: In a copy storage pool definition, the REUSEDELAY parameter delays volumes from being returned to scratch or being reused. The value should be set high enough to ensure that the database can be restored to an earlier point in time and that the database references to files in the storage pool is still valid. For example, a user may want to retain database backups for seven days and, therefore, sets REUSEDELAY to 7.

- Back up its storage pools every night.
- Perform a full backup of the database once a week and incremental backups on the other days.
- Ship the database and copy storage pool volumes to an offsite location every day.

To protect client data, the administrator does the following:

1. Creates a copy storage pool named DISASTER-RECOVERY. Only scratch tapes are used, and the maximum number of scratch volumes is set to 100. The copy storage pool is defined by entering:

```
define stgpool disaster-recovery tapecart pooltype=copy
maxscratch=100
```

2. Performs the first backup of the primary storage pools.

Note: The first backup of a primary storage pool is a full backup and, depending on the size of the storage pool, could take a long time.

3. Defines schedules for the following daily operations:
 - a. Incremental backups of the primary storage pools each night by issuing:


```
backup stgpool backuppool disaster-recovery maxprocess=2
backup stgpool archivepool disaster-recovery maxprocess=2
backup stgpool spacemgpool disaster-recovery maxprocess=2
backup stgpool tapepool disaster-recovery maxprocess=2
```

These commands use multiple, parallel processes to perform an incremental backup of each primary storage pool to the copy pool. Only those files for which a copy does not already exist in the copy pool are backed up.

Note: Migration should be turned off during the rest of the day. You could add a schedule to migrate from disk to tape at this point. In this way, the backups are done while the files are still on disk.

- b. Change the access mode to OFFSITE for volumes that have read-write or read-only access, are onsite, and are at least partially filled. This is done by entering:

```
update volume * access=offsite location='vault site info'
wherestgpool=disaster-recovery whereaccess=readwrite,readonly
wherestatus=filling,full
```

- c. Back up the database by entering:

```
backup db type=incremental devclass=cartridge scratch=yes
```

4. Does the following operations nightly after the scheduled operations have completed:
 - a. Backs up the volume history, device configuration, and server options.
 - b. Moves the volumes marked offsite, the database backup volumes, volume history files, device configuration files, and server options to the offsite location.
 - c. Identifies offsite volumes that should be returned onsite by using the QUERY VOLUME command:

```
query volume stgpool=disaster-recovery access=offsite status=empty
```

These volumes, which have become empty through expiration, reclamation, and file space deletion, have waited the delay time specified by the REUSEDELAY parameter. The administrator periodically returns outdated backup database volumes. These volumes are displayed with the QUERY

VOLHISTORY command and can be released for reuse with the DELETE VOLHISTORY command.

5. Brings the volumes identified in step 4c on page 323 onsite and updates their access to read-write.

Recovering to a Point in Time from a Disaster

In this scenario, the company's processor on which ADSM resides, the database, and all onsite storage pool volumes are destroyed by fire. An administrator restores the server to the point in time of the last backup by doing the following:

1. Install the ADSM server on the replacement processor with the same server options and the same size database and recovery log as on the destroyed system.
2. Move the latest backup and all of the DISASTER-RECOVERY volumes onsite from the offsite location.

Note: Do not change the access mode of these volumes until after you have completed step 7.

3. If a current, undamaged volume history file exists, save it.
4. Restore the volume history and device configuration files and the server options.
5. Restore the database from the latest backup level by issuing the DSMSERV RESTORE DB command (see "Recovering by Using Database and Storage Pool Backups" on page 314).
6. Change the access mode of all the existing primary storage pool volumes in the damaged storage pools to DESTROYED by entering:

```
update volume * access=destroyed wherestgpool=backuppoo1
update volume * access=destroyed wherestgpool=archivepool
update volume * access=destroyed wherestgpool=spacemgpool
update volume * access=destroyed wherestgpool=tapepool
```

7. Issue the QUERY VOLUME command to identify any volumes in the DISASTER-RECOVERY storage pool that were onsite at the time of the disaster. Any volumes that were onsite would have been destroyed in the disaster and could not be used for restore processing. Delete each of these volumes from the database by using the DELETE VOLUME command with the DISCARDATA option. Any files backed up to these volumes cannot be restored.
8. Change the access mode of the remaining volumes in the DISASTER-RECOVERY pool to READWRITE by entering:

```
update volume * access=readwrite wherestgpool=disaster-recovery
```

Note: Clients can get files from ADSM at this point. If a client tries to get a file that was stored on a destroyed volume, the retrieval request goes to the copy storage pool. In this way, clients can access their files without waiting for the primary storage pool to be restored. When you update volumes brought from offsite to change their access, you greatly speed recovery time.

9. Define new volumes in the primary storage pool so the files on the damaged volumes can be restored to the new volumes. The new volumes also allow clients to backup, archive, or migrate files to the server. You do not need to perform this step if you use only scratch volumes in the storage pool.
10. Restore files in the primary storage pool from the copies located in the DISASTER-RECOVERY pool by entering:

```
restore stgpool backuppool maxprocess=2
restore stgpool archivepool maxprocess=2
restore stgpool spacemgpool maxprocess=2
restore stgpool tapepool maxprocess=2
```

These commands use multiple parallel processes to restore files to primary storage pools. After all the files have been restored for a destroyed volume, that volume is automatically deleted from the database. See “When a Storage Pool Restoration is Incomplete” on page 129 for what to do if one or more volumes cannot be fully restored.

11. To ensure against another loss of data, immediately back up all storage volumes and the database. Then resume normal activity, including weekly disaster backups and movement of data to the offsite location.

Recovering a Lost or Damaged Storage Pool Volume

If a company makes the preparations described in “Protecting Your Database and Storage Pool” on page 322 it can recover from a media loss by using ADSM features.

In this scenario, an operator inadvertently destroys a tape volume (DSM087) belonging to the TAPEPOOL storage pool. An administrator performs the following actions to recover the data stored on the destroyed volume by using the offsite copy storage pool:

1. Determine the copy pool volumes that contain the backup copies of the files that were stored on the volume that was destroyed by entering:

```
restore volume dsm087 preview=volumesonly
```

This command produces a list of offsite volumes that contain the backed up copies of the files that were on tape volume DSM087.

2. Set the access mode of the copy volumes identified as UNAVAILABLE to prevent reclamation.

Note: This precaution prevents the movement of files stored on these volumes until volume DSM087 is restored.

3. Bring the identified volumes to the onsite location and set their access mode to READWRITE.
4. Restore the destroyed files by entering:

```
restore volume dsm087
```

This command sets the access mode of the DSM087 to DESTROYED and attempts to restore all the files that were stored on volume DSM087. The files are not actually restored to volume DSM087, but to another volume in the TAPEPOOL storage pool. All references to the files on DSM087 are deleted from the database and the volume itself is deleted from the database.

5. Set the access mode of the volumes used to restore DSM087 to OFFSITE using the UPDATE VOLUME command.
6. Return the volumes to the offsite location.

Part 7. Appendix, Glossary, and Index

Appendix A. Interface Cross-Reference

The following table lists each ADSM command and shows if and where the function performed by that command can be performed on the graphical user interface. The column entitled "GUI" shows the locations where you perform the tasks. You can find detailed help for using the GUI in its online help facility.

Note: The CMS administrative client has the command line interface only; you cannot access the GUI from this client.

For details about the commands, refer to the *ADSM Administrator's Reference* and the command-line interface online help (accessed through the HELP command).

<i>Table 11 (Page 1 of 8). Interface Cross Reference</i>	
Command	GUI
ACTIVATE POLICYSET	1. Policy Domains 2. Policy Sets
ASSIGN DEFMGMTCLASS	1. Policy Domains 2. Management Classes
AUDIT LICENSES	1. Server
AUDIT VOLUME	1. Storage Pools 2. Storage Pool Volumes
BACKUP DB	Database
BACKUP DEVCONFIG	Server
BACKUP STGPOOL	Storage Pools
BACKUP VOLHISTORY	1. Server 2. Sequential Volume History
CANCEL PROCESS	1. Server 2. Processes
CANCEL REQUEST	Not available
CANCEL SESSION	1. Server 2. Sessions
COMMIT	Not available
COPY DOMAIN	Policy Domains
COPY MGMTCLASS	1. Policy Domains 2. Management Class
COPY POLICYSET	1. Policy Domains 2. Policy Sets

Table 11 (Page 2 of 8). Interface Cross Reference

Command	GUI
COPY SCHEDULE	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Command Schedules or <ol style="list-style-type: none"> b. Backup/Archive Schedules
DEFINE ASSOCIATION	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Events or <ol style="list-style-type: none"> b. Backup/Archive Events
DEFINE COPYGROUP	<ol style="list-style-type: none"> 1. Policy Domains 2. Backup Copy Groups
DEFINE DBBACKUPTRIGGER	Database
DEFINE DBCOPY	<ol style="list-style-type: none"> 1. Database 2. Database Volumes
DEFINE DBVOLUME	<ol style="list-style-type: none"> 1. Database 2. Database Volumes
DEFINE DEVCLASS	Not available
DEFINE DOMAIN	Policy Domains
DEFINE EXIT	Not available
DEFINE LOGCOPY	<ol style="list-style-type: none"> 1. Database Recovery Log 2. Recovery Log Volumes
DEFINE LOGVOLUME	<ol style="list-style-type: none"> 1. Database Recovery Log 2. Recovery Log Volumes
DEFINE MGMTCLASS	<ol style="list-style-type: none"> 1. Policy Domains 2. Management Class
DEFINE POLICYSET	<ol style="list-style-type: none"> 1. Policy Domains 2. Policy Sets
DEFINE SCHEDULE	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Command Schedules or <ol style="list-style-type: none"> b. Backup/Archive Schedules
DEFINE STGPOOL	Storage Pools
DEFINE VOLUME	<ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes

Table 11 (Page 3 of 8). Interface Cross Reference

Command	GUI
DELETE ASSOCIATION	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Events or <ol style="list-style-type: none"> b. Backup/Archive Events
DELETE COPYGROUP	<ol style="list-style-type: none"> 1. Policy Domains 2. Backup Copy Groups or Archive Copy Groups
DELETE DBBACKUPTRIGGER	Database
DELETE DBVOLUME	<ol style="list-style-type: none"> 1. Database 2. Database Volumes
DELETE DEVCLASS	Not available
DELETE DOMAIN	Policy Domains
DELETE EVENT	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Events or <ol style="list-style-type: none"> b. Backup/Archive Events
DELETE EXIT	Not available
DELETE FILESPACE	File Spaces
DELETE LOGVOLUME	<ol style="list-style-type: none"> 1. Database Recovery Log 2. Recovery Log Volumes
DELETE MGMTCLASS	<ol style="list-style-type: none"> 1. Policy Domains 2. Management Class
DELETE POLICYSET	<ol style="list-style-type: none"> 1. Policy Domains 2. Policy Sets
DELETE SCHEDULE	<ol style="list-style-type: none"> 1. Central Scheduler 2. Administrative Command Schedules or <ol style="list-style-type: none"> 3. Backup/Archive Schedules
DELETE STGPOOL	Storage Pools
DELETE VOLHISTORY	<ol style="list-style-type: none"> 1. Server 2. Sequential Volume History
DELETE VOLUME	<ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes
DISABLE	Server
DISMOUNT VOLUME	Not available

Table 11 (Page 4 of 8). Interface Cross Reference

Command	GUI
DSMMDISK	Not available
DSMSERV DISPLAY DBBACKUPVOLUME	Not available
DSMSERV DISPLAY DBVOLUMES	Not available
DSMSERV DISPLAY LOGVOLUMES	Not available
DSMSERV EXTEND LOG	Not available
DSMSERV RESTORE DB	Not available
ENABLE	Server
EXPIRE INVENTORY	Not available
EXPORT ADMIN	Server
EXPORT NODE	Server
EXPORT POLICY	Server
EXPORT SERVER	Server
EXTEND DB	Database
EXTEND LOG	Database Recovery Log
GRANT AUTHORITY	Administrators
HALT	Server
HELP	Help (from a menu bar)
IMPORT ADMIN	Server
IMPORT NODE	Server
IMPORT POLICY	Server
IMPORT SERVER	Server
LOCK ADMIN	Administrators
LOCK NODE	Nodes
MACRO	Not available
MOVE DATA	<ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes
QUERY ACTLOG	<ol style="list-style-type: none"> 1. Server 2. Activity Log
QUERY ADMIN	Administrators

Table 11 (Page 5 of 8). Interface Cross Reference

Command	GUI
QUERY ASSOCIATION	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Events or <ol style="list-style-type: none"> b. Backup/Archive Events
QUERY AUDITOCUPANCY	Nodes
QUERY CONTENT	<ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes
QUERY COPYGROUP	<ol style="list-style-type: none"> 1. Policy Domains 2. Backup Copy Groups
QUERY DB	Database
QUERY DBBACKUPTRIGGER	Database
QUERY DBVOLUME	<ol style="list-style-type: none"> 1. Database 2. Database Volumes
QUERY DEVCLASS	Not available
QUERY DOMAIN	Policy Domains
QUERY EVENT	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Events or <ol style="list-style-type: none"> b. Backup/Archive Events
QUERY EXIT	Not available
QUERY FILESPACE	File Spaces
QUERY LICENSE	<ol style="list-style-type: none"> 1. Server
QUERY LOG	Database Recovery Log
QUERY LOGVOLUME	<ol style="list-style-type: none"> 1. Database Recovery Log 2. Recovery Log Volumes
QUERY MGMTCLASS	<ol style="list-style-type: none"> 1. Policy Domains 2. Management Class
QUERY MOUNT	Not available
QUERY NODE	Nodes
QUERY OCCUPANCY	Not available
QUERY OPTION	Not available
QUERY POLICYSET	<ol style="list-style-type: none"> 1. Policy Domains 2. Policy Sets

Table 11 (Page 6 of 8). Interface Cross Reference

Command	GUI
QUERY PROCESS	<ol style="list-style-type: none"> 1. Server 2. Processes
QUERY REQUEST	Not available
QUERY SCHEDULE	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Command Schedules or b. Backup/Archive Schedules
QUERY SESSION	<ol style="list-style-type: none"> 1. Server 2. Sessions
QUERY STATUS	Server
QUERY STGPOOL	Storage Pools
QUERY VOLHISTORY	<ol style="list-style-type: none"> 1. Server 2. Sequential Volume History
QUERY VOLUME	<ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes
QUIT	Not available
REDUCE DB	Database
REDUCE LOG	Database Recovery Log
REGISTER ADMIN	Administrators
REGISTER LICENSE	Not available
REGISTER NODE	Nodes
REMOVE ADMIN	Administrators
REMOVE NODE	Nodes
RENAME ADMIN	Administrators
RENAME FILESPACE	File Spaces
RENAME NODE	Nodes
REPLY	Not available
RESET BUFPOOL	Not available
RESET DBMAXUTILIZATION	Database
RESET LOGCONSUMPTION	Not available
RESET LOGMAXUTILIZATION	Database Recovery Log
RESTORE STGPOOL	Storage Pools

Table 11 (Page 7 of 8). Interface Cross Reference

Command	GUI
RESTORE VOLUME	<ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes
REVOKE AUTHORITY	Administrators
ROLLBACK	Not available
SET ACCOUNTING	Server
SET ACTLOGRETENTION	Server
SET AUTHENTICATION	Server
SET EVENTRETENTION	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Events or b. Backup/Archive Events
SET LICENSEAUDITPERIOD	1. Server
SET LOGMODE	Database Recovery Log
SET MAXCMDRETRIES	Central Scheduler
SET MAXSCHEDESESSIONS	Central Scheduler
SET PASSEXP	Server
SET QUERYSCHEDPERIOD	Central Scheduler
SET RANDOMIZE	Central Scheduler
SET REGISTRATION	Server
SET RETRYPERIOD	Central Scheduler
SET SCHEDMODES	Central Scheduler
SET SERVERNAME	Server
UNLOCK ADMIN	Administrators
UNLOCK NODE	Nodes
UPDATE ADMIN	Administrators
UPDATE COPYGROUP	<ol style="list-style-type: none"> 1. Policy Domains 2. Backup Copy Groups
UPDATE DBBACKUPTRIGGER	Database
UPDATE DEVCLASS	Not available
UPDATE DOMAIN	Policy Domains
UPDATE EXIT	Not available

Table 11 (Page 8 of 8). Interface Cross Reference

Command	GUI
UPDATE MGMTCLASS	<ol style="list-style-type: none"> 1. Policy Domains 2. Management Class
UPDATE NODE	Nodes
UPDATE POLICYSET	<ol style="list-style-type: none"> 1. Policy Domains 2. Policy Sets
UPDATE SCHEDULE	<ol style="list-style-type: none"> 1. Central Scheduler 2. Either <ol style="list-style-type: none"> a. Administrative Command Schedules or b. Backup/Archive Schedules
UPDATE STGPOOL	Storage Pools
UPDATE VOLUME	<ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes
VALIDATE POLICYSET	<ol style="list-style-type: none"> 1. Policy Domains 2. Policy Sets
VARY	<p><i>Database volumes:</i></p> <ol style="list-style-type: none"> 1. Database 2. Database Volumes <p><i>Recovery log volumes:</i></p> <ol style="list-style-type: none"> 1. Database Recovery Log 2. Recovery Log Volumes <p><i>Storage pool volumes:</i></p> <ol style="list-style-type: none"> 1. Storage Pools 2. Storage Pool Volumes

Glossary

The terms in this glossary are defined as they pertain to the ADSM library. If you do not find the term you are looking for, refer to the *IBM Dictionary of Computing*, New York: McGraw-Hill, 1994.

This glossary may include terms and definitions from:

- The *American National Standard Dictionary for Information Systems*, ANSI X3.172-1990, copyright (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42nd Street, New York 10036.
- The *Information Technology Vocabulary*, developed by Subcommittee 1, Joint Technical Committee 1, of the International Organization for Standardization and the International Electrotechnical Commission (ISO/IEC JTC2/SC1).

A

absolute. A backup copy group mode value indicating that a file is considered for incremental backup even if the file has not changed since the last backup. See also *mode*. Contrast with *modified*.

access mode. A storage pool and storage volume attribute that specifies whether data can be written to or read from storage pools or storage volumes. The access mode can be read/write, read-only, or unavailable. Volumes in primary storage pools can also have an access mode of destroyed. Volumes in copy storage pools can also have an access mode of offsite.

accounting facility. A facility that records statistics about client session activity.

accounting records. Files that record session resource usage at the end of each client session.

action choice. A choice in a pull-down menu that causes an action. See also *routing choice*.

activate. The process of validating the contents of a policy set and copying the policy set to the ACTIVE policy set.

active policy set. The policy set within a policy domain that contains the most recently activated policy currently in use by all client nodes assigned to that policy domain. See *policy set*.

active version. The most recent backup copy of a file stored by ADSM. Such a file is exempt from deletion until a backup detects that the user has either replaced the file with a newer version, or has explicitly deleted the file from the workstation. Contrast with *inactive version*.

activity log. A log that records normal activity messages generated by the server. These messages include information about server and client operations, such as the start time of sessions or device I/O errors. Each message includes a message ID, date and time stamp, and a text description. The number of days to retain messages in the activity log can be specified.

administrative client. A program that runs on a file server, workstation, or mainframe that allows administrators to control and monitor the server through administrator commands. Contrast with *backup-archive client*.

administrative command schedule. A database record that describes the planned processing of an administrative command during a specific time period. See also *client schedule*.

administrative privilege class. A permission granted to an administrator that controls the commands that the administrator can issue. See *system privilege class*, *analyst privilege class*, *operator privilege class*, *policy privilege class* or *storage privilege class*.

administrative session. A period of time in which an administrator user ID can communicate with a server to perform administrative tasks. Contrast with *client node session*.

administrator. A user who has been registered to the server. Administrators can be authorized to one or more of the following administrative privilege classes: system, policy, storage, operator, or analyst. Administrators can use the administrative client to enter server commands and queries in accordance with their privileges.

administrator definition. Server control information that includes the administrator's name, password, contact information, administrative privilege classes, policy domains and storage pools assigned to an administrator, and whether the administrative ID is locked from the server. An administrator definition can be exported from a source server and imported to a target server at a later date.

ADSM. ADSTAR Distributed Storage Manager.

ADSM application program interface (API). A set of functions that applications running on a client platform can call to store, query, and retrieve objects from ADSM storage.

ADSTAR Distributed Storage Manager (ADSM). A client/server program that provides storage management to customers in a multivendor computer environment.

Advanced Interactive Executive (AIX). An operating system used in the RISC System/6000 computers. The AIX operating system is IBM's implementation of the UNIX operating system.

Advanced Peer-to-Peer Networking (APPN). An extension to the LU6.2 peer orientation for end-user services. See *SNA LU6.2* and *Systems Network Architecture*.

Advanced Program-to-Program Communication (APPC). An implementation of the SNA/SDLC LU6.2 protocol that allows interconnected systems to communicate and share the processing of programs. See *SNA LU6.2*, *Systems Network Architecture*, and *Common Programming Interface Communications*.

AFS. Andrew file system.

AIX. Advanced Interactive Executive.

analyst privilege class. An administrative privilege class that allows an administrator to reset statistics.

Andrew file system (AFS). A distributed file system developed for UNIX operating systems.

API. Application program interface.

APPC. Advanced Program-to-Program Communication.

APPN. Advanced Peer-to-Peer Networking.

archive. A function that allows users to copy one or more files to a storage pool for long-term storage. Archive copies may be accompanied by descriptive information and may be retrieved by archive date, by file name, or by description. Contrast with *retrieve*.

archive copy. A user file that has been archived to an ADSM storage pool.

archive copy group. A policy object containing attributes that control the generation, destination, and expiration of archive files. An archive copy group belongs to a management class.

ARCHIVEPOOL. A disk storage pool defined by ADSM at installation. It can be the destination for client files that are archived to the server. See *storage pool*.

archive retention grace period. The number of days ADSM retains an archive copy when the server is unable to rebind the file to an appropriate management class.

AS/400. Application System/400.

assigned capacity. The portion of available space that can be used to store database or recovery log information. See also *available space*.

association. The relationship between a client node and a client schedule. An association identifies the name of a schedule, the name of the policy domain to which the schedule belongs, and the name of a client node that performs scheduled operations.

audit. The process of checking for logical inconsistencies between information that the server has and the actual condition of the system. ADSM has processes for auditing volumes, the database, libraries, and licenses. For example, in auditing a volume ADSM checks for inconsistencies between information about backed up or archived files stored in the database and actual data associated with each backup version or archive copy in server storage.

authentication. The process of checking a user's password before allowing that user access to the server. Authentication can be turned on or off by an administrator with system privilege.

autochanger. A small multislot tape device that has a mechanism that automatically puts tape cartridges into the tape drive or drives. Also called *medium* or *media changer*, or a *library*.

available space. The amount of space, in megabytes, that is available to the database and recovery log. This space can be used to extend the capacity of the database or recovery log, or to provide sufficient free space before a volume is deleted from the database or recovery log.

B

background process. A server process that runs in the background, allowing the administrative client to be used for other work.

backup. The process of copying information for safekeeping. ADSM has processes for backing up user files, the database, and storage pools. For example, users can back up one or more files to a storage pool to ensure against loss of data. Contrast with *restore*. See also *database backup series* and *incremental backup*.

backup-archive client. A program that runs on a workstation or file server and provides a means for users to back up, archive, restore, and retrieve files. Contrast with *administrative client*.

backup copy. A user file that has been backed up to an ADSM storage pool.

backup copy group. A policy object containing attributes that control the generation, destination, and expiration of backup files. A backup copy group belongs to a management class.

BACKUPPOOL. A disk storage pool defined by ADSM at installation. It can be the destination for client files that are backed up to the server. See *storage pool*.

backup retention grace period. The number of days ADSM retains a backup version after the server is unable to rebind the file to an appropriate management class.

backup series. See *database backup series*.

backup version. A file, directory, or file space that a user has backed up, which resides in ADSM server storage. There may be more than one backup version of a file in the storage pool, but at most only one is an active backup version. See *active version* and *inactive version*.

binding. The process of associating a file with a management class name. See *rebinding*.

buffer. Storage used to compensate for differences in the data rate flow, when transferring data from one device to another.

buffer pool. Temporary space used by the server to hold database or recovery log pages. See *database buffer pool* and *recovery log buffer pool*.

buffer pool size. The size of an area in memory used to store database or recovery log pages.

bus converter. A device that translates between different Hewlett-Packard internal I/O bus architectures.

C

cache. The process of leaving a duplicate copy on random access media when the server migrates a file to another storage pool in the hierarchy.

cartridge. A sequential storage media that contains magnetic tape in a protective housing. Contrast with *tape reel*.

CARTRIDGE. On ADSM servers that support it, a device class that is used to categorize tape devices that support tape cartridges, such as the 3495 Tape Library Dataserver.

cartridge system tape (CST). The base tape cartridge media used with 3480 or 3490 Magnetic Tape Subsystems. When specified as a media type in ADSM, CST identifies standard length tape. Contrast with *enhanced capacity cartridge system tape*.

central scheduler. A function that allows an administrator to schedule client operations and administrative commands. The operations can be scheduled to occur periodically or on an explicit date. See *client schedule* and *administrative command schedule*.

CID. Configuration Installation and Distribution.

client. A program running on a PC, workstation, file server, LAN server, or mainframe that requests services of another program, called the server. There are three types of ADSM clients: administrative, backup-archive, and space management. See *administrative client*, *backup-archive client*, and *space management client*.

Client Access/400. A software product that supports advanced program-to-program communications (APPC) in the DOS, OS/2, and Microsoft Windows environments and provides a set of end user services.

client domain. The set of drives, file systems, or volumes selected by a backup-archive client user during a backup or archive operation.

client migration. The process of copying a file from a client node to ADSM storage and replacing the file with

a stub file on the client node. The process is controlled by the user and by space management attributes in the management class. See also *space management*.

client node. A file server or workstation on which the backup-archive client program has been installed, which has been registered to the server.

client node definition. Server control information that includes the client's user ID, password, contact information, policy domain, file compression status, deletion authority, and whether the user ID is locked from the server. A client node definition can be exported from a source server so that it can be imported to a target server at a later date.

client node session. A period of time in which a user can communicate with a server to perform backup, archive, restore, or retrieval requests. Contrast with *administrative session*.

client options file. A file that a client can edit, containing a default set of processing options that identify the server, communication method, backup and archive options, space management options, and scheduling options. Also called the *dsm.opt* file.

client polling scheduling mode. A client/server communication technique where the client queries the server for work.

client schedule. A database record that describes the planned processing of a client operation during a specific time period. The client operation can be a backup, archive, restore, or retrieve operation, a client operating system command, or a macro. See also *administrative command schedule*.

client/server. A system architecture in which one or more programs (clients) request computing or data services from another program (server).

client system options file. A file, used on UNIX clients, containing a default set of processing options that identify the ADSM servers to be contacted for services. This file also specifies communication methods and options for backup, archive, space management, and scheduling. Also called the *dsm.sys* file. See also *client user options file*.

client user options file. A user-created file, used on UNIX clients, containing a default set of processing options that identify the server, communication method, backup and archive options, space management options,

and scheduling options. Also called the *dsm.opt* file. See also *client system options file*.

closed registration. A registration process in which an administrator must register workstations as client nodes with the server. Contrast with *open registration*.

collocation. A process that attempts to keep all data belonging to a single client node on a minimal number of sequential access media volumes within a storage pool. The purpose of collocation is to minimize the number of volumes that must be accessed when a large amount of data must be restored.

command line interface. A type of user interface where commands are specified on the command line when the backup-archive or administrative client is started. Contrast with *graphical user interface*.

commit. To make changes permanent in the database files. Changes made to the database files are not permanent until they are committed.

Common Programming Interface Communications (CPI-C). A programming interface that allows program-to-program communication using SNA LU6.2. See also *Systems Network Architecture*.

Common User Access (CUA). Guidelines for the dialog between a human and a workstation or terminal. One of the three SAA architectural areas.

communication manager. A component of OS/2 that allows a workstation to connect to a host computer and use the host resources as well as the resources of other personal computers to which the workstation is attached, either directly or through a host.

communication method. The method used by a client and server for exchanging information.

communication protocol. A set of defined interfaces that allow computers to communicate with each other.

compression. The process of saving storage space by eliminating empty fields or unnecessary data to shorten the length of the file. In ADSM, compression can occur at a workstation before files are backed up or archived to server storage. On some types of tape drives, hardware compression can be used.

Configuration Installation and Distribution (CID). IBM's term for capabilities to automate installation. CID-enabled products are capable of unattended, remote installation.

contextual help. A type of online help that provides specific information for each selectable object, menu choice, notebook tab, field, and control or push button in a window.

conversion. On VM servers, the process of changing from WDSF/VM to ADSM.

copy group. A policy object that contains attributes that control the generation, destination, and expiration of backup and archive files. There are two kinds of copy groups: backup and archive. Copy groups belong to management classes. See also *frequency*, *destination*, *mode*, *serialization*, *retention*, and *version*.

copy status. The status of volume copies defined to the database or recovery log. The copy status can be synchronized, stale, off-line, or undefined.

copy storage pool. A named set of volumes that contains copies of files that reside in primary storage pools. Copy storage pools are used to back up the data stored in primary storage pools. A copy storage pool cannot be a destination for a backup copy group, an archive copy group, or a management class (for space-managed files). See *primary storage pool* and *destination*.

CPI-C. Common Programming Interface Communications.

CST. Cartridge system tape.

CUA. Common User Access.

D

daemon. In the AIX operating system, a program that runs unattended to perform a standard service. Some daemons are triggered automatically to perform their tasks; others operate periodically.

daemon process. In the AIX operating system, a process begun by the root user or by the root shell that can be stopped only by the root user. Daemon processes generally provide services that must be available at all times, such as sending data to a printer.

damaged file. A file for which ADSM has detected data-integrity errors.

DASD. Direct access storage device.

database. A collection of information about all objects managed by the server, including policy management objects, users and administrators, and client nodes.

database audit. A utility that checks for and optionally corrects inconsistent database references.

database backup series. One full backup of the database, plus up to 32 incremental backups made since that full backup. Each full backup that is run starts a new database backup series. A backup series is identified with a number.

database backup trigger. A set of criteria that defines when and how database backups are run automatically. The criteria determine how often the backup is run, whether the backup is a full or incremental backup, and where the backup is stored.

database buffer pool. Storage that is used as a cache to allow database pages to remain in memory for long periods of time, so that the server can make continuous updates to pages without requiring input or output (I/O) operations from external storage.

database dump. A utility that copies database entries to media for later reload in case a catastrophic error should occur.

database load. A utility that copies database entries from media to a newly installed database.

database volume. A volume that has been assigned to the database.

dataserver. See *Tape Library Dataserver*.

data set. See *linear data set*.

data storage. The primary and copy storage pools used by the server to store users' files: backup versions, archive copies, and files migrated from client nodes (space-managed files). Synonymous with *server storage*. See *primary storage pool*, *copy storage pool*, *storage pool volume*, and *volume*.

DDM. Distributed Data Management.

default management class. A management class assigned to a policy set, which is used to govern backed up or archived files when a user does not explicitly bind a file to a specific management class.

definition. Server control information that includes administrator, client node, and policy definitions. A definition can be exported from a source server to

external media so that it can be imported to a target server at a later date.

deletion exit. An installation-wide exit that informs a tape management system or operator that the server has deleted a sequential access media volume from its database.

delimiter. (1) A character used to indicate the beginning and end of a character string. (2) A character that groups or separates words or values in a line of input.

density. On MVS and VM servers, a device class attribute that identifies the bits per inch that can be stored on tape reels. ADSM supports 1600 and 6250 bits per inch (bpi).

desktop. On-screen representation of a desk top.

desktop client. The group of clients supported by ADSM that are not UNIX-based and are not OpenEdition MVS. For example, a DOS client is a desktop client.

destination. A copy group or management class attribute that specifies the primary storage pool to which a client file will be backed up, archived, or migrated. At installation, ADSM provides storage destinations named BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL.

device class. A named group of storage devices. Each device class has a unique name and represents a device type of disk, file, optical disk, or tape.

device configuration file. A file that contains information about defined device classes, and, on AIX servers, defined libraries and drives. The file can be created by using an ADSM command or by using an option in the server options file. The information is a copy of the device configuration information in the ADSM database.

device driver. A collection of subroutines that control the interface between I/O device adapters and the processor.

device type. A category of storage device. Each device class must be categorized with one of the supported device types, for example, DISK or CARTRIDGE.

direct access storage device (DASD). A device in which access time is effectively independent of the location of the data.

DISK. A device class that is defined by ADSM at installation. It is used to categorize disk drives, such as 3390 DASD or 3380 DASD.

diskette. A small, magnetic disk enclosed in a jacket.

disk operating system (DOS). An operating system used in IBM PC, PS/2, and compatible computers.

Distributed Data Management (DDM). A feature of the System Support Program Product that allows an application program (client) to use server program functions to work on files that reside in a remote system.

DLL. Dynamic link library.

DLT. Digital linear tape.

domain. See *policy domain* or *client domain*.

DOS. Disk operating system.

drive. A device used to read and write data on a medium such as a disk, diskette, or tape.

dsm.opt file. See *client options file* and *client user options file*.

dsm.serv.opt. See *server options file*.

dsm.sys file. See *client system options file*.

dynamic. A copy group serialization value that specifies that ADSM accepts the first attempt to back up or archive a file regardless of whether the file is modified during the backup or archive process. See also *serialization*. Contrast with *shared dynamic*, *shared static*, and *static*.

dynamic link library. A file containing executable code and data bound to a program at load time or run time, rather than during linking. The code and data in a dynamic link library can be shared by several applications simultaneously.

E

ECCST. Enhanced capacity cartridge system tape.

enhanced capacity cartridge system tape (ECCST). Cartridge system tape with increased capacity that can only be used with 3490E tape subsystems. Contrast with *cartridge system tape*.

error log. A character file written on random access media that contains information about errors detected by the server or client.

estimated capacity. The available space, in megabytes, of a storage pool.

Ethernet. A data link protocol and LAN that interconnects personal computers and workstations via coaxial cable.

event. Administrative commands or client operations that are scheduled to be executed at a particular time.

event record. A database record that describes actual status and results for events.

exclude. The process of identifying files or directories in an include-exclude list to prevent these objects from being backed up whenever a user or schedule issues an incremental or selective backup operation, or to prevent these objects from being migrated off the client node via ADSM space management.

exclude-include list. See *include-exclude list*.

exit. To execute an instruction within a portion of a computer program in order to terminate the execution of that portion.

exit machine. On a VM server, a virtual machine that runs the mount and deletion installation-wide exits on VM systems.

expiration. The process by which files are identified for deletion because their expiration date or retention period has passed. Backed up or archived files are marked expired by ADSM based on the criteria defined in the backup or archive copy group.

expiration date. On MVS, VM, and VSE servers, a device class attribute used to notify tape management systems of the date when ADSM no longer needs a tape volume. The date is placed in the tape label so that the tape management system does not overwrite the information on the tape volume before the expiration date.

export. The process of copying administrator definitions, client node definitions, policy definitions, server control information or file data to external media.

export/import facility. See *import/export facility*.

extend. The process of increasing the portion of available space that can be used to store database or recovery log information. Contrast with *reduce*.

F

file data. File space definitions, authorization rules, backed up files, archive copies, and space-managed files. File data can be exported from a source server to external media so that it can be imported to a target server at a later date.

file record extent. The extent of the file enumerated in number of records.

file space. A logical space in a client's storage that can contain a group of files. For clients on systems such as OS/2, a file space is a logical partition and is identified by a volume label. For clients on systems such as AIX and UNIX, a file space can consist of any subset of directories and subdirectories stemming from a virtual mount point. Clients can restore, retrieve, or delete their file spaces from ADSM server storage. ADSM does not necessarily store all the files from a single file space together, but can identify all the files in server storage that came from a single file space.

File Transfer Protocol (FTP). In TCP/IP, the protocol that makes it possible to transfer data among hosts and to use foreign hosts indirectly.

format. A device class attribute that specifies the recording format used to read or write to sequential access media, for example to cartridge tape.

frequency. A copy group attribute that specifies the minimum interval, in days, between incremental backups.

FTP. File Transfer Protocol.

full backup. An ADSM function that copies the entire database. A full backup begins a new database backup series. Contrast with *incremental backup*. See *database backup series*.

fuzzy copy. A backup version or archive copy of a file that might not accurately reflect what is currently in the file because ADSM backed up or archived the file while the file was being modified.

G

general help. A type of online help that provides an overview of the function of the window.

graphical user interface (GUI). A type of user interface that takes advantage of a high-resolution monitor, including some combination of graphics, the object-action paradigm, the use of pointing devices, menu bars, overlapping windows, and icons. See *windowed interface*. Contrast with *command line interface*.

group of mirrored volumes. One, two, or three volume copies defined to the database or recovery log. Each volume copy in the group contains exactly the same portion of the database or recovery log. See *mirroring*.

GUI. Graphical user interface.

H

handle. A data structure that is a temporary local identifier for an object. A handle identifies an object at a specific location by binding it.

HDA. Head-disk assembly.

head-disk assembly (HDA). A field replaceable unit in a direct access storage device containing the disks and actuators.

help index. A type of online help that provides an alphabetic listing of all help topics.

hierarchical storage management (HSM) client. A program that runs on workstations to allow users to maintain free space on their workstations by migrating and recalling files to and from ADSM storage. The HSM client allows use of ADSM space management functions. Synonymous with *space management client*.

high migration threshold. A percentage of the storage pool capacity that identifies when ADSM can start migrating files to the next available storage pool in the hierarchy. Contrast with *low migration threshold*. See *server migration*.

HP-UX. Hewlett-Packard UNIX operating system. HP-UX is one of the operating systems that ADSM supports as a client environment and a server environment.

HSM client. Hierarchical storage management client.

I

import. The process of copying administrator definitions, client node definitions, policy definitions, server control information or file data from external media to a target server.

import/export facility. The facility that allows system administrators to copy definitions and file data from a source server to external media to move or copy information between servers. Any subset of information can be imported to a target server from the external media.

inactive version. A backup version of a file for which a more recently backed up version exists. Inactive backup versions are eligible for expiration processing according to the management class assigned to the file. Contrast with *active version*.

include-exclude file. On UNIX clients, a file containing statements that ADSM uses to determine whether to back up or migrate certain files, and to determine the associated management classes to use for backup, archive, and space management. See *include-exclude list*.

include-exclude list. A group of include and exclude option statements in a file. ADSM uses the statements to determine whether to back up or migrate certain files, and to determine the associated management classes to use for backup, archive, and space management. The exclude options identify files that should not be backed up or migrated off the client node. The include options identify files that are exempt from the exclusion rules, or assign a management class to a file or group of files for backup, archive, or space management services. The include-exclude list is defined either in the include-exclude file (for UNIX clients) or in the client options file (for other clients).

inconsistencies. Any discrepancy between the information recorded in the database about backed up or archived files and the actual data associated with backed up or archived files residing in server storage.

incremental backup. (1) A function that allows users to back up files or directories that are new or have changed since the last incremental backup. With this function, users can back up files or directories from a client domain that are not excluded in the include-exclude list and that meet the requirements for

frequency, mode, and serialization as defined in the backup copy group of the management class assigned to the files. Contrast with *selective backup*. (2) An ADSM function that copies only the pages in the database that are new or changed since the last full or incremental backup. Contrast with *full backup*. See *database backup series*.

internal mounting facility. On a VM server, a VM facility that allows the server to request tape mounts by sending a message to a mount operator. The message is repeated until the tape is mounted or until the mount wait time is exceeded.

inter-user communication vehicle (IUCV) facility. On a VM server, a VM communication method used to pass data between virtual machines and VM components.

IPX/SPX. Internetwork Packet Exchange/Sequenced Packet Exchange. IPX/SPX is Novell NetWare's communication protocol.

IUCV. Inter-user communication vehicle.

K

KB. Kilobyte.

kernel. The part of an operating system that performs basic functions such as allocating hardware resources.

kernel extension. A program that modifies parts of the kernel that can be customized to provide additional services and calls. See *kernel*.

kilobyte (KB). 1024 bytes.

L

LAN. Local area network.

length. A device class attribute that specifies the length of cartridge tape by specifying one of the following media types: CST for standard length tape or ECCST for double length tape.

library. (1) A repository for demountable recorded media, such as magnetic tapes. (2) In ADSM, a collection of one or more drives, and possibly robotic devices (depending on the library type), which can be used to access storage volumes. (3) In the AS/400 system, a system object that serves as a directory to

other objects. A library groups related objects, and allows the user to find objects by name.

linear data set. A type of MVS data set that ADSM uses for the database, the recovery log, and storage pools. The data set must be preallocated using VSAM IDCAMS and formatted by ADSM for its use. See *minidisk*.

load. See *mount*.

local area network (LAN). A network in which a set of devices are connected to one another for communication and that can be connected to a larger network.

log pool size. The size of an area in memory used to store recovery log pages.

logical volume. The combined space from all volumes defined to either the database or the recovery log. In ADSM, the database is one logical volume and the recovery log is one logical volume.

low migration threshold. A percentage of the storage pool capacity that specifies when ADSM can stop the migration of files to the next storage pool. Contrast with *high migration threshold*. See *server migration*.

M

macro file. An optional file that contains one or more administrative commands and is invoked from an administrative client.

management class. A policy object that users can bind to each file to specify how the server manages the file. The management class can contain a backup copy group, an archive copy group, and space management attributes. The copy groups determine how the ADSM server manages backup versions or archive copies of files. The space management attributes determine whether files are eligible for migration from client nodes to ADSM storage, and under what conditions. See also *copy group*, *binding* and *rebinding*.

mask. A pattern of characters that controls the keeping, deleting, or testing of positions of another pattern of characters or bits.

maximum extension. Specifies the maximum amount of storage space, in megabytes, that you can extend the database or recovery log.

maximum reduction. Specifies the maximum amount of storage space, in megabytes, that you can reduce the database or recovery log.

maximum utilization. The highest percentage of assigned capacity used by the database or recovery log.

MB. Megabyte.

megabyte (MB). (1) For processor storage and real and virtual memory, 2²⁰ or 1 048 576 bytes. (2) For disk storage capacity and transmission rates, 1 000 000 bytes.

migrate. (1) To move data from one storage pool to the storage pool specified as the next pool in the hierarchy. The process is controlled by the high and low migration thresholds for the first storage pool. See *high migration threshold* and *low migration threshold*. (2) To copy a file from a client node to ADSM storage. ADSM replaces the file with a stub file on the client node. The process is controlled by the include-exclude list and by space management attributes in management classes.

migration. The process of moving data from one storage location to another. See *client migration* and *server migration*.

minidisk. A logical subdivision of a VM physical disk that provides storage on contiguous cylinders of DASD. On a VM server, a minidisk can be defined as a disk volume that can be used by the database, recovery log, or a storage pool. See also *linear data set*.

mirroring. A feature that protects against data loss within the database or recovery log by writing the same data to multiple disks at the same time. Mirroring supports up to three exact copies of each database or recovery log volume. See *group of mirrored volumes*.

mm. Millimeter.

mode. A copy group attribute that specifies whether to back up a file that has not been modified since the last time the file was backed up. See *modified* and *absolute*.

modified. A backup copy group mode value indicating that a file is considered for incremental backup only if it has changed since the last backup. A file is considered changed if the date, size, owner, or permissions have changed. See *mode*. Contrast with *absolute*.

Motif. A graphical user interface that performs window management and contains a high level toolkit for application program development. It provides an icon view of the UNIX file system. Also known as X-Windows/Motif or Motif X—Toolkit.

mount. To place a data medium (such as a tape cartridge) on a drive in a position to operate.

mount exit. On a VM server, an installation-wide exit (DSMMOUNT EXEC) that requests tape mounts on behalf of the server on VM systems.

mount limit. A device class attribute specifying the maximum number of volumes that can be simultaneously accessed from the same device class, that is, the maximum number of mount points. See *mount point*.

mount operator. On a VM server, a VM user ID that can receive tape mount messages from the server.

mount point. A logical drive through which ADSM accesses volumes in a sequential access device class. For a device class with a removable media device type (for example, CARTRIDGE), a mount point is a logical drive associated with a physical drive. For a device class with the device type of FILE, a mount point is a logical drive associated with an I/O stream. The number of mount points for a device class is determined by the mount limit for that class. See *mount limit*.

mount request. A server request to mount a sequential access media volume so that data can be read from or written to the sequential access media.

mount retention period. A device class attribute that specifies the maximum amount of time, in minutes, that the server retains a mounted sequential access media volume that is not being used before it dismounts the sequential access media volume.

mount wait period. A device class attribute that specifies the maximum amount of time, in minutes, that the server waits for a sequential access volume mount request to be satisfied before canceling the request.

Multiple Virtual Storage (MVS). One of the family of IBM operating systems for the System/370 or System/390 processor, such as MVS/ESA. MVS is one of the supported server environments.

MVS. Multiple Virtual Storage.

N

Named Pipes. A communication protocol that is built into the OS/2 operating system. It can be used to establish communications between an ADSM/2 server and OS/2 clients. The client and ADSM/2 server must reside on the same system.

NetBIOS. Network Basic Input/Output System.

network adapter. A physical device, and its associated software, that enables a processor or controller to be connected to a network.

Network Basic Input/Output System (NetBIOS). An operating system interface for application programs used on IBM personal computers that are attached to the IBM Token-Ring Network.

Network File System (NFS). A protocol defined by Sun Microsystems that extends TCP/IP network file services. NFS permits remote node files to appear as though they are stored on a local workstation.

Networking Services/DOS (NS/DOS). A software product that supports advanced program-to-program communications (APPC) in the DOS and Microsoft Windows 3.1 environments. With NS/DOS, communications applications on your workstation "talk to" partner applications on other systems that support APPC.

NFS. Network File System.

node. A unique name used to identify a workstation to the server. See also *client node*.

notebook. A graphical representation that resembles a spiral-bound notebook that contains pages separated into sections by tabbed divider-pages. A user can "turn" the pages of a notebook to move from one section to another.

notify operator. A VM user ID that specifies an operator who receives messages about severe errors and abnormal conditions.

O

object. A collection of data managed as a single entity.

offsite volume. A removable media volume that is at a location where it cannot be mounted for use.

OpenEdition MVS. MVS/ESA services that support an environment within which operating systems, servers, distributed systems, and workstations share common interfaces. OpenEdition MVS supports standard application development across multivendor systems and is required to create and use applications that conform to the POSIX standard.

open registration. A registration process in which users can register their own workstations as client nodes with the server. Contrast with *closed registration*.

Operating System/2 (OS/2). An operating system used in IBM PC AT, PS/2, and compatible computers. OS/2 is one of the supported client environments and one of the supported server environments.

operator privilege class. An administrative privilege class that allows an administrator to issue commands that control the operation of the server. This privilege class allows disabling or halting the server to perform maintenance, enabling the server, canceling server processes, and managing tape.

optical disk. A disk that contains data readable by optical techniques.

optical drive. A drive mechanism that rotates an optical disc.

optical library. A disk storage device that houses optical disk drives and optical disks, and contains a mechanism for moving optical disks between a storage area and optical disk drives.

OS/2. Operating System/2.

OS/400. Operating System/400.

owner. The owner of backup-archive files sent from a multiuser client node, such as AIX.

P

page. (1) A block of instructions, data, or both. (2) In ADSM, a unit of space allocation within database volumes. (3) In a virtual storage system, a fixed block that has a virtual address and is transferred as a unit between real storage and auxiliary storage.

paging. (1) The action of transferring instructions, data, or both, between real storage and external page storage. (2) Moving data between memory and a mass storage device as the data is needed.

pattern-matching expression. A string expression that uses wildcard characters to specify one or more ADSM objects. See also *wildcard character*.

PC Support/400. A software product that supports advanced program-to-program communications (APPC) in the DOS, OS/2, and Microsoft Windows environments and provides a set of end user services.

platform. The operating system environment in which a program runs.

policy definition. Server control information that includes information about policy domains, policy sets (including the ACTIVE policy set), management classes (including the default management class), copy groups, schedules, and associations between client nodes and schedules. A policy definition can be exported from a source server so that it can be imported to a target server at a later date.

policy domain. A policy object that contains policy sets, management classes, and copy groups that is used by a group of client nodes. See *policy set*, *management class*, and *copy group*.

policy privilege class. An administrative privilege class that allows an administrator to manage policy objects, register client nodes, and schedule client operations (such as backup services) for client nodes. Administrators can be authorized with unrestricted or restricted policy privilege. See *unrestricted policy privilege* or *restricted policy privilege*.

policy set. A policy object that contains a group of management class definitions that exist for a policy domain. At any one time there can be many policy sets within a policy domain but only one policy set can be active. See *management class* and *active policy set*.

premigration. For an HSM client, the process of copying files that are eligible for migration to ADSM storage, but leaving the original file intact on the local system.

primary storage pool. A named set of volumes that ADSM uses to store backup versions of files, archive copies of files, and files migrated from client nodes via ADSM space management. A primary storage pool may be backed up to a copy storage pool either automatically or by command. See *destination* and *copy storage pool*.

privilege class. A level of authority granted to an ADSM administrator. ADSM has five privilege classes: system, policy, storage, operator, and analyst. The privilege class determines which ADSM administrative tasks the administrator can perform. For example, an administrator with system privilege class can perform any administrative task.

programmable workstation communication services (PWSCS). A product that provides transparent high performance communications between programs running on workstations or on host systems.

protection status. A device class attribute that specifies whether to update the RACF profile to identify which users have access to cartridge tapes associated with this device class on MVS servers.

PWSCS. Programmable workstation communication services.

Q

QIC. Quarter-inch cartridge (a type of magnetic tape media).

R

random access media. Any volume accessed in a nonsequential manner. In ADSM, volumes are accessed in a nonsequential manner if they reside in the DISK device class.

randomization. The percentage of the startup window that the server can use to randomize start times for different client nodes associated with a schedule.

rebinding. The process of associating a file with a new management class name. For example, rebinding occurs when the management class associated with a file is deleted. See *binding*.

recall. A function that allows users to access files that have been migrated from their workstations to ADSM storage via ADSM space management. Contrast with *migrate*.

reclamation. A process of consolidating the remaining data from many sequential access media onto a single new sequential access media.

reclamation threshold. A value that specifies a percentage of space on sequential access media volumes that can be occupied by reclaimable space. The remainder of the space is for active data. (Space becomes reclaimable when files are expired.)

recovery log. A log of updates that are about to be written to the database. The log can be used to recover from system and media failures.

recovery log buffer pool. Used to hold new transactions records until they can be written to the recovery log.

reduce. The process of freeing up enough space to allow you to delete a volume from the database or recovery log. Contrast with *extend*.

REEL. On ADSM servers that support it, a device class that is used to categorize tape devices that support tape reels, such as the 3420 9-track tape device.

register. Defines a client node or administrator who can access the server. See *registration*.

registration. The process of identifying a client node or administrator to the server.

reply operator. On a VM server, a VM user ID that specifies an operator who will reply to tape mount requests by the server.

restore. The process of returning a backup copy to an active storage location for use. ADSM has processes for restoring its database, storage pools, storage pool volumes, and users' backed-up files. For example, users can copy a backup version of a file from the storage pool to the workstation. The backup version in the storage pool is not affected. Contrast with *backup*.

restricted policy privilege. An administrative privilege class that enables an administrator to manage policy objects only for the policy domains for which the administrator has been authorized.

restricted storage privilege. An administrative privilege class that enables an administrator to control the allocation and use of storage resources only for the storage pools for which the administrator has been authorized.

retention. The amount of time, in days, that inactive backed up or archived files will be retained in the storage pool before they are deleted. The following copy group attributes define retention: retain extra versions, retain only version, retain version.

retention period. On an MVS server, a device class attribute that specifies how long files are retained on sequential access media. When used, ADSM passes this information to the MVS operating system to ensure that other tape management systems do not overwrite tape volumes that contain retained data.

retrieve. A function that allows users to copy an archive copy from the storage pool to the workstation. The archive copy in the storage pool is not affected. Contrast with *archive*.

RLIO. Record Level Input/Output.

rollback. To remove changes that were made to database files since the last commit point.

root. In the AIX and UNIX environments, the user name for the system user with the most authority.

root user. In the AIX and UNIX environments, an expert user who can log in and execute restricted commands, shut down the system, and edit or delete protected files. Also called the *superuser*.

routing choice. A choice in a pull-down menu that, when selected, brings up another window. See also *action choice*.

S

SAA. Systems Application Architecture.

schedule. A database record that describes scheduled client operations or administrative commands. See *administrative command schedule* and *client schedule*.

scheduling mode. The type of scheduling operation set for the server and client. ADSM supports two scheduling modes for client operations: client-polling and server-prompted.

scratch volume. A volume that is available for ADSM use. The volume is labeled, is either blank or contains no valid data, and is not defined to ADSM.

SCSI. Small computer system interface.

selective backup. A function that allows users to back up specific files or directories from a client domain. With this function, users can back up files or directories that are not excluded in the include-exclude list and that meet the requirement for serialization as defined in the backup copy group of the management class assigned to the files. Contrast with *incremental backup*.

sequential access media. Any volume that is accessed in a sequential manner, as opposed to a random manner. In ADSM, volumes are accessed sequentially if they reside in a device class other than DISK.

serialization. A copy group attribute that specifies what ADSM does if files are modified during back up or archive processing. The value of this attribute determines whether processing continues, is retried, or is stopped. See *static*, *dynamic*, *shared static*, and *shared dynamic*.

server. A program that provides services to other programs (clients).

server migration. The process of moving data from one storage pool to the next storage pool as controlled by the high and low migration thresholds. See *high migration threshold* and *low migration threshold*.

server options file. A file that specifies processing options for communication methods, tape handling, pool sizes, language, and date, time, and number formats.

server program. The program that provides backup, archive, space management, and administrative services to clients. The server program must be at the necessary level to provide all of these services.

server-prompted scheduling mode. A client/server communication technique where the server contacts the client when work needs to be done.

server storage. The primary and copy storage pools used by the server to store users' files: backup versions, archive copies, and files migrated from client nodes (space-managed files). Synonymous with *data storage*. See *primary storage pool*, *copy storage pool*, *storage pool volume*, and *volume*.

session resource usage. The amount of wait time, CPU time, and space used or retrieved during a client session.

shared dynamic. A copy group serialization value that specifies that a file must not be modified during a backup or archive operation. ADSM attempts to retry the backup or archive operation a number of times; if the file is in use during each attempt, ADSM will back up or archive the file on its last try even though the file is in use. See also *serialization*. Contrast with *dynamic*, *shared static*, and *static*.

shared static. A copy group serialization value that specifies that the file must not be modified during backup or archive. ADSM will retry the backup or archive operation a number of times; if the file is in use during each attempt, ADSM will not back up or archive the file. See also *serialization*. Contrast with *dynamic*, *shared dynamic*, and *static*.

shell. In the AIX and UNIX environments, a software interface between a user and the operating system of a computer. Shell programs interpret commands and user interactions on devices such as keyboards, pointing devices, and touch-sensitive screens and communicate them to the operating system.

signal. (1) A simple method of communication between two processes. One process can inform the other process when an event occurs. (2) In operating system operations, a method of inter-process communication that simulates software interrupts.

signal handler. A subroutine called when a signal occurs.

SMIT. System Management Interface Tool.

SNA LU6.2. Systems Network Architecture Logical Unit 6.2.

socket. (1) An endpoint for communication between processes or applications. (2) A pair consisting of TCP port and IP address, or UDP port and IP address.

space-managed file. A file that is migrated from and recalled to a client node via ADSM space management.

space management. The process of keeping sufficient free storage space available on a client node by migrating files to ADSM storage. The files are migrated based on criteria defined in management classes to which files are bound, and the include-exclude list.

Synonymous with *hierarchical storage management*. See also *migration*.

space management client. A program that runs on workstations to allow users to maintain free space on their workstations by migrating and recalling files to and from ADSM storage. Synonymous with *hierarchical storage management client*.

SPACEMGPPOOL. A disk storage pool defined by ADSM at installation. It can be the destination for files that are migrated from client nodes via ADSM space management. See *storage pool*.

stale copy status. Specifies that a volume copy is not available to the database or recovery log.

STANDARD copy group. A backup or archive copy group that is defined by ADSM at installation. See *copy group*.

STANDARD management class. A management class that is defined by ADSM at installation. See *management class*.

STANDARD policy domain. A policy domain that is defined by ADSM at installation. See *policy domain*.

STANDARD policy set. A policy set that is defined by ADSM at installation. See *policy set*.

stanza. A group of lines in a file that together have a common function or define a part of the system. Stanzas are usually separated by blank lines or colons, and each stanza has a name.

startup window. A time period during which a schedule must be initiated.

static. A copy group serialization value that specifies that the file must not be modified during backup or archive. If the file is modified during the attempt, ADSM will not back up or archive the file. See also *serialization*. Contrast with *dynamic*, *shared dynamic*, and *shared static*.

storage hierarchy. A logical ordering of primary storage pools, as defined by an administrator with system privilege. Generally, the ordering is based on the speed and capacity of the devices that the storage pools use. In ADSM, the storage hierarchy is defined by

identifying the *next* storage pool in a storage pool definition. See *storage pool*.

storage management services. A component that allows a central system to act as a file backup and archive server for local area network file servers and workstations.

storage pool. A named set of storage volumes that ADSM uses to store client data. A storage pool is either a primary storage pool or a copy storage pool. See *primary storage pool* and *copy storage pool*.

storage pool volume. A volume that has been assigned to an ADSM storage pool. See *volume*, *copy storage pool*, and *primary storage pool*.

storage privilege class. An administrative privilege class that allows an administrator to control the allocation and use of storage resources for the server, such as monitoring the database, recovery log, and server storage. Administrators can be authorized with unrestricted or restricted storage privilege. See *restricted storage privilege* or *unrestricted storage privilege*.

stub file. A file that replaces the original file on a client node when the file is migrated from the client node to ADSM storage.

superuser. See *root user*.

synchronized copy status. Specifies that the volume is the only volume copy or is synchronized with other volume copies in the database or recovery log. When synchronized, mirroring has started.

system privilege class. An administrative privilege class that allows an administrator to issue all server commands.

Systems Application Architecture (SAA). Software interfaces, conventions, and protocols that provide a framework for designing and developing applications that are consistent across systems.

Systems Network Architecture (SNA). A set of rules for data to be transmitted in a network. Application programs communicate with each other using a layer of SNA called advanced program-to-program communications (APPC).

T

tape. A recording medium consisting of a long, narrow, flexible strip with a magnetic coating wound onto a reel or into a cartridge. See *cartridge* and *tape reel*.

tape library. (1) A term used to refer to a collection of tape cartridges. (2) An automated device that performs tape cartridge mounts and demounts without operator intervention.

Tape Library Dataserver. An automated tape library consisting of mechanical components, cartridge storage frames, IBM tape subsystems, and controlling hardware and software. The tape library dataserver performs tape cartridge mounts and demounts without operator intervention.

tape reel. A cylinder with flanges on which magnetic tape is wound. Devices such as the 3420 9-track tape device support tape reels. Contrast with *cartridge*.

tape volume prefix. A device class attribute that is the high-level-qualifier of the file name or the data set name in the standard tape label.

task help. A type of online help that provides a list of tasks that can be completed with a selected object. When you select a task, the help provides step-by-step information on how to complete the task.

TCP/IP. Transmission Control Protocol/Internet Protocol.

Telnet. In TCP/IP, the protocol that opens the connection to the system.

Transmission Control Protocol/Internet Protocol (TCP/IP). A set of communication protocols that support peer-to-peer connectivity functions for both local and wide area networks.

trusted communication agent. A program that performs communication tasks on behalf of the client or server, and ensures the security of the communications.

U

unit name. On an MVS server, a device class attribute that specifies a group of tape devices used with the MVS server. A unit name can be a generic device type, an esoteric unit name, or a physical device.

unrestricted policy privilege. An administrative

privilege class that enables an administrator to manage policy objects for any policy domain.

unrestricted storage privilege. An administrative privilege class that enables an administrator to control the database, recovery log, and all storage pools.

utilization. The percent of assigned capacity used by the database or recovery log at a specific point of time.

V

validate. The process of ensuring that the active policy set contains a default management class and reporting on copy group definition errors.

version. The maximum number of backup copies retained for files and directories. The following copy group attributes define version criteria: *versions data exists* and *versions data deleted*.

Virtual Machine (VM). One of the family of IBM operating systems for the System/370 or System/390 processor, including VM/ESA, VM/XA, VM/SP, and VM/HPO. VM is one of the supported server environments.

Virtual Storage Extended (VSE). One of the family of IBM operating systems for the System/370 or System/390 processor, including VSE/ESA. VSE is one of the supported server environments.

VM. Virtual Machine.

volume. The basic unit of storage for the database, recovery log, or a storage pool. A volume can be an LVM logical volume, a standard file system file, a tape cartridge, or an optical cartridge. Each volume is identified by a unique volume identifier. See *database volume*, *scratch volume*, and *storage pool volume*.

volume history file. A file that contains information about: volumes used for database backups and database dumps; volumes used for export of administrator, node, policy, or server data; and sequential access storage pool volumes that have been added, reused, or deleted. The information is a copy of the same types of volume information in the ADSM database.

volume set. An entire image of the database or recovery log, as displayed on the administrative graphical user interface.

VSE. Virtual Storage Extended.

W

WDSF/VM. Workstation Data Save Facility/Virtual Machine.

wildcard character. A character or set of characters used to specify an unknown number or set of characters in a search string. Also called *pattern-matching character*.

window. A part of a display screen with visible boundaries in which information is displayed.

windowed interface. A type of user interface that is either a graphical user interface or a text based interface. The text based interface maintains a close affinity to the graphical user interface, including action

bars and their associated pull-downs and windows. See *graphical user interface*.

workstation. A personal computer system capable of maintaining data files.

Workstation Data Save Facility/Virtual Machine (WDSF/VM). The predecessor product to ADSTAR Distributed Storage Manager.

WORM. A type of optical media that can only be written to and cannot be erased.

X

X Windows. A network transparent windowing system developed by MIT. It is the basis for other products, such as Enhanced X Windows which runs on the AIX operating system.

Index

A

- absolute mode, description of 176
- access mode 132
- accounting record
 - description of 228
 - determining for storage pool 110, 113
 - monitoring 228
- ACTIVATE POLICYSET command 181, 329
- activity log
 - adjusting the size 226
 - description of 226
 - monitoring 226
 - querying 227
 - setting the retention period 227
- administrative client
 - description of 3
 - viewing information after IMPORT or EXPORT 278
- administrative commands
 - AUDIT LICENSE 254
 - AUDIT VOLUME 141
 - BACKUP DB 314
 - BACKUP DEVCONFIG 313
 - BACKUP STGPOOL 302
 - BACKUP VOLHISTORY 311
 - DEFINE DEVCLASS 75
 - DEFINE DOMAIN 172
 - DEFINE SCHEDULE 204
 - DEFINE STGPOOL 112
 - DEFINE VOLUME 133
 - DELETE DEVCLASS 78
 - DELETE LOGVOLUME 245
 - DELETE VOLHISTORY 311, 312
 - DELETE VOLUME 148
 - DISMOUNT DEVICE 46
 - DISMOUNT VOLUME 46
 - EXTEND LOG 308
 - GRANT AUTHORITY 256
 - HELP 230
 - MOVE DATA 144
 - QUERY ACTLOG 227
 - QUERY DB 243
 - QUERY DBBACKUPTRIGGER 310
 - QUERY DEVCLASS 77
 - QUERY LICENSE 255
 - QUERY MOUNT 43
- administrative commands (*continued*)
 - QUERY OCCUPANCY 123, 124, 125
 - QUERY OPTION 225
 - QUERY PROCESS 146
 - QUERY REQUEST 43, 45
 - QUERY STGPOOL 117, 118, 287
 - QUERY VOLHISTORY 311
 - QUERY VOLUME 135, 147
 - REGISTER ADMIN 256
 - REGISTER LICENSE 252
 - RENAME ADMIN 262
 - RESET DBMAXUTILIZATION 235, 236
 - RESET LOGCONSUMPTION 308
 - RESET LOGMAXUTILIZATION 235, 236
 - RESTORE STGPOOL 303, 324
 - RESTORE VOLUME 325
 - SET ACCOUNTING 228
 - SET ACTLOGRETENTION 226
 - SET AUTHENTICATION 255
 - SET LICENSEAUDITPERIOD 255
 - SET LOGMODE 311
 - SET PASSEXP 255
 - SET SCHEDMODES 200
 - SET SERVERNAME 225
 - UPDATE ADMIN 256
 - UPDATE DBBACKUPTRIGGER 310
 - UPDATE DEVCLASS 70
 - UPDATE SCHEDULE 204
 - UPDATE VOLUME 133
- administrative privilege class
 - analyst 260
 - description of 256
 - granting authority 256
 - operator 260
 - policy 258
 - reducing 261
 - revoking all 261
 - storage 258, 259
 - system 257
- administrator
 - authorizing to manage a policy domain 256
 - description of 3
 - locking 263
 - managing registration 251
 - querying 263
 - registering 256

- administrator (*continued*)
 - removing 262
 - renaming 262
 - unlocking 263
 - updating 256
 - viewing information about 263
- analyst privilege class
 - changing administrative authority 261
 - description of 260
 - granting 260
- API
 - See application programming interface
- application client, registering 271
- application programming interface
 - compression option 271
 - deletion option 272
 - description of 3
 - registering to server 271
- ARCHDELETE parameter 266
- archive
 - allowing client deletion of 266
 - amount of space used 125
 - defining criteria 170
 - description of 21
 - processing 166
- archive copy group
 - defining 179, 181
 - deleting 187
 - description of 158
- archive file management 156
- archiving a file 156, 166
- ASSIGN DEFMGMTCLASS command 181, 329
- assigned capacity 235, 241
- association
 - defining 196
 - deleting 213
 - description of 204
 - querying 212
 - viewing information about 212
- audit license 257
- AUDIT LICENSE command 254, 329
- AUDIT VOLUME command 139, 141, 329
- auditing
 - license, automatic by server 254
 - multiple volumes in sequential access storage pool 142
 - single volume in sequential access storage pool 143
 - volume in disk storage pool 141

- authentication, client/server 255
- authority
 - granting to administrators 256
 - revoking 260
- automating
 - client operations 195
 - server operations 194

B

- BACKDELETE parameter 266
- background processes 222
- backup
 - allowing client deletion of 266
 - amount of space used 125
 - database 309, 314
 - defining criteria 170
 - description of 21
 - file management 156
 - file, by client 156, 164, 166
 - incremental 156, 164
 - selective 156, 166
 - storage pool 302
 - when to perform for database 307
- backup copy group
 - defining 175, 179
 - deleting 187
 - description of 158
 - frequency 164
 - mode 164
 - serialization 164
- BACKUP DB command 314, 329
- BACKUP DEVCONFIG command 313, 329
- backup period, specifying for incremental 200
- BACKUP STGPOOL command 302, 329
- BACKUP VOLHISTORY command 311, 329
- backup-archive client
 - allowing file deletion by 266
 - description of 3
 - registering 265
- batch file, scheduling on client 193, 207
- binding
 - description of 161
 - file to a management class 161
- buffer pool 246
- BUFPOOLSIZE option 248

C

- cache
 - description of 21
 - disabling for disk storage pools 94
 - enabling for disk storage pools 94, 111
 - monitoring utilization on disk 122
- CANCEL PROCESS command 121, 223, 329
- CANCEL REQUEST command 45
- CANCEL SESSION command 221, 329
- capacity, assigned 235, 241
- cartridge 70
- central scheduling
 - controlling the workload 200
 - coordinating 198
 - description of 22, 193
- class, administrator privilege
 - analyst 260
 - description of 256
 - granting authority 256
 - operator 260
 - policy 258
 - reducing 261
 - revoking all 261
 - storage 258, 259
 - system 257
- class, device
 - amount of space used 124
 - CARTRIDGE 70
 - defining for database backup 306
 - deleting 78
 - description of 20
 - DISK 69
 - FILE 69
 - requesting information about 77
 - selecting for import and export 275
 - sequential 70, 75
 - tape 70
- class, policy privilege
 - changing administrative authority 261
 - description of 258
 - granting 258
- class, storage privilege
 - changing administrative authority 261
 - description of 259
 - granting 259
- client
 - administrative 3
 - application 271
 - backup-archive 21
 - client (*continued*)
 - HSM (space management) 3
 - client files, deleting 147
 - client migration 167
 - client node
 - allowing file deletion by 266
 - amount of space used 124
 - locking 267
 - managing registration 251, 264
 - querying 268
 - registering 265, 271
 - removing 271
 - renaming 267
 - setting password authentication 255
 - setting scheduling mode 200
 - unlocking 267
 - updating 267
 - viewing information about 268
 - client queries to the server, setting the frequency 203
 - client session
 - canceling 221
 - managing 219
 - querying 219
 - viewing information about 219
 - client system options file 272
 - client-polling scheduling 199, 202
 - client/server, description of 3
 - closed registration
 - description of 265
 - setting 265
 - collocation
 - changing, effect of 99
 - definition 95, 111, 114
 - description of 21
 - determining whether to use collocation 95, 111, 114
 - enabling for sequential storage pool 95, 111, 114
 - how it affects reclamation 104
 - how the server selects volumes when disabled 98
 - how the server selects volumes when enabled 98
 - migration thresholds 93
 - command file, scheduling on client 193, 207
 - command retry attempts
 - setting the amount of time between 203
 - setting the number of 203
 - commands, administrative
 - AUDIT LICENSE 254
 - AUDIT VOLUME 141
 - BACKUP DB 314
 - BACKUP DEVCONFIG 313
 - BACKUP STGPOOL 302

commands, administrative (*continued*)

- BACKUP VOLHISTORY 311
- DEFINE DEVCLASS 75
- DEFINE DOMAIN 172
- DEFINE SCHEDULE 204
- DEFINE STGPOOL 112
- DEFINE VOLUME 133
- DELETE DEVCLASS 78
- DELETE LOGVOLUME 245
- DELETE VOLHISTORY 311, 312
- DELETE VOLUME 148
- DISMOUNT DEVICE 46
- DISMOUNT VOLUME 46
- EXTEND LOG 308
- GRANT AUTHORITY 256
- HELP 230
- MOVE DATA 144
- QUERY ACTLOG 227
- QUERY DB 243
- QUERY DBBACKUPTRIGGER 310
- QUERY DEVCLASS 77
- QUERY LICENSE 255
- QUERY MOUNT 43
- QUERY OCCUPANCY 123, 124, 125
- QUERY OPTION 225
- QUERY PROCESS 146
- QUERY REQUEST 43, 45
- QUERY STGPOOL 117, 118, 287
- QUERY VOLHISTORY 311
- QUERY VOLUME 135, 147
- REGISTER ADMIN 256
- REGISTER LICENSE 252
- RENAME ADMIN 262
- RESET DBMAXUTILIZATION 235, 236
- RESET LOGCONSUMPTION 308
- RESET LOGMAXUTILIZATION 235, 236
- RESTORE STGPOOL 303, 324
- RESTORE VOLUME 325
- SET ACCOUNTING 228
- SET ACTLOGRETENTION 226
- SET AUTHENTICATION 255
- SET LICENSEAUDITPERIOD 255
- SET LOGMODE 311
- SET PASSEXP 255
- SET SCHEDMODES 200
- SET SERVERNAME 225
- UPDATE ADMIN 256
- UPDATE DBBACKUPTRIGGER 310
- UPDATE DEVCLASS 70
- UPDATE SCHEDULE 204

commands, administrative (*continued*)

- UPDATE VOLUME 133
- compression
 - option for API 271
 - setting at client registration 265
 - tape volume capacity, effect on 79
- configuration file, device
 - backup 312
 - example 313
 - information 312
 - recreating 313
- configuring
 - planning your storage environment 14
- console mode 278
- COPY DOMAIN command 172, 329
- copy group
 - deleting 187
 - description of 22
- COPY MGMTCLASS command 174, 329
- COPY POLICYSET command 173, 329
- COPY SCHEDULE command 208, 330

D

- data
 - considering user needs for recovering 15
 - exporting 273
 - importing 273
 - protection, methods 297
- data movement, querying about the process 146
- data storage
 - client files, process for storing 4
 - concepts overview 4
 - considering user needs for recovering 15
 - deleting files from 147
 - evaluating 14
 - managing 4
 - monitoring 139
 - planning 14
 - tailoring definitions 289
 - using disk devices 27
 - using tape devices 31
- database
 - adding space to 238
 - available space 235, 236
 - backup 314
 - backup trigger 309
 - buffer pool 246, 248
 - committing data to 248
 - defining a volume 240

- database (*continued*)
 - defining mirrored volumes 304
 - deleting a volume 245
 - deleting space 242
 - description of 22, 233
 - determining how much space is allocated 234, 236
 - ensuring integrity of 23
 - estimating the amount of space needed 236
 - logical volume 234, 236
 - managing 233
 - mirroring 303
 - monitoring space 235, 236
 - monitoring the buffer 248
 - optimizing performance 246
 - querying the buffer pool 247
 - recovering 314
 - reducing capacity 244
 - resetting buffer pool statistics 246
 - restoring 308
 - storage pool size effect 233
 - transactions 233, 234
 - viewing information about 247
 - volume placement 239
- database backup and recovery
 - defining device classes 306
 - full backup 307
 - incremental backup 307
 - point-in-time 316
 - roll-forward 299, 319
 - to most current state 319
 - trigger 309
- database backup trigger and roll-forward mode 319
- database recovery
 - example recovery procedures 322
 - general strategy 297
 - methods 297
 - providing 297
 - when to backup 307
- day of the week, description of 204
- default management class
 - description 160
 - where specified 159
- DEFINE ASSOCIATION command 196, 330
- DEFINE COPYGROUP command 175, 179, 181, 330
- DEFINE DBBACKUPTRIGGER 306, 309
- DEFINE DBCOPY command 304, 330
- DEFINE DBVOLUME command 240, 330
- DEFINE DEVCLASS command 75
- DEFINE DOMAIN command 172, 330
- DEFINE LOGCOPY command 314, 330
- DEFINE LOGVOLUME command 240, 330
- DEFINE MGMTCLASS command 174, 330
- DEFINE POLICYSET command 173, 330
- DEFINE SCHEDULE command 204, 330
- DEFINE STGPOOL command 112, 330
- DEFINE VOLUME command 133, 330
- delete
 - empty volume 148, 312
 - files 147
 - scratch volume 85, 312
 - storage volume 148
 - volume with residual data 148
- DELETE ASSOCIATION command 213
- DELETE COPYGROUP command 187
- DELETE DBBACKUPTRIGGER 309
- DELETE DBVOLUME command 245
- DELETE DOMAIN command 188
- DELETE EVENT command 212
- DELETE FILESPACE command 270
- DELETE LOGVOLUME command 245
- DELETE MGMTCLASS command 187
- DELETE POLICYSET command 188
- DELETE SCHEDULE command 209
- DELETE STGPOOL command 126
- DELETE VOLHISTORY command 311, 312
- DELETE VOLUME command 148
- deletion exit, using 65
- DEVCONFIG option 312
- device class
 - amount of space used 124
 - CARTRIDGE 70
 - defining for database backup 306
 - deleting 78
 - description of 20
 - DISK 69
 - FILE 69
 - requesting information about 77
 - selecting for import and export 275
 - sequential 70, 75
 - tape 70
- device configuration file
 - backup 312
 - example 313
 - information 312
 - recreating 313
- device type
 - CARTRIDGE 69
 - DISK 69
 - FILE 69

- device type (*continued*)
 - REEL 70
- DISABLE command 221
- disaster recovery
 - auditing storage pool volumes 320
 - example recovery procedures 322
 - general strategy 297
 - methods 297
 - providing 297
 - when to backup 297, 307
- disk device class, defined 69
- disk storage pool
 - cache, use of 95
 - estimating space 108
 - estimating space for archived files 109
 - estimating space for backed up files 108
 - migration threshold 89
- DISMOUNT DEVICE command 46
- DISMOUNT VOLUME command 46
- documentation, user xviii
- DSMDELETE EXEC 37, 65
- DSMINST EXEC 27, 239
- DSMMDISK EXEC 27, 133, 239, 304, 314
- DSMMOUNT EXEC 37, 39, 65
- DSMOP EXEC 42
- DSMSERV DISPLAY DBBACKUPVOLUME command 313
- DSMSERV RESTORE DB command 313
- dynamic serialization, description of 175, 180

E

- ENABLE command 222
- error states for tape volumes 41
- event record
 - deleting 212
 - description of 193
 - removing from the database 211
- event retention period 211
- event, description of 193
- exit machines
 - deletion 65
 - mount 50
- EXITVM option 48
- EXPINTERVAL option 163, 183
- expiration date, setting 205
- expiration processing
 - description 105
 - files eligible 163
 - starting 183

- EXPIRE INVENTORY command 163, 183
- export
 - labeling tapes 276
 - monitoring 276
 - planning for sequential media 275
 - PREVIEW parameter 275
 - querying about a process 277
 - querying the activity log 279
 - using scratch media 276
 - viewing information about a process 277
- EXPORT ADMIN command 282
- EXPORT commands 277, 278
- EXPORT NODE command 283
- EXPORT POLICY command 284
- EXPORT SERVER command 275, 282
- exporting
 - administrator data 282
 - client node data 283
 - data to tape 280
 - description of 22, 273
 - policy data 284
 - server data 282
- EXTEND DB command 241
- EXTEND LOG command 241

F

- file data, importing 273
- FILE device type
 - defining device class 69
 - deleting scratch volumes 312
- file size, determining maximum for storage pool 111
- file space
 - deleting 266, 270
 - description of 21, 269
 - querying 269
 - renaming 293
 - viewing information about 269
- files
 - allowing client to delete 266
 - deleting 147
 - server migration of 89
- formatting a volume for a storage pool 27
- frequency, description of 176

G

- GRANT AUTHORITY command 256

H

- HALT command 218
- halting the server 218
- HELP command 230
- hierarchical storage management
 - archive policy, relationship to 167
 - backup policy, relationship to 167
 - description 156
 - files, destination for 174
 - migration of client files
 - description 157
 - eligibility 167
 - policy for, setting 174
 - premigration 157
 - recall of migrated files 157
 - reconciliation between client and server 157
 - selective migration 157
 - setting policy for 167, 174
 - space-managed file, definition 156
 - stub file 157
- hierarchy, storage
 - defining in reverse order 112
 - establishing 85
- HSM
 - See hierarchical storage management

I

- I/O error, tape 41
- import
 - monitoring 276
 - PREVIEW parameter 275, 285
 - querying about a process 277
 - querying the activity log 279
 - recovering from an error 293
 - viewing information about a process 277
- IMPORT ADMIN command 284
- IMPORT commands 277, 278
- IMPORT NODE command 284, 291
- IMPORT POLICY command 284
- IMPORT SERVER command 284, 291
- importing
 - data 284
 - date of creation 291
 - description of 22, 273
 - directing messages to an output file 288
 - duplicate file spaces 291
 - file data 290
 - policy definitions 288

- importing (*continued*)
 - server control data 289
 - server storage definitions 287, 289
 - subsets of information 292
- include-exclude file
 - description of 22
 - for policy environment 170
- incremental backup
 - file eligibility for 164
 - full 164
 - partial 165
 - specifying frequency 200
- initial start date, description of 204
- initial start time, description of 204
- interface, application programming
 - compression option 271
 - deletion option 272
 - description of 3
 - registering to server 271
- interfaces to ADSM 19
- internal mounting facility
 - canceling 45
 - using 37

L

- license
 - compliance 254
 - features
 - for additional clients 252
 - for clients other than AIX 253
 - for device module support 253, 254
 - monitoring 254
 - using 251
- LOCK ADMIN command 263
- LOCK NODE command 267
- log mode
 - normal 306, 309
 - roll-forward 306, 309
 - setting 306
- logical devices 9, 28
- LOGPOOLSIZ option 248

M

- MACRO administrative command, using 266
- macro, scheduling on client 193, 207
- magnetic disk devices 9, 27
- management class
 - assigning a default 181

- management class (*continued*)
 - associating a file with 161
 - binding a file to 161
 - controlling user access 159
 - copying 169, 174
 - default 160
 - defining 174
 - deleting 187
 - description of 157, 158, 159
 - rebinding a file 163
 - updating 169, 174
- management class configuration 159
- maximum extension 240
- MDISK statement 304
- media loss, recovery from 325
- messages
 - directing import messages to an output file 288
 - mount, using the administrative client 35
- migration
 - canceling the server process 121
 - controlling start of, server 92
 - defining threshold for disk storage pool 91
 - defining threshold for tape storage pool 93
 - demand 157
 - description 156, 167
 - description, server process 89
 - monitoring thresholds for storage pools 118
 - premigration for HSM client 157
 - providing additional space for server process 121
 - providing users with immediate access to files on disk 92
 - reconciliation 157
 - selective, for HSM client 157
 - starting server process 89, 92
 - stub file on HSM client 157
 - threshold 157
 - threshold for a storage pool
 - high 89
 - low 89
- mirrored volume 304
 - description of 305
 - querying 305
 - viewing information about 305
- mirroring
 - advantages 303
 - database 304
 - defining volumes 305
 - description of 23
 - recovery log 298, 304, 305
 - recovery procedure 314
- mode
 - description of 176
 - scheduling 200
- modified mode, description of 176
- mount
 - limit, for tapes 70
 - query 43
 - retention period 71
 - wait period 71
- mount exit program 42, 50
- mount messages, tape 39, 40
- mount mode 35
- mount operations 42
- mounted tapes, querying 43
- MOVE DATA command 144
- moving data
 - from offsite volume in a copy storage pool 145
 - monitoring the movement of 147
 - procedures 145
 - requesting processing information 146
 - to another storage pool 144
 - to other volumes in same storage pool 144

O

- occupancy, querying 123
- offsite volumes, moving data in a copy storage pool 145
- open registration
 - description of 265
 - setting 265
- operator privilege class
 - description of 260
 - granting 260
 - revoking 261
- option, server
 - BUFPOOLSIZE 246
 - DEVCONFIG 312
 - EXPINTERVAL 183
 - IDLETIMEOUT 220
 - LOGPOOLSIZE 248
 - MAXSESSIONS 236
 - NOAUDITSTORAGE 255
 - VOLUMEHISTORY 311
- options, querying
 - BUFPOOLSIZE 248
 - LOGPOOLSIZE 248
 - VIRTUALMOUNTPOINT 269
- options, server
 - See* server option

P

- page, description of 246
- password
 - resetting an administrative 256
 - setting authentication for a client 255
 - setting expiration 255
- performance
 - cache, improved retrievability of files 29
 - concurrent client/server operation considerations 201
 - database or recovery log, optimizing 246
 - database read, increase with mirroring 303
 - workstation, compression option considerations 266
- period, specifying for an incremental backup 200
- policies, managing ADSM 155
- policy definitions, importing 288
- policy domain
 - creating 172
 - deleting 188
 - description of 157, 158
 - updating 169, 172
- policy objects
 - deleting 187
 - description of 157
 - querying 184
- policy operations 156
- policy privilege class
 - changing administrative authority 261
 - description of 258
 - granting 258
- policy set
 - activating 181
 - copying 169, 173
 - defining 173
 - deleting 188
 - description of 157, 158
 - updating 173
 - validating 181, 183
- policy, storage management
 - description of 22, 157
 - managing 155
 - tailoring 169
 - using standard 168
- pool, storage
 - amount of space used 124
 - auditing a volume 139
 - backup and recovery 302
 - copy 82
 - creating a hierarchy 85
 - pool, storage (*continued*)
 - defining 110
 - defining for disk 112
 - defining for tape 112
 - deleting 126
 - description of 81
 - determining access mode 110, 113
 - determining maximum file size 111
 - determining whether to use collocation 95, 111, 114
 - enabling cache for disk 94, 111
 - estimating space for archived files on disk 109
 - estimating space for backed up files on disk 108
 - estimating space for disk 108
 - estimating space for sequential 109
 - estimating space in multiple 85
 - managing 81
 - monitoring 117
 - moving files 144
 - moving files between 144
 - overview 11
 - primary 82
 - querying 117
 - random access 82
 - recovery log, effect on 233
 - restore 303, 324
 - sequential access 82
 - updating 110
 - updating for disk 112
 - using cache on disk 94, 111
 - viewing information about 117
 - premigration 157
 - PREVIEW parameter 275, 285
 - privilege class, administrator
 - analyst 260
 - description of 256
 - granting authority 256
 - operator 260
 - policy 258
 - reducing 261
 - revoking all 261
 - storage 258, 259
 - system 257
 - privilege class, policy
 - changing administrative authority 261
 - description of 258
 - granting 258
 - process
 - background 222
 - canceling 223
 - expiration 105

- process (*continued*)
 - number for migration 111
 - number for storage pool backup 116
 - number for storage pool restore 128
 - reclamation 100, 103
- PROFILE EXEC for exit machines 47
- programming interface notice xiii
- protecting your data 297
- publications xviii

Q

- QUERY ACTLOG command 227, 279
- QUERY ADMIN command 263
- QUERY ASSOCIATION command 212
- QUERY CONTENT command 137
- QUERY COPYGROUP command 184, 290
- QUERY DB command 243, 247
- QUERY DBBACKUPTRIGGER command 310
- QUERY DBVOLUME command 243, 305
- QUERY DEVCLASS command 275
- QUERY DOMAIN command 186
- QUERY EVENT command 209
- QUERY EXIT command 44
- QUERY FILESPACE command 269
- QUERY LICENSE command 255
- QUERY LOG command 248
- QUERY LOGVOLUME command 243, 305
- QUERY MGMTCLASS command 185
- QUERY MOUNT command 43
- QUERY NODE command 268
- QUERY OCCUPANCY 124, 125
- QUERY OCCUPANCY command 123
- QUERY OPTION command 225
- QUERY POLICYSET command 186
- QUERY PROCESS command 121, 146, 223, 277
- QUERY REQUEST command 43
- QUERY SCHEDULE command 197
- QUERY SESSION command 219
- QUERY STATUS 224
- QUERY STGPOOL command 117, 118, 122
- QUERY VOLHISTORY command 312
- QUERY VOLUME command 135, 147
- querying for general information 135
- querying policy objects 184
- querying storage volumes 135

R

- randomize, description of 201
- read-only access mode 132
- read/write access mode 132
- rebinding
 - description of 163
 - file to a management class 163
- recalling a file
 - selective 157
 - transparent 157
- reclamation
 - affect of collocation on 104
 - delaying reuse of volumes 104, 105
 - description of 21
 - offsite volume 103
 - setting a threshold for sequential storage pool 100, 111, 114
 - threshold 21
 - with single drive 105
- reclamation threshold, setting for sequential storage pool 100, 111, 114
- recovering storage pools 302
- recovering the database 314
- recovery from disaster
 - See disaster recovery
- recovery log
 - adding space to 238
 - available space 235, 236
 - buffer pool 249
 - consistent database image 233
 - defining a volume 240
 - defining mirrored volumes 304
 - deleting a volume 245
 - deleting space 242
 - description of 22, 233
 - determining how much space is allocated 234, 236
 - estimating the amount of space needed 236
 - logical volume 234, 236
 - managing 233
 - mirroring 298, 303
 - monitoring space 234, 236
 - monitoring the buffer pool 249
 - optimizing performance 246
 - querying the buffer pool 248
 - reducing capacity 244
 - size of 308
 - storage pool size effect 233
 - viewing information about 248
 - volume placement 239

- recovery log (*continued*)
 - when to backup 297, 303, 307
- recovery log mode
 - normal 306, 309
 - roll-forward 306, 309
 - setting 306
- recovery, disaster
 - auditing storage pool volumes 320
 - example recovery procedures 322
 - general strategy 297
 - methods 297
 - providing 297
 - when to backup 297, 307
- REDUCE DB command 244
- REDUCE LOG command 244
- REEL device type 69, 70
- REGISTER ADMIN command 256
- REGISTER LICENSE command 252
- REGISTER NODE command 265
- registering a workstation 271
- registration
 - closed 265
 - description of 265
 - managing client node 264
 - managing for a client node 251
 - managing for an administrator 251
 - open 265
 - setting for a client node 265
- REMOVE ADMIN command 262
- REMOVE NODE command 271
- RENAME ADMIN command 262
- RENAME FILESPACE command 293
- RENAME NODE command 267
- renaming an administrator ID 262
- REPLY command 44
- RESET BUFPOOL command 246
- RESET DBMAXUTILIZATION command 235, 236
- RESET LOGCONSUMPTION command 308
- RESET LOGMAXUTILIZATION command 235, 236
- resetting
 - administrative password 256
 - buffer pool statistic 246
 - database and recovery log volume utilization counter 236
 - user password expiration 255
- restarting the server 219
- RESTORE STGPOOL command 303, 324
- RESTORE VOLUME command 325
- restoring a file 156

- restoring the database
 - point-in-time 314
 - to its most current state 319
- restricted policy privilege
 - changing administrative authority 260
 - granting 258
- restricted storage privilege
 - changing administrative authority 260
 - granting 259
- retain extra versions, description of 179
- retain only version, description of 179
- retention grace period
 - description of archive 172
 - description of backup 172
 - using archive 172
 - using backup 172
- retrieving a file 156
- reuse of sequential volumes
 - delaying 104, 105
- REVOKE AUTHORITY command 260
- roll-forward recovery
 - database backup trigger 319
 - mirroring recovery log 319
 - recovery log 319

S

- schedule
 - associating client node 196
 - client options to use 207
 - coordinating 198
 - copying 208
 - day of the week 204
 - defining 204
 - deleting 209
 - description of 193
 - expiration date 205
 - files to process 207
 - frequency of service 205
 - initial start date 204
 - initial time 204
 - managing associations 204
 - missed, querying 198, 210
 - priority 205
 - querying 197
 - results of 209
 - startup window 200, 204
 - type of action 207
 - updating 204
 - viewing information about 197

- schedule event
 - managing 209
 - querying 209
 - viewing information about 209
- scheduled operations, setting the maximum 201
- scheduler workload, controlling 200
- scheduling mode
 - client-polling 199
 - description of 193
 - selecting 200
 - server-prompted 199
 - setting on a client node 200
 - setting on the server 200
- scheduling, central
 - controlling the workload 200
 - coordinating 198
 - description of 22, 193
- scratch volume
 - deleting 85, 312
 - description 36
 - FILE volumes 29
 - number allowed in a storage pool 111, 114
 - using in storage pools 85
- script, scheduling on client 193, 207
- secondary server attachment, registering 254
- security
 - See administrative privilege class
 - See password
- selective backup 156, 166
- selective recall 157
- sequential storage pool
 - auditing a single volume in 143
 - auditing multiple volumes in 142
 - collocation 99
 - estimating space 109
 - migration threshold 93
 - reclamation 100
- server
 - canceling process 223
 - description of 3
 - description of how tapes are selected 39
 - disabling 221
 - disabling access 221
 - enabling 222
 - enabling access 221
 - halting 218
 - managing operation 217
 - managing processes 222
 - querying about processes 223
 - querying options 225
- server (*continued*)
 - querying status 224
 - restarting 219
 - scheduling mode 199
 - setting the name 225
 - starting 217
 - stopping 218
 - viewing information about 224
 - viewing information about processes 223
 - VM privilege classes 38
- server console, description of 256
- server option
 - BUFPOOLSIZE 246
 - DEVCONFIG 312
 - EXPINTERVAL 183
 - IDLETIMEOUT 220
 - LOGPOOLSIZE 248
 - MAXSESSIONS 236
 - NOAUDITSTORAGE 255
 - VOLUMEHISTORY 311
- server storage
 - client files, process for storing 4
 - concepts overview 4
 - considering user needs for recovering 15
 - deleting files from 147
 - evaluating 14
 - managing 4
 - monitoring 139
 - planning 14
 - tailoring definitions 289
 - using disk devices 27
 - using tape devices 31
- server-prompted scheduling 199
- session
 - canceling 221
 - setting the maximum percentage for scheduled operations 201
- SET ACCOUNTING command 228
- SET ACTLOGRETENTION command 227
- SET AUTHENTICATION command 255
- SET EVENTRETENTION command 211
- SET LICENSEAUDITPERIOD command 255
- SET LOGMODE command 311
- SET MAXCMDRETRIES command 203
- SET MAXSCHEDSESSIONS command 201
- SET PASSEXP command 255
- SET QUERYSCHEDPERIOD command 203
- SET RANDOMIZE command 201
- SET REGISTRATION command 265

- SET RETRYPERIOD command 203
- SET SCHEDMODES command 200
- SET SERVERNAME command 225
- setting a password 22, 255
- setting compression 265
- SFS
 - See shared file system (SFS)
- shared dynamic serialization, description of 175, 180
- shared file system (SFS) 28
- shared static serialization, description of 175, 180
- single drive manual volume reclamation 105
- space
 - adding to the database or recovery log 238
 - deleting from the database or recovery log 242
 - estimating database and recovery log requirements 236
- space management
 - See hierarchical storage management
- space-managed file 156
- standard management class, copying 174
- standard storage management policies, using 168
- start time, randomizing for a schedule 201
- starting the server 217
- startup window, description of 201
- static serialization, description of 175, 180
- stopping the server 218
- storage hierarchy
 - defining in reverse order 112
 - establishing 85
- storage management policy
 - description of 22, 157
 - managing 155
 - tailoring 169
 - using standard 168
- storage occupancy, querying 123
- storage pool
 - amount of space used 124
 - auditing a volume 139
 - backup and recovery 302
 - copy 82
 - creating a hierarchy 85
 - defining 110
 - defining for disk 112
 - defining for tape 112
 - deleting 126
 - description of 81
 - determining access mode 110, 113
 - determining maximum file size 111
 - determining whether to use collocation 95, 111, 114
 - enabling cache for disk 94, 111

- storage pool (*continued*)
 - estimating space for archived files on disk 109
 - estimating space for backed up files on disk 108
 - estimating space for disk 108
 - estimating space for sequential 109
 - estimating space in multiple 85
 - managing 81
 - monitoring 117
 - moving files 144
 - moving files between 144
 - overview 11
 - primary 82
 - querying 117
 - random access 82
 - recovery log, effect on 233
 - restore 303, 324
 - sequential access 82
 - updating 110
 - updating for disk 112
 - using cache on disk 94, 111
 - viewing information about 117
- storage pool backup
 - full 302
 - incremental 302
- storage privilege class
 - changing administrative authority 261
 - description of 259
 - granting 259
- storage volume
 - See also volume
 - auditing 139
 - contents 137
 - information about 135
 - managing 131
 - monitoring use 135
 - overview 11
- stub file 157
- system privilege class
 - changing administrative authority 261
 - description of 257
 - granting 257

T

- tape
 - controlling mount messages 39
 - deletion exit 65
 - dismounting 46
 - error states 41
 - exit machines 37

- tape (*continued*)
 - exporting data 280
 - handling mounts 42
 - internal mounting facility 37
 - label prefix 71
 - managing 31
 - mounted 43
 - planning for exporting data 275
 - recording format 72, 73
 - requesting 40
 - reuse in storage pools 36
 - scratch, determining use 85, 111, 114
 - setting mount retention period
- tape management system, using 51, 65
- threshold
 - migration, for storage pool 89, 93
 - reclamation 100
- TRACE commands
- trademarks xv
- transactions
 - database 233, 234
 - how ADSM processes 234
- transparent recall 157
- type, device
 - CARTRIDGE 69
 - DISK 69
 - FILE 69
 - REEL 70

U

- unavailable access mode 132
- unavailable error state, tape 41
- unavailable tape volumes, recovering 42
- UNLOCK ADMIN command 263
- UNLOCK NODE command 267
- unplanned shutdown 218
- unrestricted policy privilege
 - changing administrative privilege 260
 - granting 258
- unrestricted storage privilege
 - changing administrative authority 260
 - granting 258
- unusable space for database and recovery log 235
- UPDATE ADMIN command 256
- UPDATE COPYGROUP command 175, 179
- UPDATE DBBACKUPTRIGGER command 310
- UPDATE DOMAIN command 172
- UPDATE MGMTCLASS command 174

- UPDATE NODE command 267
- UPDATE POLICYSET command 173
- UPDATE SCHEDULE command 204
- UPDATE VOLUME command 133
- usable space 235
- user documentation xviii
- utilization
 - description of 235
 - monitoring 235, 236

V

- VALIDATE POLICYSET command 181
- VARY command 224
- varying volumes on or off line 224
- versions data deleted, description of 178
- versions data exists, description of 176
- VIRTUALMOUNTPOINT option 269
- VM privilege class
 - exit machines 39
 - overview 38
 - server 38
- volume
 - allocating space for disk 27, 239, 304
 - auditing 139
 - auditing considerations 140
 - capacity, compression effect 79
 - defining for database 240
 - defining for recovery log 240
 - defining to storage pools 133
 - deleting 148, 312
 - detailed report 139
 - determining which are mounted 43
 - disk storage 133
 - disk storage pool 141
 - dismounting 46
 - error states on tape 41
 - inventory maintenance 35
 - mirroring 304
 - monitoring movement of data 147
 - monitoring use 135
 - mount retention period 71
 - moving files between 143
 - preparing for storage pool 131
 - querying 135
 - querying contents 137
 - querying for general information 135
 - random access storage pools 82, 85, 133
 - recovery using mirroring 314
 - removing 35

- volume (*continued*)
 - returning 36
 - reuse delay 104, 105
 - scratch, using 85
 - sequential 133
 - setting access mode 132
 - standard report 138
 - updating to storage pools 41, 133
 - varying 224
- volume capacity 74
- volume copy
 - allocating to separate disks 303
 - description of 304
- volume history backup 311
 - and point-in-time 311
- volume history files, establishing 311
- VOLUMEHISTORY option 311

W

- workstation, registering 271

Communicating Your Comments to IBM

ADSTAR Distributed Storage Manager
for VM
Administrator's Guide
Version 2
Publication No. GC35-0228-00

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM. Whichever method you choose, make sure you send your name, address, and telephone number if you would like a reply.

Feel free to comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. However, the comments you send should pertain to only the information in this manual and the way in which the information is presented. To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

If you are mailing a readers' comment form (RCF) from a country other than the United States, you can give the RCF to the local IBM branch office or IBM representative for postage-paid mailing.

- If you prefer to send comments by mail, use the RCF at the back of this book.
- If you prefer to send comments by FAX, use this number:
 - United States and Canada: 520 799-2906
 - Other countries: (1) 520 799-2906

The contact department is 61C/031.

- If you prefer to send comments by electronic mail, use one of the following addresses:
 - Internet: starpubs@vnet.ibm.com (or `starpubs` at `vnet.ibm.com`)
 - IBMLink from U.S.A.: STARPUBS at SJEVM5
 - IBMLink from Canada: STARPUBS at TORIBM
 - IBM Mail Exchange: USIB3VVD at IBMMAIL

Make sure to include the following in your note:

- Title and publication number of this book
- Page number or topic to which your comment applies.

Readers' Comments — We'd Like to Hear from You

**ADSTAR Distributed Storage Manager
for VM
Administrator's Guide
Version 2**

Publication No. GC35-0228-00

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Complete	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to find	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Easy to understand	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Well organized	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Applicable to your tasks	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Please tell us how we can improve this book:

Thank you for your responses. May we contact you? Yes No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Name

Address

Company or Organization

Phone No.

Readers' Comments — We'd Like to Hear from You
GC35-0228-00



Cut or Fold
Along Line

Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

International Business Machines Corporation
Information Development
Department 61C
9000 South Rita Road
TUCSON AZ 85775-4401



Fold and Tape

Please do not staple

Fold and Tape

GC35-0228-00

Cut or Fold
Along Line



Program Number: 5654-A02



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

GC35-0228-00



Spine information:



ADSTAR Distributed Storage Manager
for VM

Administrator's Guide

Version 2