

In this IBM Maximo[®] Asset Management version 7.1 training module, you learn how to install the IBM Performance Analysis Suite.

IBM
Assumptions
These assumptions are made:
You understand that the installation package download includes optional files
 You verified successful installation of Java version 6 or later before installation of the IBM Performance Analysis Suite
The installation is for a Windows Server 2008 operating system environment

Optional files are included in the installation package. Java version 6 or later must be installed before installation of the IBM Performance Analysis Suite. The charting functionality of IBM Performance Analysis Suite is available only after downloading, extracting, and installing the .zip files.

	IBM
Objectives	
When you complete this IBM Maximo Asset Management version 7.1 Performance Analysis Suite training module, you can do these tasks:	
 Installation of the Performance Analysis Suite on a Windows OS 	
 Configure the IBM Performance Analysis Suite tool to check Tivoli's process automation engine performance-related settings 	
Configure IBM Performance Analysis Suite Secure Shell access to a Maximo server	
• Add a process automation engine database entry and a new process automation engine database connection	
Add a WebSphere [®] Application Server entry and a new application server connection	
Add a web server entry	
© 2014 IBM	Corporation

These objectives are covered in this module:

Install the Performance Analysis Suite on a Windows OS

Install the optional plug-ins that provide the IBM Performance Analysis Suite charting functionality

Configuring the IBM Performance Analysis Suite tool to check Tivoli's process automation engine performance-related settings

Configuring the IBM Performance Analysis Suite Secure Shell access to a Maximo server

Adding a process automation engine database entry and a new process automation engine database connection

Adding a WebSphere Application Server entry and a new application server connection

Adding a web server entry

IBM
Performance Analysis Suite download
 Go to the download URL location: <u>https://www.ibm.com/developerworks/community/groups/service/html/communityview?communityUu</u> <u>id=28cb6d68-ab67-4203-96f9-5538e654a5ff</u> Download perfanalyst-1.1.0-general.zip
 Extract the downloaded file
© 2014 IBM Corporation

Download the Performance Analysis Suite from IBM developerWorks. Download the tool, which includes the documentation. Extract the files to any folder location of your choice.

Γ

					IBM
Starting the perfanalyst application					
	getevent.sn		13/10/2012 14:34	SHIFIE	ZKB
To start the Derformance Archiele Oritor	getsnap.sh		13/10/2012 14:34	SH File	2 KB
To start the Performance Analysis Suite:	ire-6u45-window	ws-i586	29/04/2013 17:11	Application	16,691 KB
 Verify installation of Java 6 or later 	perfanalyst		09/11/2012 22:05	Windows Batch File	1 KB
	merfanalyst		10/11/2012 17:56	Executable Jar File	200 KB
 Double-click the perfanalyst application to start it 	UserGuide		05/11/2012 21:36	Firefox Document	1 KB
Click File and select Open					
	Performance Anal	lvst			
	ile Profile View He	elp			
	Open CT	RL+O	1		
	Load Workspace CT	RL+L			
-	Save Workspace CT	RL+S	Analyst User Guide		
	Reload CT	TRL+R			
	Exit		a program aimed	ram aimed to help analyze performance proble	
Ĩ	Sustam Pag	quiror	nont		
	System Red	quirei			
			272		
					© 2014 IBM Corporation

Verify that the system on which you run the tool has Java 6 or later installed. From the installation directory, double-click the perfanalyst application to start it. A splash screen shows briefly, then the application opens and shows the user guide. Click **File** and select **Open**.



Select TPAE::Config from the list of optional plug-ins and click **OK**.



You need an environment profile to access the components of the running system. Click the upper left icon in the Environments window to create a new environment profile.

	IBM
Configuring the environment profile (2 of 2)	
Enter a profile name and click the New button in the Hosts section	
Name of the Environm X	
Name: WIN-2008-Entr	
Cancel Save	
Calife	
🔜 Environment Profile Management	
WIN-2008-Entr . * TPAe Databases	
hostname userid database type port db_userid db_home	
🗄 Hosts 🔪 🌾	
hostname-userid platform	
	© 2014 IBM Corporation

Enter a profile name and click **Save**. Next, the Environment Profile Management window opens with a new empty profile. Click the New icon in the Hosts section.

	IBM
Configuring the host and user information	
Enter host information for the server where Maximo runs.	
Host/User Management	
Host: WIN-2008-Entr	
Platform: win Protocol: ssh	
User ID: Administrator	
Key File:	
Password:	
Repeat J	
Cancel Save	
	© 2014 IBM Corporation

On the host user management pane, enter the host, the platform, the protocol to use for connection, the user ID, and the password for the Maximo server. Repeat the password entry and click **Save**.

	IBM
Configuring the database manager	
 Click to create a new database entry and enter information to allow connection to the Maximo datab 	ase.
🛅 TPAe Databases	
hostname userid database type port db_userid db_home	
TPAe Database Manager	
Host: WIN-2008-Entr Host User: Administrator	
Vendor: db2 Database: maxdb75 JDBC Port: 50005	
DB User: db2admin Password: ••••• Repeat: •••••	
DB Home: C:\IBM\SQLLIB	
Cancel Save	
© 2014 IBM (Corporation

In the environment management profile window, click the "new" icon in the process automation engine databases section. In the TPAe Database Manager window, select the host and host user. Next, enter the database vendor, the database name, JDBC port, database user name, and password. Repeat the password entry. Enter the database home path in the DB Home field and click **Save**.

	IBM
Configuring the connection to WebSphere Application Server	
 Click to create a new entry and enter information to connect to WebSphere Application Server. 	
🚡 WebSphere Deployment Manager	
hostname userid profile port was_admin_userid was_home	
WebSphere Deployment Manager	
Host: WIN-2008-Entr Host User: Administrator	
Dmgr Profile: ctgDmgr01 Port: 8879	
Dmgr Admin: wasadmin Password: ••••• Repeat: •••••	
WAS Home: C:\IBM\WebSphere\AppServer	
Cancel Save	
© 2014	BM Corporation

In the environment management profile window, click the "new" icon in the WebSphere Deployment Manager pane. In the WebSphere deployment manager window, select the host and host user. Enter the deployment manager profile name, port number, the deployment manager user name, and the password for connection to the deployment manager. Repeat the password entry. Next, enter the WebSphere Application Server home path in the **WAS Home:** field and click **Save**.

	IBM
Configuring the IBM HTTP Server information	17
 Click to create a new Http Server entry, enter HTTP information, and click Save. 	
🖏 IBM Http Server 💊 🛠	
hostname userid ihs_home	
IBM Http Server	
Host: WIN-2008-Entr Host User: Administrator	
IHS Home: C:/IBM/HttpServer	
Cancel Save	
	© 2014 IBM Corporation

In the environment management profile window, click the "new" icon in the IBM HTTP Server section. In the "IBM Http Server" pane, select the Host and Host User.

Next, enter the IHS Home information and click **Save**. After that the Environment Profile Management window is shown. Click **Save** to save your environment profile.



In the Environments window, select the new profile that you created and click **OK**.



On this slide, the TPAE::Config plug-in output is shown. The **Dashboard** tab provides a diagram of adherence to IBM-suggested preferred practices for a Maximo installation. You can click any violation warnings to show more information. The other tabs show information for each area that is tested and show any violations. You can also click **File** and select **Save Workspace** to save the information to a file.

	IBW
Summary	
Now you can accomplish these tasks:	
Install the Performance Analysis Suite on a Windows operating system	
 Configure the IBM Performance Analysis Suite tool to check Tivoli's process automation engine performance-related settings 	
Configure IBM Performance Analysis Suite Secure Shell access to a Maximo server	
 Add a process automation engine database entry and a new process automation engine database connection 	•
Add a WebSphere Application Server entry and a new application server connection	
 Add a web server entry 	
© 2014 IB	M Corporation

Now that you have completed this training module, you can accomplish these tasks:

Install Performance Analysis Suite on a Windows operating system

Install the optional plug-ins that provide the IBM Performance Analysis Suite charting functionality

Configure the IBM Performance Analysis Suite tool to check Tivoli's process automation engine performance-related settings

Configure IBM Performance Analysis Suite Secure Shell access to a Maximo server

Add a process automation engine database entry and a process automation engine database connection

Add a WebSphere Application Server entry and an application server connection

Add a web server entry

Trademarks, disclaimer, and copyright information

IBM, the IBM logo, ibm.com, Maximo, and WebSphere are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of other IBM trademarks is available on the web at "Copyright and trademark information" at http://www.ibm.com/legal/copytrade.shtml

Windows, and the Windows logo are registered trademarks of Microsoft Corporation in the United States, other countries, or both.

Other company, product, or service names may be trademarks or service marks of others.

THE INFORMATION CONTAINED IN THIS PRESENTATION IS PROVIDED FOR INFORMATIONAL PURPOSES ONLY. WHILE EFFORTS WERE MADE TO VERIFY THE COMPLETENESS AND ACCURACY OF THE INFORMATION CONTAINED IN THIS PRESENTATION, IT IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. IN ADDITION, THIS INFORMATION IS BASED ON IBM'S CURRENT PRODUCT PLANS AND STRATEGY, WHICH ARE SUBJECT TO CHANGE BY IBM WITHOUT NOTICE. IBM SHALL NOT BE RESPONSIBLE FOR ANY DAMAGES ARISING OUT OF THE USE OF, OR OTHERWISE RELATED TO, THIS PRESENTATION OR ANY OTHER DOCUMENTATION. NOTHING CONTAINED IN THIS PRESENTATION IS INTENDED TO, NOR SHALL HAVE THE EFFECT OF, CREATING ANY WARRANTIES OR REPRESENTATIONS FROM IBM (OR ITS SUPPLIERS OR LICENSORS), OR ALTERING THE TERMS AND CONDITIONS OF ANY AGREEMENT OR LICENSE GOVERNING THE USE OF IBM PRODUCTS OR SOFTWARE.

© Copyright International Business Machines Corporation 2014. All rights reserved.

© 2014 IBM Corporation

IBM