

# Installing and using Compiz Fusion

Manolis Kiagias

manolis@FreeBSD.org

\$FreeBSD: release/9.2.0/en\_US.ISO8859-1/articles/compiz-fusion/article.xml 41645  
2013-05-17 18:49:52Z gabor \$

Copyright © 2008 Manolis Kiagias

\$FreeBSD: release/9.2.0/en\_US.ISO8859-1/articles/compiz-fusion/article.xml 41645  
2013-05-17 18:49:52Z gabor \$

FreeBSD is a registered trademark of the FreeBSD Foundation.

Many of the designations used by manufacturers and sellers to distinguish their products are claimed as trademarks. Where those designations appear in this document, and the FreeBSD Project was aware of the trademark claim, the designations have been followed by the “™” or the “®” symbol.

The Linux world has been overwhelmed lately by what seems to be the latest fashion: 3D Desktop effects. While their usefulness is rather heavily debated, the wow factor behind the composited desktop holds quite well. Several different programs have emerged, like **Compiz** (<http://compiz.org/>), **Beryl** (<http://www.beryl-project.org/>), and the latest **Compiz Fusion** (<http://www.compiz-fusion.org/>). You do not need to miss these effects when using FreeBSD. These instructions will help you install and configure your system for the latest 3D desktop experience using **Compiz Fusion** and nVidia drivers (if applicable).

## 1 Introduction

While installing **Compiz Fusion** from the Ports Collection is a rather trivial task, configuring it requires a few more steps that are not described in the port’s documentation. This article will help you configure your **Xorg** server for composite operation, setup your nVidia card, and finally guide you to the final steps for executing the `compiz` program itself.

After reading this article, you will know:

- How to setup the latest nVidia driver (if required) for your system.
- How to setup your `xorg.conf` file for desktop composition.
- How to install and configure **Compiz Fusion** using the Ports Collection.
- How to troubleshoot common problems associated with desktop effects.

## 2 Setting up the FreeBSD nVidia driver

Desktop effects can cause quite a load on your graphics card. If you are using an nVidia-based graphics card, you will need to install and configure the proprietary FreeBSD driver that is suitable for your system. If you are using another card, that you know can handle desktop effects, you may skip this section and continue with the `xorg.conf` configuration.

### 2.1 Determining the correct driver to use

There are various versions of the nVidia drivers in the Ports Collection. The correct one to use depends on the actual model (and age) of your graphics card:

- The latest versions of nVidia cards are supported by the `x11/nvidia-driver` port.
- nVidia cards like the GeForce 2MX/3/4 series are supported by the 96xx series of drivers, available in the `x11/nvidia-driver-96xx` port.
- Even older cards, like GeForce and RIVA TNT are supported by the 71xx series of drivers, available in the `x11/nvidia-driver-71xx` port.

In fact, nVidia provides detailed information on which card is supported by which driver. This information is available directly on their web site: [http://www.nvidia.com/object/IO\\_32667.html](http://www.nvidia.com/object/IO_32667.html).

### 2.2 Installing the nVidia driver

Having determined the correct driver to use for your card, installation is as simple as installing any other port.

**Note:** Make sure to update your ports tree using your favorite method (e.g., **portsnap**) before you install any application from the ports system. Graphics drivers and the desktop effects programs are under heavy development, and are updated regularly.

For example, to install the latest driver:

```
# cd /usr/ports/x11/nvidia-driver
# make install clean
```

The driver will create a kernel module, which should be loaded at system startup. You will need to add the following line to the `/boot/loader.conf` file:

```
nvidia_load="YES"
```

**Note:** You may attempt to immediately load the kernel module into the running kernel by issuing a command like `kldload nvidia`, however it has been noted that the latest versions of **Xorg** will not function properly if the driver is not loaded at boot time. After editing `/boot/loader.conf`, a reboot is recommended.

With the kernel module loaded, you normally only need to change a single line in your `xorg.conf` file to enable the proprietary driver:

Find the following line in `/etc/X11/xorg.conf`:

```
Driver      "nv"
```

and change it to:

```
Driver      "nvidia"
```

Start your GUI as usual, and you should be greeted by the nVidia splash. Everything should work as usual. Note, that at this point you have only set up **Xorg** to use the nVidia driver, but further configuration is needed before you can actually use 3D desktop effects. This is described in the following sections.

**Note:** Although not strictly necessary, you may also wish to install `x11/nvidia-xconfig` and `x11/nvidia-settings` ports. The former can assist you in writing settings to `/etc/X11/xorg.conf` from the command line, and the latter will allow you to modify screen settings from a GUI while running the **Xorg** system.

### 3 Configuring xorg.conf for desktop effects

Before you install and run **Compiz Fusion**, you need to add a few settings to `/etc/X11/xorg.conf`:

Add the following section to enable composite effects:

```
Section "Extensions"
Option      "Composite" "Enable"
EndSection
```

Locate the “Screen” section which should look similar to the one below:

```
Section "Screen"
Identifier   "Screen0"
Device      "Card0"
Monitor     "Monitor0"
...
```

and add the following two lines (after “Monitor” will do):

```
DefaultDepth    24
Option          "AddARGBGLXVisuals" "True"
```

Locate the “Subsection” that refers to the screen resolution that you wish to use. For example, if you wish to use 1280x1024, locate the section that follows. If the desired resolution does not appear in any subsection, you may add the relevant entry by hand:

```
SubSection      "Display"
Viewport        0 0
Modes           "1280x1024"
EndSubSection
```

A color depth of 24 bits is needed for desktop composition, change the above subsection to:

```
SubSection      "Display"
Viewport        0 0
Depth           24
Modes           "1280x1024"
EndSubSection
```

Finally, confirm that the “glx” and “extmod” modules are loaded in the “Module” section:

```
Section "Module"
Load      "extmod"
Load      "glx"
...
```

**Note:** If you installed the `x11/nvidia-xconfig` port, you should be able to perform most of the above settings by entering the following commands (as root):

```
# nvidia-xconfig --add-argb-glx-visuals
# nvidia-xconfig --composite
# nvidia-xconfig --depth=24
```

You may wish to run `nvidia-xconfig -A | more` to see a list of all the options offered by the above program.

## 4 Installing and configuring Compiz Fusion

Installing **Compiz Fusion** is as simple as any other port:

```
# cd /usr/ports/x11-wm/compiz-fusion
# make install clean
```

Make sure to select the “EXTRA” plugins and the “EMERALD” window decorator from the options dialog that appears. If you are using **GNOME**, or already have support for `gconf` in your system, you may also wish to select “gconf support”. In this way, your effect settings will be integrated with the other desktop settings, and will be viewable via `gconf-editor`. **Compiz Fusion** can however save its settings to flat files, if such an integration is not wanted. In this case, a `.compizconfig` directory will be created inside your home directory.

When the installation is finished, start your graphic desktop and at a terminal, enter the following commands (as a normal user):

```
% compiz --replace --sm-disable --ignore-desktop-hints ccp &
% emerald --replace &
```

Your screen will flicker for a few seconds, as your window manager (e.g. **Metacity** if you are using **GNOME**) is replaced by **Compiz Fusion**. **Emerald** takes care of the window decorations (i.e. close, minimize, maximize buttons, title bars and so on).

You may convert this to a trivial script and have it run at startup automatically (e.g. by adding to “Sessions” in a **GNOME** desktop):

```
#!/bin/sh
compiz --replace --sm-disable --ignore-desktop-hints ccp &
```

```
emerald --replace &
```

Save this in your home directory as, for example, `start-compiz` and make it executable:

```
% chmod +x ~/start-compiz
```

Then use the GUI to add it to **Startup Programs** (located in **System, Preferences, Sessions** on a **GNOME** desktop).

To actually select all the desired effects and their settings, execute (again as a normal user) the **Compiz Config Settings Manager**:

```
% ccsn
```

**Note:** In **GNOME**, this can also be found in the **System, Preferences** menu.

If you have selected “gconf support” during the build, you will also be able to view these settings using `gconf-editor` under `apps/compiz`.

## 5 Troubleshooting Compiz Fusion

The following section covers frequently asked questions regarding problems when running **Compiz Fusion**.

**1. I have installed **Compiz Fusion**, and after running the commands you mention, my windows are left without title bars and buttons. What is wrong?**

You are probably missing a setting in `/etc/X11/xorg.conf`. Review this file carefully and check especially the `DefaultDepth` and `AddARGBGLXVisuals` directives.

**2. When I run the command to start **Compiz Fusion**, the X server crashes and I am back at the console. What is wrong?**

If you check your `/var/log/Xorg.0.log` file, you will probably find error messages during the X startup. The most common would be:

```
(EE) NVIDIA(0):      Failed to initialize the GLX module; please check in your X
(EE) NVIDIA(0):      log file that the GLX module has been loaded in your X
(EE) NVIDIA(0):      server, and that the module is the NVIDIA GLX module.  If
(EE) NVIDIA(0):      you continue to encounter problems, Please try
(EE) NVIDIA(0):      reinstalling the NVIDIA driver.
```

This is usually the case when you upgrade **Xorg**. You will need to reinstall the `x11/nvidia-driver` port so `glx` is built again.