

MQSeries



Application Programming Reference Summary

MQSeries



Application Programming Reference Summary

Note!

Before using this information and the product it supports, be sure to read the general information under Chapter 6, "Notices" on page 95.

Fourth edition (February 1998)

This edition applies to the following products:

- MQSeries for AIX V5.0
- MQSeries for AS/400 V4R2
- MQSeries for AT&T GIS UNIX V2.2
- MQSeries for Digital OpenVMS V2.2
- MQSeries for HP-UX V5.0
- MQSeries for MVS/ESA V1.2
- MQSeries for OS/2 Warp V5.0
- MQSeries for SINIX and DC/OSx V2.2
- MQSeries for SunOS V2.2
- MQSeries for Sun Solaris V5.0
- MQSeries for Tandem NonStop Kernel V2.2
- MQSeries for Windows NT V5.0
- MQSeries for Windows V2.0
- MQSeries for Windows V2.1

and to any subsequent releases and modifications until otherwise indicated in new editions.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address given below.

At the back of this publication is a page titled "Sending your comments to IBM". If you want to make comments, but the methods described are not available to you, please address them to:

IBM United Kingdom Laboratories,
Information Development,
Mail Point 095,
Hursley Park,
Winchester,
Hampshire,
England,
SO21 2JN

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 1993,1998. All rights reserved.**

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

Contents

About this book	ix
Related MQSeries publications	ix
Terms used in this book	x
Windows products	x
Appearance of values in this book	x
Chapter 1. MQI calls	1
MQBACK	1
MQBEGIN	1
MQCLOSE	2
MQCMIT	2
MQCONN	3
MQCONNX	3
MQDISC	3
MQGET	4
MQINQ	4
MQOPEN	5
MQPUT	5
MQPUT1	6
MQSET	6
MQSYNC	7
Chapter 2. Data conversion	9
MQDATA CONVEXIT	9
MQXCNV	10
MQDXP (data-conversion exit parameter)	10
Chapter 3. Data types	11
Elementary data types	12
Elementary data types - C	13
Elementary data types - COBOL	14
Elementary data types - PL/I	15
Elementary data types - System/390 assembler	16
Elementary data types - TAL programming language	17
Structure data types	18
MQBO (begin options)	18
MQCIH (CICS bridge header)	19
MQCNO (connect options)	20
MQDH (distribution header)	20
MQDLH (dead-letter header)	21
MQGMO (get-message options)	22
MQIIH (IMS information header)	23
MQMD (message descriptor)	24
MQMDE (message descriptor extension)	25
MQOD (object descriptor)	26

Contents

MQOR (object record)	26
MQPMO (put-message options)	27
MQPMR (put-message record)	27
MQRMH (reference-message header)	28
MQRR (response record)	28
MQTM (trigger message)	29
MQTMC (trigger message in character format)	29
MQTMC2 (trigger message—character format 2)	30
MQXP (API-crossing exit parameter block)	30
MQXQH (transmission-queue header)	31
Chapter 4. Attributes of MQSeries objects	33
Local and model queue attributes	33
Local definition of remote queue attributes	35
Alias queue attributes	35
Namelist attributes	36
Process definition attributes	36
Queue manager attributes	37
Chapter 5. MQI constants	39
MQ_* (Lengths of character string and byte fields)	39
MQACT_* (Accounting token)	41
MQAT_* (Application type)	42
MQBO_* (Begin options)	43
MQBO_* (Begin options structure identifier)	43
MQBO_* (Begin options version)	43
MQCA_* (Character attribute selector)	44
MQCC_* (Completion code)	45
MQCCSI_* (Coded character set identifier)	45
MQCFUNC_* (CICS header function name)	45
MQCGWI_* (CICS header get-wait interval)	46
MQCI_* (Correlation identifier)	46
MQCIH_* (CICS header flags)	46
MQCIH_* (CICS header length)	46
MQCIH_* (CICS header structure identifier)	47
MQCIH_* (CICS header version)	47
MQCLT_* (CICS header link type)	47
MQCMDL_* (Command level)	48
MQCNO_* (Connect options)	48
MQCNO_* (Connect options structure identifier)	49
MQCNO_* (Connect options version)	49
MQCO_* (Close options)	49
MQCODL_* (CICS header output data length)	50
MQCRC_* (CICS header return code)	50
MQCUOWC_* (CICS header unit-of-work control)	51
MQDCC_* (Convert-characters masks and factors)	51
MQDCC_* (Convert-characters option)	52
MQDH_* (Distribution header structure identifier)	52

Contents

MQDH_* (Distribution header version)	53
MQDHF_* (Distribution header flags)	53
MQDL_* (Distribution list support)	53
MQDLH_* (Dead-letter header structure identifier)	54
MQDLH_* (Dead-letter header structure version)	54
MQDXP_* (Data-conversion exit identifier)	54
MQDXP_* (Data-conversion exit version)	54
MQEC_* (Signal event control block completion code)	55
MQEI_* (Expiry interval)	55
MQENC_* (Encoding)	55
MQENC_* (Encoding mask)	56
MQENC_* (Encoding for packed-decimal integers)	56
MQENC_* (Encoding for floating-point numbers)	56
MQENC_* (Encoding for binary integers)	56
MQEVR_* (Event reporting)	57
MQFB_* (Feedback)	57
MQFMT_* (Format)	58
MQGI_* (Group identifier)	59
MQGMO_* (Get-message options)	60
MQGMO_* (Get-message options structure identifier)	61
MQGMO_* (Get-message options version)	61
MQGS_* (Group status)	61
MQHC_* (Connect handle)	62
MQHO_* (Object handle)	62
MQIA_* (Integer attribute selector)	62
MQIAUT_* (IMS authenticator)	64
MQIAV_* (Integer attribute value)	64
MQICM_* (IMS commit mode)	65
MQIIH_* (IMS header flags)	65
MQIIH_* (IMS header length)	65
MQIIH_* (IMS header structure identifier)	66
MQIIH_* (IMS header version)	66
MQISS_* (IMS security scope)	66
MQIT_* (Index type)	67
MQITII_* (IMS transaction instance identifier)	67
MQITS_* (IMS transaction state)	67
MQMD_* (Message descriptor structure identifier)	67
MQMD_* (Message descriptor version)	68
MQMDE_* (Message descriptor extension length)	68
MQMDE_* (Message descriptor extension structure identifier)	68
MQMDE_* (Message descriptor extension version)	69
MQMDEF_* (Message descriptor extension flags)	69
MQMDS_* (Message delivery sequence)	69
MQMF_* (Message flags)	70
MQMF_* (Message flags masks)	70
MQMI_* (Message identifier)	71
MQMO_* (Match options)	71
MQMT_* (Message type)	71

Contents

MQOD_* (Object descriptor length)	72
MQOD_* (Object descriptor structure identifier)	72
MQOD_* (Object descriptor version)	72
MQOII_* (Object instance identifier)	72
MQOL_* (Original length)	72
MQOO_* (Open options)	73
MQOT_* (Object type)	73
MQPER_* (Persistence)	74
MQPL_* (Platform)	74
MQPMO_* (Put-message options)	75
MQPMO_* (Put-message options structure length)	75
MQPMO_* (Put-message options structure identifier)	75
MQPMO_* (Put-message options structure version)	76
MQPMRF_* (Put-message record field flags)	76
MQPRI_* (Priority)	76
MQQA_* (Inhibit get)	77
MQQA_* (Inhibit put)	77
MQQA_* (Backout hardening)	77
MQQA_* (Queue shareability)	77
MQQDT_* (Queue definition type)	77
MQQSIE_* (Service interval events)	78
MQQT_* (Queue type)	78
MQRC_* (Reason code)	79
MQRMH_* (Reference message header structure identifier)	86
MQRMH_* (Reference message header version)	86
MQRMHF_* (Reference message header flags)	86
MQRO_* (Report options)	87
MQRO_* (Report-options mask)	87
MQSCO_* (Queue scope)	88
MQSEG_* (Segmentation)	88
MQSP_* (Syncpoint)	88
MQSS_* (Segment status)	89
MQTC_* (Trigger control)	89
MQTM_* (Trigger message structure identifier)	89
MQTM_* (Trigger message structure version)	90
MQTMC_* (Trigger message character format structure)	90
MQTMC_* (Trigger message character format version)	90
MQTT_* (Trigger type)	91
MQUS_* (Usage)	91
MQWI_* (Wait interval)	91
MQXC_* (Exit command identifier)	91
MQXCC_* (Exit response)	92
MQXDR_* (Data-conversion exit response)	92
MQXP_* (Exit parameter block)	93
MQXP_* (Exit parameter block version)	93
MQXQH_* (Transmission queue header structure identifier)	93
MQXQH_* (Transmission queue header structure version)	93
MQXR_* (Exit reason)	94

Contents

MQXT_* (Exit identifier)	94
MQXUA_* (Exit user area)	94
Chapter 6. Notices	95
Trademarks	96

Contents

About this book

About this book

| This book summarizes the information in the *MQSeries Application Programming Reference* manual. It contains summaries of:

- The message queue interface (MQI) calls
- Data types used by the MQI calls
- Attributes of MQSeries objects
- MQI constants

The information in this book is applicable to all platforms, unless otherwise stated.

| This book does not cover the PCF commands, events, or constants, that are documented in the *MQSeries Programmable System Management* book. Nor does it cover the channel-exit calls or the constants for channels and exits that are documented in the *MQSeries Intercommunication* book.

Related MQSeries publications

For detailed information about the MQI, see these MQSeries publications:

- *IBM MQSeries Application Programming Guide*, SC33-0807
- *IBM MQSeries Application Programming Reference*, SC33-1673

| This book specifies the values of all the named constants in the *Application Programming Reference* manual. For other MQI constants, refer to:

- *IBM MQSeries Intercommunication*, SC33-1872
- *IBM MQSeries Programmable System Management*, SC33-1482

| The information in this book does not apply to the MQSeries for AS/400 V4R2 product using the RPG programming language. For RPG information, refer to:

- *IBM MQSeries for AS/400 Application Programming Reference (RPG)*, SC33-1957

About this book

Terms used in this book

In this book, the term *UNIX systems* refers to the following MQSeries products:

- MQSeries for AIX V5.0
- MQSeries for AT&T GIS UNIX V2.2
- MQSeries for HP-UX V5.0
- MQSeries for SINIX and DC/OSx V2.2
- MQSeries for SunOS V2.2
- MQSeries for Sun Solaris V5.0

The term “MQSeries Version 5 products” applies to the following MQSeries products:

- MQSeries for AIX V5.0
- MQSeries for HP-UX V5.0
- MQSeries for OS/2 Warp V5.0
- MQSeries for Sun Solaris V5.0
- MQSeries for Windows NT V5.0

Windows products

The following table lists the MQSeries products available for Windows, and shows the Windows platforms on which each runs.

Product	Windows 3.1	Windows 95	Windows NT
MQSeries for Windows Client	Yes	Yes	Yes
MQSeries for Windows NT	No	No	Yes
MQSeries for Windows V2.0	Yes	Yes	No
MQSeries for Windows V2.1	No	Yes	Yes

MQSeries for Windows Versions 2.0 and 2.1 support most of the features of the MQI described in this book. For information on these products, see the *MQSeries for Windows User's Guide*.

Appearance of values in this book

In this book:

- The symbol 'b' represents a single blank character.
- The value 'blanks' denotes the null string in C and blank characters in other programming languages.
- The notation X'hhhh' represents a hexadecimal value. Each 'h' denotes a single hexadecimal digit.

Chapter 1. MQI calls

Full details of these calls can be found in the *MQSeries Application Programming Reference* manual.

MQBACK

Purpose: Indicates to the queue manager that all messages put or retrieved as part of a unit of work since the last syncpoint are to be backed out.

Table 1. MQBACK call

Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output
Note: This call is not supported by MQSeries for AS/400, and can be used with MQSeries for MVS/ESA in the batch environment only. On Tandem NSK, this call always returns a <i>CompCode</i> of MQCC_FAILED and a <i>Reason</i> of MQRC_ENVIRONMENT_ERROR.		

MQBEGIN

Purpose: Begins a unit of work that is coordinated by the queue manager.

Table 2. MQBEGIN call

Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>BeginOptions</i>	(MQBO)	input/output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output
Note: This call is supported on MQSeries Version 5 products only.		

MQCLOSE • MQCMIT

MQCLOSE

Purpose: Relinquishes access to an object (inverse of MQOPEN).

Table 3. MQCLOSE call

Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>Hobj</i>	(MQHOBJ)	input/output
<i>Options</i>	(MQLONG)	input
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQCMIT

Purpose: Indicates to the queue manager that the application has reached a syncpoint, and that all of the messages put or retrieved as part of a unit of work since the last syncpoint are to be made permanent.

Table 4. MQCMIT call

Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

Note: This call is not supported by MQSeries for AS/400, and can be used with MQSeries for MVS/ESA in the batch environment only. On Tandem NSK, this call always returns a *CompCode* of MQCC_FAILED and a *Reason* of MQRC_ENVIRONMENT_ERROR.

MQCONN

Purpose: Connects an application program to a queue manager.

Table 5. MQCONN call

Parameter	Data type	Usage
<i>Name</i>	(MQCHAR48)	input
<i>Hconn</i>	(MQHCONN)	output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQCONNX

Purpose: Provides options when connecting an application program to a queue manager.

Table 6. MQCONNX call

Parameter	Data type	Usage
<i>Name</i>	(MQCHAR48)	input
<i>ConnectOpts</i>	(MQCNO)	input/output
<i>Hconn</i>	(MQHCONN)	output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output
Note: This call is supported on MQSeries Version 5 products only.		

MQDISC

Purpose: Disconnects an application program from a queue manager (inverse of MQCONN).

Table 7. MQDISC call

Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input/output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQGET • MQINQ

MQGET

Purpose: Retrieves a message from a queue owned by the local queue manager.

Table 8. MQGET call

Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>Hobj</i>	(MQHOBJ)	input
<i>MsgDesc</i>	(MQMD)	input/output
<i>GetMsgOpts</i>	(MQGMO)	input/output
<i>BufferLength</i>	(MQLONG)	input
<i>Buffer</i>	(MQBYTE x <i>BufferLength</i>)	output
<i>DataLength</i>	(MQLONG)	output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQINQ

Purpose: Returns the attributes of an object.

Table 9. MQINQ call

Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>Hobj</i>	(MQHOBJ)	input
<i>SelectorCount</i>	(MQLONG)	input
<i>Selectors</i>	(MQLONG x <i>SelectorCount</i>)	input
<i>IntAttrCount</i>	(MQLONG)	input
<i>IntAttrs</i>	(MQLONG x <i>IntAttrCount</i>)	output
<i>CharAttrLength</i>	(MQLONG)	input
<i>CharAttrs</i>	(MQCHAR x <i>CharAttrLength</i>)	output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQOPEN

Purpose: Establishes access to an object.

<i>Table 10. MQOPEN call</i>		
Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>ObjDesc</i>	(MQOD)	input/output
<i>Options</i>	(MQLONG)	input
<i>Hobj</i>	(MQHOBJ)	output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQPUT

Purpose: Puts a message on an open queue.

<i>Table 11. MQPUT call</i>		
Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>Hobj</i>	(MQHOBJ)	input
<i>MsgDesc</i>	(MQMD)	input/output
<i>PutMsgOpts</i>	(MQPMO)	input/output
<i>BufferLength</i>	(MQLONG)	input
<i>Buffer</i>	(MQBYTE x <i>BufferLength</i>)	input
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQPUT1 •MQSET

MQPUT1

Purpose: Puts one message on a queue. This is equivalent to using the sequence of calls: MQOPEN, MQPUT, MQCLOSE.

<i>Table 12. MQPUT1 call</i>		
Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>ObjDesc</i>	(MQOD)	input
<i>MsgDesc</i>	(MQMD)	input/output
<i>PutMsgOpts</i>	(MQPMO)	input/output
<i>BufferLength</i>	(MQLONG)	input
<i>Buffer</i>	(MQBYTE x <i>BufferLength</i>)	input
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQSET

Purpose: Changes the attributes of a queue.

<i>Table 13. MQSET call</i>		
Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>Hobj</i>	(MQHOBJ)	input
<i>SelectorCount</i>	(MQLONG)	input
<i>Selectors</i>	(MQLONG x <i>SelectorCount</i>)	input
<i>IntAttrCount</i>	(MQLONG)	input
<i>IntAttrs</i>	(MQLONG x <i>IntAttrCount</i>)	input
<i>CharAttrLength</i>	(MQLONG)	input
<i>CharAttrs</i>	(MQCHAR x <i>CharAttrLength</i>)	input
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQSYNC

MQSYNC

Purpose: Synchronizes statistics updates. This call is included for backwards compatibility but performs no function.

Table 14. MQSYNC call

Parameter	Data type	Usage
<i>TransID</i>	(MQLONG x <i>TransID</i>)	input
<i>CommitAbort</i>	MQBYTE	input
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output
Note: This call is supported on MQSeries for Tandem NonStop Kernel only.		

MQSYNC

Chapter 2. Data conversion

A full description of the data-conversion exit call can be found in the *MQSeries Application Programming Reference* manual.

MQDATACONVEXIT

Purpose: Describes the parameters that are passed to the data-conversion exit.

<i>Table 15. MQDATACONVEXIT call</i>		
Parameter	Data type	Usage
<i>DataConvExitParms</i>	(MQDXP)	input/output
<i>MsgDesc</i>	(MQMD)	input/output
<i>InBufferLength</i>	(MQLONG)	input
<i>InBuffer</i>	(MQBYTE x <i>InBufferLength</i>)	input
<i>OutBufferLength</i>	(MQLONG)	input
<i>OutBuffer</i>	(MQBYTE x <i>OutBufferLength</i>)	output

MQXCNVC •MQDXP

MQXCNVC

Purpose: Converts characters from one character set to another. This call can be used only from a data-conversion exit.

<i>Table 16. MQXCNVC call</i>		
Parameter	Data type	Usage
<i>Hconn</i>	(MQHCONN)	input
<i>Options</i>	(MQLONG)	input
<i>SourceCCSID</i>	(MQLONG)	input
<i>SourceLength</i>	(MQLONG)	input
<i>SourceBuffer</i>	(MQCHAR x <i>SourceLength</i>)	input
<i>TargetCCSID</i>	(MQLONG)	input
<i>TargetLength</i>	(MQLONG)	input
<i>TargetBuffer</i>	(MQCHAR x <i>TargetLength</i>)	output
<i>DataLength</i>	(MQLONG)	output
<i>CompCode</i>	(MQLONG)	output
<i>Reason</i>	(MQLONG)	output

MQDXP (data-conversion exit parameter)

<i>Table 17. MQDXP structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQDXP_STRUC_ID	'DXPb'
<i>Version</i>	MQLONG	MQDXP_VERSION_1	1
<i>ExitOptions</i>	MQLONG	none	0
<i>AddOptions</i>	MQLONG	none	0
<i>Encoding</i>	MQLONG	none	0
<i>CodedCharSetId</i>	MQLONG	none	0
<i>DataLength</i>	MQLONG	none	0
<i>CompCode</i>	MQLONG	MQCC_OK	0
<i>Reason</i>	MQLONG	MQRC_NONE	0
<i>ExitResponse</i>	MQLONG	MQXDR_OK	0
<i>Hconn</i>	MQHCONN	none	0

Chapter 3. Data types

MQI calls use both elementary and structure data types. These correspond to data types that can be declared in a language that supports user-defined data types (for example, the C programming language). However, all user-defined data types ultimately resolve to elementary data types, or to aggregates of elementary data types (known as arrays or structures).

The elementary data types are:

MQBYTE	Byte
MQBYTE16	String of 16 bytes
MQBYTE24	String of 24 bytes
MQBYTE32	String of 32 bytes
MQBYTE64	String of 64 bytes
MQCHAR	Single-byte character
MQCHARn	String of n single-byte characters
MQHCONN	Connection handle
MQHOBJ	Object handle
MQLONG	Long integer
MQPTR	Pointer
PMQLONG	Pointer to data of type MQLONG

The structure data types are:

MQBO	Begin options
MQCNO	Connect options
MQGMO	Get-message options
MQMD	Message descriptor
MQMDE	Message descriptor extension
MQOD	Object descriptor
MQOR	Object record
MQPMO	Put-message options
MQPMR	Put-message record
MQRR	Response record
MQXP	API-crossing exit parameter

Elementary data types

MQSeries also uses the following structure data types to describe the formats of some messages and message headers:

MQDH	Distribution header
MQDLH	Dead-letter header
MQIIH	IMS information header
MQRMH	Reference message header
MQTM	Trigger message
MQTMC	Trigger message (character format)
MQTMC2	Trigger message (character format 2)
MQXQH	Transmission queue header

The following structure data types pertaining to MQSeries events are described in the *MQSeries Programmable System Management* book.

MQCFH	PCF header
MQCFIN	PCF integer parameter
MQCFST	PCF string parameter
MQCFIL	PCF integer list parameter
MQCFSL	PCF string list parameter

Elementary data types

The MQI uses the following elementary data types:

MQBYTE	A single byte (that is, a string of eight bits)
MQCHAR	A single character in a defined character set
MLONG	A 4-byte signed binary integer

All other data types equate either directly to these elementary data types or to aggregates of them (that is, arrays or structures).

In C language, the parameters of some of the MQI calls are defined as being pointers to the relevant data type.

Elementary data types - C

Elementary data types - C

These are typical declarations of the data types in C:

Table 18. C declarations of data types

Data type	Representation
MQBYTE	typedef unsigned char MQBYTE;
MQBYTE16	typedef MQBYTE MQBYTE16[16];
MQBYTE24	typedef MQBYTE MQBYTE24[24];
MQBYTE32	typedef MQBYTE MQBYTE32[32];
MQBYTE64	typedef MQBYTE MQBYTE64[64];
MQCHAR	typedef char MQCHAR;
MQCHAR4	typedef MQCHAR MQCHAR4[4];
MQCHAR8	typedef MQCHAR MQCHAR8[8];
MQCHAR12	typedef MQCHAR MQCHAR12[12];
MQCHAR16	typedef MQCHAR MQCHAR16[16];
MQCHAR20	typedef MQCHAR MQCHAR20[20];
MQCHAR28	typedef MQCHAR MQCHAR28[28];
MQCHAR32	typedef MQCHAR MQCHAR32[32];
MQCHAR48	typedef MQCHAR MQCHAR48[48];
MQCHAR64	typedef MQCHAR MQCHAR64[64];
MQCHAR128	typedef MQCHAR MQCHAR128[128];
MQCHAR256	typedef MQCHAR MQCHAR256[256];
MQHCONN	typedef MQLONG MQHCONN;
MQHOBJ	typedef MQLONG MQHOBJ;
MQPTR	typedef void MQPOINTER MQPTR;
PMQLONG	typedef MQLONG MQPOINTER PMQLONG;

Elementary data types - COBOL

Elementary data types - COBOL

These are typical declarations of the data types in COBOL:

Data type	Representation
MQBYTE	PIC X
MQBYTE16	PIC X(16)
MQBYTE24	PIC X(24)
MQBYTE32	PIC X(32)
MQBYTE64	PIC X(64)
MQCHAR	PIC X
MQCHAR4	PIC X(4)
MQCHAR8	PIC X(8)
MQCHAR12	PIC X(12)
MQCHAR16	PIC X(16)
MQCHAR20	PIC X(20)
MQCHAR28	PIC X(28)
MQCHAR32	PIC X(32)
MQCHAR48	PIC X(48)
MQCHAR64	PIC X(64)
MQCHAR128	PIC X(128)
MQCHAR256	PIC X(256)
MQHCONN	PIC S9(9) BINARY
MQHOBJ	PIC S9(9) BINARY
MQLONG	PIC S9(9) BINARY
MQPTR	POINTER
PMQLONG	POINTER

Elementary data types - PL/I

Elementary data types - PL/I

These are typical declarations of the data types in PL/I:

Table 20. PL/I declarations of data types

Data type	Representation
MQBYTE	char(1)
MQBYTE16	char(16)
MQBYTE24	char(24)
MQBYTE32	char(32)
MQBYTE64	char(64)
MQCHAR	char(1)
MQCHAR4	char(4)
MQCHAR8	char(8)
MQCHAR12	char(12)
MQCHAR16	char(16)
MQCHAR20	char(20)
MQCHAR28	char(28)
MQCHAR32	char(32)
MQCHAR48	char(48)
MQCHAR64	char(64)
MQCHAR128	char(128)
MQCHAR256	char(256)
MQHCONN	fixed bin(31)
MQHOBJ	fixed bin(31)
MQLONG	fixed bin(31)
PMQLONG	pointer

Elementary data types - S/390 assembler

Elementary data types - System/390 assembler

These are typical declarations of the data types in System/390 assembler.

Data type	Representation
MQBYTE	DS XL1
MQBYTE16	DS XL16
MQBYTE24	DS XL24
MQBYTE32	DS XL32
MQBYTE64	DS XL64
MQCHAR	DS CL1
MQCHAR4	DS CL4
MQCHAR8	DS CL8
MQCHAR12	DS CL12
MQCHAR16	DS CL16
MQCHAR20	DS CL20
MQCHAR28	DS CL28
MQCHAR32	DS CL32
MQCHAR48	DS CL48
MQCHAR64	DS CL64
MQCHAR128	DS CL128
MQCHAR256	DS CL256
MQHCONN	DS F
MQHOBJ	DS F
MQLONG	DS F
PMQLONG	DS F

Elementary data types - TAL

Elementary data types - TAL programming language

The elementary data types for the TAL programming language are:

Data Type	Representation
MQBYTE	STRING
MQBYTE24	BEGIN STRING BYTE [0:23];END
MQBYTE32	BEGIN STRING BYTE [0:31];END
MQCHAR	STRING
MQCHAR4	BEGIN STRING BYTE [0:3];END
MQCHAR8	BEGIN STRING BYTE [0:7]; END
MQCHAR12	BEGIN STRING BYTE [0:11];END
MQCHAR28	BEGIN STRING BYTE [0:27];END
MQCHAR32	BEGIN STRING BYTE [0:31];END
MQCHAR48	BEGIN STRING BYTE [0:47];END
MQCHAR64	BEGIN STRING BYTE [0:63];END
MQCHAR128	BEGIN STRING BYTE [0:127];END
MQCHAR256	BEGIN STRING BYTE [0:255];END
MQHCONN	INT(32)
MQHOBJ	INT(32)
MLONG	INT(32)

MQBO

Structure data types

Full details of MQI call structures can be found in the *MQSeries Application Programming Reference* manual.

In the following tables, the initial values of the fields are shown.

MQBO (begin options)

<i>Table 23. MQBO structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQBO_STRUC_ID	'B0bb'
<i>Version</i>	MQLONG	MQBO_VERSION_1	1
<i>Options</i>	MQLONG	MQBO_NONE	0

Note: This structure is supported on MQSeries Version 5 products only.

MQCIH

MQCIH (CICS bridge header)

Table 24. MQCIH structure

Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQCIH_STRUC_ID	'CIHb'
<i>Version</i>	MLONG	MQCIH_VERSION_1	1
<i>StrucLength</i>	MLONG	MQCIH_LENGTH_1	164
<i>Encoding</i>	MLONG	none	0
<i>CodedCharSetId</i>	MLONG	none	0
<i>Format</i>	MQCHAR8	MQFMT_NONE	'bbbbbbb'
<i>Flags</i>	MLONG	MQCIH_NONE	0
<i>ReturnCode</i>	MLONG	MQCRC_OK	0
<i>CompCode</i>	MLONG	MQCC_OK	0
<i>Reason</i>	MLONG	MQRC_NONE	0
<i>UOWControl</i>	MLONG	MQCUOWC_ONLY	273
<i>GetWaitInterval</i>	MLONG	MQCGWI_DEFAULT	-2
<i>LinkType</i>	MLONG	MQCLT_PROGRAM	1
<i>OutputDataLength</i>	MLONG	MQCODL_AS_INPUT	-1
<i>FacilityKeepTime</i>	MLONG	none	0
<i>ADSDescriptor</i>	MLONG	MQCADSD_NONE	0
<i>ConversationalTask</i>	MLONG	MQCCT_NO	0
<i>TaskEndStatus</i>	MLONG	MQCTES_NOSYNC	0
<i>Facility</i>	MQBYTE8	MQCFAC_NONE	Nulls
<i>Function</i>	MQCHAR4	MQCFUNC_NONE	'bbb'
<i>AbendCode</i>	MQCHAR4	none	'bbb'
<i>Authenticator</i>	MQCHAR8	none	'bbbbbbb'
<i>Reserved1</i>	MQCHAR8	none	'bbbbbbb'
<i>ReplyToFormat</i>	MQCHAR8	MQFMT_NONE	'bbbbbbb'
<i>RemoteSysId</i>	MQCHAR4	none	'bbb'
<i>RemoteTransId</i>	MQCHAR4	none	'bbb'
<i>TransactionId</i>	MQCHAR4	none	'bbb'
<i>FacilityLike</i>	MQCHAR4	none	'bbb'
<i>AttentionId</i>	MQCHAR4	none	'bbb'
<i>StartCode</i>	MQCHAR4	MQCSC_NONE	'bbb'
<i>CancelCode</i>	MQCHAR4	none	'bbb'
<i>NextTransactionId</i>	MQCHAR4	none	'bbb'
<i>Reserved2</i>	MQCHAR8	none	'bbbbbbb'
<i>Reserved3</i>	MQCHAR8	none	'bbbbbbb'

Note: This structure is supported on MVS/ESA only.

MQCNO •MQDH

MQCNO (connect options)

<i>Table 25. MQCNO structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQCNO_STRUC_ID	'CNOb'
<i>Version</i>	MQLONG	MQCNO_VERSION_1	1
<i>Options</i>	MQLONG	MQCNO_NONE	0

Note: This structure is supported on MQSeries Version 5 products only.

MQDH (distribution header)

<i>Table 26. MQDH structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQDH_STRUC_ID	'DHbb'
<i>Version</i>	MQLONG	MQDH_VERSION_1	1
<i>StrucLength</i>	MQLONG	none	0
<i>Encoding</i>	MQLONG	none	0
<i>CodedCharSetId</i>	MQLONG	none	0
<i>Format</i>	MQCHAR8	MQFMT_NONE	'bbbbbbbb'
<i>Flags</i>	MQLONG	MQDHF_NONE	0
<i>PutMsgRecFields</i>	MQLONG	MQPMRF_NONE	0
<i>RecsPresent</i>	MQLONG	none	0
<i>ObjectRecOffset</i>	MQLONG	none	0
<i>PutMsgRecOffset</i>	MQLONG	none	0

Note: This structure is supported on MQSeries Version 5 products and MQSeries for AS/400 only.

MQDLH

MQDLH (dead-letter header)

<i>Table 27. MQDLH structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQDLH_STRUC_ID	'DLHb'
<i>Version</i>	MQLONG	MQDLH_VERSION_1	1
<i>Reason</i>	MQLONG	MQRC_NONE	0
<i>DestQName</i>	MQCHAR48	none	blanks
<i>DestQMgrName</i>	MQCHAR48	none	blanks
<i>Encoding</i>	MQLONG	MQENC_NATIVE MVS/ESA: OS/2(C): OS/2(COBOL): AS/400: UNIX systems: Windows NT(C): Windows NT(COBOL):	785 546 17 273 273 546 17
<i>CodedCharSetId</i>	MQLONG	none	0
<i>Format</i>	MQCHAR8	MQFMT_NONE	'bbbbbbb'
<i>PutApplType</i>	MQLONG	none	0
<i>PutApplName</i>	MQCHAR28	none	blanks
<i>PutDate</i>	MQCHAR8	none	blanks
<i>PutTime</i>	MQCHAR8	none	blanks
Note: This structure is not supported on MQSeries for Windows.			

MQGMO

MQGMO (get-message options)

<i>Table 28. MQGMO structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQGMO_STRUC_ID	'GMOb'
<i>Version</i>	MQLONG	MQGMO_VERSION_1	1
<i>Options</i>	MQLONG	MQGMO_NO_WAIT	0
<i>WaitInterval</i>	MQLONG	none	0
<i>Signal1</i>	MVS/ESA: PMQLONG All others: MQLONG	none none	NULL 0
<i>Signal2</i>	MQLONG	none	0
<i>ResolvedQName</i>	MQCHAR48	none	blanks
<i>MatchOptions</i> (1)	MQLONG	MQMO_MATCH_MSG_ID MQMO_MATCH_CORREL_ID	3
<i>GroupStatus</i> (1)	MQCHAR	MQGS_NOT_IN_GROUP	blanks
<i>SegmentStatus</i> (1)	MQCHAR	MQSS_NOT_A_SEGMENT	blanks
<i>Segmentation</i> (1)	MQCHAR	MQSEG_INHIBITED	blanks
Note:			
1. This field is supported on MQSeries Version 5 products and MQSeries for AS/400 only.			

MQIIH (IMS information header)

<i>Table 29. MQIIH structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQIIH_STRUC_ID	'IIHb'
<i>Version</i>	MLONG	MQIIH_VERSION_1	1
<i>StrucLength</i>	MLONG	MQIIH_LENGTH_1	84
<i>Encoding</i>	MLONG	MQENC_NATIVE MVS/ESA: OS/2(C): OS/2(COBOL): AS/400: UNIX systems: Windows NT(C): Windows NT(COBOL):	785 546 17 273 273 546 17
<i>CodedCharSetId</i>	MLONG	MQCCSI_Q_MGR	0
<i>Format</i>	MQCHAR8	MQFMT_NONE	'bbbbbbb'
<i>Flags</i>	MLONG	MQIIH_NONE	0
<i>LTermOverride</i>	MQCHAR8	none	blanks
<i>MFSMapName</i>	MQCHAR8	none	blanks
<i>ReplyToFormat</i>	MQCHAR8	MQFMT_NONE	'bbbbbbb'
<i>Authenticator</i>	MQCHAR8	MQIAUT_NONE	'bbbbbbb'
<i>TranInstanceId</i>	MQBYTE16	MQITII_NONE	nulls
<i>TranState</i>	MQCHAR	MQITS_NOT_IN_CONVERSATION	'b'
<i>CommitMode</i>	MQCHAR	MQICM_COMMIT_THEN_SEND	'0'
<i>SecurityScope</i>	MQCHAR	MQISS_CHECK	'c'
<i>Reserved</i>	MQCHAR	none	'b'
Note: This structure is not supported on MQSeries for Windows or MQSeries for Tandem NonStop Kernel.			

MQMD

MQMD (message descriptor)

<i>Table 30. MQMD structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQMD_STRUC_ID	'MDbb'
<i>Version</i>	MLONG	MQMD_VERSION_1	1
<i>Report</i>	MLONG	MQRO_NONE	0
<i>MsgType</i>	MLONG	MQMT_DATAGRAM	8
<i>Expiry</i>	MLONG	MQEI_UNLIMITED	-1
<i>Feedback</i>	MLONG	MQFB_NONE	0
<i>Encoding</i>	MLONG	MQENC_NATIVE MVS/ESA: OS/2(C): OS/2(COBOL): AS/400: UNIX systems: Windows NT(C): Windows NT(COBOL):	785 546 17 273 273 546 17
<i>CodedCharSetId</i>	MLONG	MQCCSI_Q_MGR	0
<i>Format</i>	MQCHAR8	MQFMT_NONE	'bbbbbbbb'
<i>Priority</i>	MLONG	MQPRI_PRIORITY_AS_Q_DEF	-1
<i>Persistence</i>	MLONG	MQPER_PERSISTENCE_AS_Q_DEF	2
<i>MsgId</i>	MQBYTE24	MQMI_NONE	nulls
<i>CorrelId</i>	MQBYTE24	MQCI_NONE	nulls
<i>BackoutCount</i>	MLONG	none	0
<i>ReplyToQ</i>	MQCHAR48	none	blanks
<i>ReplyToQMgr</i>	MQCHAR48	none	blanks
<i>UserIdentifier</i>	MQCHAR12	none	blanks
<i>AccountingToken</i>	MQBYTE32	MQACT_NONE	nulls
<i>ApplIdentityData</i>	MQCHAR32	none	blanks
<i>PutApplType</i>	MLONG	MQAT_NO_CONTEXT	0
<i>PutApplName</i>	MQCHAR28	none	blanks
<i>PutDate</i>	MQCHAR8	none	blanks
<i>PutTime</i>	MQCHAR8	none	blanks
<i>ApplOriginData</i>	MQCHAR4	none	blanks
<i>GroupId (1)</i>	MQBYTE24	MQGI_NONE	nulls
<i>MsgSeqNumber (1)</i>	MLONG	none	1
<i>Offset (1)</i>	MLONG	none	0
<i>MsgFlags (1)</i>	MLONG	MQMF_NONE	0
<i>OriginalLength (1)</i>	MLONG	MQOL_UNDEFINED	-1
Note:			
1. This field is supported on MQSeries Version 5 products and MQSeries for AS/400 only, that is, only when MQMD_VERSION_2 is selected.			

MQMDE

MQMDE (message descriptor extension)

<i>Table 31. MQMDE structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQMDE_STRUC_ID	'MDEb'
<i>Version</i>	MQLONG	MQMDE_VERSION_2	2
<i>StrucLength</i>	MQLONG	MQMDE_STRUC_LENGTH_2	72
<i>Encoding</i>	MQLONG	MQENC_NATIVE MVS/ESA: OS/2(C): OS/2(COBOL): AS/400: UNIX systems: Windows NT(C): Windows NT(COBOL):	785 546 17 273 273 546 17
<i>CodedCharSetId</i>	MQLONG	MQCCSI_Q_MGR	0
<i>Format</i>	MQCHAR8	MQFMT_NONE	'bbbbbbbb'
<i>Flags</i>	MQLONG	MQMDEF_NONE	0
<i>GroupId</i>	MQBYTE24	MQGI_NONE	nulls
<i>MsgSeqNumber</i>	MQLONG	none	1
<i>Offset</i>	MQLONG	none	0
<i>MsgFlags</i>	MQLONG	MQMF_NONE	0
<i>OriginalLength</i>	MQLONG	MQOL_UNDEFINED	-1
Note: This structure is supported on MQSeries Version 5 products and MQSeries for AS/400 only.			

MQOD •MQOR

MQOD (object descriptor)

<i>Table 32. MQOD structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQOD_STRUC_ID	'0Dbb'
<i>Version</i>	MLONG	MQOD_VERSION_1	1
<i>ObjectType</i>	MLONG	MQOT_Q	1
<i>ObjectName</i>	MQCHAR48	none	blanks
<i>ObjectQMgrName</i>	MQCHAR48	none	blanks
<i>DynamicQName</i>	MQCHAR48	none MVS/ESA: none All others:	'CSQ.*' 'AMQ.*'
<i>AlternateUserId</i>	MQCHAR12	none	blanks
<i>RecsPresent (1)</i>	MLONG	none	0
<i>KnownDestCount (1)</i>	MLONG	none	0
<i>UnknownDestCount (1)</i>	MLONG	none	0
<i>InvalidDestCount (1)</i>	MLONG	none	0
<i>ObjectRecOffset (1)</i>	MLONG	none	0
<i>ResponseRecOffset (1)</i>	MLONG	none	0
<i>ObjectRecPtr (1)</i>	MQPTR	none	null(2)
<i>ResponseRecPtr (1)</i>	MQPTR	none	null(2)
Notes:			
1. This field is supported on MQSeries Version 5 products and MQSeries for AS/400 only. 2. This value is a null pointer in C and null bytes otherwise.			

MQOR (object record)

<i>Table 33. MQOR structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>ObjName</i>	MQCHAR48	none	blanks
<i>ObjectQMgrName</i>	MQCHAR48	none	blanks
Note: This structure is supported on MQSeries Version 5 products and MQSeries for AS/400 only.			

MQPMO (put-message options)

<i>Table 34. MQPMO structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQPMO_STRUC_ID	'PMOb'
<i>Version</i>	MLONG	MQPMO_VERSION_1	1
<i>Options</i>	MLONG	MQPMO_NONE	0
<i>Timeout</i>	MLONG	none	-1
<i>Context</i>	MQHOBj	none	0
<i>KnownDestCount</i>	MLONG	none	0
<i>UnknownDestCount</i>	MLONG	none	0
<i>InvalidDestCount</i>	MLONG	none	0
<i>ResolvedQName</i>	MQCHAR48	none	blanks
<i>ResolvedQMgrName</i>	MQCHAR48	none	blanks
<i>RecsPresent</i> (1)	MLONG	none	0
<i>PutMsgRecFields</i> (1)	MLONG	MQPMRF_NONE	0
<i>PutMsgRecOffset</i> (1)	MLONG	none	0
<i>ResponseRecOffset</i> (1)	MLONG	none	0
<i>PutMsgRecPtr</i> (1)	none	nulls	
<i>ResponseRecPtr</i> (1)	MQPTR	none	nulls
Note:			
1. This field is supported on MQSeries Version 5 products and MQSeries for AS/400 only.			

MQPMR (put-message record)

<i>Table 35. MQPMR structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>MsgId</i>	MQBYTE24	MQMI_NONE	nulls
<i>CorrelId</i>	MQBYTE24	MQCI_NONE	nulls
<i>GroupId</i>	MQBYTE24	MQGI_NONE	nulls
<i>Feedback</i>	MLONG	MQFB_NONE	0
<i>AccountingToken</i>	MQBYTE32	MQACT_NONE	nulls
Note: This structure is supported on MQSeries Version 5 products and MQSeries for AS/400 only.			
This structure does not have a fixed layout. All fields are optional, but those that are present must occur in the sequence shown.			

MQRMH •MQRR

MQRMH (reference-message header)

<i>Table 36. MQRMH structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQRMH_STRUC_ID	'RMHb'
<i>Version</i>	MLONG	MQRMH_VERSION_1	1
<i>StrucLength</i>	MLONG	none	0
<i>Encoding</i>	MLONG	MQENC_NATIVE MVS/ESA: OS/2(C): OS/2(COBOL): AS/400: UNIX systems: Windows NT(C): Windows NT(COBOL):	785 546 17 273 273 546 17
<i>CodedCharSetId</i>	MLONG	MQCCSI_Q_MGR	0
<i>Format</i>	MQCHAR8	MQFMT_NONE	'bbbbbbb'
<i>Flags</i>	MLONG	MQRMHF_NOT_LAST	0
<i>ObjectType</i>	MQCHAR8	none	'bbbbbbb'
<i>ObjectInstanceId</i>	MQBYTE24	MQOII_NONE	nulls
<i>SrcEnvLength</i>	MLONG	none	0
<i>SrcEnvOffset</i>	MLONG	none	0
<i>SrcNameLength</i>	MLONG	none	0
<i>SrcNameOffset</i>	MLONG	none	0
<i>DestEnvLength</i>	MLONG	none	0
<i>DestEnvOffset</i>	MLONG	none	0
<i>DestNameLength</i>	MLONG	none	0
<i>DestNameOffset</i>	MLONG	none	0
<i>DataLogicalLength</i>	MLONG	none	0
<i>DataLogicalOffset</i>	MLONG	none	0
<i>DataLogicalOffset2</i>	MLONG	none	0
Note: This structure is supported on MQSeries Version 5 products and MQSeries for AS/400 only.			

MQRR (response record)

<i>Table 37. MQRR structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>CompCode</i>	MLONG	MQCC_OK	0
<i>Reason</i>	MLONG	MQRC_NONE	0
Note: This structure is supported on MQSeries Version 5 products and MQSeries for AS/400 only.			

MQTM (trigger message)

<i>Table 38. MQTM structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQTM_STRUC_ID	'TMbb'
<i>Version</i>	MLONG	MQTM_VERSION_1	1
<i>QName</i>	MQCHAR48	none	blanks
<i>ProcessName</i>	MQCHAR48	none	blanks
<i>TriggerData</i>	MQCHAR64	none	blanks
<i>ApplType</i>	MLONG	none	0
<i>ApplId</i>	MQCHAR256	none	blanks
<i>EnvData</i>	MQCHAR128	none	blanks
<i>UserData</i>	MQCHAR128	none	blanks
Note: This structure is not supported on MQSeries for Windows.			

MQTMC (trigger message in character format)

<i>Table 39. MQTMC structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQTMC_STRUC_ID	'TMCb'
<i>Version</i>	MQCHAR4	MQTMC_VERSION_1	'bbb1'
<i>QName</i>	MQCHAR48	none	blanks
<i>ProcessName</i>	MQCHAR48	none	blanks
<i>TriggerData</i>	MQCHAR64	none	blanks
<i>ApplType</i>	MQCHAR4	none	blanks
<i>ApplId</i>	MQCHAR256	none	blanks
<i>EnvData</i>	MQCHAR128	none	blanks
<i>UserData</i>	MQCHAR128	none	blanks
Note: This structure is supported on MQSeries for AS/400 only.			

MQTMC2 • MQXP

MQTMC2 (trigger message—character format 2)

<i>Table 40. MQTMC2 structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQTMC_STRUC_ID	'TMCb'
<i>Version</i>	MQCHAR4	MQTMC_VERSION_2	'bbb2'
<i>QName</i>	MQCHAR48	none	blanks
<i>ProcessName</i>	MQCHAR48	none	blanks
<i>TriggerData</i>	MQCHAR64	none	blanks
<i>ApplType</i>	MQCHAR4	none	blanks
<i>ApplId</i>	MQCHAR256	none	blanks
<i>EnvData</i>	MQCHAR128	none	blanks
<i>UserData</i>	MQCHAR128	none	blanks
<i>QMgrName</i>	MQCHAR48	none	blanks

Note: This structure is not supported on MQSeries for Windows.

MQXP (API-crossing exit parameter block)

<i>Table 41. MQXP structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQXP_STRUC_ID	'XQHb'
<i>Version</i>	MLONG	MQXP_VERSION_1	1
<i>ExitId</i>	MLONG	MQXT_API_CROSSING_EXIT	1
<i>ExitReason</i>	MLONG	none	0
<i>ExitResponse</i>	MLONG	MQXCC_OK	0
<i>ExitCommand</i>	MLONG	none	0
<i>ExitParmCount</i>	MLONG	none	0
<i>Reserved</i>	MLONG	none	0
<i>ExitUserArea</i>	MQBYTE16	MQXUA_NONE	nulls

Note: This structure is supported on MVS/ESA only.

MQXQH

MQXQH (transmission-queue header)

<i>Table 42. MQXQH structure</i>			
Field name	Data type	Name of constant	Value of constant
<i>StrucId</i>	MQCHAR4	MQXQH_STRUC_ID	'XQHb'
<i>Version</i>	MQLONG	MQXQH_VERSION_1	1
<i>RemoteQName</i>	MQCHAR48	none	blanks
<i>RemoteQMgrName</i>	MQCHAR48	none	blanks
<i>MsgDesc</i>	MQMD	Names and values as in Table 30 on page 24	

MQXQH

Object attributes • Local and model queues

Chapter 4. Attributes of MQSeries objects

Full details of these attributes can be found in the *Application Programming Reference* manual.

Local and model queue attributes

<i>Table 43 (Page 1 of 2). Attributes of local and model queues</i>		
Attribute	Data type	Name of Selector
<i>BackoutRequeueQName</i>	MQCHAR48	MQCA_BACKOUT_REQ_Q_NAME
<i>BackoutThreshold</i>	MLONG	MQIA_BACKOUT_THRESHOLD
<i>CreationDate</i>	MQCHAR12	MQCA_CREATION_DATE
<i>CreationTime</i>	MQCHAR8	MQCA_CREATION_TIME
<i>CurrentQDepth(1)</i>	MLONG	MQIA_CURRENT_Q_DEPTH
<i>DefinitionType</i>	MLONG	MQIA_DEFINITION_TYPE
<i>DefInputOpenOption</i>	MLONG	MQIA_DEF_INPUT_OPEN_OPTION
<i>DefPersistence</i>	MLONG	MQIA_DEF_PERSISTENCE
<i>DefPriority</i>	MLONG	MQIA_DEF_PRIORITY
<i>DistLists(2)</i>	MLONG	MQIA_DIST_LISTS
<i>HardenGetBackout(3)</i>	MLONG	MQIA_HARDEN_GET_BACKOUT
<i>IndexType(3)</i>	MLONG	MQIA_INDEX_TYPE
<i>InhibitGet</i>	MLONG	MQIA_INHIBIT_GET
<i>InhibitPut</i>	MLONG	MQIA_INHIBIT_PUT
<i>InitiationQName(4)</i>	MQCHAR48	MQCA_INITIATION_Q_NAME
<i>MaxMsgLength</i>	MLONG	MQIA_MAX_MSG_LENGTH
<i>MaxQDepth</i>	MLONG	MQIA_MAX_Q_DEPTH
<i>MsgDeliverySequence</i>	MLONG	MQIA_MSG_DELIVERY_SEQUENCE
<i>OpenInputCount(1)</i>	MLONG	MQIA_OPEN_INPUT_COUNT
<i>OpenOutputCount(1)</i>	MLONG	MQIA_OPEN_OUTPUT_COUNT
<i>ProcessName(4, 5)</i>	MQCHAR48	MQCA_PROCESS_NAME
<i>QDepthHighEvent(6)</i>	MLONG	MQIA_Q_DEPTH_HIGH_EVENT (PCF)
<i>QDepthHighLimit(6)</i>	MLONG	MQIA_Q_DEPTH_HIGH_LIMIT (PCF)
<i>QDepthLowEvent(6)</i>	MLONG	MQIA_Q_DEPTH_LOW_EVENT (PCF)
<i>QDepthLowLimit(6)</i>	MLONG	MQIA_Q_DEPTH_LOW_LIMIT (PCF)
<i>QDepthMaxEvent(6)</i>	MLONG	MQIA_Q_DEPTH_MAX_EVENT (PCF)
<i>QDesc</i>	MQCHAR64	MQCA_Q_DESC
<i>QName</i>	MQCHAR48	MQCA_Q_NAME
<i>QServiceInterval(6)</i>	MLONG	MQIA_Q_SERVICE_INTERVAL (PCF)

Local and model queues

<i>Table 43 (Page 2 of 2). Attributes of local and model queues</i>		
Attribute	Data type	Name of Selector
<i>QServiceIntervalEvent</i> (6)	MLONG	MQIA_Q_SERVICE_INTERVAL_EVENT (PCF)
<i>QType</i>	MLONG	MQIA_Q_TYPE
<i>RetentionInterval</i>	MLONG	MQIA_RETENTION_INTERVAL
<i>Scope</i> (4, 7)	MLONG	MQIA_SCOPE
<i>Shareability</i>	MLONG	MQIA_SHAREABILITY
<i>StorageClass</i> (3)	MQCHAR8	MQCA_STORAGE_CLASS
<i>TriggerControl</i> (4)	MLONG	MQIA_TRIGGER_CONTROL
<i>TriggerData</i> (4)	MQCHAR64	MQCA_TRIGGER_DATA
<i>TriggerDepth</i> (4)	MLONG	MQIA_TRIGGER_DEPTH
<i>TriggerMsgPriority</i> (4)	MLONG	MQIA_TRIGGER_MSG_PRIORITY
<i>TriggerType</i> (4)	MLONG	MQIA_TRIGGER_TYPE
<i>Usage</i>	MLONG	MQIA_USAGE
Notes:		
<ol style="list-style-type: none"> 1. Applies to local queues only 2. Applies to OS/2, AS/400, UNIX systems, and Windows NT only 3. Applies to MVS/ESA only 4. Does not apply to Windows Version 2.0 or Version 2.1 5. Optional in the case of triggering channels on MQSeries Version 5 products and MQSeries for AS/400 6. Applies to OS/2, AS/400, UNIX systems, Windows NT and Windows Version 2.1 only 7. Not supported on MVS/ESA or AS/400 		

Remote queues • Alias queues

Local definition of remote queue attributes

<i>Table 44. Attributes of local definitions of remote queues</i>		
Attribute	Data type	Name of Selector
<i>DefPersistence</i>	MLONG	MQIA_DEF_PERSISTENCE
<i>DefPriority</i>	MLONG	MQIA_DEF_PRIORITY
<i>InhibitPut</i>	MLONG	MQIA_INHIBIT_PUT
<i>QDesc</i>	MQCHAR64	MQCA_Q_DESC
<i>QName</i>	MQCHAR48	MQCA_Q_NAME
<i>QType</i>	MLONG	MQIA_Q_TYPE
<i>RemoteQMgrName</i>	MQCHAR48	MQCA_REMOTE_Q_MGR_NAME
<i>RemoteQName</i>	MQCHAR48	MQCA_REMOTE_Q_NAME
<i>Scope(1)</i>	MLONG	MQIA_SCOPE
<i>XmitQName</i>	MQCHAR48	MQCA_XMIT_Q_NAME
Note:		
1. This attribute does not apply to AS/400, MVS/ESA, Windows Version 2.0, or Windows Version 2.1.		

Alias queue attributes

<i>Table 45. Attributes of alias queues</i>		
Attribute	Data type	Name of Selector
<i>BaseQName</i>	MQCHAR48	MQCA_BASE_Q_NAME
<i>DefPersistence</i>	MLONG	MQIA_DEF_PERSISTENCE
<i>DefPriority</i>	MLONG	MQIA_DEF_PRIORITY
<i>InhibitGet</i>	MLONG	MQIA_INHIBIT_GET
<i>InhibitPut</i>	MLONG	MQIA_INHIBIT_PUT
<i>QDesc</i>	MQCHAR64	MQCA_Q_DESC
<i>QName</i>	MQCHAR48	MQCA_Q_NAME
<i>QType</i>	MLONG	MQIA_Q_TYPE
<i>Scope(1)</i>	MLONG	MQIA_SCOPE
Note:		
1. This attribute does not apply to AS/400, MVS/ESA, Windows Version 2.0, or Windows Version 2.1.		

Namelist • Process definitions

Namelist attributes

<i>Table 46. Attributes of namelists</i>		
Attribute	Data type	Name of Selector
<i>NameCount</i>	MLONG	MQIA_NAME_COUNT
<i>NamelistDesc</i>	MQCHAR64	MQCA_NAMELIST_DESC
<i>NamelistName</i>	MQCHAR48	MQCA_NAMELIST_NAME
<i>Names</i>	MQCHAR48 x <i>NameCount</i>	MQCA_NAMES
Note: Namelists are supported on MVS/ESA only.		

Process definition attributes

<i>Table 47. Attributes of process definitions</i>		
Attribute	Data type	Name of Selector
<i>ApplId</i>	MQCHAR256	MQCA_APPL_ID
<i>ApplType</i>	MLONG	MQIA_APPL_TYPE
<i>EnvData</i>	MQCHAR128	MQCA_ENV_DATA
<i>ProcessDesc</i>	MQCHAR64	MQCA_PROCESS_DESC
<i>ProcessName</i>	MQCHAR48	MQCA_PROCESS_NAME
<i>UserData</i>	MQCHAR128	MQCA_USER_DATA
Notes:		
<ul style="list-style-type: none">• On MQSeries Version 5 products and MQSeries for AS/400, the process definition object is optional in the case of triggering channels.• Process definitions are not supported on Windows Version 2.0 or Windows Version 2.1.		

Queue manager attributes

<i>Table 48. Attributes of a queue manager</i>		
Attribute	Data type	Name of Selector
<i>AuthorityEvent(1)</i>	MLONG	MQIA_AUTHORITY_EVENT
<i>CodedCharSetId</i>	MLONG	MQIA_CODED_CHAR_SET_ID
<i>CommandInputQName</i>	MQCHAR48	MQCA_COMMAND_INPUT_Q_NAME
<i>CommandLevel</i>	MLONG	MQIA_COMMAND_LEVEL
<i>DeadLetterQName(1, 2)</i>	MQCHAR48	MQCA_DEAD_LETTER_Q_NAME
<i>DefXmitQName</i>	MQCHAR48	MQCA_DEF_XMIT_Q_NAME
<i>DistLists(3)</i>	MLONG	MQIA_DIST_LISTS
<i>InhibitEvent(1)</i>	MLONG	MQIA_INHIBIT_EVENT
<i>LocalEvent(1)</i>	MLONG	MQIA_LOCAL_EVENT
<i>MaxHandles</i>	MLONG	MQIA_MAX_HANDLES
<i>MaxMsgLength</i>	MLONG	MQIA_MAX_MSG_LENGTH
<i>MaxPriority</i>	MLONG	MQIA_MAX_PRIORITY
<i>MaxUncommittedMsgs</i>	MLONG	MQIA_MAX_UNCOMMITTED_MSGS
<i>PerformanceEvent(1)</i>	MLONG	MQIA_PERFORMANCE_EVENT
<i>Platform</i>	MLONG	MQIA_PLATFORM
<i>QMgrDesc</i>	MQCHAR64	MQCA_Q_MGR_DESC
<i>QMgrName</i>	MQCHAR48	MQCA_Q_MGR_NAME
<i>RemoteEvent(1)</i>	MLONG	MQIA_REMOTE_EVENT
<i>StartStopEvent(1)</i>	MLONG	MQIA_START_STOP_EVENT
<i>SyncPoint</i>	MLONG	MQIA_SYNCPOINT
<i>TriggerInterval(1, 2)</i>	MLONG	MQIA_TRIGGER_INTERVAL
Notes:		
1. This attribute does not apply to Windows Version 2.0.		
2. This attribute does not apply to Windows Version 2.1.		
3. This attribute applies to MQSeries Version 5 products and MQSeries for AS/400 only.		

Queue manager

Chapter 5. MQI constants

Full details of the MQI call constants are in the *MQSeries Application Programming Reference* manual. Full details of the events, commands, and responses constants are in the *MQSeries Programmable System Management* book.

The information in these tables applies to all platforms except where indicated by an X.

Note: The presence or absence of an X is not an indication of whether the constant is supplied in the MQI header. In the case of input fields, such as MQIA_*, the system does not *act on* those indicated with an X. In the case of output fields, such as MQRC_*, the system does not *generate* those indicated with an X.

MQ_* (Lengths of character string and byte fields)

Table 49 (Page 1 of 3). MQ_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQ_ABEND_CODE_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_ACCOUNTING_TOKEN_LENGTH									32	00000020
MQ_APPL_IDENTITY_DATA_LENGTH									32	00000020
MQ_APPL_NAME_LENGTH									28	0000001C
MQ_APPL_ORIGIN_DATA_LENGTH									4	00000004
MQ_ATTENTION_ID_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_AUTHENTICATOR_LENGTH		X	X	X	X	X	X	X	8	00000008
MQ_BRIDGE_NAME_LENGTH		X	X	X	X	X	X	X	24	00000018
MQ_CANCEL_CODE_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_CHANNEL_DATE_LENGTH									12	0000000C
MQ_CHANNEL_DESC_LENGTH									64	00000040
MQ_CHANNEL_NAME_LENGTH									20	00000014
MQ_CHANNEL_TIME_LENGTH									8	00000008
MQ_CONN_NAME_LENGTH									264	00000108
MQ_CORREL_ID_LENGTH									24	00000018
MQ_CREATION_DATE_LENGTH									12	0000000C
MQ_CREATION_TIME_LENGTH									8	00000008
MQ_EXIT_DATA_LENGTH									32	00000020
MQ_EXIT_NAME_LENGTH		X	X	X	X	X	X	X	8	00000008
	X	X		X	X	X	X	X	20	00000014
	X		X						128	00000080
MQ_EXIT_USER_AREA_LENGTH									16	00000010

MQ_*

Table 49 (Page 2 of 3). MQ_* constants										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQ_FACILITY_LENGTH		X	X	X	X	X	X	X	8	00000008
MQ_FACILITY_LIKE_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_FORMAT_LENGTH									8	00000008
MQ_FUNCTION_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_GROUP_ID_LENGTH	X			(1)	X	X			24	00000018
MQ_LTERM_OVERRIDE_LENGTH		X	X	X	X	X	X	X	8	00000008
MQ_LUWID_LENGTH									16	00000010
MQ_MCA_JOB_NAME_LENGTH									28	0000001C
MQ_MCA_NAME_LENGTH									20	00000014
MQ_MFS_MAP_NAME_LENGTH		X	X	X	X	X	X	X	8	00000008
MQ_MODE_NAME_LENGTH									8	00000008
MQ_MSG_HEADER_LENGTH									4000	0000FA0
MQ_MSG_ID_LENGTH									24	00000018
MQ_NAMELIST_DESC_LENGTH		X	X	X	X	X	X	X	64	00000040
MQ_NAMELIST_NAME_LENGTH		X	X	X	X	X	X	X	48	00000030
MQ_OBJECT_INSTANCE_ID_LENGTH	X			(1)	X	X	X		24	00000018
MQ_PASSWORD_LENGTH									12	0000000C
MQ_PROCESS_APPL_ID_LENGTH									256	0000100
MQ_PROCESS_DESC_LENGTH									64	00000040
MQ_PROCESS_ENV_DATA_LENGTH									128	00000080
MQ_PROCESS_NAME_LENGTH									48	00000030
MQ_PROCESS_USER_DATA_LENGTH									128	00000080
MQ_PUT_APPL_NAME_LENGTH									28	0000001C
MQ_PUT_DATE_LENGTH									8	00000008
MQ_PUT_TIME_LENGTH									8	00000008
MQ_Q_DESC_LENGTH									64	00000040
MQ_Q_MGR_DESC_LENGTH									64	00000040
MQ_Q_MGR_NAME_LENGTH									48	00000030
MQ_Q_NAME_LENGTH									48	00000030
MQ_REMOTE_SYS_ID_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_SHORT_CONN_NAME_LENGTH									20	00000014
MQ_START_CODE_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_STORAGE_CLASS_LENGTH		X	X	X	X	X	X	X	8	00000008
MQ_TOTAL_EXIT_DATA_LENGTH	X								999	00003E7
MQ_TOTAL_EXIT_NAME_LENGTH	X								999	00003E7

MQACT_*

Table 49 (Page 3 of 3). MQ_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQ_TP_NAME_LENGTH									64	00000040
MQ_TRAN_INSTANCE_ID_LENGTH		X	X	X	X	X	X	X	16	00000010
MQ_TRANSACTION_ID_LENGTH		X	X	X	X	X	X	X	4	00000004
MQ_TRIGGER_DATA_LENGTH									64	00000040
MQ_USER_ID_LENGTH									12	0000000C
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQACT_* (Accounting token)

Table 50. MQACT_* constants

Constant	Value
MQACT_NONE	32 nulls

MQAT_*

MQAT_* (Application type)

Table 51. MQAT_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQAT_DEFAULT									environment specific	
MQAT_UNKNOWN									-1	FFFFFFF
MQAT_NO_CONTEXT									0	0000000
MQAT_CICS									1	0000001
MQAT_MVS									2	0000002
MQAT_IMS									3	0000003
MQAT_OS2									4	0000004
MQAT_DOS									5	0000005
MQAT_AIX									6	0000006
MQAT_UNIX									6	0000006
MQAT_QMGR									7	0000007
MQAT_OS400									8	0000008
MQAT_WINDOWS									9	0000009
MQAT_CICS_VSE									10	000000A
MQAT_WINDOWS_NT									11	000000B
MQAT_VMS									12	000000C
MQAT_NSK									13	000000D
MQAT_GUARDIAN									13	000000D
MQAT_VOS									14	000000E
MQAT_IMS_BRIDGE									19	0000013
MQAT_XCF									20	0000014
MQAT_CICS_BRIDGE		X	X	X	X	X	X	X	21	0000015
MQAT_USER_FIRST									65536	00010000
MQAT_USER_LAST									999999999	3B9AC9FF

MQBO_* (Begin options)

Table 52. MQBO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQBO_NONE	X	X	(1)	X	X	X			0	00000000
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQBO_* (Begin options structure identifier)

Table 53. MQBO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQBO_STRUC_ID	X	X	(1)	X	X	X			BObb
Note:									
1. Supported on AIX, HP-UX, and Sun Solaris only									

MQBO_* (Begin options version)

Table 54. MQBO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQBO_VERSION_1	X	X	(1)	X	X	X			1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQCA_*

MQCA_* (Character attribute selector)

Table 55. MQCA_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCA_FIRST									2001	000007D1
MQCA_APPL_ID									2001	000007D1
MQCA_BASE_Q_NAME									2002	000007D2
MQCA_COMMAND_INPUT_Q_NAME									2003	000007D3
MQCA_CREATION_DATE									2004	000007D4
MQCA_CREATION_TIME									2005	000007D5
MQCA_DEAD_LETTER_Q_NAME							X		2006	000007D6
MQCA_ENV_DATA									2007	000007D7
MQCA_INITIATION_Q_NAME									2008	000007D8
MQCA_NAMELIST_DESC		X	X	X	X	X	X	X	2009	000007D9
MQCA_NAMELIST_NAME		X	X	X	X	X	X	X	2010	000007DA
MQCA_PROCESS_DESC									2011	000007DB
MQCA_PROCESS_NAME									2012	000007DC
MQCA_Q_DESC									2013	000007DD
MQCA_Q_MGR_DESC									2014	000007DE
MQCA_Q_MGR_NAME									2015	000007DF
MQCA_Q_NAME									2016	000007E0
MQCA_REMOTE_Q_MGR_NAME									2017	000007E1
MQCA_REMOTE_Q_NAME									2018	000007E2
MQCA_BACKOUT_REQ_Q_NAME									2019	000007E3
MQCA_NAMES		X	X	X	X	X	X	X	2020	000007E4
MQCA_USER_DATA									2021	000007E5
MQCA_STORAGE_CLASS		X	X	X	X	X	X	X	2022	000007E6
MQCA_TRIGGER_DATA							X		2023	000007E7
MQCA_XMIT_Q_NAME									2024	000007E8
MQCA_DEF_XMIT_Q_NAME									2025	000007E9
MQCA_CHANNEL_AUTO_DEF_EXIT	X			(1)	X	X	X		2026	000007EA
MQCA_LAST_USED									environment specific	
MQCA_LAST									4000	00000FA0
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQCC_* (Completion code)

Table 56. MQCC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCC_UNKNOWN							X		-1	FFFFFFF
MQCC_OK									0	0000000
MQCC_WARNING									1	0000001
MQCC_FAILED									2	0000002

MQCCSI_* (Coded character set identifier)

Table 57. MQCCSI_* constants

Constant	Decimal	Hex.
MQCCSI_EMBEDDED	-1	FFFFFFF
MQCCSI_DEFAULT	0	0000000
MQCCSI_Q_MGR	0	0000000

MQCFUNC_* (CICS header function name)

Table 58. MQCFUNC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQCFUNC_MQCONN		X	X	X	X	X	X	X	CONN
MQCFUNC_MQGET		X	X	X	X	X	X	X	GETb
MQCFUNC_MQINQ		X	X	X	X	X	X	X	INQb
MQCFUNC_MQOPEN		X	X	X	X	X	X	X	OPEN
MQCFUNC_MQPUT		X	X	X	X	X	X	X	PUTb
MQCFUNC_MQPUT1		X	X	X	X	X	X	X	PUT1
MQCFUNC_NONE		X	X	X	X	X	X	X	bbbb

MQCGWI_* • MQCIH_*

MQCGWI_* (CICS header get-wait interval)

Table 59. MQCGWI_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCGWI_DEFAULT	X	X	X	X	X	X	X	X	-2	FFFFFFFE

MQCI_* (Correlation identifier)

Table 60. MQCI_* constants

Constant	Value
MQCI_NONE	24 nulls
MQCI_NEW_SESSION	414D51214E45575F534553...

MQCIH_* (CICS header flags)

Table 61. MQCIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCIH_NONE	X	X	X	X	X	X	X	X	0	00000000

MQCIH_* (CICS header length)

Table 62. MQCIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCIH_LENGTH_1	X	X	X	X	X	X	X	X	164	000000A4

MQCIH_* (CICS header structure identifier)

Table 63. MQCIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQCIH_STRUC_ID	X	X	X	X	X	X	X	X	CIHb

MQCIH_* (CICS header version)

Table 64. MQCIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCIH_VERSION_1	X	X	X	X	X	X	X	X	1	00000001

MQCLT_* (CICS header link type)

Table 65. MQCLT_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCLT_PROGRAM	X	X	X	X	X	X	X	X	1	00000001

MQCMDL_* • MQCNO_*

MQCMDL_* (Command level)

Table 66. MQCMDL_* constants

Constant	Decimal	Hex.
MQCMDL_LEVEL_1	100	00000064
MQCMDL_LEVEL_101	101	00000065
MQCMDL_LEVEL_110	110	0000006E
MQCMDL_LEVEL_114	114	00000072
MQCMDL_LEVEL_120	120	00000078
MQCMDL_LEVEL_200	200	000000C8
MQCMDL_LEVEL_201	201	000000C9
MQCMDL_LEVEL_220	220	000000DC
MQCMDL_LEVEL_221	221	000000DD
MQCMDL_LEVEL_320	320	00000140
MQCMDL_LEVEL_420	420	000001A4
MQCMDL_LEVEL_500	500	000001F4

MQCNO_* (Connect options)

Table 67. MQCNO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCNO_NONE	X		X	(1)	X	X	X		0	00000000
MQCNO_STANDARD_BINDING	X			(1)	X	X	X		0	00000000
MQCNO_FASTPATH_BINDING	X		X	(1)	X	X	X		1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQCNO_* (Connect options structure identifier)

Table 68. MQCNO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQCNO_STRUC_ID	X	X	(1)	X	X	X			CNOb
Note:									
1. Supported on AIX, HP-UX, and Sun Solaris only									

MQCNO_* (Connect options version)

Table 69. MQCNO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCNO_VERSION_1	X	X	(1)	X	X	X			1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQCO_* (Close options)

Table 70. MQCO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCO_NONE									0	00000000
MQCO_DELETE							X		1	00000001
MQCO_DELETE_PURGE							X		2	00000002

MQCODL_* • MQCRC_*

MQCODL_* (CICS header output data length)

Table 71. MQCODL_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCODL_AS_INPUT		X	X	X	X	X	X	X	-1	FFFFFFF

MQCRC_* (CICS header return code)

Table 72. MQCRC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCRC_OK		X	X	X	X	X	X	X	0	0000000
MQCRC_CICS_EXEC_ERROR		X	X	X	X	X	X	X	1	0000001
MQCRC_MQ_API_ERROR		X	X	X	X	X	X	X	2	0000002
MQCRC_BRIDGE_ERROR		X	X	X	X	X	X	X	3	0000003
MQCRC_BRIDGE_ABEND		X	X	X	X	X	X	X	4	0000004
MQCRC_APPLICATION_ABEND		X	X	X	X	X	X	X	5	0000005
MQCRC_SECURITY_ERROR		X	X	X	X	X	X	X	6	0000006
MQCRC_PROGRAM_NOT_AVAILABLE		X	X	X	X	X	X	X	7	0000007
MQCRC_BRIDGE_TIMEOUT		X	X	X	X	X	X	X	8	0000008
MQCRC_TRANSID_NOT_AVAILABLE		X	X	X	X	X	X	X	9	0000009

MQCUOWC_* • MQDCC_*

MQCUOWC_* (CICS header unit-of-work control)

Table 73. MQCUOWC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQCUOWC_MIDDLE		X	X	X	X	X	X	X	16	00000016
MQCUOWC_FIRST		X	X	X	X	X	X	X	17	00000011
MQCUOWC_COMMIT		X	X	X	X	X	X	X	256	00000100
MQCUOWC_LAST		X	X	X	X	X	X	X	272	00000110
MQCUOWC_ONLY		X	X	X	X	X	X	X	273	00000111
MQCUOWC_BACKOUT		X	X	X	X	X	X	X	4352	00001100

MQDCC_* (Convert-characters masks and factors)

Table 74. MQDCC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQDCC_SOURCE_ENC_FACTOR							X		16	00000010
MQDCC_SOURCE_ENC_MASK							X		240	000000F0
MQDCC_TARGET_ENC_FACTOR							X		256	00000100
MQDCC_TARGET_ENC_MASK							X		3840	00000F00

MQDCC_* • MQDH_*

MQDCC_* (Convert-characters option)

Table 75. MQDCC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQDCC_NONE							X		0	00000000
MQDCC_SOURCE_ENC_UNDEFINED							X		0	00000000
MQDCC_TARGET_ENC_UNDEFINED							X		0	00000000
MQDCC_DEFAULT_CONVERSION							X		1	00000001
MQDCC_SOURCE_ENC_NORMAL							X		16	00000010
MQDCC_SOURCE_ENC_REVERSED							X		32	00000020
MQDCC_TARGET_ENC_NORMAL							X		256	00000100
MQDCC_TARGET_ENC_REVERSED							X		512	00000200
MQDCC_SOURCE_ENC_NATIVE							X			
MQDCC_TARGET_ENC_NATIVE							X			

MQDH_* (Distribution header structure identifier)

Table 76. MQDH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Value
MQDH_STRUC_ID	X			(1) X	X	X	X		DHbb
Note:	1. Supported on AIX, HP-UX, and Sun Solaris only								

MQDH_* (Distribution header version)

Table 77. MQDH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQDH_VERSION_1	X			(1) X	X	X	X		1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQDHF_* (Distribution header flags)

Table 78. MQDHF_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQDHF_NONE	X			(1) X	X	X	X		0	00000000
MQDHF_NEW_MSG_IDS	X			(1) X	X	X	X		1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQDL_* (Distribution list support)

Table 79. MQDL_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQDL_NOT_SUPPORTED	X			(1) X	X	X	X		0	00000000
MQDL_SUPPORTED	X			(1) X	X	X	X		1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQDLH_* • MQDXP_*

MQDLH_* (Dead-letter header structure identifier)

<i>Table 80. MQDLH_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQDLH_STRUC_ID							X			DLHb

MQDLH_* (Dead-letter header structure version)

<i>Table 81. MQDLH_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQDLH_VERSION_1							X		1	00000001

MQDXP_* (Data-conversion exit identifier)

<i>Table 82. MQDXP_* constants</i>	
Constant	Value
MQDXP_STRUC_ID	DXPb

MQDXP_* (Data-conversion exit version)

<i>Table 83. MQDXP_* constants</i>		
Constant	Decimal	Hex.
MQDXP_VERSION_1	1	00000001

MQEC_* • MQENC_*

MQEC_* (Signal event control block completion code)

<i>Table 84. MQEC_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQEC_MSG_ARRIVED		X	X	X	X	X	(1)	X	2	00000002
MQEC_WAIT_INTERVAL_EXPIRED		X	X	X	X	X	(1)	X	3	00000003
MQEC_WAIT_CANCELED		X	X	X	X	X	(1)	X	4	00000004
MQEC_Q_MGR QUIESCING		X	X	X	X	X	X	X	5	00000005
MQEC_CONNECTION QUIESCING		X	X	X	X	X	X	X	6	00000006
Note:										
1. Supported on MQSeries for Windows Version 2.1 only										

MQEI_* (Expiry interval)

<i>Table 85. MQEI_* constants</i>		
Constant	Decimal	Hex.
MQEI_UNLIMITED	-1	FFFFFFF

MQENC_* (Encoding)

<i>Table 86. MQENC_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQENC_NATIVE	X	(1)	X	X	X	X	(1)	(1)	17	00000011
	X	X	X	X	X	X	X	X	273	00000111
	X	(2)	X	X	X	X	(2)	(2)	546	00000222
	X	X	X	X	X	X	X	X	785	00000311
Note:										
1. Applies to COBOL only										
2. Applies to C programs and also to DOS and Windows clients										

MQENC_*

MQENC_* (Encoding mask)

<i>Table 87. MQENC_* constants</i>		
Constant	Decimal	Hex.
MQENC_INTEGER_MASK	15	0000000F
MQENC_DECIMAL_MASK	240	000000F0
MQENC_FLOAT_MASK	3840	00000F00
MQENC_RESERVED_MASK	-4096	FFFFFF00

MQENC_* (Encoding for packed-decimal integers)

<i>Table 88. MQENC_* constants</i>		
Constant	Decimal	Hex.
MQENC_DECIMAL_UNDEFINED	0	00000000
MQENC_DECIMAL_NORMAL	16	00000010
MQENC_DECIMAL_REVERSED	32	00000020

MQENC_* (Encoding for floating-point numbers)

<i>Table 89. MQENC_* constants</i>		
Constant	Decimal	Hex.
MQENC_FLOAT_UNDEFINED	0	00000000
MQENC_FLOAT_IEEE_NORMAL	256	00000100
MQENC_FLOAT_IEEE_REVERSED	512	00000200
MQENC_FLOAT_S390	768	00000300

MQENC_* (Encoding for binary integers)

<i>Table 90. MQENC_* constants</i>		
Constant	Decimal	Hex.
MQENC_INTEGER_UNDEFINED	0	00000000
MQENC_INTEGER_NORMAL	1	00000001
MQENC_INTEGER_REVERSED	2	00000002

MQEVR_* • MQFB_*

MQEVR_* (Event reporting)

<i>Table 91. MQEVR_* constants</i>		
Constant	Decimal	Hex.
MQEVR_DISABLED	0	00000000
MQEVR_ENABLED	1	00000001

MQFB_* (Feedback)

<i>Table 92 (Page 1 of 2). MQFB_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQFB_NONE									0	00000000
MQFB_SYSTEM_FIRST									1	00000001
MQFB_QUIT									256	00000100
MQFB_EXPIRATION									258	00000102
MQFB_COA									259	00000103
MQFB_COD									260	00000104
MQFB_CHANNEL_COMPLETED									262	00000106
MQFB_CHANNEL_FAIL_RETRY									263	00000107
MQFB_CHANNEL_FAIL									264	00000108
MQFB_APPL_CANNOT_BE_STARTED									265	00000109
MQFB_TM_ERROR							X		266	0000010A
MQFB_APPL_TYPE_ERROR									267	0000010B
MQFB_STOPPED_BY_MSG_EXIT									268	0000010C
MQFB_XMIT_Q_MSG_ERROR									271	0000010F
MQFB_PAN	X			(1) X	X	X	X		275	0000010G
MQFB_NAN	X			(1) X	X	X	X		276	0000010H
MQFB_DATA_LENGTH_ZERO		X	X	X	X	X	X	X	291	00000123
MQFB_DATA_LENGTH_NEGATIVE		X	X	X	X	X	X	X	292	00000124
MQFB_DATA_LENGTH_TOO_BIG		X	X	X	X	X	X	X	293	00000125
MQFB_BUFFER_OVERFLOW		X	X	X	X	X	X	X	294	00000126
MQFB_LENGTH_OFF_BY_ONE		X	X	X	X	X	X	X	295	00000127
MQFB_IIH_ERROR		X	X	X	X	X	X	X	296	00000128
MQFB_NOT_AUTHORIZED_FOR_IMS		X	X	X	X	X	X	X	298	0000012A
MQFB_IMS_ERROR		X	X	X	X	X	X	X	300	0000012C
MQFB_IMS_FIRST		X	X	X	X	X	X	X	301	0000012D
MQFB_IMS_LAST		X	X	X	X	X	X	X	399	0000018F

MQFMT_*

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQFB_CICS_INTERNAL_ERROR		X	X	X	X	X	X	X	401	00000191
MQFB_CICS_NOT_AUTHORIZED		X	X	X	X	X	X	X	402	00000192
MQFB_CICS_BRIDGE_FAILURE		X	X	X	X	X	X	X	403	00000193
MQFB_CICS_CORREL_ID_ERROR		X	X	X	X	X	X	X	404	00000194
MQFB_CICS_CCSID_ERROR		X	X	X	X	X	X	X	405	00000195
MQFB_CICS_ENCODING_ERROR		X	X	X	X	X	X	X	406	00000196
MQFB_CICS_CIH_ERROR		X	X	X	X	X	X	X	407	00000197
MQFB_CICS_UOW_ERROR		X	X	X	X	X	X	X	408	00000198
MQFB_CICS_COMMAREA_ERROR		X	X	X	X	X	X	X	409	00000199
MQFB_CICS_APPL_NOT_STARTED		X	X	X	X	X	X	X	410	0000019A
MQFB_CICS_APPL_ABENDED		X	X	X	X	X	X	X	411	0000019B
MQFB_CICS_DLQ_ERROR		X	X	X	X	X	X	X	412	0000019C
MQFB_CICS_UOW_BACKED_OUT		X	X	X	X	X	X	X	413	0000019D
MQFB_SYSTEM_LAST									65535	0000FFFF
MQFB_APPL_FIRST									65536	00010000
MQFB_APPL_LAST									999999999	3B9AC9FF
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQFMT_* (Format)

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQFMT_NONE									bbbbbbbb
MQFMT_ADMIN									MQADMINb
MQFMT_CHANNEL_COMPLETED									MQCHCOMb
MQFMT_CICS		X	X	X	X	X	X	X	MQCICSbb
MQFMT_COMMAND_1									MQCMD1bb
MQFMT_COMMAND_2									MQCMD2bb
MQFMT_DEAD_LETTER_HEADER							X		MQDEADbb
MQFMT_DIST_HEADER	X			(1)	X	X	X		MQDISTbb

MQGI_*

Table 93 (Page 2 of 2). MQFMT_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQFMT_EVENT									MQEVENTb
MQFMT_IMS		X	X	X	X	X	X	X	MQIMSbbb
MQFMT_IMS_VAR_STRING		X	X	X	X	X	X	X	MQIMSVSb
MQFMT_MD_EXTENSION	X			(1)	X	X	X		MQHMEbb
MQFMT_PCF									MQPCFbbb
MQFMT_REF_MSG_HEADER	X			(1)	X	X	X		MQHREFbb
MQFMT_STRING									MQSTRbbb
MQFMT_TRIGGER							X		MQTRIGbb
MQFMT_XMIT_Q_HEADER									MQXMITbb
Note:									
1. Supported on AIX, HP-UX, and Sun Solaris only									

MQGI_* (Group identifier)

Table 94. MQGI_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQGI_NONE	X			(1)	X	X	X		24 nulls
Note:									
1. Supported on AIX, HP-UX, and Sun Solaris only									

MQGMO_*

MQGMO_* (Get-message options)

Table 95. MQGMO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQGMO_NO_WAIT									0	00000000
MQGMO_NONE									0	00000000
MQGMO_WAIT									1	00000001
MQGMO_SYNCPOINT									2	00000002
MQGMO_NO_SYNCPOINT									4	00000004
MQGMO_SET_SIGNAL		X	X	X	X		(1) X		8	00000008
MQGMO_BROWSE_FIRST									16	00000010
MQGMO_BROWSE_NEXT									32	00000020
MQGMO_ACCEPT_TRUNCATED_MSG									64	00000040
MQGMO_MARK_SKIP_BACKOUT		X	X	X	X	X	X	X	128	00000080
MQGMO_MSG_UNDER_CURSOR									256	00000100
MQGMO_LOCK	X					X	X		512	00000200
MQGMO_UNLOCK	X					X	X		1024	00000400
MQGMO_BROWSE_MSG_UNDER_CURSOR	X								2048	00000800
MQGMO_SYNCPOINT_IF_PERSISTENT							X		4096	00001000
MQGMO_FAIL_IF QUIESCING									8192	00002000
MQGMO_CONVERT							X		16384	00004000
MQGMO_LOGICAL_ORDER	X			(2) X	X	X			32768	00008000
MQGMO_COMPLETE_MSG	X			(2) X	X	X			65536	00010000
MQGMO_ALL_MSGS_AVAILABLE	X			(2) X	X	X			131072	00020000
MQGMO_ALL_SEGMENTS_AVAILABLE	X			(2) X	X	X			262144	00040000
Notes:										
1. Supported on MQSeries for Windows Version 2.1 only										
2. Supported on AIX, HP-UX, and Sun Solaris only										

MQGMO_* (Get-message options structure identifier)

Table 96. MQGMO_* constants

Constant	Value
MQGMO_STRUC_ID	GMOb

MQGMO_* (Get-message options version)

Table 97. MQGMO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQGMO_VERSION_1									1	00000001
MQGMO_VERSION_2	X			(1)	X	X	X		2	00000002

Note:
1. Supported on AIX, HP-UX, and Sun Solaris only

MQGS_* (Group status)

Table 98. MQGS_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQGS_NOT_IN_GROUP	X			(1)	X	X	X		b
MQGS_MSG_IN_GROUP	X			(1)	X	X	X		G
MQGS_LAST_MSG_IN_GROUP	X			(1)	X	X	X		L

Note:
1. Supported on AIX, HP-UX, and Sun Solaris only

MQHC_* • MQIA_*

MQHC_* (Connect handle)

Table 99. MQHC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQHC_DEF_HCONN		X		X	X	X	X	X	0	00000000
MQHC_UNUSABLE_HCONN	X								-1	FFFFFFF

MQHO_* (Object handle)

Table 100. MQHO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQHO_UNUSABLE_HOBJ	X								-1	FFFFFFF

MQIA_* (Integer attribute selector)

Table 101 (Page 1 of 3). MQIA_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQIA_FIRST									1	00000001
MQIA_APPL_TYPE									1	00000001
MQIA_CODED_CHAR_SET_ID									2	00000002
MQIA_CURRENT_Q_DEPTH									3	00000003
MQIA_DEF_INPUT_OPEN_OPTION									4	00000004
MQIA_DEF_PERSISTENCE									5	00000005
MQIA_DEF_PRIORITY									6	00000006
MQIA_DEFINITION_TYPE									7	00000007
MQIA_HARDEN_GET_BACKOUT									8	00000008
MQIA_INHIBIT_GET									9	00000009
MQIA_INHIBIT_PUT									10	0000000A

MQIA_*

Table 101 (Page 2 of 3). MQIA_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital O/VMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQIA_MAX_HANDLES									11	0000000B
MQIA_USAGE									12	0000000C
MQIA_MAX_MSG_LENGTH									13	0000000D
MQIA_MAX_PRIORITY									14	0000000E
MQIA_MAX_Q_DEPTH									15	0000000F
MQIA_MSG_DELIVERY_SEQUENCE									16	00000010
MQIA_OPEN_INPUT_COUNT									17	00000011
MQIA_OPEN_OUTPUT_COUNT									18	00000012
MQIA_NAME_COUNT		X	X	X	X	X	X	X	19	00000013
MQIA_Q_TYPE									20	00000014
MQIA_RETENTION_INTERVAL									21	00000015
MQIA_BACKOUT_THRESHOLD									22	00000016
MQIA_SHAREABILITY									23	00000017
MQIA_TRIGGER_CONTROL							X		24	00000018
MQIA_TRIGGER_INTERVAL							X		25	00000019
MQIA_TRIGGER_MSG_PRIORITY							X		26	0000001A
MQIA_TRIGGER_TYPE							X		28	0000001C
MQIA_TRIGGER_DEPTH							X		29	0000001D
MQIA_SYNCPOINT									30	0000001E
MQIA_COMMAND_LEVEL									31	0000001F
MQIA_PLATFORM									32	00000020
MQIA_MAX_UNCOMMITTED_MSGS									33	00000021
MQIA_DIST_LISTS	X			(1) X	X	X			34	00000022
MQIA_TIME_SINCE_RESET	X						(2)		35	00000023
MQIA_HIGH_Q_DEPTH	X						(2)		36	00000024
MQIA_MSG_ENQ_COUNT	X						(2)		37	00000025
MQIA_MSG_DEQ_COUNT	X						(2)		38	00000026
MQIA_Q_DEPTH_HIGH_LIMIT	X						(2)		40	00000028
MQIA_Q_DEPTH_LOW_LIMIT	X						(2)		41	00000029
MQIA_Q_DEPTH_MAX_EVENT	X						(2)		42	0000002A
MQIA_Q_DEPTH_HIGH_EVENT	X						(2)		43	0000002B
MQIA_Q_DEPTH_LOW_EVENT	X						(2)		44	0000002C
MQIA_SCOPE	X	X			X	X			45	0000002D
MQIA_Q_SERVICE_INTERVAL_EVENT	X						(2)		46	0000002E
MQIA_AUTHORITY_EVENT	X						(2)		47	0000002F

MQIAUT_* • MQIAV_*

<i>Table 101 (Page 3 of 3). MQIA_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQIA_INHIBIT_EVENT	X						(2)		48	00000030
MQIA_LOCAL_EVENT	X						(2)		49	00000031
MQIA_REMOTE_EVENT	X						(2)		50	00000032
MQIA_START_STOP_EVENT	X						(2)		52	00000034
MQIA_PERFORMANCE_EVENT	X						(2)		53	00000035
MQIA_Q_SERVICE_INTERVAL	X						(2)		54	00000036
MQIA_CHANNEL_AUTO_DEF	X			(1)	X	X	X		55	00000037
MQIA_CHANNEL_AUTO_DEF_EVENT	X			(1)	X	X	X		56	00000038
MQIA_INDEX_TYPE		X	X	X	X	X	X	X	57	00000039
MQIA_LAST_USED									environment specific	
MQIA_LAST									2000	00000700
Notes:										
1. Supported on AIX, HP-UX, and Sun Solaris only										
2. Supported on Windows Version 2.1 only										

MQIAUT_* (IMS authenticator)

<i>Table 102. MQIAUT_* constants</i>									
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQIAUT_NONE		X	X	X	X	X	X	X	bbbbbbbb

MQIAV_* (Integer attribute value)

<i>Table 103. MQIAV_* constants</i>		
Constant	Decimal	Hex.
MQIAV_NOT_APPLICABLE	-1	FFFFFFF
MQIAV_UNDEFINED	-2	FFFFFFE

MQICM_* • MQIIH_*

MQICM_* (IMS commit mode)

Table 104. MQICM_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQICM_COMMIT_THEN_SEND		X	X	X	X	X	X	X	0
MQICM_SEND_THEN_COMMIT		X	X	X	X	X	X	X	1

MQIIH_* (IMS header flags)

Table 105. MQIIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQIIH_NONE		X	X	X	X	X	X	X	0	00000000

MQIIH_* (IMS header length)

Table 106. MQIIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQIIH_LENGTH_1		X	X	X	X	X	X	X	84	00000054

MQIIH_* • MQISS_*

MQIIH_* (IMS header structure identifier)

Table 107. MQIIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQIIH_STRUC_ID	X	X	X	X	X	X	X	X	IIHb

MQIIH_* (IMS header version)

Table 108. MQIIH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQIIH_VERSION_1	X	X	X	X	X	X	X	X	1	00000001

MQISS_* (IMS security scope)

Table 109. MQISS_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQISS_CHECK	X	X	X	X	X	X	X	X	C
MQISS_FULL	X	X	X	X	X	X	X	X	F

MQIT_* (Index type)

Table 110. MQIT_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQIT_NONE		X	X	X	X	X	X	X	0	00000000
MQIT_MSG_ID		X	X	X	X	X	X	X	1	00000001
MQIT_CORREL_ID		X	X	X	X	X	X	X	2	00000002

MQITII_* (IMS transaction instance identifier)

Table 111. MQITII_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQITII_NONE		X	X	X	X	X	X	X	16 nulls

MQITS_* (IMS transaction state)

Table 112. MQITS_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQITS_IN_CONVERSATION		X	X	X	X	X	X	X	C
MQITS_NOT_IN_CONVERSATION		X	X	X	X	X	X	X	b

MQMD_* (Message descriptor structure identifier)

Table 113. MQMD_* constants

Constant	Value
MQMD_STRUC_ID	MDbb

MQMD_* • MQMDE_*

MQMD_* (Message descriptor version)

Table 114. MQMD_* constants										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQMD_VERSION_1									1	00000001
MQMD_VERSION_2	X			(1)	X	X	X		2	00000002
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQMDE_* (Message descriptor extension length)

Table 115. MQMDE_* constants										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQMDE_LENGTH_2	X			(1)	X	X	X		72	00000048

MQMDE_* (Message descriptor extension structure identifier)

Table 116. MQMDE_* constants									
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQMDE_STRUC_ID	X			(1)	X	X	X		MDEb
Note:									
1. Supported on AIX, HP-UX, and Sun Solaris only									

MQMDE_* (Message descriptor extension version)

Table 117. MQMDE_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQMDE_VERSION_2	X			(1) X	X	X	X		2	00000002
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQMDEF_* (Message descriptor extension flags)

Table 118. MQMDEF_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQMDEF_NONE	X			(1) X	X	X	X		0	00000000
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQMDS_* (Message delivery sequence)

Table 119. MQMDS_* constants

Constant	Decimal	Hex.
MQMDS_PRIORITY	0	00000000
MQMDS_FIFO	1	00000001

MQMF_*

MQMF_* (Message flags)

Table 120. MQMF_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQMF_SEGMENTATION_INHIBITED	X			(1) X	X	X	X		0	00000000
MQMF_NONE	X			(1) X	X	X	X		0	00000000
MQMF_SEGMENTATION_ALLOWED	X			(1) X	X	X	X		1	00000001
MQMF_SEGMENT	X			(1) X	X	X	X		2	00000002
MQMF_LAST_SEGMENT	X			(1) X	X	X	X		4	00000004
MQMF_MSG_IN_GROUP	X			(1) X	X	X	X		8	00000008
MQMF_LAST_MSG_IN_GROUP	X			(1) X	X	X	X		16	00000010

Note:
1. Supported on AIX, HP-UX, and Sun Solaris only

MQMF_* (Message flags masks)

Table 121. MQMF_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQMF_ACCEPT_UNSUP_MASK	X			(1) X	X	X	X		-1048576	FFF00000
MQMF_ACCEPT_UNSUP_IF_XMIT_MASK	X			(1) X	X	X	X		1044480	000FF000
MQMF_REJECT_UNSUP_MASK	X			(1) X	X	X	X		4095	00000FFF

Note:
1. Supported on AIX, HP-UX, and Sun Solaris only

MQMI_* • MQMT_*

MQMI_* (Message identifier)

<i>Table 122. MQMI_* constants</i>	
Constant	Value
MQMI_NONE	24 nulls

MQMO_* (Match options)

<i>Table 123. MQMO_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQMO_NONE	X			(1)	X	X	X		0	00000000
MQMO_MATCH_MSG_ID	X			(1)	X	X	X		1	00000001
MQMO_MATCH_CORREL_ID	X			(1)	X	X	X		2	00000002
MQMO_MATCH_GROUP_ID	X			(1)	X	X	X		4	00000004
MQMO_MATCH_MSG_SEQ_NUMBER	X			(1)	X	X	X		8	00000008
MQMO_MATCH_OFFSET	X			(1)	X	X	X		16	00000010
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQMT_* (Message type)

<i>Table 124. MQMT_* constants</i>		
Constant	Decimal	Hex.
MQMT_SYSTEM_FIRST	1	00000001
MQMT_REQUEST	1	00000001
MQMT_REPLY	2	00000002
MQMT_REPORT	4	00000004
MQMT_DATAGRAM	8	00000008
MQMT_SYSTEM_LAST	65535	0000FFFF
MQMT_APPL_FIRST	65536	00010000
MQMT_APPL_LAST	99999999	3B9AC9FF

MQOD_* • MQOL_*

MQOD_* (Object descriptor length)

Table 125. MQOD_* constants		
Constant	Decimal	Hex.
MQOD_CURRENT_LENGTH		environment specific

MQOD_* (Object descriptor structure identifier)

Table 126. MQOD_* constants	
Constant	Value
MQOD_STRUC_ID	0dbb

MQOD_* (Object descriptor version)

Table 127. MQOD_* constants		
Constant	Decimal	Hex.
MQOD_VERSION_1	1	00000001
MQOD_VERSION_2	2	00000002

MQOII_* (Object instance identifier)

Table 128. MQOII_* constants									
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQOII_NONE	X	X	X	X	X	X	X	X	24 nulls

MQOL_* (Original length)

Table 129. MQOL_* constants		
Constant	Decimal	Hex.
MQOL_UNDEFINED	-1	FFFFFFF

MQOO_* •MQOT_*

MQOO_* (Open options)

Table 130. MQOO_ constants*

Constant	Decimal	Hex.
MQOO_INPUT_AS_Q_DEF	1	00000001
MQOO_INPUT_SHARED	2	00000002
MQOO_INPUT_EXCLUSIVE	4	00000004
MQOO_BROWSE	8	00000008
MQOO_OUTPUT	16	00000010
MQOO_INQUIRE	32	00000020
MQOO_SET	64	00000040
MQOO_SAVE_ALL_CONTEXT	128	00000080
MQOO_PASS_IDENTITY_CONTEXT	256	00000100
MQOO_PASS_ALL_CONTEXT	512	00000200
MQOO_SET_IDENTITY_CONTEXT	1024	00000400
MQOO_SET_ALL_CONTEXT	2048	00000800
MQOO_ALTERNATE_USER_AUTHORITY	4096	00001000
MQOO_FAIL_IF QUIESCING	8192	00002000

MQOT_* (Object type)

Table 131 (Page 1 of 2). MQOT_ constants*

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQOT_Q									1	00000001
MQOT_NAMELIST		X	X	X	X	X	X	X	2	00000002
MQOT_PROCESS									3	00000003
MQOT_Q_MGR									5	00000005
MQOT_CHANNEL									6	00000006
MQOT_RESERVED_1		X	X	X	X	X	X	X	7	00000007
MQOT_ALL									1001	000003E9
MQOT_ALIAS_Q									1002	000003EA
MQOT_MODEL_Q									1003	000003EB
MQOT_LOCAL_Q									1004	000003EC
MQOT_REMOTE_Q									1005	000003ED
MQOT_SENDER_CHANNEL									1007	000003EF
MQOT_SERVER_CHANNEL									1008	000003F0
MQOT_REQUESTER_CHANNEL									1009	000003F1

MQPER_* • MQPL_*

Table 131 (Page 2 of 2). MQOT_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital O/VMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQOT_RECEIVER_CHANNEL									1010	000003F2
MQOT_CURRENT_CHANNEL									1011	000003F3
MQOT_SAVED_CHANNEL									1012	000003F4

MQPER_* (Persistence)

Table 132. MQPER_* constants

Constant	Decimal	Hex.
MQPER_NOT_PERSISTENT	0	00000000
MQPER_PERSISTENT	1	00000001
MQPER_PERSISTENCE_AS_Q_DEF	2	00000002

MQPL_* (Platform)

Table 133. MQPL_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital O/VMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQPL_MVS		X	X	X	X	X	X	X	1	00000001
MQPL_OS2	X		X	X	X	X	X	X	2	00000002
MQPL_AIX	X	X	X		X	X	X	X	3	00000003
MQPL_UNIX	X	X	X		X	X	X	X	3	00000003
MQPL_OS400	X	X		X	X	X	X	X	4	00000004
MQPL_WINDOWS	X	X	X	X	X	X		X	5	00000005
MQPL_WINDOWS_NT	X	X	X	X	X	X	X		11	0000000B
MQPL_VMS	X	X	X	X		X	X	X	12	0000000C
MQPL_NSK	X	X	X	X	X		X	X	13	0000000D

MQPMO_* (Put-message options)

Table 134. MQPMO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQPMO_NONE									0	00000000
MQPMO_SYNCPOINT									2	00000002
MQPMO_NO_SYNCPOINT									4	00000004
MQPMO_DEFAULT_CONTEXT									32	00000020
MQPMO_NEW_MSG_ID	X			(1) X	X	X	X		64	00000040
MQPMO_NEW_CORREL_ID	X			(1) X	X	X	X		128	00000080
MQPMO_PASS_IDENTITY_CONTEXT									256	00000100
MQPMO_PASS_ALL_CONTEXT							X		512	00000200
MQPMO_SET_IDENTITY_CONTEXT									1024	00000400
MQPMO_SET_ALL_CONTEXT									2048	00000800
MQPMO_ALTERNATE_USER_AUTHORITY									4096	00001000
MQPMO_FAIL_IF QUIESCING									8192	00002000
MQPMO_NO_CONTEXT									16384	00004000
MQPMO_LOGICAL_ORDER	X			(1) X	X	X	X		32768	00008000
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQPMO_* (Put-message options structure length)

Table 135. MQPMO_* constants

Constant	Decimal	Hex.
MQPMO_CURRENT_LENGTH	environment specific	

MQPMO_* (Put-message options structure identifier)

Table 136. MQPMO_* constants

Constant	Value
MQPMO_STRUC_ID	PMOb

MQPMO_* • MQPRI_*

MQPMO_* (Put-message options structure version)

Table 137. MQPMO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQPMO_VERSION_1									1	00000001
MQPMO_VERSION_2	X			(1) X	X	X	X		2	00000002
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQPMRF_* (Put-message record field flags)

Table 138. MQPMRF_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQPMRF_NONE	X			(1) X	X	X	X		0	00000000
MQPMRF_MSG_ID	X			(1) X	X	X	X		1	00000001
MQPMRF_CORREL_ID	X			(1) X	X	X	X		2	00000002
MQPMRF_GROUP_ID	X			(1) X	X	X	X		4	00000004
MQPMRF_FEEDBACK	X			(1) X	X	X	X		8	00000008
MQPMRF_ACCOUNTING_TOKEN	X			(1) X	X	X	X		16	00000010
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQPRI_* (Priority)

Table 139. MQPRI_* constants

Constant	Decimal	Hex.
MQPRI_PRIORITY_AS_Q_DEF	-1	FFFFFFF

MQQA_* •MQQDT_*

MQQA_* (Inhibit get)

<i>Table 140. MQQA_* constants</i>		
Constant	Decimal	Hex.
MQQA_GET_ALLOWED	0	00000000
MQQA_GET_INHIBITED	1	00000001

MQQA_* (Inhibit put)

<i>Table 141. MQQA_* constants</i>		
Constant	Decimal	Hex.
MQQA_PUT_ALLOWED	0	00000000
MQQA_PUT_INHIBITED	1	00000001

MQQA_* (Backout hardening)

<i>Table 142. MQQA_* constants</i>		
Constant	Decimal	Hex.
MQQA_BACKOUT_NOT_HARDENED	0	00000000
MQQA_BACKOUT_HARDENED	1	00000001

MQQA_* (Queue shareability)

<i>Table 143. MQQA_* constants</i>		
Constant	Decimal	Hex.
MQQA_NOT_SHAREABLE	0	00000000
MQQA_SHAREABLE	1	00000001

MQQDT_* (Queue definition type)

<i>Table 144. MQQDT_* constants</i>		
Constant	Decimal	Hex.
MQQDT_PREDEFINED	1	00000001
MQQDT_PERMANENT_DYNAMIC	2	00000002
MQQDT_TEMPORARY_DYNAMIC	3	00000003

MQQSIE_* •MQQT_*

MQQSIE_* (Service interval events)

<i>Table 145. MQQSIE_* constants</i>		
Constant	Decimal	Hex.
MQQSIE_NONE	0	00000000
MQQSIE_HIGH	1	00000001
MQQSIE_OK	2	00000002

MQQT_* (Queue type)

<i>Table 146. MQQT_* constants</i>										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital O/VMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQQT_LOCAL									1	00000001
MQQT_MODEL									2	00000002
MQQT_ALIAS									3	00000003
MQQT_REMOTE									6	00000006
MQQT_ALL				X	X	(1)			1001	000003E9
Note:										
1. Supported on Windows 2.1 only										

MQRC_* (Reason code)

Table 147 (Page 1 of 7). MQRC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRC_NONE									0	00000000
MQRC_ALIAS_BASE_Q_TYPE_ERROR									2001	000007D1
MQRC_ALREADY_CONNECTED									2002	000007D2
MQRC_BACKED_OUT			X						2003	000007D3
MQRC_BUFFER_ERROR									2004	000007D4
MQRC_BUFFER_LENGTH_ERROR									2005	000007D5
MQRC_CHAR_ATTR_LENGTH_ERROR									2006	000007D6
MQRC_CHAR_ATTRS_ERROR									2007	000007D7
MQRC_CHAR_ATTRS_TOO_SHORT									2008	000007D8
MQRC_CONNECTION_BROKEN									2009	000007D9
MQRC_DATA_LENGTH_ERROR									2010	000007DA
MQRC_DYNAMIC_Q_NAME_ERROR									2011	000007DB
MQRC_ENVIRONMENT_ERROR									2012	000007DC
MQRC_EXPIRY_ERROR									2013	000007DD
MQRC_FEEDBACK_ERROR									2014	000007DE
MQRC_GET_INHIBITED									2016	000007E0
MQRC_HANDLE_NOT_AVAILABLE									2017	000007E1
MQRC_HCONN_ERROR									2018	000007E2
MQRC_HOBJ_ERROR									2019	000007E3
MQRC_INHIBIT_VALUE_ERROR									2020	000007E4
MQRC_INT_ATTR_COUNT_ERROR									2021	000007E5
MQRC_INT_ATTR_COUNT_TOO_SMALL									2022	000007E6
MQRC_INT_ATTRS_ARRAY_ERROR									2023	000007E7
MQRC_SYNCPOINT_LIMIT_REACHED									2024	000007E8
MQRC_MAX_CONNS_LIMIT_REACHED									2025	000007E9
MQRC_MD_ERROR									2026	000007EA
MQRC_MISSING_REPLY_TO_Q									2027	000007EB
MQRC_MSG_TYPE_ERROR									2029	000007ED
MQRC_MSG_TOO_BIG_FOR_Q									2030	000007EE
MQRC_MSG_TOO_BIG_FOR_Q_MGR									2031	000007EF
MQRC_NO_MSG_AVAILABLE									2033	000007F1
MQRC_NO_MSG_UNDER_CURSOR									2034	000007F2
MQRC_NOT_AUTHORIZED									2035	000007F3

MQRC_*

Table 147 (Page 2 of 7). MQRC_* constants										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRC_NOT_OPEN_FOR_BROWSE									2036	000007F4
MQRC_NOT_OPEN_FOR_INPUT									2037	000007F5
MQRC_NOT_OPEN_FOR_INQUIRE									2038	000007F6
MQRC_NOT_OPEN_FOR_OUTPUT									2039	000007F7
MQRC_NOT_OPEN_FOR_SET									2040	000007F8
MQRC_OBJECT_CHANGED									2041	000007F9
MQRC_OBJECT_IN_USE									2042	000007FA
MQRC_OBJECT_TYPE_ERROR									2043	000007FB
MQRC_OD_ERROR									2044	000007FC
MQRC_OPTION_NOT_VALID_FOR_TYPE									2045	000007FD
MQRC_OPTIONS_ERROR									2046	000007FE
MQRC_PERSISTENCE_ERROR									2047	000007FF
MQRC_PERSISTENT_NOT_ALLOWED									2048	00000800
MQRC_PRIORITY_EXCEEDS_MAXIMUM	X								2049	00000801
MQRC_PRIORITY_ERROR									2050	00000802
MQRC_PUT_INHIBITED									2051	00000803
MQRC_Q_DELETED									2052	00000804
MQRC_Q_FULL									2053	00000805
MQRC_Q_NOT_EMPTY									2055	00000807
MQRC_Q_SPACE_NOT_AVAILABLE	X								2056	00000808
MQRC_Q_TYPE_ERROR									2057	00000809
MQRC_Q_MGR_NAME_ERROR									2058	0000080A
MQRC_Q_MGR_NOT_AVAILABLE									2059	0000080B
MQRC_REPORT_OPTIONS_ERROR									2061	0000080D
MQRC_SECOND_MARK_NOT_ALLOWED		X	X	X	X	X	X	X	2062	0000080E
MQRC_SECURITY_ERROR									2063	0000080F
MQRC_SELECTOR_COUNT_ERROR									2065	00000811
MQRC_SELECTOR_LIMIT_EXCEEDED									2066	00000812
MQRC_SELECTOR_ERROR									2067	00000813
MQRC_SELECTOR_NOT_FOR_TYPE									2068	00000814
MQRC_SIGNAL_OUTSTANDING		X	X	X	X	X	(2)	X	2069	00000815
MQRC_SIGNAL_REQUEST_ACCEPTED		X	X	X	X	X	(2)	X	2070	00000816
MQRC_STORAGE_NOT_AVAILABLE									2071	00000817
MQRC_SYNCPOINT_NOT_AVAILABLE	X								2072	00000818
MQRC_TRIGGER_CONTROL_ERROR							X		2075	0000081B

MQRC_*

Table 147 (Page 3 of 7). MQRC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital O/VMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRC_TRIGGER_DEPTH_ERROR							X		2076	0000081C
MQRC_TRIGGER_MSG_PRIORITY_ERR							X		2077	0000081D
MQRC_TRIGGER_TYPE_ERROR							X		2078	0000081E
MQRC_TRUNCATED_MSG_ACCEPTED									2079	0000081F
MQRC_TRUNCATED_MSG_FAILED									2080	00000820
MQRC_UNKNOWN_ALIAS_BASE_Q									2082	00000822
MQRC_UNKNOWN_OBJECT_NAME									2085	00000825
MQRC_UNKNOWN_OBJECT_Q_MGR									2086	00000826
MQRC_UNKNOWN_REMOTE_Q_MGR									2087	00000827
MQRC_WAIT_INTERVAL_ERROR									2090	0000082A
MQRC_XMIT_Q_TYPE_ERROR									2091	0000082B
MQRC_XMIT_Q_USAGE_ERROR									2092	0000082C
MQRC_NOT_OPEN_FOR_PASS_ALL									2093	0000082D
MQRC_NOT_OPEN_FOR_PASS_IDENT									2094	0000082E
MQRC_NOT_OPEN_FOR_SET_ALL									2095	0000082F
MQRC_NOT_OPEN_FOR_SET_IDENT									2096	00000830
MQRC_CONTEXT_HANDLE_ERROR									2097	00000831
MQRC_CONTEXT_NOT_AVAILABLE									2098	00000832
MQRC_SIGNAL1_ERROR		X	X	X	X	X	(2)	X	2099	00000833
MQRC_OBJECT_ALREADY_EXISTS									2100	00000834
MQRC_OBJECT_DAMAGED	X								2101	00000835
MQRC_RESOURCE_PROBLEM	X								2102	00000836
MQRC_ANOTHER_Q_MGR_CONNECTED	X		X						2103	00000837
MQRC_UNKNOWN_REPORT_OPTION									2104	00000838
MQRC_STORAGE_CLASS_ERROR		X	X	X	X	X	X	X	2105	00000839
MQRC_COD_NOT_VALID_FOR_XCF_Q		X	X	X	X	X	X	X	2106	0000083A
MQRC_XWAIT_CANCELED		X	X	X	X	X	X	X	2107	0000083B
MQRC_XWAIT_ERROR		X	X	X	X	X	X	X	2108	0000083C
MQRC_SUPPRESSED_BY_EXIT		X	X	X	X	X	X	X	2109	0000083D
MQRC_FORMAT_ERROR									2110	0000083E
MQRC_SOURCE_CCSID_ERROR									2111	0000083F
MQRC_SOURCE_INTEGER_ENC_ERROR									2112	00000840
MQRC_SOURCE_DECIMAL_ENC_ERROR									2113	00000841
MQRC_SOURCE_FLOAT_ENC_ERROR									2114	00000842
MQRC_TARGET_CCSID_ERROR									2115	00000843

MQRC_*

Table 147 (Page 4 of 7). MQRC_* constants										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRC_TARGET_INTEGER_ENC_ERROR									2116	00000844
MQRC_TARGET_DECIMAL_ENC_ERROR									2117	00000845
MQRC_TARGET_FLOAT_ENC_ERROR									2118	00000846
MQRC_NOT_CONVERTED									2119	00000847
MQRC_CONVERTED_MSG_TOO_BIG									2120	00000848
MQRC_NO_EXTERNAL_PARTICIPANTS	X		X (1)	X	X	X			2121	00000849
MQRC_PARTICIPANT_NOT_AVAILABLE	X		X (1)	X	X	X			2122	0000084A
MQRC_OUTCOME_MIXED	X		X (1)	X	X	X			2123	0000084B
MQRC_OUTCOME_PENDING	X		X (1)	X	X	X			2124	0000084C
MQRC_BRIDGE_STARTED		X	X	X	X	X	X	X	2125	0000084D
MQRC_BRIDGE_STOPPED		X	X	X	X	X	X	X	2126	0000084E
MQRC_ADAPTER_STORAGE_SHORTAGE		X	X	X	X	X	X	X	2127	0000084F
MQRC_UOW_IN_PROGRESS	X		X (1)	X	X	X			2128	00000850
MQRC_ADAPTER_CONN_LOAD_ERROR		X	X	X	X	X	X	X	2129	00000851
MQRC_ADAPTER_SERV_LOAD_ERROR		X	X	X	X	X	X	X	2130	00000852
MQRC_ADAPTER_DEFS_ERROR		X	X	X	X	X	X	X	2131	00000853
MQRC_ADAPTER_DEFS_LOAD_ERROR		X	X	X	X	X	X	X	2132	00000854
MQRC_ADAPTER_CONV_LOAD_ERROR		X	X	X	X	X	X	X	2133	00000855
MQRC_BO_ERROR	X		X (1)	X	X	X			2134	00000856
MQRC_DH_ERROR	X		(1)	X	X	X			2135	00000857
MQRC_MULTIPLE_REASONS	X		(1)	X	X	X			2136	00000858
MQRC_OPEN_FAILED	X		(1)	X	X	X			2137	00000859
MQRC_ADAPTER_DISC_LOAD_ERROR		X	X	X	X	X	X	X	2138	0000085A
MQRC_CNO_ERROR	X		X (1)	X	X	X			2139	0000085B
MQRC_CICS_WAIT_FAILED		X	X	X	X	X	X	X	2140	0000085C
MQRC_DLH_ERROR	X		(1)	X	X	X			2141	0000085D
MQRC_HEADER_ERROR	X		(1)	X	X	X			2142	0000085E
MQRC_SOURCE_LENGTH_ERROR									2143	0000085F
MQRC_TARGET_LENGTH_ERROR									2144	00000860
MQRC_SOURCE_BUFFER_ERROR									2145	00000861
MQRC_TARGET_BUFFER_ERROR									2146	00000862
MQRC_IIH_ERROR	X			X	X	X			2148	00000864
MQRC_PCF_ERROR	X			X	X				2149	00000865
MQRC_DBCS_ERROR									2150	00000866
MQRC_OBJECT_NAME_ERROR	X		(1)	X	X	X			2152	00000868

MQRC_*

Table 147 (Page 5 of 7). MQRC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRC_OBJECT_Q_MGR_NAME_ERROR	X			(1)	X	X	X		2153	00000869
MQRC_RECS_PRESENT_ERROR	X			(1)	X	X	X		2154	0000086A
MQRC_OBJECT_RECORDS_ERROR	X			(1)	X	X	X		2155	0000086B
MQRC_RESPONSE_RECORDS_ERROR	X			(1)	X	X	X		2156	0000086C
MQRC_ASID_MISMATCH		X	X	X	X	X	X	X	2157	0000086D
MQRC_PMO_RECORD_FLAGS_ERROR	X			(1)	X	X	X		2158	0000086E
MQRC_PUT_MSG_RECORDS_ERROR	X			(1)	X	X	X		2159	0000086F
MQRC_CONN_ID_IN_USE		X	X	X	X	X	X	X	2160	00000870
MQRC_Q_MGR QUIESCING									2161	00000871
MQRC_Q_MGR STOPPING									2162	00000872
MQRC_DUPLICATE_RECOV_COORD		X	X	X	X	X	X	X	2163	00000873
MQRC_PMO_ERROR									2173	0000087D
MQRC_API_EXIT_LOAD_ERROR		X	X	X	X	X	X	X	2183	00000887
MQRC_REMOTE_Q_NAME_ERROR									2184	00000888
MQRC_INCONSISTENT_PERSISTENCE	X				X	X			2185	00000889
MQRC_GMO_ERROR									2186	0000088A
MQRC_CICS_BRIDGE_RESTRICTION		X	X	X	X	X	X	X	2187	0000088B
MQRC_TMC_ERROR	X				X	X	X		2191	0000088F
MQRC_PAGESET_FULL		X	X	X	X	X	X	X	2192	00000890
MQRC_PAGESET_ERROR		X	X	X	X	X	X	X	2193	00000891
MQRC_NAME_NOT_VALID_FOR_TYPE									2194	00000892
MQRC_UNEXPECTED_ERROR									2195	00000893
MQRC_UNKNOWN_XMIT_Q									2196	00000894
MQRC_UNKNOWN_DEF_XMIT_Q									2197	00000895
MQRC_DEF_XMIT_Q_TYPE_ERROR									2198	00000896
MQRC_DEF_XMIT_Q_USAGE_ERROR									2199	00000897
MQRC_NAME_IN_USE		X	X	X	X	X	X	X	2201	00000899
MQRC_CONNECTION QUIESCING		X	X	X	X	X	X	X	2202	0000089A
MQRC_CONNECTION STOPPING		X	X	X	X	X	X	X	2203	0000089B
MQRC_ADAPTER_NOT_AVAILABLE		X	X	X	X	X	X	X	2204	0000089C
MQRC_NO_MSG_LOCKED	X								2209	000008A1
MQRC_CONNECTION_NOT_AUTHORIZED		X	X	X	X	X	X	X	2217	000008A9
MQRC_MSG_TOO_BIG_FOR_CHANNEL									2218	000008AA
MQRC_CALL_IN_PROGRESS									2219	000008AB
MQRC_RMH_ERROR	X			(1)	X	X	X		2220	000008AC

MQRC_*

Table 147 (Page 6 of 7). MQRC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRC_Q_MGR_ACTIVE									2222	000008AE
MQRC_Q_MGR_NOT_ACTIVE									2223	000008AF
MQRC_Q_DEPTH_HIGH									2224	000008B0
MQRC_Q_DEPTH_LOW									2225	000008B1
MQRC_Q_SERVICE_INTERVAL_HIGH									2226	000008B2
MQRC_Q_SERVICE_INTERVAL_OK									2227	000008B3
MQRC_UNIT_OF_WORK_NOT_STARTED	X	X	X	X	X		X	X	2232	000008B8
MQRC_CHANNEL_AUTO_DEF_OK	X				X	X	X		2233	000008B9
MQRC_CHANNEL_AUTO_DEF_ERROR	X				X	X	X		2234	000008BA
MQRC_CFH_ERROR	X				X	X			2235	000008BB
MQRC_CFIL_ERROR	X				X	X			2236	000008BC
MQRC_CFIN_ERROR	X				X	X			2237	000008BD
MQRC_CFSL_ERROR	X				X	X			2238	000008BE
MQRC_CFST_ERROR	X				X	X			2239	000008BF
MQRC_INCOMPLETE_GROUP	X			(1)	X	X	X		2241	000008C1
MQRC_INCOMPLETE_MSG	X			(1)	X	X	X		2242	000008C2
MQRC_INCONSISTENT_CCSIDS	X			(1)	X	X	X		2243	000008C3
MQRC_INCONSISTENT_ENCODINGS	X			(1)	X	X	X		2244	000008C4
MQRC_INCONSISTENT_UOW	X			(1)	X	X	X		2245	000008C5
MQRC_INVALID_MSG_UNDER_CURSOR	X			(1)	X	X	X		2246	000008C6
MQRC_MATCH_OPTIONS_ERROR	X			(1)	X	X	X		2247	000008C7
MQRC_MDE_ERROR	X			(1)	X	X	X		2248	000008C8
MQRC_MSG_FLAGS_ERROR	X			(1)	X	X	X		2249	000008C9
MQRC_MSG_SEQ_NUMBER_ERROR	X			(1)	X	X	X		2250	000008CA
MQRC_OFFSET_ERROR	X			(1)	X	X	X		2251	000008CB
MQRC_ORIGINAL_LENGTH_ERROR	X			(1)	X	X	X		2252	000008CC
MQRC_SEGMENT_LENGTH_ZERO	X			(1)	X	X	X		2253	000008CD
MQRC_UOW_NOT_AVAILABLE	X			(1)	X	X	X		2255	000008CF
MQRC_WRONG_GMO_VERSION	X			(1)	X	X	X		2256	000008D0
MQRC_WRONG_MD_VERSION	X			(1)	X	X	X		2257	000008D1
MQRC_GROUP_ID_ERROR	X			(1)	X	X	X		2258	000008D2
MQRC_INCONSISTENT_BROWSE	X			(1)	X	X	X		2259	000008D3
MQRC_XQH_ERROR	X				X	X			2260	000008D4
MQRC_SRC_ENV_ERROR	X			(1)	X	X	X		2261	000008D5
MQRC_SRC_NAME_ERROR	X			(1)	X	X	X		2262	000008D6

MQRC_*

Table 147 (Page 7 of 7). MQRC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRC_DEST_ENV_ERROR	X			(1)	X	X	X		2263	000008D7
MQRC_DEST_NAME_ERROR	X			(1)	X	X	X		2264	000008D8
MQRC_TM_ERROR	X				X	X	X		2265	000008D9
MQRC_HCONFIG_ERROR	X	X					X		2280	000008E8
MQRC_FUNCTION_ERROR	X	X					X		2281	000008E9
MQRC_CHANNEL_STARTED									2282	000008EA
MQRC_CHANNEL_STOPPED									2283	000008EB
MQRC_CHANNEL_CONV_ERROR									2284	000008EC
MQRC_SERVICE_NOT_AVAILABLE	X	X					X		2285	000008ED
MQRC_INITIALIZATION_FAILED	X	X					X		2286	000008EE
MQRC_TERMINATION_FAILED	X	X					X		2287	000008EF
MQRC_UNKNOWN_Q_NAME	X	X					X		2288	000008F0
MQRC_SERVICE_ERROR	X	X					X		2289	000008F1
MQRC_Q_ALREADY_EXISTS	X	X					X		2290	000008F2
MQRC_USER_ID_NOT_AVAILABLE	X	X					X		2291	000008F3
MQRC_UNKNOWN_ENTITY	X	X					X		2292	000008F4
MQRC_UNKNOWN_AUTH_ENTITY	X	X					X		2293	000008F5
MQRC_UNKNOWN_REF_OBJECT	X	X					X		2294	000008F6
MQRC_CHANNEL_ACTIVATED									2295	000008F7
MQRC_CHANNEL_NOT_ACTIVATED									2296	000008F8
MQRC_UOW_CANCELED	X	X	X	X	X		X	X	2297	000008F9
Notes:										
1. Supported on AIX, HP-UX, and Sun Solaris only										
2. Supported on MQSeries for Windows Version 2.1 only										

MQRMH_* • MQRMHF_*

MQRMH_* (Reference message header structure identifier)

Table 148. MQRMH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQRMH_STRUC_ID	X			(1) X	X	X	X		RMHb
Note:									
1. Supported on AIX, HP-UX, and Sun Solaris only									

MQRMH_* (Reference message header version)

Table 149. MQRMH_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRMH_VERSION_1	X			(1) X	X	X	X		1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQRMHF_* (Reference message header flags)

Table 150. MQRMHF_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRMHF_NOT_LAST	X			(1) X	X	X	X		0	00000000
MQRMHF_LAST	X			(1) X	X	X	X		1	00000001
Note:										
1. Supported on AIX, HP-UX, and Sun Solaris only										

MQRO_* (Report options)

Table 151. MQRO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMs	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQRO_NONE									0	00000000
MQRO_COPY_MSG_ID_TO_CORREL_ID									0	00000000
MQRO_NEW_MSG_ID									0	00000000
MQRO_DEAD_LETTER_Q	X								0	00000000
MQRO_PAN					X	X	X		1	00000001
MQRO_NAN					X	X	X		2	00000002
MQRO_PASS_CORREL_ID									64	00000040
MQRO_PASS_MSG_ID									128	00000080
MQRO_COA									256	00000100
MQRO_COA_WITH_DATA									768	00000300
MQRO_COA_WITH_FULL_DATA	X								1792	00000700
MQRO_COD									2048	00000800
MQRO_COD_WITH_DATA									6144	00001800
MQRO_COD_WITH_FULL_DATA	X								14336	00003800
MQRO_EXPIRATION									2097152	00200000
MQRO_EXPIRATION_WITH_DATA									6291456	00600000
MQRO_EXPIRATION_WITH_FULL_DATA	X								14680064	00E00000
MQRO_EXCEPTION									16777216	01000000
MQRO_EXCEPTION_WITH_DATA									50331648	03000000
MQRO_EXCEPTION_WITH_FULL_DATA	X								117440512	07000000
MQRO_DISCARD_MSG	X								134217728	08000000

MQRO_* (Report-options mask)

Table 152. MQRO_* constants

Constant	Decimal	Hex.
MQRO_REJECT_UNSUP_MASK	270270464	101C0000
MQRO_ACCEPT_UNSUP_MASK	-270532353	EFE000FF
MQRO_ACCEPT_UNSUP_IF_XMIT_MASK	261888	0003FF00

MQSCO_* • MQSP_*

MQSCO_* (Queue scope)

Table 153. MQSCO_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQSCO_Q_MGR	X	X			X	X			1	00000001
MQSCO_CELL	X	X			X	X			2	00000002

MQSEG_* (Segmentation)

Table 154. MQSEG_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQSEG_INHIBITED	X			(1)	X	X	X		b
MQSEG_ALLOWED	X			(1)	X	X	X		A
Note:									
1. Supported on AIX, HP-UX, and Sun Solaris only									

MQSP_* (Syncpoint)

Table 155. MQSP_* constants

Constant	Decimal	Hex.
MQSP_NOT_AVAILABLE	0	00000000
MQSP_AVAILABLE	1	00000001

MQSS_* (Segment status)

Table 156. MQSS_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQSS_NOT_A_SEGMENT	X			(1) X	X	X	X		b
MQSS_LAST_SEGMENT	X			(1) X	X	X	X		L
MQSS_SEGMENT	X			(1) X	X	X	X		S

Note:
1. Supported on AIX, HP-UX, and Sun Solaris only

MQTC_* (Trigger control)

Table 157. MQTC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQTC_OFF							X		0	00000000
MQTC_ON							X		1	00000001

MQTM_* (Trigger message structure identifier)

Table 158. MQTM_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQTM_STRUC_ID							X		TMbb

MQTM_* •MQTMC_*

MQTM_* (Trigger message structure version)

Table 159. MQTM_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQTM_VERSION_1							X		1	00000001

MQTMC_* (Trigger message character format structure)

Table 160. MQTMC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQTMC_STRUC_ID							X		TMCb

MQTMC_* (Trigger message character format version)

Table 161. MQTMC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQTMC_VERSION_1	X	X		X	X	X	X	X	bbb1
MQTMC_VERSION_2							X		bbb2

MQTT_* (Trigger type)

Table 162. MQTT_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQTT_NONE							X		0	00000000
MQTT_FIRST							X		1	00000001
MQTT_EVERY							X		2	00000002
MQTT_DEPTH							X		3	00000003

MQUS_* (Usage)

Table 163. MQUS_* constants

Constant	Decimal	Hex.
MQUS_NORMAL	0	00000000
MQUS_TRANSMISSION	1	00000001

MQWI_* (Wait interval)

Table 164. MQWI_* constants

Constant	Decimal	Hex.
MQWI_UNLIMITED	-1	FFFFFFF

MQXC_* (Exit command identifier)

Table 165 (Page 1 of 2). MQXC_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQXC_MQOPEN		X	X	X	X	X	X	X	1	00000001
MQXC_MQCLOSE		X	X	X	X	X	X	X	2	00000002
MQXC_MQGET		X	X	X	X	X	X	X	3	00000003
MQXC_MQPUT		X	X	X	X	X	X	X	4	00000004
MQXC_MQPUT1		X	X	X	X	X	X	X	5	00000005

MQXCC_* • MQXDR_*

Table 165 (Page 2 of 2). MQXC_* constants										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQXC_MQINQ	X	X	X	X	X	X	X	X	6	00000006
MQXC_MQSET	X	X	X	X	X	X	X	X	8	00000008
MQXC_MQBACK	X	X	X	X	X	X	X	X	9	00000009
MQXC_MQCMIT	X	X	X	X	X	X	X	X	10	0000000A

MQXCC_* (Exit response)

Table 166. MQXCC_* constants										
Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQXCC_CLOSE_CHANNEL									-6	FFFFFFFA
MQXCC_SUPPRESS_EXIT									-5	FFFFFFFB
MQXCC_SEND_SEC_MSG									-4	FFFFFFFC
MQXCC_SEND_AND_REQUEST_SEC_MSG									-3	FFFFFFFD
MQXCC_SKIP_FUNCTION		X		X	X	X	X	X	-2	FFFFFFFE
MQXCC_SUPPRESS_FUNCTION									-1	FFFFFFF
MQXCC_OK									0	00000000

MQXDR_* (Data-conversion exit response)

Table 167. MQXDR_* constants		
Constant	Decimal	Hex.
MQXDR_OK	0	00000000
MQXDR_CONVERSION_FAILED	1	00000001

MQXP_* (Exit parameter block)

Table 168. MQXP_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQXP_STRUC_ID	X	X	X	X	X	X	X	X	XPbb

MQXP_* (Exit parameter block version)

Table 169. MQXP_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQXP_VERSION_1	X	X	X	X	X	X	X	X	1	00000001

MQXQH_* (Transmission queue header structure identifier)

Table 170. MQXQH_* constants

Constant	Value
MQXQH_STRUC_ID	XQHb

MQXQH_* (Transmission queue header structure version)

Table 171. MQXQH_* constants

Constant	Decimal	Hex.
MQXQH_VERSION_1	1	00000001

MQXR_* •MQXUA_*

MQXR_* (Exit reason)

Table 172. MQXR_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQXR_BEFORE		X	X	X	X	X	X	X	1	00000001
MQXR_AFTER		X	X	X	X	X	X	X	2	00000002

MQXT_* (Exit identifier)

Table 173. MQXT_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Decimal	Hex.
MQXT_API_CROSSING_EXIT		X	X	X	X	X	X	X	1	00000001
MQXT_CHANNEL_SEC_EXIT									11	0000000B
MQXT_CHANNEL_MSG_EXIT									12	0000000C
MQXT_CHANNEL_SEND_EXIT									13	0000000D
MQXT_CHANNEL_RCV_EXIT									14	0000000E
MQXT_CHANNEL_MSG_RETRY_EXIT									15	0000000F
MQXT_CHANNEL_AUTO_DEF_EXIT	X			(1)	X	X	X		16	00000010

Note:

- Supported on AIX, HP-UX, and Sun Solaris only

MQXUA_* (Exit user area)

Table 174. MQXUA_* constants

Constant	MVS/ESA	OS/2	AS/400	UNIX systems	Digital OVMS	Tandem NSK	Windows	Windows NT	Value
MQXUA_NONE	X	X	X	X	X	X	X	X	16 nulls

Chapter 6. Notices

The following paragraph does not apply to any country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore this statement may not apply to you.

References in this publication to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Subject to IBM's valid intellectual property or other legally protectable rights, any functionally equivalent product, program, or service may be used instead of the IBM product, program, or service. The evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, are the responsibility of the user.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact Laboratory Counsel, MP151, IBM United Kingdom Laboratories, Hursley Park, Winchester, Hampshire, England SO21 2JN. Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Licensing, IBM Corporation, 500 Columbus Avenue, Thornwood, New York 10594, U.S.A.

Notices

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

AIX	AS/400	CICS
IBM	IBMLink	IMS
MQ	MQSeries	MVS/ESA
OS/2	OS/400	System/390
S/390		

PC Direct is a trademark of Ziff Communications Company and is used by IBM Corporation under license.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

C-bus is a trademark of Corollary, Inc.

Microsoft, Windows, Windows NT, and the Windows logo are registered trademarks of Microsoft Corporation.

Java and HotJava are trademarks of Sun Microsystems, Inc.

Other company, product, and service names, which may be denoted by a double asterisk (**), may be trademarks or service marks of others.

Sending your comments to IBM

MQSeries

**Application Programming
Reference Summary**

SX33-6095-03

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM.

Feel free to comment on what you regard as specific errors or omissions, and on the accuracy, organization, subject matter, or completeness of this book. Please limit your comments to the information in this book and the way in which the information is presented.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate, without incurring any obligation to you.

You can send your comments to IBM in any of the following ways:

- By mail, use the Readers' Comment Form (RCF)
- By fax:
 - From outside the U.K., after your international access code use 44 1962 870229
 - From within the U.K., use 01962 870229
- Electronically, use the appropriate network ID:
 - IBM Mail Exchange: GBIBM2Q9 at IBMMAIL
 - IBMLink: WINVMD(IDRCF)
 - Internet: idrcf@winvmd.vnet.ibm.com

Whichever you use, ensure that you include:

- The publication number and title
- The page number or topic to which your comment applies
- Your name/address/telephone number/fax number/network ID.

Readers' Comments

MQSeries

**Application Programming
Reference Summary**

SX33-6095-03

Use this form to tell us what you think about this manual. If you have found errors in it, or if you want to express your opinion about it (such as organization, subject matter, appearance) or make suggestions for improvement, this is the form to use.

To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer. This form is provided for comments about the information in this manual and the way it is presented.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Be sure to print your name and address below if you would like a reply.

Name

Address

Company or Organization

Telephone

Email

MQSeries

Application Programming Reference Summary SX33-6095-03



You can send your comments POST FREE on this form from any one of these countries:


Australia	Finland	Iceland	Netherlands	Singapore	United States
Belgium	France	Israel	New Zealand	Spain	of America
Bermuda	Germany	Italy	Norway	Sweden	
Cyprus	Greece	Luxembourg	Portugal	Switzerland	
Denmark	Hong Kong	Monaco	Republic of Ireland	United Arab Emirates	

If your country is not listed here, your local IBM representative will be pleased to forward your comments to us. Or you can pay the postage and send the form direct to IBM (this includes mailing in the U.K.).

2 Fold along this line

By air mail
Par avion

IBRS/CCRI NUMBER: PHQ - D/1348/SO



REPONSE PAYEE
GRANDE-BRETAGNE

IBM United Kingdom Laboratories
Information Development Department (MP095)
Hursley Park,
WINCHESTER, Hants
SO21 2ZZ United Kingdom

3 Fold along this line

From: Name _____
Company or Organization _____
Address _____

EMAIL _____
Telephone _____

4 Fasten here with adhesive tape

1 Cut along this line

1 Cut along this line





Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

SX33-6095-03

